TUNIX

perating system manual

Contents

What is TUNIX?	1
The Commodore KERNAL	1
Memory	2
Performance	2
System calls	2
Task Switches	2
I/O	3
Educational Purpose	3
Installing TUNIX	5
Running TUNIX	6
The Init Process	6
Using The Console	6
Programming For TUNIX	7
No Standard I/O File Handles	7
CBM & TUNIX KERNAL I/O	8
General behaviour	8
SETNAM - Set file name	8
SETLFS - Set parameters	8
OPEN - Open logical file.	9
CHKIN - Set input device by LFN	9
CKOUT - Set output device by LFN	10
BASIN - Input character from channel	10
GETIN - Input character from channel	10
BSOUT - output a character to channel	10
CLRCN - Close default input and output files	11
CLOSE - Close logical file	11
CLALL - close all channels and files	11
LOAD - load RAM from a device	11

SAVE - save RAM to a device	. 12
System Calls	13
Doing System Calls	. 13
Returned Lists And Tables	. 14
Code Examples	. 14
General	. 14
"": Schedule	. 14
"G\$": List general infomation	. 15
"GM": Set Mode (task-switching)	. 15
"GX": Shut down	. 15
Processes	. 15
"P\$": Process list	. 15
"P": Process ID	. 16
"PI": Process info	. 16
"PNname": Process name	. 17
"PF": Fork	. 17
"PEname and args": Execute	. 17
"PX": Exit	. 17
"PW": Wait	. 17
"PK[c]": Kill	. 17
"PS": Suspend	. 18
"PR": Resume	
Extended Memory	. 18
"M\$": Get memory information	
"MA": Allocate a bank	
"MF": Free a bank	
Drivers	
"DL": Driver list	
"DRvvname": Register	
"DD": Assign driver to device	
"DUd": Unassign driver	
"DVd": Get vectors of device	
"DA" Allocate IO page	
"DC": Commit IO page	
"DF": Free IO page	
Signals	
"SSn": Send signal to process	. 20

TUNIX	operating	system	manual
	operating	3 y 3 C C 1 1 1	manaat

"SRhh": Register handler	
Internals	22
Extended Memory Management	22
Task Switching	22
Banking: Managing Pieces Of Address Space	22
Process Creation	24
Drivers	25
Signal polling	25
FIFO	25
DAM dick	25

UNDER CONSTRUCTION iii

What is TUNIX?

It is UNDER CONSTRUCTION.

TUNIX is a KERNAL extension for the Commodore VIC-20 with UltiMem expansion that adds pre-emptive multi-tasking, loadable drivers and recover-on-reset.

The Commodore KERNAL

The Commodore KERNAL is essentially the operating system of Commodore 8-bit computers, such as the Commodore PET, VIC, C64 and so on. It plays a foundational role in making the Commodore computers versatile and user-friendly. It's what allowed programmers to create a vast array of software, from simple text editors to complex games, without having to start from scratch every time. This operating system layer facilitated the explosion of creative and useful applications that defined the Commodore experience.

It's basic functions are:

- Input/Output (I/O) Management: The KERNAL is responsible for handling all the communication between the computer's hardware components, like the keyboard, screen, disk drives, and printers. Whenever you press a key or a program wants to display something on the screen, the KERNAL is the intermediary that makes that happen.
- File Management: It provides the functionality for reading, writing, and managing files on disk. This includes opening files, saving data, and listing directory contents. It's like the librarian that knows where every book is placed and helps you to find or store them.
- Memory Management: The KERNAL also plays a crucial role in managing the computer's memory, deciding which parts of the memory are used for what purpose. Think of it as organizing your desk space efficiently so you can work without clutter.
- Device Management: Commodore computers could connect to various external devices, such as printers, modems, or external disk drives. The KERNAL includes routines (set sequences of instructions) for managing these devices seamlessly, allowing software to use them without needing to know the nitty-gritty details of how they work.

• Error Handling: When something goes wrong, like trying to read a file that doesn't exist, the KERNAL steps in to handle the error, often providing messages to the user or software about what went wrong.

Memory

Except for the IO23 area, which is reserved for TUNIX and drivers, all address space is available to programs.

Performance

(The time spans mentioned here have been guessed.)

Jim Brain's UltiMem expansion makes the TUNIX project possible in the first place. Thanks to it, most process switching can be done in hardware and by automatically generated speed code. ¹

TUNIX isn't optimized for performance but for simplicity and robustness. The following sections cover some essential timings in more detail.

System calls

The most expensive operation is the fork() system call, which can take up to 0.4s to complete since the address space of the forked process is cloned completely. Without speed code this would take about 0.8s.

Task Switches

Switching from one native VIC application to another takes 21ms, from a native to a TUNIX app takes 7ms (175ms the other way around), and a swith from a TUNIX app to another TUNIX app brills at 0.3ms to 10ms.

Time-consuming task switches aren't much of a factor as native apps are not multi-tasking and only run when they are connected to an active console. TUNIX apps can still run alongside unless that has been disabled (e.g. to run programs that take over the machine, to get the maximum performance out of the machine).

¹Speed code is devoid of instructions that test or take turns. E.g. instead of looping over the same piece of code again and again, speed code instructions are repeated a fixed number of times to spare end-of- loop tests and conditional jumps. The backdraw is that the code is highly- specialized and can gain impractical sizes. Copying an 8K memory block takes about 48K of speed code but is several magnitudes faster than a regular copy loop, saving the TUNIX day.

1/0

Calling a driver takes 0.27ms. This leaves us with at least 17.7s overhead for transmitting or receiving 64K characters via device drivers.

The TUNIX system call driver's overhead is parsing and dispatching commands. Resource allocation and deallocation uses fast deque operations at constant execution times.

Educational Purpose

By providing a platform that is both historically interesting and technically challenging, TUNIX encourages the exploration of computing principles, hands-on learning, and the joy of bringing new capabilities to old hardware, all within the context of a community-driven project:

- Understanding Operating Systems: TUNIX introduces Unix-like functionalities to a platform that was not originally designed for such complexity. This offers learners a unique opportunity to understand the components of an operating system, such as multitasking, memory management, and file systems, in a simplified and accessible environment.
- Programming Fundamentals: The project's development and its support for programming in
 environments like BASIC, ANSI-C, and potentially others provide a practical context for learning
 programming fundamentals. It allows students to experience the development cycle, from
 writing and debugging code to integrating with an operating system.
- Historical Insights: By enhancing a vintage computing platform, TUNIX provides insights into the
 evolution of computing technology, offering a hands-on history lesson. It shows how limitations
 of early computers were overcome and how these systems laid the groundwork for modern
 computing paradigms.
- Principles of Unix: The Unix philosophy emphasizes simplicity, modularity, and reusability.
 TUNIX makes these principles tangible for learners, allowing them to explore how small, focused
 programs can work together to perform complex tasks. This can deepen understanding of
 software design and architecture.
- Low-Level Computing Concepts: TUNIX offers exposure to low-level computing concepts, including assembly language programming and direct hardware interaction, within a controlled and understandable environment. This can demystify how software interfaces with hardware, an important area of computer science education.
- Problem Solving and Innovation: Given the VIC-20's hardware limitations, TUNIX challenges
 developers and learners to think creatively about resource management, optimization, and
 functionality implementation. This can foster problem-solving skills and innovative thinking,
 valuable competencies in any technical field.

- Collaboration and Open Source Contribution: If structured as an open-source project, TUNIX
 provides a platform for collaborative learning and contribution. Participants can learn from each
 other, share knowledge, and contribute to a collective project, gaining experience in version
 control, code review, and documentation in the process.
- Cross-Disciplinary Learning: TUNIX bridges computer science with electrical engineering, history, and even elements of graphic design and user experience. This multidiscipli- nary approach can appeal to a wide range of learners, encouraging cross- pollination of ideas and techniques.

Installing TUNIX

TUNIX can recover-on-reset. Whenever a process hangs up the system, it can be killed by pressing the reset button of the UltiMem expansion and TUNIX will continue with the other processes. It requires the TUNIX boot loader to be installed on the UltiMem ROM, which is highly recommended to regular users.

An already installed boot ROMs can be relocated within the first 64K of the UltiMem Flash ROM and booted instead of TUNIX by pressing the SHIFT key during reset. It can also be launched from within TUNIX.

Running TUNIX

After starting the TUNIX program it'll entertain you with some diagnostic messages and boot an instance of BASIC with process ID 1. Now you can load drivers or run apps in addition to native ones.

Plain TUNIX is not very practical. By appending an asterisk "*" and the name and arguments of another program to its load name, TUNIX can be instructed to load and run that as the init process.

The init process should be loading the desired drivers and launch the user's preferred interface. To start TUNIX with the default init program, launch it with:

```
1 LOAD"TUNIX\*INIT",8
```

The Init Process

The init process loads filenames of apps to launch from file INIT.CFG, line by line, and goes to sleep.

Using The Console

Pressing and releasing the C= & SHIFT key alone opens the console menu. Ten slots are available and can be selected by pressing their number. 'C' creates a new BASIC instance in a slot. 'M' followed by a number moves it to another slot and 'X' empties a slot.

Each slot also has a memory and device configuration. You may for example select the TUNIX 40x24 char terminal, or simulate an unexpanded VIC. Wanted drivers must be loaded in one of the slots.

Programming For TUNIX

TUNIX can be used with any programming language that supports regular file I/O. Implementing drivers will most likely require using assembly language at some point, no matter what the rest of the driver was written in.

The number one set of programming tools for TUNIX is the cc65 compiler suite for 6502/6518-CPU platforms. It comes with an ANSI-C compiler, assembler and linker, a Unix-like standard C library, exhaustive documentation, and a vibrant community.

No Standard I/O File Handles

Unlike Unixoids the KERNAL does not provide default LFNs for standard I/O. Instead, apps reset the current LFN- derived device pair (aka "channels") to the keyboard and screen device using the CLRCN system call. To make up for this, driver LFNDEV connects LFNs to devices, so a process' standard I/O can be pipelined.

To get around resetting the channel pair you may decide to OPEN device #0 and #3 to have LFNs for CHKIN and CKOUT.

CBM & TUNIX KERNAL I/O

This section describes the behaviour of the original KERNAL functions, along with the slightly different behaviour of TUNIX to support a multi-tasking envi-ronment better.

All I/O call performance is reduced by about 1ms per operation in addtion to the operation itself.

General behaviour

Functions that return with an error code do so with the carry flag set and an error code in the accumulator (A).

Pointers passed in Y and X registers have the low byte in the X register and the high byte in the Y register respectively.

SETNAM - Set file name.

This routine is used to set the filename for the OPEN, SAVE, or LOAD system calls. A pointer to the filename is expected in the YX register pair (X is the low byte) and the length of the in A.

SETNAM never returns with an error.

SETLFS - Set parameters.

SETLFS will set the logical file number (A), device number (X), and secondary address (Y) for OPEN, LOAD or SAVE.

The logical file numner (or LFN for short) used with OPEN will be translated to the device number by CHKIN/CKOUT for BASIN, BSOUT or GETIN.

The device number may range from 0 to 255 (30 with standard KERNAL I/O). These are the commonly used device numbers:

```
1 0: Keyboard
2 1: Tape
3 2: RS-232
4 3: Screen
5 4+5: Printers
6 6+7: Plotters
7 8-12: Disk drives
8 13-30: user defined
9 --
10 31: TUNIX system calls
```

The secondary (SA) is sent to IEC devices. The c1541 DOS uses it to distinguish between open files like the LFN does. That's why the SA usually has the same value as the LFN in human-readable code.

SETLFS never returns with an error.

OPEN - Open logical file.

OPEN assigns the device and SA to the LFN that was specified when calling SETLFS. A filename must have been set using SETNAM.

The LFN of a successfully opened file can be used with CHKIN and CKOUT to set the input and output device for BASIN, BSOUT and GETIN.

TUNIX copies the filename to the IO area (255 byte maximum) and translates the LFN to a GLFN before calling OPEN.

OPEN clears the STATUS byte. On error, it returns with the carry flag set and one of these codes in A:

- 1: Too many files.
- 2: File already open.
- 4: File not found. Tape device only.
- 5: Device not present.
- 6: Not an input file. Also if logical file number is 0.
- 9: Illegal device number. Also if tape buffer is below \$0200.

CHKIN - Set input device by LFN.

Takes the LFN in X and sets the input device of BASIN and GETIN to the one assigned to that LFN when OPEN was called.

One of these error codes may be returned:

- 3: file not open
- 5: device not present
- 6: file is not an input file

CKOUT - Set output device by LFN.

Takes the LFN in X and sets the output device of BASIN and GETIN to the one assigned to that LFN when OPEN was called.

One of these error codes may be returned:

- 3: file not open
- 5: device not present
- 7: file is not an output file

BASIN - Input character from channel

Reads a byte from the device selected by CHKOUT, CLRCN or CLALL and returns it in A. If no device was selected, BASIN reads from device #0.

When reading from the KERNAL keyboard, the input is buffered up to a length of 80 before or a carriage return is typed. Meanwhile, the cursor is blinking.

On error this routine returns with the carry flag set and additional flags in the STATUS zeropage locate (also see the READST system call).

GETIN - Input character from channel

Same as BASIN but returning 0 with the keyboard if no input is available.

BSOUT - output a character to channel

Writes a byte to the device selected by CHKOUT, CLRCN or CLALL, otherwise it writes to device #3.

NOTE: Care must be taken when using routine to send data to a serial device since data will be sent to all open output channels on the bus. Unless this is desired, all open output channels on the serial bus other than the actually intended destination channel must be closed by a call to CLOSE before.

On error BSOUT returns with the carry flag set and additional flags in the STATUS zeropage location (also see the READST system call).

The Y register is not destroyed.

CLRCN - Close default input and output files

Set the the input device to the key-board (0) and the output device to the screen (3), the only means to access standard I/O.

CLRCN never returns with an error.

CLOSE - Close logical file

Closes the LFN passed A. Never returns with an error.

CLALL - close all channels and files

When KERNAL version is called, the pointers into the open file table are reset, closing all files. Also the I/O channels selected with CHKIN/CKOUT are reset to the console, like CLRCN does.

With TUNIX, CLALL does not just drop all open files like the standard KERNAL but calls CLOSE on each driver, and the I/O channels are reset as well.

CLALL never returns with an error.

LOAD - load RAM from a device

Loads a block of bytes to memory and can also be used to verify them with a block in memory withot affecting it (by setting A to 1 instead of 0).

SETNAM and SETLFS must be called beforehand. The LFN used with SETLFS is ignored.

The destination address of the block is specified by either the first bytes of the file (if the SA is not 0). In that case the address is taken from the YX register pair (with X as the low byte). YX will return the address of the byte following the end of the block.

LOAD returns the same error codes as OPEN:

- 1: Too many files.
- 2: File already open.
- 4: File not found. Tape device only.
- 5: Device not present.
- 6: Not an input file. Also if device number is 0 (keyboard).
- 9: Illegal device number. Also if tape buffer is below \$0200.

SAVE - save RAM to a device

Mirroring LOAD, this saves a block of memory to a device. SETNAM and SETLFS must have been called beforehand. The LFN used with SETLFN is ignored.

SAVE expects the zeropage location of the address of the memory block in A. The YX register contains the size of the memory block (X is the low byte).

SAVE may return one of these error codes if the carry flag is set:

- 1: Too many files.
- 2: File already open.
- 4: File not found. Tape device only.
- 5: Device not present.
- 7: Not an output file. Also if device number is 3 (screen).
- 9: Illegal device number. Also if tape buffer is below \$0200.

System Calls

Doing System Calls

System calls are performed via opening a file on device #31. The first character of the filename denotes the command group, the second the command in that group. Argument bytes may follow. First arguments are passed as the secondary address to SETLFS.

After sending a system call via OPEN, an error code may be read using BASIN. It may be followed by return values.

On assembly level the carry flag tells if an error occured (carry set with code in accumulator instead of the return value). For both ca65 and cc65, system call libraries are around.

```
1 // Get process ID.
2 open (31, 31, 0, "P");
3 // (Never returns with an error.)
4 chkin (31);
5 pid = basin ();
```

Most system calls return an error code:

```
1 // Put process 1 to sleep.
2 open (31, 31, 1, "PS");
3 chkin (31);
4 err = basin ();
5 if (err)
6 printf ("Process 1 already asleep.");
```

Some return an error code and return values:

```
1 // Fork
2 open (31, 31, 0, "PF");
3 chkin (31);
4 err = basin ();
5 if (err)
6    error ();
7 id = basin ();
8 if (!id)
9    child_stuff ();
```

Returned Lists And Tables

Some functions either return a list of key/value pairs or a table. Both are lines of comma-separated values. Tables are headed with a list of column names. Key/value lists always have the keys in the first column.

Column names and keys are composed of upper case ASCII letters.

Values are either decimals, hexadecimal bytes or words of fixed length (2 or 4 characters) starting with a "\$", or strings surrounded by double quotes. Quotes inside strings are printed as quadruple quotes ("").

The order and number of keys may vary, depending on the function and the version of TUNIX. Assuming fixed layouts will jeopardize backwards- compatibility.

An example for a table:

```
1 ID,PID,NAME
2 0,0,"INIT"
3 1,0,"CONSOLE"
4 1,0,"RAMDISK"
5 1,0,"C1541"
6 1,0,"SLIP"
7 1,0,"UIP"
8 2,0,"BASIC"
9 3,0,"SOMETHING ""COOL"""
```

Code Examples

Lower case letters in system call file- name examples are byte values. Letters in brackets are optional.

C examples are for the cc65 compiler suite and need to include header file 'cbm.h'.

General

"": Schedule

A filename of length 0. Does nothing but give TUNIX the opportunity to switch to the next process without doing anything else. Like any of the other system calls it may or may not switch unless in single-tasking mode (command "SS") or the current process has been put to sleep.

```
1 OPEN31,31,31,""
```

```
1 lda #31
2 tax
3 jsr SETFLS
4 lda #0
5 jsr SETNAM
6 jsr OPEN
7
8 ; Library version:
9 jsr tunix_schedule
```

```
1 cbm_k_open (31, 31, 0, "");
```

"G\$": List general infomation

This function returns a list with these keys:

- 1. "NPROCS": Number of processes.
- 2. "MPROCS": Max. number of processes.
- 3. "NDRVS": Number of drivers.
- 4. "MDRVS": Max. number of drivers.
- 5. "NIOPAGES": Number of IO pages.
- 6. "UIOPAGES": Number of used IO pages.

"GM": Set Mode (task-switching).

Enables or disables task-switching for the current process. It is disabled if the seconday address of the system call is 0. That shoud be done sparingly in a multi-tasking environment. Switches are scheduled before system calls return and are highly unpredictable.

Processes that did not free the screen will have that switched in for the time they are running.

"GX": Shut down

Kills all processes and returns to BASIC.

Processes

"P\$": Process list

Returns a list with these fields:

. *ID: Process ID.* . PID: Parent rocess ID. . *NAME: Pathname if the executable.* . FLAGS: (R)running, (S) sleeping, (Z)ombie . *MEM: Allocated memory in bytes.* . NDRV: Number of registered drivers. . *NIOP: Number of allocated IO pages.* . LFNS: Number of logical file numbers.

Running processes are listed before sleeping ones, followed by zombies.

```
1 ID,PID,NAME,FLAGS,MEM,NDRV,NIOP,LFNS
2 1,0,"CONSOLE",R,49152,0,0,8
3 2,1,"BASIC",R,49152,0,0,3
4 0,0,"INIT",S,49152,0,0,2
```

"P": Process ID

Returns current process ID.

"PI": Process info

Secondary address: process ID.

Discloses all internal information about the process specified in the SA. Returns a key/value list with these keys:

- "ID": Process ID.
- "FLAGS": One of "BRSZ" (baby, running, sleeping, zombie).
- "EXITCODE": Exit code. It should have no other value than 0 unless killed.
- "WAITING": Processes waiting for exit.
- "MEMORY": Banks assigned to RAM123 (TUNIX), IO23 (TUNIX), RAM123, BLK1, BLK2, BLK3 and BLK5.
- "#BANKS": Number of extended memory banks.
- "BANKS": List of extended memory banks.
- "STACK": Last saved tack pointer.
- "LFNS": Used LFNs.
- "GLFNS": Assigned global LFNs.
- "IOPAGES": Allocated IO pages.
- "DRIVERS": Registered drivers.
- "DEVICES": Device drivers.
- "SIGNALS": Signals to receive.

"PNname": Process name

The secondary address is the process ID.

Sets the name of process 'p' (zero- terminated string) if it follows the command. Returns the current name if none was set.

"PF": Fork

Makes a copy of the current process with a new ID that is returned to the parent. For the child an ID of 0 is returned. Open files are shared by both processes and be closed by both.

Extended memory banks are inherited but not those that were banked in when the fork was initiated.

"PEname and args": Execute

Replaces the current process by an executable in TUNIX format. But fear not: 'runprg' and 'basic' will also launch native programs.

"PX": Exit

Secondary address: exit code.

Exits the current process with an exit code. All resources are freed but it remains on the process list until its parent exits or returns from a wait() for the exit code and its waiting list is empty (see wait()).

"PW": Wait

Secondary address: process ID.

Waits for a process to exit and returns its exit code.

"PK[c]": Kill

Secondary address: process ID.

Kills any process with an optional exit code (default is 255 if none is specified). Parents have to call wait() to make the process leave the system.

"PS": Suspend

Secondary address: process ID.

Moves process to the sleeping list so that it won't be executed after the next switch.

"PR": Resume

Secondary address: process ID.

Moves a process to the running list. It will run again then the running list is restarted in the scheduler.

Extended Memory

Allocation and deallocation of extended memory banks happens fast at an almost constant speed. Banks may be placed anywhere except in the IO23 area.

"M\$": Get memory information

- 2. "USED": Number of used banks.
- 3. "FREE": Number of free banks
- 4. "RESERVED": Number of reserved ones.
- 5. "FAULTY": Number of faulty ones.
- 6. "TOTAL": Number of banks.
- 7. "BANKSIZE": Size of a bank in bytes.

"MA": Allocate a bank

Allocates a bank and returns its ID. Returns with an error when out of memory.

"MF": Free a bank

Secondary address: bank ID.

Frees a bank. All processes sharing it need to free it before it can be released back into the global pool. All banks of a process will be freed on exit.

Drivers

Processes may register named KERNAL I/O tables of drivers. Drivers process KERNAL I/O calls for a device they've been assigned to. A driver may be assigned to many devices of different processes simultaneously.

When a driver function is called, TUNIX only banks in BLK1 of the process that registered the driver to make up for the low hardware performance. The context of TUNIX is still that of the calling process. The driver must make sure that used zeropage locations are restored upon return to the caller.

Also, TUNIX translates logical file numbers to global logical file numners (GLFNs), so they won't collide with those used by other processes unless they got shared after a fork. An LFN is always translated to the same GLFN until the process exits.

"DL": Driver list

Returns a list with these fields:

TUNIX returns these fields:

- ID: Process ID.
- PID: Parent rocess ID.
- NAME: Pathname if the executable.
- FLAGS: (R)running, (S) sleeping, (Z)ombie
- MEM: Allocated memory in bytes.
- IOP: Number of allocated IO pages.

Example output:

```
1 ID,PID,NAME,FLAGS,MEM,IOP
2 0,0,INIT,S,49152,0
3 1,0,CONSOLE,R,49152,1
4 2,1,BASIC,R,49152,0
```

"DRvvname...": Register

The secondary address is unused.

Registers a named KERNAL I/O vector table. Global to all processes. It unregisters when the driver exits.

"DD": Assign driver to device

Secondary address: process ID.

"DUd": Unassign driver

Secondary address: process ID.

"DVd": Get vectors of device

Secondary address: device number.

Used to overlay vectors by a another driver.

"DA" Allocate IO page

Returns the high byte of the page which will be present in all processes. Used to run interrupt handlers. Needs to be committed (to be portable) before use.

"DC": Commit IO page

Secondary address: IO page.

Copies the page from the current pro-cess to all others.

"DF": Free IO page

Frees the IO page specified by the secondary address.

Signals

Signals are asynchronuous calls of other processes' functions. These functions, called *handlers*, can be *registered* by *signal type* (a byte value) or default handlers are called instead when a signal is *delivered*. The exact handler to call is determined at the time it is sent.

Signal type values can be chosen freely as long as they are not used by TUNIX itself. A byte of payload can be sent as well as the source of a signal is not tracked to allow post-mortem delivery (with the process ID of the sender gone).

Pending signals are queued so low-level interrupt handlers can send them with little overhead. Sending is cancelled if a signal of the same type is already on the queue. It is not checked if the target process provides a handler for the signal type. The signal is discarded on delivery when the handler is missing.

"SSp": Send signal to process

Secondary address: signal type.

"SRhh": Register handler

Secondary address: signal type.

"SU": Unregister handler

Secondary address: signal type.

Internals

Extended Memory Management

Globally, only free banks are tracked via 'banks[]' and '*free_bank'. The latter could be stored in banks[0] instead. Items in 'bank_refs' increment for each process that shares a bank.

Locally (per-process), only allocated banks are tracked in deque 'lbanks/lbanksb', starting with 'first_lbank'.

Task Switching

There are two functions in TUNIX that perform a task switch: fork_raw() and switch(). fork_raw() copies the current process in its whole, including the stack and it's pointer. When the new process is being switched to, it returns from fork_raw() like it's parent but with its parent's ID on the stack. That way fork() can tell if it deals with a returning parent or child.

switch() just exchanges the address space and thus the stack to contiue with the next process.

On the VIC-20 low memory must be copied twice for a task switch as the UltiMem expansion cannot access internal memory.

Banking: Managing Pieces Of Address Space

TUNIX occupies the IO23 area to be around for all processes. BLK1 holds the kernel and global data and RAM123 contains per-process data. These blocks are used by processes as well. So when a programm enters an I/O function, the TUNIX kernel and data are banked in to work and the process' banks need to come back on return. This seems to be solved easily by saving a process' bank configuration in its kernel tables but it makes calling I/O functions from within drivers impossible, as they are working in the caller's context but in their own address spaces. Calling I/O would overwrite the process' bank configuration with the driver's set, and desaster would be inevitable.

To get around this, the bank number of BLK1 is pushed on the stack and popped off on return. Other blocks are preserved the same way just in time.

Process Creation

A completey new process is created once when TUNIX starts: process 0. From then on, running processes are created by the fork() system call only. The fork() system call duplicates the running process and returns the ID of the new process called a 'child process', or 'child' for short.

Forking an already existing process spares initializations as the whole of the program is copied as well as inter- process communication overhead as both processes have all information required to run. Merely shared resources need some updates.

To fork a process its whole address space is copied into a new set of banks and the GLFN reference counts are incremented to reflect the cloned list of LFNs. Also, the processs is assigned a new ID.

A freshly forked process that did not yet run is called a 'baby process' (a notion unique to TUNIX). Before it returns from fork(), the duplicated bank configuration on the stack, which is restored in all cases, is overwritten by the new banks and the child is marked as being a regular, running process.

Drivers

Signal polling

Some programming lanugages can not implement signal handlers. A driver could allow to read incoming signals.

FIFO

For inter-process communication.

RAM disk