GeoPy Documentation

Release 1.21.0

GeoPy Contributors

Contents

1	Installation	3		
2	geopy 2.0	5		
3	Geocoders			
	3.1 Default Options Object	8		
	3.2 Usage with Pandas	10		
	3.3 ArcGIS	12		
	3.4 AzureMaps	14		
	3.5 Baidu	15		
	3.6 BANFrance	16		
	3.7 Bing	18		
	3.8 DataBC	19		
	3.9 GeocodeEarth	20		
	3.10 GeocodeFarm	22		
	3.11 Geolake	23		
	3.12 GeoNames	24		
	3.13 GoogleV3	26		
	3.14 HERE	30		
	3.15 IGNFrance	32		
	3.16 MapBox	34		
	3.17 OpenCage	35		
	3.18 OpenMapQuest	37		
	3.19 Nominatim	40		
	3.20 Pelias	43		
	3.21 Photon	45		
	3.22 PickPoint	46		
	3.23 LiveAddress	49		
	3.24 TomTom	50		
	3.25 What3Words	51		
	3.26 Yandex	53		
4	Calculating Distance	55		
5	Data	59		
6	Exceptions	63		

7	Logging	65
8	Semver	67
9	Changelog	69
10	Indices and search	7 1
Рy	thon Module Index	73
Inc	dex	75



Documentation https://geopy.readthedocs.io/

Source Code https://github.com/geopy/geopy

Issue Tracker https://github.com/geopy/geopy/issues

Stack Overflow https://stackoverflow.com/questions/tagged/geopy

PyPI https://pypi.org/project/geopy/

geopy is a Python 2 and 3 client for several popular geocoding web services.

geopy makes it easy for Python developers to locate the coordinates of addresses, cities, countries, and landmarks across the globe using third-party geocoders and other data sources.

geopy is tested against CPython (versions 2.7, 3.4, 3.5, 3.6, 3.7, 3.8), PyPy, and PyPy3. geopy does not and will not support CPython 2.6.

Contents 1

2 Contents

	CHAPTER 1
	Installation
pip install geopy	

CHAPTER 2

geopy 2.0

geopy 2.0 will be released in 2020, presumably in Q1. Only Python >=3.5 and >=pypy3.5 will be supported. The 1.x branch will not receive any features after that, although critical bugfixes might be backported on request.

Python 2.7 support in new releases is already being removed in many other scientific Python packages, such as *numpy* and *pandas* (see https://python3statement.org/), so this is a good time to get rid of the 2.7 burden for geopy as well.

The last minor release of 1.x series will contain deprecation warnings for all of the breaking changes introduced in 2.0, thus make sure to check your code with warnings enabled (i.e. run python with the -Wd switch) to ensure a smoother transition from 1.x to 2.0.

CHAPTER 3

Geocoders

Each geolocation service you might use, such as Google Maps, Bing Maps, or Nominatim, has its own class in geopy.geocoders abstracting the service's API. Geocoders each define at least a geocode method, for resolving a location from a string, and may define a reverse method, which resolves a pair of coordinates to an address. Each Geocoder accepts any credentials or settings needed to interact with its service, e.g., an API key or locale, during its initialization.

To geolocate a query to an address and coordinates:

```
>>> from geopy.geocoders import Nominatim
>>> geolocator = Nominatim(user_agent="specify_your_app_name_here")
>>> location = geolocator.geocode("175 5th Avenue NYC")
>>> print(location.address)
Flatiron Building, 175, 5th Avenue, Flatiron, New York, NYC, New York, ...
>>> print((location.latitude, location.longitude))
(40.7410861, -73.9896297241625)
>>> print(location.raw)
{'place_id': '9167009604', 'type': 'attraction', ...}
```

To find the address corresponding to a set of coordinates:

```
>>> from geopy.geocoders import Nominatim
>>> geolocator = Nominatim(user_agent="specify_your_app_name_here")
>>> location = geolocator.reverse("52.509669, 13.376294")
>>> print(location.address)
Potsdamer Platz, Mitte, Berlin, 10117, Deutschland, European Union
>>> print((location.latitude, location.longitude))
(52.5094982, 13.3765983)
>>> print(location.raw)
{'place_id': '654513', 'osm_type': 'node', ...}
```

Locators' geocode and reverse methods require the argument query, and also accept at least the argument exactly_one, which is True by default. Geocoders may have additional attributes, e.g., Bing accepts user_location, the effect of which is to bias results near that location. geocode and reverse methods may return three types of values:

- When there are no results found, returns None.
- When the method's exactly_one argument is True and at least one result is found, returns a geopy. location.Location object, which can be iterated over as:

```
(address<String>, (latitude<Float>, longitude<Float>))
```

Or can be accessed as location.address, location.latitude, location.longitude, location.altitude, and location.raw. The last contains the full geocoder's response for this result.

• When exactly_one is False, and there is at least one result, returns a list of geopy.location. Location objects, as above:

```
[location, [...]]
```

If a service is unavailable or otherwise returns a non-OK response, or doesn't receive a response in the allotted timeout, you will receive one of the *Exceptions* detailed below.

Every geocoder accepts an argument format_string that defaults to '%s' where the input string to geocode is interpolated. For example, if you only need to geocode locations in *Cleveland, Ohio*, you could do:

geopy.geocoders.get_geocoder_for_service(service)

For the service provided, try to return a geocoder class.

```
>>> from geopy.geocoders import get_geocoder_for_service
>>> get_geocoder_for_service("nominatim")
geopy.geocoders.osm.Nominatim
```

If the string given is not recognized, a geopy.exc.GeocoderNotFound exception is raised.

3.1 Default Options Object

```
class geopy.geocoders.options
```

The *options* object contains default configuration values for geocoders, e.g. *timeout* and *User-Agent*. Instead of passing a custom value to each geocoder individually, you can override a default value in this object.

Please note that not all geocoders use all attributes of this object. For example, some geocoders don't respect the default_scheme attribute. Refer to the specific geocoder's initializer doc for a list of parameters which that geocoder accepts.

Example for overriding default timeout and user_agent:

```
>>> import geopy.geocoders
>>> from geopy.geocoders import Nominatim
>>> geopy.geocoders.options.default_user_agent = 'my_app/1'
>>> geopy.geocoders.options.default_timeout = 7
>>> geolocator = Nominatim()
>>> print(geolocator.headers)
{'User-Agent': 'my_app/1'}
>>> print(geolocator.timeout)
7
```

Attributes:

default_format_string String containing '%s' where the string to geocode should be interpolated before querying the geocoder. Used by *geocode* calls only. For example: '%s, Mountain View, CA'.

default_proxies Tunnel requests through HTTP proxy.

By default the system proxies are respected (e.g. *HTTP_PROXY* and *HTTPS_PROXY* env vars or platform-specific proxy settings, such as macOS or Windows native preferences – see urllib.request.ProxyHandler for more details). The *proxies* value for using system proxies is None.

To disable system proxies and issue requests directly, explicitly pass an empty dict as a value for *proxies*: { }.

To use a custom HTTP proxy location, pass a string. Valid examples are:

- "192.0.2.0:8080"
- "john:passw0rd@192.0.2.0:8080"
- "http://john:passw0rd@192.0.2.0:8080"

Please note:

- Scheme part (http://) of the proxy is ignored.
- Only *http* proxy is supported. Even if the proxy scheme is *https*, it will be ignored, and the connection between client and proxy would still be unencrypted. However, *https* requests via *http* proxy are still supported (via *HTTP CONNECT* method).

Raw urllib-style *proxies* dict might be provided instead of a string:

• {"https": "192.0.2.0:8080"} - means that HTTP proxy would be used only for requests having *https* scheme. String *proxies* value is automatically used for both schemes, and is provided as a shorthand for the urllib-style *proxies* dict.

For more information, see documentation on urllib.request.ProxyHandler.

Changed in version 1.15.0: Added support for the string value.

default_scheme Use 'https' or 'http' as the API URL's scheme.

default_ssl_context An ssl.SSLContext instance with custom TLS verification settings. Pass None to use the interpreter's defaults (starting from Python 2.7.9 and 3.4.3 that is to use the system's trusted CA certificates; the older versions don't support TLS verification completely).

For older versions of Python (before 2.7.9 and 3.4.3) this argument is ignored, as *urlopen* doesn't accept an ssl context there, and a warning is issued.

To use the CA bundle used by *requests* library:

```
import ssl
import certifi
import geopy.geocoders
ctx = ssl.create_default_context(cafile=certifi.where())
geopy.geocoders.options.default_ssl_context = ctx
```

To disable TLS certificate verification completely:

```
import ssl
import geopy.geocoders
ctx = ssl.create_default_context()
ctx.check_hostname = False
```

(continues on next page)

(continued from previous page)

```
ctx.verify_mode = ssl.CERT_NONE
geopy.geocoders.options.default_ssl_context = ctx
```

See docs for the ssl.SSLContext class for more examples.

default_timeout Time, in seconds, to wait for the geocoding service to respond before raising a geopy.

exc.GeocoderTimedOut exception. Pass None to disable timeout.

Note: Currently None as a value is processed correctly only for the <code>geopy.geocoders.options.default_timeout</code> option value. <code>timeout=None</code> as a method argument (i.e. <code>geocoder.geocode(..., timeout=None))</code> would be treated as "use timeout, as set in <code>geopy.geocoders.options.default_timeout</code>", and a deprecation warning would be raised. In <code>geopy 2.0</code> this will change, so that <code>timeout=None</code> would actually disable timeout.

default_user_agent User-Agent header to send with the requests to geocoder API.

```
default_format_string = '%s'
default_proxies = None
default_scheme = 'https'
default_ssl_context = None
default_timeout = 1
default_user_agent = 'geopy/1.21.0'
```

3.2 Usage with Pandas

It's possible to geocode a pandas DataFrame with geopy, however, rate-limiting must be taken into account.

A large number of DataFrame rows might produce a significant amount of geocoding requests to a Geocoding service, which might be throttled by the service (e.g. by returning *Too Many Requests* 429 HTTP error or timing out).

geopy.extra.rate_limiter.RateLimiter class provides a convenient wrapper, which can be used to automatically add delays between geocoding calls to reduce the load on the Geocoding service. Also it can retry failed requests and swallow errors for individual rows.

If you're having the *Too Many Requests* error, you may try the following:

- Use geopy.extra.rate limiter.RateLimiter with non-zero min delay seconds.
- Try a different Geocoding service (please consult with their ToS first, as some services prohibit bulk geocoding).
- Take a paid plan on the chosen Geocoding service, which provides higher quota.
- Provision your own local copy of the Geocoding service (such as Nominatim).

RateLimiter allows to perform bulk operations while gracefully handling error responses and adding delays when needed.

In the example below a delay of 1 second (min_delay_seconds=1) will be added between each pair of geolocator.geocode calls; all geopy.exc.GeocoderServiceError exceptions will be retried (up to max retries times):

```
import pandas as pd
df = pd.DataFrame({'name': ['paris', 'berlin', 'london']})

from geopy.geocoders import Nominatim
geolocator = Nominatim(user_agent="specify_your_app_name_here")

from geopy.extra.rate_limiter import RateLimiter
geocode = RateLimiter(geolocator.geocode, min_delay_seconds=1)
df['location'] = df['name'].apply(geocode)

df['point'] = df['location'].apply(lambda loc: tuple(loc.point) if loc else None)
```

This would produce the following DataFrame:

To pass extra options to the geocode call:

```
from functools import partial
df['location'] = df['name'].apply(partial(geocode, language='de'))
```

To see a progress bar:

```
from tqdm import tqdm
tqdm.pandas()
df['location'] = df['name'].progress_apply(geocode)
```

Before using this class, please consult with the Geocoding service ToS, which might explicitly consider bulk requests (even throttled) a violation.

New in version 1.16.0.

```
__init__ (func, min_delay_seconds=0.0, max_retries=2, error_wait_seconds=5.0, swal-low_exceptions=True, return_value_on_exception=None)
```

Parameters

- $\textbf{func} \ (\textit{callable}) A \ function \ which \ should \ be \ wrapped \ by \ the \ \textit{RateLimiter}.$
- min_delay_seconds (float) Minimum delay in seconds between the wrapped func calls.
- max_retries (int) Number of retries on exceptions. Only geopy.exc.

 GeocoderServiceError exceptions are retried others are always re-raised.

 max_retries + 1 requests would be performed at max per query. Set

 max_retries=0 to disable retries.

- **error_wait_seconds** (*float*) Time to wait between retries after errors. Must be greater or equal to min_delay_seconds.
- **swallow_exceptions** (bool) Should an exception be swallowed after retries? If not, it will be re-raised. If yes, the return_value_on_exception will be returned.
- return_value_on_exception Value to return on failure when swallow exceptions=True.

3.3 ArcGIS

Geocoder using the ERSI ArcGIS API.

Documentation at: https://developers.arcgis.com/rest/geocode/api-reference/overview-world-geocoding-service. htm

__init__ (username=None, password=None, referer=None, token_lifetime=60, scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, format_string=None, ssl_context=DEFAULT_SENTINEL, auth_domain='www.arcgis.com', domain='geocode.arcgis.com')

Parameters

- username (str) ArcGIS username. Required if authenticated mode is desired.
- password (str) ArcGIS password. Required if authenticated mode is desired.
- referer (str) Required if authenticated mode is desired. Referer HTTP header to send with each request, e.g., 'http://www.example.com'. This is tied to an issued token, so fielding queries for multiple referrers should be handled by having multiple ArcGIS geocoder instances.
- token_lifetime (int) Desired lifetime, in minutes, of an ArcGIS-issued token.
- **scheme** (str) See geopy.geocoders.options.default_scheme. If authenticated mode is in use, it must be 'https'.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default user agent.

New in version 1.12.0.

• format_string (str) - See geopy.geocoders.options. default_format_string.

New in version 1.14.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

• auth_domain (str) - Domain where the target ArcGIS auth service is hosted. Used only in authenticated mode (i.e. username, password and referer are set).

New in version 1.17.0.

• **domain** (str) – Domain where the target ArcGIS service is hosted.

New in version 1.17.0.

geocode (*query*, *exactly_one=True*, *timeout=DEFAULT_SENTINEL*, *out_fields=None*) Return a location point by address.

Parameters

- query (str) The address or query you wish to geocode.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- out_fields (str or iterable) A list of output fields to be returned in the attributes field of the raw data. This can be either a python list/tuple of fields or a comma-separated string. See https://developers.arcgis.com/rest/geocode/api-reference/geocoding-service-output.htm for a list of supported output fields. If you want to return all supported output fields, set out_fields="**".

New in version 1.14.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (*query*, *exactly_one=True*, *timeout=DEFAULT_SENTINEL*, *distance=None*, *wkid=4326*) Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- exactly_one (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **distance** (*int*) Distance from the query location, in meters, within which to search. ArcGIS has a default of 100 meters, if not specified.
- wkid (str) WKID to use for both input and output coordinates.

Deprecated since version 1.14.0: It wasn't working before because it was specified incorrectly in the request parameters, and won't work even if we fix the request, because <code>geopy.point.Point</code> normalizes the coordinates according to WKID 4326. Please open an issue in the geopy issue tracker if you believe that custom which values should be supported. This parameter is scheduled for removal in geopy 2.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.3. ArcGIS 13

3.4 AzureMaps

Bases: geopy.geocoders.tomtom.TomTom

AzureMaps geocoder based on TomTom.

Documentation at: https://docs.microsoft.com/en-us/azure/azure-maps/index

New in version 1.15.0.

__init__ (subscription_key, format_string=None, scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, ssl_context=DEFAULT_SENTINEL, domain='atlas.microsoft.com')

Parameters

- **subscription_key** (str) Azure Maps subscription key.
- format_string (str) See geopy.geocoders.options. default_format_string.
- **scheme** (str) **See** geopy.geocoders.options.default_scheme.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.
- ssl_context (ssl.SSLContext) See geopy.geocoders.options. default_ssl_context.
- **domain** (str) Domain where the target Azure Maps service is hosted.

Return a location point by address.

Parameters

- **query** (str) The address or query you wish to geocode.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **limit** (*int*) Maximum amount of results to return from the service. Unless exactly_one is set to False, limit will always be 1.
- **typeahead** (bool) If the "typeahead" flag is set, the query will be interpreted as a partial input and the search will enter predictive mode.
- language (str) Language in which search results should be returned. When data in specified language is not available for a specific field, default language is used. List of supported languages (case-insensitive): https://developer.tomtom.com/online-search/online-search-documentation/supported-languages

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=None) Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- exactly_one (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- language (str) Language in which search results should be returned. When data in specified language is not available for a specific field, default language is used. List of supported languages (case-insensitive): https://developer.tomtom.com/online-search/online-search-documentation/supported-languages

New in version 1.18.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.5 Baidu

Documentation at: http://lbsyun.baidu.com/index.php?title=webapi/guide/webservice-geocoding New in version 1.0.0.

__init__ (api_key, scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, format_string=None, ssl_context=DEFAULT_SENTINEL, security key=None)

Parameters

- api_key (str) The API key (AK) required by Baidu Map to perform geocoding requests. API keys are managed through the Baidu APIs console (http://lbsyun.baidu.com/apiconsole/key).
- scheme (str) See geopy.geocoders.options.default_scheme.

 Changed in version 1.14.0: Default scheme has been changed from http to https.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

3.5. Baidu 15

• format_string (str) - See geopy.geocoders.options. default format string.

New in version 1.14.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

• **security_key** (*str*) – The security key (SK) to calculate the SN parameter in request if authentication setting requires (http://lbsyun.baidu.com/index.php?title=lbscloud/api/appendix).

New in version 1.15.0.

geocode (*query*, *exactly_one=True*, *timeout=DEFAULT_SENTINEL*)
Return a location point by address.

Parameters

- **query** (*str*) The address or query you wish to geocode.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL)
Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available. Baidu's API will always return at most one result.

New in version 1.14.0.

• **timeout** (*int*) – Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.6 BANFrance

```
 \begin{array}{c} \textbf{class} \ \ \text{geopy.geocoders.BANFrance} \ (\textit{domain='api-adresse.data.gouv.fr'}, & \textit{format\_string=None}, \\ \textit{scheme=None}, & \textit{timeout=DEFAULT\_SENTINEL}, \\ \textit{proxies=DEFAULT\_SENTINEL}, & \textit{user\_agent=None}, \\ \textit{ssl\_context=DEFAULT\_SENTINEL}) \end{array}
```

Geocoder using the Base Adresse Nationale France API.

Documentation at: https://adresse.data.gouv.fr/api

New in version 1.18.0.

__init__ (domain='api-adresse.data.gouv.fr', format_string=None, scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, ssl_context=DEFAULT_SENTINEL)

Parameters

- **domain** (*str*) Currently it is 'api-adresse.data.gouv.fr', can be changed for testing purposes.
- format_string (str) See geopy.geocoders.options. default_format_string.
- scheme (str) See geopy.geocoders.options.default_scheme.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.
- ssl_context (ssl.SSLContext) See geopy.geocoders.options. default_ssl_context.

geocode (*query*, *limit=None*, *exactly_one=True*, *timeout=DEFAULT_SENTINEL*)
Return a location point by address.

Parameters

- **query** (str) The address or query you wish to geocode.
- limit (int) Defines the maximum number of items in the response structure. If not provided and there are multiple results the BAN API will return 5 results by default. This will be reset to one if exactly_one is True.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **exactly_one** (bool) Return one result or a list of results, if available.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL)
Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, geopy.location.Location or a list of them, if exactly_one=False.

3.6. BANFrance 17

3.7 Bing

Geocoder using the Bing Maps Locations API.

Documentation at: https://msdn.microsoft.com/en-us/library/ff701715.aspx

__init__ (api_key, format_string=None, scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, ssl_context=DEFAULT_SENTINEL)

Parameters

- api_key (str) Should be a valid Bing Maps API key (https://www.microsoft.com/en-us/maps/create-a-bing-maps-key).
- format_string (str) See geopy.geocoders.options. default_format_string.
- scheme (str) See geopy.geocoders.options.default_scheme.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- **user_agent** (str) **See** geopy.geocoders.options. default user agent.

New in version 1.12.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

geocode (query, exactly_one=True, user_location=None, timeout=DEFAULT_SENTINEL, culture=None, include_neighborhood=None, include_country_code=False)
Return a location point by address.

Parameters

• **query** (str) – The address or query you wish to geocode.

For a structured query, provide a dictionary whose keys are one of: *addressLine*, *locality* (city), *adminDistrict* (state), *countryRegion*, or *postalcode*.

- **exactly_one** (bool) Return one result or a list of results, if available.
- user_location (geopy.point.Point) Prioritize results closer to this location.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **culture** (*str*) Affects the language of the response, must be a two-letter country code.

New in version 1.4.0.

• include_neighborhood (bool) - Sets whether to include the neighborhood field in the response.

New in version 1.4.0.

• **include_country_code** (bool) – Sets whether to include the two-letter ISO code of the country in the response (field name 'countryRegionIso2').

New in version 1.4.0.

Return type None, geopy.location.Location or a list of them, if exactly_one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL, culture=None, include_country_code=False)
Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **culture** (str) Affects the language of the response, must be a two-letter country code.
- include_country_code (bool) Sets whether to include the two-letter ISO code of the country in the response (field name 'countryRegionIso2').

Return type None, *geopy.location.Location* or a list of them, if exactly one=False.

3.8 DataBC

```
class geopy.geocoders.DataBC (scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, format_string=None, ssl_context=DEFAULT_SENTINEL)

Geocoder using the Physical Address Geocoder from DataBC.
```

deceder using the raysical radiess deceder from Databe.

Documentation at: http://www.data.gov.bc.ca/dbc/geographic/locate/geocoding.page

```
__init__ (scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, format_string=None, ssl_context=DEFAULT_SENTINEL)
```

Parameters

- $\bullet \ \, \textbf{scheme} \, (\textit{str}) \textbf{See} \, \textit{geopy.geocoders.options.default_scheme}.$
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

• format_string (str) - See geopy.geocoders.options. default format string.

New in version 1.14.0.

3.8. DataBC 19

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default ssl context.

New in version 1.14.0.

geocode (query, max_results=25, set_back=0, location_descriptor='any', exactly_one=True, timeout=DEFAULT_SENTINEL)
Return a location point by address.

Parameters

- **query** (str) The address or query you wish to geocode.
- max_results (int) The maximum number of results to request.
- **set_back** (float) The distance to move the accessPoint away from the curb (in meters) and towards the interior of the parcel. location_descriptor must be set to accessPoint for set back to take effect.
- **location_descriptor** (*str*) The type of point requested. It can be any, access-Point, frontDoorPoint, parcelPoint, rooftopPoint and routingPoint.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.9 GeocodeEarth

Bases: geopy.geocoders.pelias.Pelias

geocode.earth, a Pelias-based service provided by the developers of Pelias itself.

New in version 1.15.0.

```
__init__ (api_key, format_string=None, domain='api.geocode.earth', timeout=DEFAULT_SENTINEL, prox-user_agent=None, scheme=None, ssl_context=DEFAULT_SENTINEL)
```

Parameters

- api_key (str) Geocode.earth API key, required.
- format_string (str) See geopy.geocoders.options. default_format_string.
- boundary_rect (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "% (latitude)s, % (longitude)s".) Coordinates to restrict search within. Example: [Point (22, 180), Point (-22, -180)].

Changed in version 1.17.0: Previously boundary_rect could be a list of 4 strings or numbers in the format of [longitude, latitude, longitude, latitude]. This

format is now deprecated in favor of a list/tuple of a pair of geopy Points and will be removed in geopy 2.0.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *boundary_rect* instead.

• **country_bias** (str) – Bias results to this country (ISO alpha-3).

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *country_bias* instead.

- **domain** (str) Specify a custom domain for Pelias API.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.
- scheme (str) See geopy.geocoders.options.default_scheme.
- ssl_context (ssl.SSLContext) See geopy.geocoders.options. default_ssl_context.

geocode (query, exactly_one=True, timeout=DEFAULT_SENTINEL, boundary_rect=None, country_bias=None, language=None) Return a location point by address.

Parameters

- query (str) The address, query or structured query to geocode you wish to geocode.
- **exactly one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- boundary_rect (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "% (latitude)s, % (longitude)s".) Coordinates to restrict search within. Example: [Point (22, 180), Point (-22, -180)].

New in version 1.19.0.

• **country_bias** (*str*) – Bias results to this country (ISO alpha-3).

New in version 1.19.0.

• **language** (*str*) – Preferred language in which to return results. Either uses standard RFC2616 accept-language string or a simple comma-separated list of language codes.

New in version 1.21.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=None) Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "%(latitude)s, %(longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available.

3.9. GeocodeEarth 21

- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **language** (str) Preferred language in which to return results. Either uses standard RFC2616 accept-language string or a simple comma-separated list of language codes.

New in version 1.21.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.10 GeocodeFarm

Geocoder using the GeocodeFarm API.

Documentation at: https://www.geocode.farm/geocoding/free-api-documentation/

__init__(api_key=None, format_string=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, ssl_context=DEFAULT_SENTINEL, scheme=None)

Parameters

- api_key (str) (optional) The API key required by GeocodeFarm to perform geocoding requests.
- format_string (str) See geopy.geocoders.options. default_format_string.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

 $\bullet \ \, \textbf{scheme} \, (\textit{str}) - \textbf{See} \, \textit{geopy.geocoders.options.default_scheme}.$

New in version 1.14.0.

geocode (query, exactly_one=True, timeout=DEFAULT_SENTINEL)
 Return a location point by address.

Parameters

- **query** (*str*) The address or query you wish to geocode.
- exactly_one (bool) Return one result or a list of results, if available.

• **timeout** (*int*) – Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL)
Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available. Geocode-Farm's API will always return at most one result.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.11 Geolake

Geocoder using the Geolake API.

Documentation at: https://geolake.com/docs/api

Terms of Service at: https://geolake.com/terms-of-use

New in version 1.18.0.

__init__ (api_key, domain='api.geolake.com', scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, format_string=None, ssl_context=DEFAULT_SENTINEL)

Parameters

- format_string (str) See geopy.geocoders.options. default_format_string.
- api_key (str) The API key required by Geolake to perform geocoding requests. You can get your key here: https://geolake.com/
- **domain** (*str*) Currently it is 'api.geolake.com', can be changed for testing purposes.
- **scheme** (str) See geopy.geocoders.options.default_scheme.
- timeout (int) See geopy.geocoders.options.default timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.

3.11. Geolake 23

- user_agent (str) See geopy.geocoders.options. default_user_agent.
- ssl_context (ssl.SSLContext) See geopy.geocoders.options. default_ssl_context.

geocode (*query*, *country_codes=None*, *exactly_one=True*, *timeout=DEFAULT_SENTINEL*)
Return a location point by address.

Parameters

• **query** (str) – The address or query you wish to geocode.

For a structured query, provide a dictionary whose keys are one of: *country*, *state*, *city*, *zipcode*, *street*, *address*, *houseNumber* or *subNumber*.

• **country_codes** (*str or list*) – Provides the geocoder with a list of country codes that the query may reside in. This value will limit the geocoder to the supplied countries. The country code is a 2 character code as defined by the ISO-3166-1 alpha-2 standard (e.g. FR). Multiple countries can be specified with a Python list.

Changed in version 1.19.0: Previously only a Python list of countries could be specified. Now a single country as a string can be specified as well.

- **exactly_one** (bool) Return one result or a list of one result.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.12 GeoNames

```
 \begin{array}{c} \textbf{class} \ \ \text{geopy.geocoders.GeoNames} \ (country\_bias=None, \\ out=DEFAULT\_SENTINEL, \\ user\_agent=None, \\ ssl\_context=DEFAULT\_SENTINEL, \\ scheme='http') \end{array}
```

GeoNames geocoder.

Documentation at: http://www.geonames.org/export/geonames-search.html

Reverse geocoding documentation at: http://www.geonames.org/export/web-services.html# findNearbyPlaceName

```
__init__ (country_bias=None, username=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, format_string=None, ssl_context=DEFAULT_SENTINEL, scheme='http')
```

Parameters

• **country_bias** (*str*) – Records from the country_bias are listed first. Two letter country code ISO-3166.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *country_bias* instead.

- **username** (*str*) **GeoNames** username, required. Sign up here: http://www.geonames. org/login
- timeout (int) See geopy.geocoders.options.default_timeout.

- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

• format_string (str) - See geopy.geocoders.options. default_format_string.

New in version 1.14.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

• scheme (str)—See geopy.geocoders.options.default_scheme. Note that at the time of writing GeoNames doesn't support https, so the default scheme is http. The value of geopy.geocoders.options.default_scheme is not respected. This parameter is present to make it possible to switch to https once GeoNames adds support for it.

New in version 1.18.0.

geocode (query, exactly_one=True, timeout=DEFAULT_SENTINEL, country=None, country_bias=None)
Return a location point by address.

Parameters

- **query** (*str*) The address or query you wish to geocode.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **country** (str or list) Limit records to the specified countries. Two letter country code ISO-3166 (e.g. FR). Might be a single string or a list of strings.

New in version 1.19.0.

• **country_bias** (*str*) – Records from the country_bias are listed first. Two letter country code ISO-3166.

New in version 1.19.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, exactly_one=DEFAULT_SENTINEL, timeout=DEFAULT_SENTINEL, feature_code=None, lang=None, find_nearby_type='findNearbyPlaceName')
Return an address by location point.

New in version 1.2.0.

Parameters

• query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) - The coordinates for which you wish to obtain the closest human-readable addresses.

3.12. GeoNames 25

• **exactly_one** (bool) – Return one result or a list of results, if available.

Changed in version 1.14.0: Default value for exactly_one was False, which differs from the conventional default across geopy. Please always pass this argument explicitly, otherwise you would get a warning. In geopy 2.0 the default value will become True.

- timeout (int) Time, in seconds, to wait for the geocoding service to respond before raising a geopy.exc.GeocoderTimedOut exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **feature_code** (str) A GeoNames feature code

New in version 1.18.0.

• lang (str) – language of the returned name element (the pseudo language code 'local' will return it in local language) Full list of supported languages can be found here: https://www.geonames.org/countries/

New in version 1.18.0.

• **find_nearby_type** (*str*) – A flag to switch between different GeoNames API endpoints. The default value is findNearbyPlaceName which returns the closest populated place. Another currently implemented option is findNearby which returns the closest toponym for the lat/lng query.

New in version 1.18.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse_timezone (query, timeout=DEFAULT_SENTINEL)

Find the timezone for a point in *query*.

GeoNames always returns a timezone: if the point being queried doesn't have an assigned Olson timezone id, a pytz.FixedOffset timezone is used to produce the geopy.timezone.Timezone.

New in version 1.18.0.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "%(latitude)s, %(longitude)s") The coordinates for which you want a timezone.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type geopy.timezone.Timezone

3.13 GoogleV3

Geocoder using the Google Maps v3 API.

Documentation at: https://developers.google.com/maps/documentation/geocoding/

Attention: Since July 2018 Google requires each request to have an API key. See https://developers.google.com/maps/documentation/geocoding/usage-and-billing

__init__(api_key=None, domain='maps.googleapis.com', scheme=None, client_id=None, secret_key=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, format_string=None, ssl_context=DEFAULT_SENTINEL, channel=")

Parameters

- api_key (str) The API key required by Google to perform geocoding requests. API keys are managed through the Google APIs console (https://code.google.com/apis/console). Make sure to have both Geocoding API and Time Zone API services enabled for this API key.
- **domain** (str) Should be the localized Google Maps domain to connect to. The default is 'maps.googleapis.com', but if you're geocoding address in the UK (for example), you may want to set it to 'maps.google.co.uk' to properly bias results.
- scheme (str) See geopy.geocoders.options.default_scheme.
- **client_id** (*str*) If using premier, the account client id.
- **secret_key** (*str*) If using premier, the account secret key.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

• format_string (str) - See geopy.geocoders.options. default_format_string.

New in version 1.14.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

• **channel** (*str*) – If using premier, the channel identifier.

New in version 1.12.0.

geocode (query=None, exactly_one=True, timeout=DEFAULT_SENTINEL, bounds=None, region=None, components=None, place_id=None, language=None, sensor=False)
Return a location point by address.

Parameters

• **query** (str) – The address or query you wish to geocode. Optional, if components param is set:

```
>>> g.geocode(components={"city": "Paris", "country": "FR"})
Location(France, (46.227638, 2.213749, 0.0))
```

Changed in version 1.14.0: Now query is optional if components param is set.

• **exactly_one** (bool) – Return one result or a list of results, if available.

3.13. GoogleV3 27

- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- bounds (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "%(latitude)s, %(longitude)s".) The bounding box of the viewport within which to bias geocode results more prominently. Example: [Point(22, 180), Point(-22, -180)].

Changed in version 1.17.0: Previously the only supported format for bounds was a list like [latitude, longitude, latitude, longitude]. This format is now deprecated in favor of a list/tuple of a pair of geopy Points and will be removed in geopy 2.0.

- region (str) The region code, specified as a ccTLD ("top-level domain") twocharacter value.
- **components** (*dict*) Restricts to an area. Can use any combination of: route, locality, administrative_area, postal_code, country.
- place_id(str) Retrieve a Location using a Place ID. Cannot be not used with query or bounds parameters.

```
>>> g.geocode(place_id='ChIJOcfP0Iq2j4ARDrXUa7ZWs34')
```

New in version 1.19.0.

- language (str) The language in which to return results.
- sensor (bool) Whether the geocoding request comes from a device with a location sensor.

Return type None, geopy.location.Location or a list of them, if exactly_one=False.

reverse (query, exactly_one=DEFAULT_SENTINEL, timeout=DEFAULT_SENTINEL, language=None, sensor=False)
Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available.

Changed in version 1.14.0: Default value for exactly_one was False, which differs from the conventional default across geopy. Please always pass this argument explicitly, otherwise you would get a warning. In geopy 2.0 the default value will become True.

- timeout (int) Time, in seconds, to wait for the geocoding service to respond before raising a geopy.exc.GeocoderTimedOut exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- language (str) The language in which to return results.
- sensor (bool) Whether the geocoding request comes from a device with a location sensor.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse timezone (query, at time=None, timeout=DEFAULT SENTINEL)

Find the timezone a point in *query* was in for a specified *at_time*.

New in version 1.18.0.

Changed in version 1.18.1: Previously a KeyError was raised for a point without an assigned Olson timezone id (e.g. for Antarctica). Now this method returns None for such requests.

Parameters

- **query** (*geopy.point.Point*, list or tuple of (latitude, longitude), or string as "%(latitude)s, %(longitude)s") The coordinates for which you want a timezone.
- at_time (datetime.datetime or None) The time at which you want the timezone of this location. This is optional, and defaults to the time that the function is called in UTC. Timezone-aware datetimes are correctly handled and naive datetimes are silently treated as UTC.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None or geopy.timezone.Timezone

timezone (location, at_time=None, timeout=DEFAULT_SENTINEL)

Find the timezone a *location* was in for a specified *at_time*, and return a pytz timezone object.

New in version 1.2.0.

Deprecated since version 1.18.0: Use GoogleV3.reverse_timezone() instead. This method will be removed in geopy 2.0.

Changed in version 1.18.1: Previously a KeyError was raised for a point without an assigned Olson timezone id (e.g. for Antarctica). Now this method returns None for such requests.

Parameters

- **location** (*geopy.point.Point*, list or tuple of (latitude, longitude), or string as "%(latitude)s, %(longitude)s") The coordinates for which you want a timezone.
- at_time (datetime.datetime or None) The time at which you want the timezone of this location. This is optional, and defaults to the time that the function is called in UTC. Timezone-aware datetimes are correctly handled and naive datetimes are silently treated as UTC.

Changed in version 1.18.0: Previously this parameter accepted raw unix timestamp as int or float. This is now deprecated in favor of datetimes and support for numbers will be removed in geopy 2.0.

• **timeout** (*int*) – Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None or pytz timezone. See pytz.timezone().

3.13. GoogleV3 29

3.14 HERE

Geocoder using the HERE Geocoder API.

Documentation at: https://developer.here.com/documentation/geocoder/

New in version 1.15.0.

__init__ (app_id=None, app_code=None, apikey=None, format_string=None, scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, ssl context=DEFAULT_SENTINEL)

Parameters

• app_id (str) - Should be a valid HERE Maps APP ID. Will eventually be replaced with APIKEY. See https://developer.here.com/authenticationpage.

Deprecated since version 1.21.0: App ID and App Code are being replaced by API Keys and OAuth 2.0 by HERE. Consider getting an apikey instead of using app_id and app_code.

• **app_code** (*str*) – Should be a valid HERE Maps APP CODE. Will eventually be replaced with APIKEY. See https://developer.here.com/authenticationpage.

Deprecated since version 1.21.0.

• apikey (str) - Should be a valid HERE Maps APIKEY. These keys were introduced in December 2019 and will eventually replace the legacy APP CODE/APP ID pairs which are already no longer available for new accounts (but still work for old accounts). More authentication details are available at https://developer.here.com/blog/announcing-two-new-authentication-types. See https://developer.here.com/authenticationpage.

New in version 1.21.0.

- format_string (str) See geopy.geocoders.options. default_format_string.
- **scheme** (str) **See** geopy.geocoders.options.default_scheme.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.
- ssl_context (ssl.SSLContext) See geopy.geocoders.options. default ssl context.

geocode (query, bbox=None, mapview=None, exactly_one=True, maxresults=None, pageinformation=None, language=None, additional_data=False, timeout=DEFAULT_SENTINEL)
Return a location point by address.

This implementation supports only a subset of all available parameters. A list of all parameters of the pure REST API is available here: https://developer.here.com/documentation/geocoder/topics/resource-geocode.html

Parameters

- query (str) The address or query you wish to geocode.
 - For a structured query, provide a dictionary whose keys are one of: *city*, *county*, *district*, *country*, *state*, *street*, *housenumber*, or *postalcode*.
- **bbox** (list or tuple of 2 items of <code>geopy.point.Point</code> or (latitude, longitude) or "%(latitude)s, %(longitude)s".) A type of spatial filter, limits the search for any other attributes in the request. Specified by two coordinate (lat/lon) pairs corners of the box. *The bbox search is currently similar to mapview but it is not extended* (cited from the REST API docs). Relevant global results are also returned. Example: [Point(22, 180), Point(-22, -180)].
- mapview (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "%(latitude)s, %(longitude)s".) The app's viewport, given as two coordinate pairs, specified by two lat/lon pairs corners of the bounding box, respectively. Matches from within the set map view plus an extended area are ranked highest. Relevant global results are also returned. Example: [Point(22, 180), Point(-22, -180)].
- **exactly_one** (bool) Return one result or a list of results, if available.
- maxresults (int) Defines the maximum number of items in the response structure. If not provided and there are multiple results the HERE API will return 10 results by default. This will be reset to one if exactly_one is True.
- pageinformation (int) A key which identifies the page to be returned when the response is separated into multiple pages. Only useful when maxresults is also provided.
- language (str) Affects the language of the response, must be a RFC 4647 language code, e.g. 'en-US'.
- additional_data (str) A string with key-value pairs as described on https: //developer.here.com/documentation/geocoder/topics/resource-params-additional.html. These will be added as one query parameter to the URL.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly one=False.

reverse (query, radius=None, exactly_one=True, maxresults=None, pageinformation=None, language=None, mode='retrieveAddresses', timeout=DEFAULT_SENTINEL) Return an address by location point.

This implementation supports only a subset of all available parameters. A list of all parameters of the pure REST API is available here: https://developer.here.com/documentation/geocoder/topics/resource-reverse-geocode.html

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- radius (float) Proximity radius in meters.
- **exactly_one** (bool) Return one result or a list of results, if available.

3.14. HERE 31

- maxresults (int) Defines the maximum number of items in the response structure. If not provided and there are multiple results the HERE API will return 10 results by default. This will be reset to one if exactly_one is True.
- pageinformation (int) A key which identifies the page to be returned when the response is separated into multiple pages. Only useful when maxresults is also provided.
- language (str) Affects the language of the response, must be a RFC 4647 language code, e.g. 'en-US'.
- mode (str) Affects the type of returned response items, must be one of: 'retrieveAddresses' (default), 'retrieveAreas', 'retrieveLandmarks', 'retrieveAll', or 'trackPosition'. See online documentation for more information.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.15 IGNFrance

Geocoder using the IGN France GeoCoder OpenLS API.

Documentation at: https://geoservices.ign.fr/documentation/geoservices/index.html

__init__ (api_key, username=None, password=None, referer=None, domain='wxs.ign.fr', scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, format_string=None, ssl_context=DEFAULT_SENTINEL)

Parameters

- api_key (str) The API key required by IGN France API to perform geocoding requests. You can get your key here: https://geoservices.ign.fr/documentation/services-acces.html. Mandatory. For authentication with referer and with username/password, the api key always differ.
- **username** (str) When making a call need HTTP simple authentication username. Mandatory if no referer set
- password (str) When making a call need HTTP simple authentication password. Mandatory if no referer set
- referer (str) When making a call need HTTP referer. Mandatory if no password and username
- **domain** (str) Currently it is 'wxs.ign.fr', can be changed for testing purposes for developer API e.g 'gpp3-wxs.ign.fr' at the moment.
- scheme (str) See geopy.geocoders.options.default_scheme.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.

• user_agent (str) - See geopy.geocoders.options. default user agent.

New in version 1.12.0.

• format_string (str) - See geopy.geocoders.options. default_format_string.

New in version 1.14.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

geocode (query, query_type='StreetAddress', maximum_responses=25, is_freeform=False, filtering=None, exactly_one=True, timeout=DEFAULT_SENTINEL)
Return a location point by address.

Parameters

- **query** (str) The query string to be geocoded.
- query_type (str) The type to provide for geocoding. It can be *PositionOfInterest*, StreetAddress or CadastralParcel. StreetAddress is the default choice if none provided.
- maximum_responses (int) The maximum number of responses to ask to the API in the query body.
- **is_freeform** (str) Set if return is structured with freeform structure or a more structured returned. By default, value is False.
- **filtering** (*str*) Provide string that help setting geocoder filter. It contains an XML string. See examples in documentation and ignfrance.py file in directory tests.
- exactly_one (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, reverse_geocode_preference=('StreetAddress',), maximum_responses=25, filter-ing=", exactly_one=DEFAULT_SENTINEL, timeout=DEFAULT_SENTINEL)

Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- reverse_geocode_preference (list) Enable to set expected results type. It can be *StreetAddress* or *PositionOfInterest*. Default is set to *StreetAddress*.
- maximum_responses (int) The maximum number of responses to ask to the API in the query body.
- **filtering** (*str*) Provide string that help setting geocoder filter. It contains an XML string. See examples in documentation and ignfrance.py file in directory tests.
- **exactly_one** (bool) Return one result or a list of results, if available.

3.15. IGNFrance

Changed in version 1.14.0: Default value for exactly_one was False, which differs from the conventional default across geopy. Please always pass this argument explicitly, otherwise you would get a warning. In geopy 2.0 the default value will become True.

• **timeout** (*int*) – Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly one=False.

3.16 MapBox

Geocoder using the Mapbox API.

Documentation at: https://www.mapbox.com/api-documentation/

New in version 1.17.0.

__init__(api_key, format_string=None, scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, ssl_context=DEFAULT_SENTINEL, domain='api.mapbox.com')

Parameters

- api_key (str) The API key required by Mapbox to perform geocoding requests. API keys are managed through Mapox's account page (https://www.mapbox.com/account/access-tokens).
- format_string (str) See geopy.geocoders.options. default_format_string.
- scheme (str) See geopy.geocoders.options.default_scheme.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.
- ssl_context (ssl.SSLContext) See geopy.geocoders.options. default_ssl_context.
- domain (str) base api domain for mapbox

Return a location point by address

Changed in version 1.20.0: Previously due to a bug the resulting geopy.location.Location's raw attribute contained a single string instead of a full service response.

Parameters

• **query** (str) – The address or query you wish to geocode.

- **exactly_one** (bool) Return one result or a list of results, if available.
 - Changed in version 1.20.0: Previously due to a bug this parameter wasn't respected.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **proximity** (*geopy.point.Point*, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) A coordinate to bias local results based on a provided location.
- **country** (*str or list*) Country to filter result in form of ISO 3166-1 alpha-2 country code (e.g. FR). Might be a Python list of strings.
 - Changed in version 1.19.0: Previously only a single string could be specified. Now a Python list of individual countries is supported.
- **bbox** (list or tuple of 2 items of *geopy.point.Point* or (latitude, longitude) or "%(latitude)s, %(longitude)s".) The bounding box of the viewport within which to bias geocode results more prominently. Example: [Point(22, 180), Point(-22, -180)].

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL)

Return an address by location point.

Changed in version 1.20.0: Previously due to a bug the resulting geopy.location.Location's raw attribute contained a single string instead of a full service response.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly one=False.

3.17 OpenCage

Geocoder using the OpenCageData API.

Documentation at: https://opencagedata.com/api

New in version 1.1.0.

3.17. OpenCage 35

__init__ (api_key, domain='api.opencagedata.com', scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, format_string=None, ssl_context=DEFAULT_SENTINEL)

Parameters

- api_key (str) The API key required by OpenCageData to perform geocoding requests. You can get your key here: https://opencagedata.com/
- domain (str) Currently it is 'api.opencagedata.com', can be changed for testing purposes.
- **scheme** (str) **See** geopy.geocoders.options.default_scheme.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- **user_agent** (str) **See** geopy.geocoders.options. default user agent.

New in version 1.12.0.

• format_string (str) - See geopy.geocoders.options. default_format_string.

New in version 1.14.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

geocode (query, bounds=None, country=None, language=None, exactly_one=True, timeout=DEFAULT_SENTINEL)
Return a location point by address.

Parameters

- **query** (str) The address or query you wish to geocode.
- **language** (str) an IETF format language code (such as es for Spanish or pt-BR for Brazilian Portuguese); if this is omitted a code of en (English) will be assumed by the remote service.
- bounds (list or tuple of 2 items of <code>geopy.point.Point</code> or (latitude, longitude) or "% (latitude)s, % (longitude)s".) Provides the geocoder with a hint to the region that the query resides in. This value will help the geocoder but will not restrict the possible results to the supplied region. The bounds parameter should be specified as 2 coordinate points corners of a bounding box. Example: [Point (22, 180), Point (-22, -180)].

Changed in version 1.17.0: Previously the only supported format for bounds was a string of "longitude, latitude, longitude, latitude". This format is now deprecated in favor of a list/tuple of a pair of geopy Points and will be removed in geopy 2.0.

• **country** (str or list) - Restricts the results to the specified country or countries. The country code is a 2 character code as defined by the ISO 3166-1 Alpha 2 standard (e.g. fr). Might be a Python list of strings.

Changed in version 1.19.0: This parameter didn't seem to be respected previously. Also, previously only a single string could be specified. Now a Python list of individual countries is supported.

• **exactly_one** (bool) – Return one result or a list of results, if available.

• **timeout** (*int*) – Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, language=None, exactly_one=DEFAULT_SENTINEL, timeout=DEFAULT_SENTINEL)
Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "%(latitude)s, %(longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- language (str) The language in which to return results.
- **exactly_one** (bool) Return one result or a list of results, if available.

Changed in version 1.14.0: Default value for <code>exactly_one</code> was False, which differs from the conventional default across geopy. Please always pass this argument explicitly, otherwise you would get a warning. In geopy 2.0 the default value will become True.

• **timeout** (*int*) – Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.18 OpenMapQuest

Bases: geopy.geocoders.osm.Nominatim

Geocoder using MapQuest Open Platform Web Services.

Documentation at: https://developer.mapquest.com/documentation/open/

Changed in version 1.17.0: OpenMapQuest now extends the Nominatim class.

```
__init__ (api_key=None, format_string=None, view_box=None, bounded=None, country_bias=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, domain='open.mapquestapi.com', scheme=None, user_agent=None, ssl_context=DEFAULT_SENTINEL)
```

Parameters

• api_key (str) - API key provided by MapQuest, required.

Changed in version 1.12.0: OpenMapQuest now requires an API key. Using an empty key will result in a <code>geopy.exc.ConfigurationError</code>.

- format_string (str) See geopy.geocoders.options. default format string.
- view_box (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "%(latitude)s, %(longitude)s".) Coordinates to restrict search within. Example: [Point (22, 180), Point (-22, -180)].

New in version 1.17.0.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *viewbox* instead.

• **bounded** (bool) – Restrict the results to only items contained within the bounding view_box.

New in version 1.17.0.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *bounded* instead.

• **country_bias** (*str or list*) - Limit search results to a specific country. This param sets a default value for the *geocode*'s country_codes.

New in version 1.17.0.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *country_codes* instead.

- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- **domain** (str) Domain where the target Nominatim service is hosted.

New in version 1.17.0.

- scheme (str) See geopy.geocoders.options.default_scheme.
- user_agent (str) See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

geocode (query, exactly_one=True, timeout=DEFAULT_SENTINEL, limit=None, addressdetails=False, language=False, geometry=None, extratags=False, country_codes=None,
 viewbox=None, bounded=None, featuretype=None, namedetails=False)
Return a location point by address.

Parameters

• query (dict or str) - The address, query or a structured query you wish to geocode.

Changed in version 1.0.0: For a structured query, provide a dictionary whose keys are one of: *street*, *city*, *county*, *state*, *country*, or *postalcode*. For more information, see Nominatim's documentation for *structured requests*:

https://nominatim.org/release-docs/develop/api/Search

• **exactly_one** (bool) – Return one result or a list of results, if available.

- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- limit (int) Maximum amount of results to return from Nominatim. Unless exactly one is set to False, limit will always be 1.

New in version 1.13.0.

- addressdetails (bool) If you want in *Location.raw* to include addressdetails such as city_district, etc set it to True
- **language** (str) Preferred language in which to return results. Either uses standard RFC2616 accept-language string or a simple comma-separated list of language codes.

New in version 1.0.0.

• **geometry** (str) – If present, specifies whether the geocoding service should return the result's geometry in *wkt*, *svg*, *kml*, or *geojson* formats. This is available via the *raw* attribute on the returned *geopy.location.Location* object.

New in version 1.3.0.

• **extratags** (bool) – Include additional information in the result if available, e.g. wikipedia link, opening hours.

New in version 1.17.0.

• **country_codes** (*str or list*) – Limit search results to a specific country (or a list of countries). A country_code should be the ISO 3166-1alpha2 code, e.g. gb for the United Kingdom, de for Germany, etc.

New in version 1.19.0.

• viewbox (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "%(latitude)s, %(longitude)s".) - Coordinates to restrict search within. Example: [Point(22, 180), Point(-22, -180)].

New in version 1.19.0.

• **bounded** (bool) – Restrict the results to only items contained within the bounding view_box. Defaults to *False*.

New in version 1.19.0.

• **featuretype** (*str*) – If present, restrict results to certain type of features. Allowed values: *country*, *state*, *city*, *settlement*.

New in version 1.21.0.

• namedetails (bool) – If you want in *Location.raw* to include namedetails, set it to True. This will be a list of alternative names, including language variants, etc.

New in version 1.21.0.

Return type None, geopy.location.Location or a list of them, if exactly_one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=False, addressde-tails=True)

Peturn on eddress by location point

Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available.
- timeout (int) Time, in seconds, to wait for the geocoding service to respond before raising a geopy.exc.GeocoderTimedOut exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **language** (str) Preferred language in which to return results. Either uses standard RFC2616 accept-language string or a simple comma-separated list of language codes.

New in version 1.0.0.

• addressdetails (bool) - Whether or not to include address details, such as city, county, state, etc. in *Location.raw*

New in version 1.14.0.

Return type None, geopy.location.Location or a list of them, if exactly one=False.

3.19 Nominatim

Nominatim geocoder for OpenStreetMap data.

Documentation at: https://nominatim.org/release-docs/develop/api/Overview/

Attention: Using Nominatim with the default <code>user_agent</code> is strongly discouraged, as it violates Nominatim's Usage Policy https://operations.osmfoundation.org/policies/nominatim/ and may possibly cause 403 and 429 HTTP errors. Please make sure to specify a custom <code>user_agent</code> with Nominatim(user_agent="my-application") or by overriding the default <code>user_agent</code>: <code>geopy.geocoders.options.default_user_agent = "my-application"</code>. In <code>geopy 2.0</code> an exception will be thrown when a custom <code>user_agent</code> is not specified.

Changed in version 1.16.0: A warning is now issued when a default *user_agent* is used which restates the *Attention* block above.

```
__init__ (format_string=None, view_box=None, bounded=None, country_bias=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, domain='nominatim.openstreetmap.org', scheme=None, user_agent=None, ssl_context=DEFAULT_SENTINEL)
```

Parameters

- format_string (str) See geopy.geocoders.options. default format string.
- view_box (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "% (latitude)s, % (longitude)s".) Coordinates to restrict search within. Example: [Point (22, 180), Point (-22, -180)].

Changed in version 1.15.0: Previously only a list of stringified coordinates was supported.

Changed in version 1.17.0: Previously view_box could be a list of 4 strings or numbers in the format of [longitude, latitude, longitude, latitude]. This format is now deprecated in favor of a list/tuple of a pair of geopy Points and will be removed in geopy 2.0.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *viewbox* instead.

• **bounded** (bool) – Restrict the results to only items contained within the bounding view_box.

New in version 1.15.0.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *bounded* instead.

• **country_bias** (*str or list*) – Limit search results to a specific country. This param sets a default value for the *geocode*'s country_codes.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *country_codes* instead.

- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- **domain** (*str*) Domain where the target Nominatim service is hosted.

New in version 1.8.2.

 \bullet scheme (str) - See geopy.geocoders.options.default_scheme.

New in version 1.8.2.

• user_agent (str) - See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

geocode (query, exactly_one=True, timeout=DEFAULT_SENTINEL, limit=None, addressdetails=False, language=False, geometry=None, extratags=False, country_codes=None,
 viewbox=None, bounded=None, featuretype=None, namedetails=False)
Return a location point by address.

Parameters

• query (dict or str) - The address, query or a structured query you wish to geocode.

Changed in version 1.0.0: For a structured query, provide a dictionary whose keys are one of: *street*, *city*, *county*, *state*, *country*, or *postalcode*. For more information, see Nominatim's documentation for *structured requests*:

https://nominatim.org/release-docs/develop/api/Search

- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

3.19. Nominatim 41

• limit (int) – Maximum amount of results to return from Nominatim. Unless exactly_one is set to False, limit will always be 1.

New in version 1.13.0.

- addressdetails (bool) If you want in *Location.raw* to include addressdetails such as city_district, etc set it to True
- **language** (*str*) Preferred language in which to return results. Either uses standard RFC2616 accept-language string or a simple comma-separated list of language codes.

New in version 1.0.0.

• **geometry** (str) – If present, specifies whether the geocoding service should return the result's geometry in *wkt*, *svg*, *kml*, or *geojson* formats. This is available via the *raw* attribute on the returned *geopy.location.Location* object.

New in version 1.3.0.

• **extratags** (bool) – Include additional information in the result if available, e.g. wikipedia link, opening hours.

New in version 1.17.0.

• **country_codes** (str or list) – Limit search results to a specific country (or a list of countries). A country_code should be the ISO 3166-1alpha2 code, e.g. gb for the United Kingdom, de for Germany, etc.

New in version 1.19.0.

• viewbox (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "% (latitude)s, % (longitude)s".) - Coordinates to restrict search within. Example: [Point (22, 180), Point (-22, -180)].

New in version 1.19.0.

• **bounded** (bool) – Restrict the results to only items contained within the bounding view box. Defaults to *False*.

New in version 1.19.0.

• **featuretype** (str) – If present, restrict results to certain type of features. Allowed values: *country*, *state*, *city*, *settlement*.

New in version 1.21.0.

• namedetails (bool) – If you want in *Location.raw* to include namedetails, set it to True. This will be a list of alternative names, including language variants, etc.

New in version 1.21.0.

Return type None, geopy.location.Location or a list of them, if exactly_one=False.

 $\begin{tabular}{ll} \textbf{reverse} (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=False, address details=True) \\ \hline \\ \textbf{reverse} (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=False, address details=True) \\ \hline \\ \textbf{reverse} (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=False, address details=True) \\ \hline \\ \textbf{reverse} (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=False, address details=True) \\ \hline \\ \textbf{reverse} (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=False, address details=True) \\ \hline \\ \textbf{reverse} (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=False, address details=True) \\ \hline \\ \textbf{reverse} (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=False, address details=True) \\ \hline \\ \textbf{reverse} (query, exactly_one=True, timeout=DEFAULT_SENTINEL, timeout=DEFAULT_$

Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available.

- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **language** (str) Preferred language in which to return results. Either uses standard RFC2616 accept-language string or a simple comma-separated list of language codes.

New in version 1.0.0.

• addressdetails (bool) - Whether or not to include address details, such as city, county, state, etc. in *Location.raw*

New in version 1.14.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.20 Pelias

```
class geopy.geocoders.Pelias(domain, api_key=None, format_string=None, boundary_rect=None, country_bias=None, timeout=DEFAULT_SENTINEL, prox-
ies=DEFAULT_SENTINEL, user_agent=None, scheme=None, ssl_context=DEFAULT_SENTINEL)
```

Pelias geocoder.

Documentation at: https://github.com/pelias/documentation

See also <code>geopy.geocoders.GeocodeEarth</code> which is a Pelias-based service provided by the developers of Pelias itself.

Changed in version 1.15.0: Mapzen geocoder has been renamed to Pelias.

__init__ (domain, api_key=None, format_string=None, boundary_rect=None, country_bias=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, scheme=None, ssl_context=DEFAULT_SENTINEL)

Parameters

- domain (str) Specify a domain for Pelias API.
- api_key (str) Pelias API key, optional.
- format_string (str) See geopy.geocoders.options. default_format_string.
- boundary_rect (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "%(latitude)s, %(longitude)s".) Coordinates to restrict search within. Example: [Point (22, 180), Point (-22, -180)].

Changed in version 1.17.0: Previously boundary_rect could be a list of 4 strings or numbers in the format of [longitude, latitude, longitude, latitude]. This format is now deprecated in favor of a list/tuple of a pair of geopy Points and will be removed in geopy 2.0.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *boundary_rect* instead.

• country_bias (str) - Bias results to this country (ISO alpha-3).

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *country_bias* instead.

3.20. Pelias 43

- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.
- scheme (str) See geopy.geocoders.options.default_scheme.
- ssl_context (ssl.SSLContext) See geopy.geocoders.options. default ssl context.

geocode (query, exactly_one=True, timeout=DEFAULT_SENTINEL, boundary_rect=None, country_bias=None, language=None) Return a location point by address.

Parameters

- query (str) The address, query or structured query to geocode you wish to geocode.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- boundary_rect (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "%(latitude)s, %(longitude)s".) Coordinates to restrict search within. Example: [Point (22, 180), Point (-22, -180)].

New in version 1.19.0.

• **country_bias** (str) – Bias results to this country (ISO alpha-3).

New in version 1.19.0.

• **language** (str) – Preferred language in which to return results. Either uses standard RFC2616 accept-language string or a simple comma-separated list of language codes.

New in version 1.21.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=None) Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "%(latitude)s, %(longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **language** (*str*) Preferred language in which to return results. Either uses standard RFC2616 accept-language string or a simple comma-separated list of language codes.

New in version 1.21.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.21 Photon

Geocoder using Photon geocoding service (data based on OpenStreetMap and service provided by Komoot on https://photon.komoot.de).

Documentation at: https://github.com/komoot/photon

Photon/Komoot geocoder aims to let you search as you type with OpenStreetMap. No API Key is needed by this platform.

Parameters

- format_string (str) See geopy.geocoders.options. default_format_string.
- **scheme** (str) **See** geopy.geocoders.options.default_scheme.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- domain (str) Should be the localized Photon domain to connect to. The default is 'photon.komoot.de', but you can change it to a domain of your own.
- user_agent (str) See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

geocode (query, exactly_one=True, timeout=DEFAULT_SENTINEL, location_bias=None, language=False, limit=None, osm_tag=None)
Return a location point by address.

Parameters

- query (str) The address or query you wish to geocode.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- location bias The coordinates to used as location bias.
- language (str) Preferred language in which to return results.
- limit (int) Limit the number of returned results, defaults to no limit.

New in version 1.12.0.

3.21. Photon 45

• osm_tag (str or list or set) - The expression to filter (include/exclude) by key and/ or value, str as 'key:value' or list/set of str if multiple filters are required as ['key:!val', '!key', ':!value'].

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=False, limit=None) Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **language** (str) Preferred language in which to return results.
- limit (int) Limit the number of returned results, defaults to no limit.

 New in version 1.12.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.22 PickPoint

Bases: geopy.geocoders.osm.Nominatim

PickPoint geocoder is a commercial version of Nominatim.

Documentation at: https://pickpoint.io/api-reference

New in version 1.13.0.

__init__ (api_key, format_string=None, view_box=None, bounded=None, country_bias=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, domain='api.pickpoint.io', scheme=None, user_agent=None, ssl_context=DEFAULT_SENTINEL)

Parameters

- api_key (str) PickPoint API key obtained at https://pickpoint.io.
- format_string (str) See geopy.geocoders.options. default_format_string.
- view_box (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "%(latitude)s, %(longitude)s".) Coordinates to restrict search within. Example: [Point(22, 180), Point(-22, -180)].

Changed in version 1.17.0: Previously view_box could be a list of 4 strings or numbers in the format of [longitude, latitude, longitude, latitude]. This format is now deprecated in favor of a list/tuple of a pair of geopy Points and will be removed in geopy 2.0.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *viewbox* instead.

• **bounded** (bool) – Restrict the results to only items contained within the bounding view box.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *bounded* instead.

• **country_bias** (*str or list*) – Limit search results to a specific country. This param sets a default value for the *geocode*'s country_codes.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *country_codes* instead.

- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- **domain** (str) Domain where the target Nominatim service is hosted.
- scheme (str) See geopy.geocoders.options.default_scheme.
- user_agent (str) See geopy.geocoders.options. default user agent.
- ssl_context (ssl.SSLContext) See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

geocode (query, exactly_one=True, timeout=DEFAULT_SENTINEL, limit=None, addressdetails=False, language=False, geometry=None, extratags=False, country_codes=None,
 viewbox=None, bounded=None, featuretype=None, namedetails=False)
Return a location point by address.

Parameters

• query (dict or str)—The address, query or a structured query you wish to geocode.

Changed in version 1.0.0: For a structured query, provide a dictionary whose keys are one of: *street*, *city*, *county*, *state*, *country*, or *postalcode*. For more information, see Nominatim's documentation for *structured requests*:

https://nominatim.org/release-docs/develop/api/Search

- **exactly one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- limit (int) Maximum amount of results to return from Nominatim. Unless exactly_one is set to False, limit will always be 1.

New in version 1.13.0.

• addressdetails (bool) – If you want in *Location.raw* to include addressdetails such as city_district, etc set it to True

3.22. PickPoint 47

• **language** (*str*) – Preferred language in which to return results. Either uses standard RFC2616 accept-language string or a simple comma-separated list of language codes.

New in version 1.0.0.

• **geometry** (str) – If present, specifies whether the geocoding service should return the result's geometry in *wkt*, *svg*, *kml*, or *geojson* formats. This is available via the *raw* attribute on the returned *geopy.location.Location* object.

New in version 1.3.0.

• **extratags** (bool) – Include additional information in the result if available, e.g. wikipedia link, opening hours.

New in version 1.17.0.

• **country_codes** (str or list) – Limit search results to a specific country (or a list of countries). A country_code should be the ISO 3166-1alpha2 code, e.g. gb for the United Kingdom, de for Germany, etc.

New in version 1.19.0.

• viewbox (list or tuple of 2 items of geopy.point.Point or (latitude, longitude) or "%(latitude)s, %(longitude)s".) - Coordinates to restrict search within. Example: [Point (22, 180), Point (-22, -180)].

New in version 1.19.0.

• **bounded** (bool) – Restrict the results to only items contained within the bounding view_box. Defaults to *False*.

New in version 1.19.0.

• **featuretype** (str) – If present, restrict results to certain type of features. Allowed values: *country*, *state*, *city*, *settlement*.

New in version 1.21.0.

• namedetails (bool) – If you want in *Location.raw* to include namedetails, set it to True. This will be a list of alternative names, including language variants, etc.

New in version 1.21.0.

Return type None, geopy.location.Location or a list of them, if exactly_one=False.

reverse(query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=False, addressde-tails=True)

Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **language** (*str*) Preferred language in which to return results. Either uses standard RFC2616 accept-language string or a simple comma-separated list of language codes.

New in version 1.0.0.

• addressdetails (bool) - Whether or not to include address details, such as city, county, state, etc. in *Location.raw*

New in version 1.14.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.23 LiveAddress

Geocoder using the LiveAddress API provided by SmartyStreets.

Documentation at: https://smartystreets.com/docs/cloud/us-street-api

```
__init___(auth_id, auth_token, candidates=None, scheme='https', timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, format_string=None, ssl_context=DEFAULT_SENTINEL)
```

Parameters

• auth_id (str) - Valid Auth ID from SmartyStreets.

New in version 1.5.0.

- auth_token (str) Valid Auth Token from SmartyStreets.
- **candidates** (*int*) An integer between 1 and 10 indicating the max number of candidate addresses to return if a valid address could be found. Defaults to 1.

Deprecated since version 1.19.0: This argument will be removed in geopy 2.0. Use *geocode*'s *candidates* instead.

• scheme (str) - Must be https.

Deprecated since version 1.14.0: Don't use this parameter, it's going to be removed in geopy 2.0.

Changed in version 1.8.0: LiveAddress now requires *https*. Specifying *scheme=http* will result in a *geopy.exc.ConfigurationError*.

- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

• format_string (str) - See geopy.geocoders.options. default_format_string.

New in version 1.14.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

3.23. LiveAddress 49

geocode (*query*, *exactly_one=True*, *timeout=DEFAULT_SENTINEL*, *candidates=None*) Return a location point by address.

Parameters

- **query** (str) The address or query you wish to geocode.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **candidates** (*int*) An integer between 1 and 10 indicating the max number of candidate addresses to return if a valid address could be found. Defaults to 1.

New in version 1.19.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

3.24 TomTom

TomTom geocoder.

Documentation at: https://developer.tomtom.com/search-api/search-api-documentation

New in version 1.15.0.

__init__ (api_key, format_string=None, scheme=None, timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, ssl_context=DEFAULT_SENTINEL, domain='api.tomtom.com')

Parameters

- api_key (str) TomTom API key.
- format_string (str) See geopy.geocoders.options. default_format_string.
- scheme (str) See geopy.geocoders.options.default_scheme.
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.
- ssl_context (ssl.SSLContext) See geopy.geocoders.options. default_ssl_context.
- **domain** (str) Domain where the target TomTom service is hosted.

Return a location point by address.

Parameters

- query (str) The address or query you wish to geocode.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- limit (int) Maximum amount of results to return from the service. Unless exactly_one is set to False, limit will always be 1.
- **typeahead** (bool) If the "typeahead" flag is set, the query will be interpreted as a partial input and the search will enter predictive mode.
- language (str) Language in which search results should be returned. When data in specified language is not available for a specific field, default language is used. List of supported languages (case-insensitive): https://developer.tomtom.com/online-search/online-search-documentation/supported-languages

Return type None, *geopy.location.Location* or a list of them, if exactly one=False.

reverse (query, exactly_one=True, timeout=DEFAULT_SENTINEL, language=None)
Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- exactly_one (bool) Return one result or a list of results, if available.
- timeout (int) Time, in seconds, to wait for the geocoding service to respond before raising a geopy.exc.GeocoderTimedOut exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- language (str) Language in which search results should be returned. When data in specified language is not available for a specific field, default language is used. List of supported languages (case-insensitive): https://developer.tomtom.com/online-search/online-search-documentation/supported-languages

New in version 1.18.0.

Return type None, geopy.location.Location or a list of them, if exactly_one=False.

3.25 What3Words

What3Words geocoder.

Documentation at: https://docs.what3words.com/api/v2/

New in version 1.5.0.

Changed in version 1.15.0: API has been updated to v2.

__init__ (api_key, format_string=None, scheme='https', timeout=DEFAULT_SENTINEL, proxies=DEFAULT_SENTINEL, user_agent=None, ssl_context=DEFAULT_SENTINEL)

3.25. What3Words 51

Parameters

- api_key (str) Key provided by What3Words (https://accounts.what3words.com/register).
- format_string (str) See geopy.geocoders.options. default_format_string.
- scheme (str) Must be https.

Deprecated since version 1.15.0: API v2 requires https. Don't use this parameter, it's going to be removed in geopy 2.0. Scheme other than https would result in a geopy. exc.ConfigurationError being thrown.

- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

geocode (query, lang='en', exactly_one=True, timeout=DEFAULT_SENTINEL)

Return a location point for a 3 words query. If the 3 words address doesn't exist, a geopy.exc. GeocoderQueryError exception will be thrown.

Parameters

- query (str) The 3-word address you wish to geocode.
- lang (str) two character language codes as supported by the API (https://docs. what3words.com/api/v2/#lang).
- **exactly_one** (bool) Return one result or a list of results, if available. Due to the address scheme there is always exactly one result for each *3 words* address, so this parameter is rather useless for this geocoder.

Changed in version 1.14.0: exactly_one=False now returns a list of a single location. This option wasn't respected before.

• **timeout** (*int*) – Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type geopy.location.Location or a list of them, if exactly_one=False.

reverse (query, lang='en', exactly_one=True, timeout=DEFAULT_SENTINEL)

Return a 3 words address by location point. Each point on surface has a 3 words address, so there's always a non-empty response.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "%(latitude)s, %(longitude)s".) The coordinates for which you wish to obtain the 3 word address.
- lang (str) two character language codes as supported by the API (https://docs.what3words.com/api/v2/#lang).

• **exactly_one** (bool) – Return one result or a list of results, if available. Due to the address scheme there is always exactly one result for each *3 words* address, so this parameter is rather useless for this geocoder.

Changed in version 1.14.0: exactly_one=False now returns a list of a single location. This option wasn't respected before.

• **timeout** (*int*) – Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type geopy.location.Location or a list of them, if exactly_one=False.

3.26 Yandex

```
class geopy.geocoders.Yandex(api_key=None, lang=None, timeout=DEFAULT_SENTINEL, prox-
ies=DEFAULT_SENTINEL, user_agent=None, scheme=None, for-
mat_string=None, ssl_context=DEFAULT_SENTINEL)
```

Yandex geocoder.

Documentation at: https://tech.yandex.com/maps/doc/geocoder/desc/concepts/input_params-docpage/ New in version 1.5.0.

Attention: Since September 2019 Yandex requires each request to have an API key. API keys can be created at https://developer.tech.yandex.ru/

```
__init__(api_key=None, lang=None, timeout=DEFAULT_SENTINEL, prox-
ies=DEFAULT_SENTINEL, user_agent=None, scheme=None, format_string=None,
ssl_context=DEFAULT_SENTINEL)
Changed in version 1.14.0: Default scheme has been changed from http to https.
```

Parameters

• api_key (str) - Yandex API key, mandatory. The key can be created at https://developer.tech.yandex.ru/

Changed in version 1.21.0: API key is mandatory since September 2019.

- lang (str) response locale, the following locales are supported: "ru_RU" (default), "uk_UA", "be_BY", "en_US", "tr_TR".
- timeout (int) See geopy.geocoders.options.default_timeout.
- proxies (dict) See geopy.geocoders.options.default_proxies.
- user_agent (str) See geopy.geocoders.options. default_user_agent.

New in version 1.12.0.

 $\bullet \ \, \textbf{scheme} \, (str) - \textbf{See} \, geopy. geocoders.options.default_scheme.$

New in version 1.14.0.

• format_string (str) - See geopy.geocoders.options. default_format_string.

New in version 1.14.0.

3.26. Yandex 53

• ssl_context (ssl.SSLContext) - See geopy.geocoders.options. default_ssl_context.

New in version 1.14.0.

geocode (query, exactly_one=True, timeout=DEFAULT_SENTINEL)
 Return a location point by address.

Parameters

- **query** (str) The address or query you wish to geocode.
- **exactly_one** (bool) Return one result or a list of results, if available.
- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

reverse (query, exactly_one=DEFAULT_SENTINEL, timeout=DEFAULT_SENTINEL, kind=None)
Return an address by location point.

Parameters

- query (geopy.point.Point, list or tuple of (latitude, longitude), or string as "% (latitude)s, % (longitude)s".) The coordinates for which you wish to obtain the closest human-readable addresses.
- exactly_one (bool) Return one result or a list of results, if available.

Changed in version 1.14.0: Default value for exactly_one was False, which differs from the conventional default across geopy. Please always pass this argument explicitly, otherwise you would get a warning. In geopy 2.0 the default value will become True.

- **timeout** (*int*) Time, in seconds, to wait for the geocoding service to respond before raising a *geopy.exc.GeocoderTimedOut* exception. Set this only if you wish to override, on this call only, the value set during the geocoder's initialization.
- **kind** (str) Type of toponym. Allowed values: *house*, *street*, *metro*, *district*, *locality*. New in version 1.14.0.

Return type None, *geopy.location.Location* or a list of them, if exactly_one=False.

CHAPTER 4

Calculating Distance

Geopy can calculate geodesic distance between two points using the geodesic distance or the great-circle distance, with a default of the geodesic distance available as the function geopy.distance.distance.

Great-circle distance (great_circle) uses a spherical model of the earth, using the mean earth radius as defined by the International Union of Geodesy and Geophysics, (2a + b)/3 = 6371.0087714150598 kilometers approx 6371.009 km (for WGS-84), resulting in an error of up to about 0.5%. The radius value is stored in distance. EARTH_RADIUS, so it can be customized (it should always be in kilometers, however).

The geodesic distance is the shortest distance on the surface of an ellipsoidal model of the earth. The default algorithm uses the method is given by Karney (2013) (geodesic); this is accurate to round-off and always converges. An older deprecated method due to Vincenty (1975) (vincenty) is also available; this is only accurate to 0.2 mm and the distance calculation fails to converge for nearly antipodal points.

```
geopy.distance.distance currently uses geodesic.
```

There are multiple popular ellipsoidal models, and which one will be the most accurate depends on where your points are located on the earth. The default is the WGS-84 ellipsoid, which is the most globally accurate. geopy includes a few other models in the distance. ELLIPSOIDS dictionary:

```
model
                              major (km)
                                           minor (km)
                                                         flattening
ELLIPSOIDS = {'WGS-84':
                                           6356.7523142, 1 / 298.257223563),
                              (6378.137,
             'GRS-80':
                                           6356.7523141, 1 / 298.257222101),
                             (6378.137,
             'Airy (1830)': (6377.563396, 6356.256909, 1 / 299.3249646),
             'Intl 1924':
                             (6378.388, 6356.911946,
                                                         1 / 297.0),
             'Clarke (1880)': (6378.249145, 6356.51486955, 1 / 293.465),
             'GRS-67':
                              (6378.1600, 6356.774719,
                                                         1 / 298.25),
             }
```

Here are examples of distance .distance usage:

```
>>> from geopy import distance
>>> newport_ri = (41.49008, -71.312796)
>>> cleveland_oh = (41.499498, -81.695391)
>>> print(distance.distance(newport_ri, cleveland_oh).miles)
538.39044536
```

(continues on next page)

(continued from previous page)

```
>>> wellington = (-41.32, 174.81)
>>> salamanca = (40.96, -5.50)
>>> print(distance.distance(wellington, salamanca).km)
19959.6792674
```

The second example above fails with *vincenty*.

Using great_circle distance:

```
>>> print(distance.great_circle(newport_ri, cleveland_oh).miles)
536.997990696
```

You can change the ellipsoid model used by the geodesic formulas like so:

```
>>> ne, cl = newport_ri, cleveland_oh
>>> print(distance.geodesic(ne, cl, ellipsoid='GRS-80').miles)
```

The above model name will automatically be retrieved from the distance. ELLIPSOIDS dictionary. Alternatively, you can specify the model values directly:

```
>>> distance.geodesic(ne, cl, ellipsoid=(6377., 6356., 1 / 297.)).miles
```

Distances support simple arithmetic, making it easy to do things like calculate the length of a path:

```
>>> from geopy import Nominatim
>>> d = distance.distance
>>> g = Nominatim(user_agent="specify_your_app_name_here")
>>> _, wa = g.geocode('Washington, DC')
>>> _, pa = g.geocode('Palo Alto, CA')
>>> print((d(ne, cl) + d(cl, wa) + d(wa, pa)).miles)
3277.30439191
```

```
geopy.distance.lonlat (x, y, z=0)
```

geopy.distance.distance accepts coordinates in (y, x)/(lat, lon) order, while some other libraries and systems might use (x, y)/(lon, lat).

This function provides a convenient way to convert coordinates of the (x, y)/(lon, lat) format to a geopy.point.Point instance.

Example:

```
>>> from geopy.distance import lonlat, distance
>>> newport_ri_xy = (-71.312796, 41.49008)
>>> cleveland_oh_xy = (-81.695391, 41.499498)
>>> print(distance(lonlat(*newport_ri_xy), lonlat(*cleveland_oh_xy)).miles)
538.3904453677203
```

Parameters

- x longitude
- y latitude
- **z** (optional) altitude

Returns Point(latitude, longitude, altitude)

```
class geopy.distance.geodesic(*args, **kwargs)
```

Calculate the geodesic distance between two points.

Set which ellipsoidal model of the earth to use by specifying an ellipsoid keyword argument. The default is 'WGS-84', which is the most globally accurate model. If ellipsoid is a string, it is looked up in the *ELLIPSOIDS* dictionary to obtain the major and minor semiaxes and the flattening. Otherwise, it should be a tuple with those values. See the comments above the *ELLIPSOIDS* dictionary for more information.

Example:

```
>>> from geopy.distance import geodesic
>>> newport_ri = (41.49008, -71.312796)
>>> cleveland_oh = (41.499498, -81.695391)
>>> print(geodesic(newport_ri, cleveland_oh).miles)
538.390445368
```

New in version 1.13.0.

```
___init___(*args, **kwargs)
```

Initialize self. See help(type(self)) for accurate signature.

```
class geopy.distance.vincenty(*args, **kwargs)
```

Deprecated since version 1.13: Use geodesic instead. Vincenty will be removed in geopy 2.0.

Calculate the geodesic distance between two points using the Vincenty's method.

Set which ellipsoidal model of the earth to use by specifying an ellipsoid keyword argument. The default is 'WGS-84', which is the most globally accurate model. If ellipsoid is a string, it is looked up in the *ELLIPSOIDS* dictionary to obtain the major and minor semiaxes and the flattening. Otherwise, it should be a tuple with those values. See the comments above the *ELLIPSOIDS* dictionary for more information.

Example:

```
>>> from geopy.distance import vincenty

>>> newport_ri = (41.49008, -71.312796)

>>> cleveland_oh = (41.499498, -81.695391)

>>> print(vincenty(newport_ri, cleveland_oh).miles)

538.390445362
```

Note: Vincenty's method for distance fails to converge for some valid (nearly antipodal) points. In such cases, use <code>geodesic</code> which always produces an accurate result.

```
__init__ (*args, **kwargs)
Initialize self. See help(type(self)) for accurate signature.
```

```
class geopy.distance.great_circle(*args, **kwargs)
```

Use spherical geometry to calculate the surface distance between two points.

Set which radius of the earth to use by specifying a radius keyword argument. It must be in kilometers. The default is to use the module constant *EARTH_RADIUS*, which uses the average great-circle radius.

Example:

```
>>> from geopy.distance import great_circle
>>> newport_ri = (41.49008, -71.312796)
>>> cleveland_oh = (41.499498, -81.695391)
>>> print(great_circle(newport_ri, cleveland_oh).miles)
536.997990696
```

```
___init___(*args, **kwargs)
```

Initialize self. See help(type(self)) for accurate signature.

CHAPTER 5

Data

```
class geopy.location.Location(address=", point=None, raw=None)
```

Contains a parsed geocoder response. Can be iterated over as (location<String>, (latitude<float>, longitude<Float)). Or one can access the properties address, latitude, longitude, or raw. The last is a dictionary of the geocoder's response for this item.

address

Location as a formatted string returned by the geocoder or constructed by geopy, depending on the service.

Return type unicode

altitude

Location's altitude.

Return type float or None

latitude

Location's latitude.

Return type float or None

longitude

Location's longitude.

Return type float or None

point

geopy.point.Point instance representing the location's latitude, longitude, and altitude.

Return type geopy.point.Point or None

raw

Location's raw, unparsed geocoder response. For details on this, consult the service's documentation.

Return type dict or None

class geopy.point.Point

A geodetic point with latitude, longitude, and altitude.

Latitude and longitude are floating point values in degrees. Altitude is a floating point value in kilometers. The reference level is never considered and is thus application dependent, so be consistent! The default for all values is 0

Points can be created in a number of ways...

With latitude, longitude, and altitude:

```
>>> p1 = Point(41.5, -81, 0)
>>> p2 = Point(latitude=41.5, longitude=-81)
```

With a sequence of 0 to 3 values (latitude, longitude, altitude):

```
>>> p1 = Point([41.5, -81, 0])
>>> p2 = Point((41.5, -81))
```

Copy another *Point* instance:

```
>>> p2 = Point(p1)

>>> p2 == p1

True

>>> p2 is p1

False
```

Give a string containing at least latitude and longitude:

```
>>> p1 = Point('41.5,-81.0')
>>> p2 = Point('41.5 N -81.0 W')
>>> p3 = Point('-41.5 S, 81.0 E, 2.5km')
>>> p4 = Point('23 26m 22s N 23 27m 30s E 21.0mi')
>>> p5 = Point('''3 26' 22" N 23 27' 30" E''')
```

Point values can be accessed by name or by index:

```
>>> p = Point(41.5, -81.0, 0)

>>> p.latitude == p[0]

True

>>> p.longitude == p[1]

True

>>> p.altitude == p[2]

True
```

When unpacking (or iterating), a (latitude, longitude, altitude) tuple is returned:

```
>>> latitude, longitude, altitude = p
```

static __new__ (cls, latitude=None, longitude=None, altitude=None)

Parameters

- **latitude** (*float*) Latitude of point.
- longitude (float) Longitude of point.
- altitude (float) Altitude of point.

classmethod from_point(point)

Create and return a new Point instance from another Point instance.

60 Chapter 5. Data

classmethod from_sequence(seq)

Create and return a new Point instance from any iterable with 0 to 3 elements. The elements, if present, must be latitude, longitude, and altitude, respectively.

classmethod from_string(string)

Create and return a Point instance from a string containing latitude and longitude, and optionally, altitude.

Latitude and longitude must be in degrees and may be in decimal form or indicate arcminutes and arcseconds (labeled with Unicode prime and double prime, ASCII quote and double quote or 'm' and 's'). The degree symbol is optional and may be included after the decimal places (in decimal form) and before the arcminutes and arcseconds otherwise. Coordinates given from south and west (indicated by S and W suffixes) will be converted to north and east by switching their signs. If no (or partial) cardinal directions are given, north and east are the assumed directions. Latitude and longitude must be separated by at least whitespace, a comma, or a semicolon (each with optional surrounding whitespace).

Altitude, if supplied, must be a decimal number with given units. The following unit abbrevations (case-insensitive) are supported:

- km (kilometers)
- m (meters)
- mi (miles)
- ft (feet)
- nm, nmi (nautical miles)

Some example strings that will work include:

```
• 41.5; -81.0
```

- 41.5, -81.0
- 41.5 -81.0
- 41.5 N -81.0 W
- -41.5 S;81.0 E
- 23 26m 22s N 23 27m 30s E
- 23 26' 22" N 23 27' 30" E
- UT: N 39°20' 0'' / W 74°35' 0''

class geopy.timezone.Timezone(pytz timezone, raw=None)

Contains a parsed response for a timezone request, which is implemented in few geocoders which provide such lookups.

New in version 1.18.0.

pytz_timezone

pytz timezone instance.

```
Return type pytz.tzinfo.BaseTzInfo
```

raw

Timezone's raw, unparsed geocoder response. For details on this, consult the service's documentation.

Return type dict or None

62 Chapter 5. Data

CHAPTER 6

Exceptions

class geopy.exc.GeopyError

Bases: Exception

Geopy-specific exceptions are all inherited from GeopyError.

class geopy.exc.ConfigurationError

Bases: geopy.exc.GeopyError

When instantiating a geocoder, the arguments given were invalid. See the documentation of each geocoder's __init__ for more details.

class geopy.exc.GeocoderServiceError

Bases: geopy.exc.GeopyError

There was an exception caused when calling the remote geocoding service, and no more specific exception could be raised by geopy. When calling geocoders' geocode or *reverse* methods, this is the most generic exception that can be raised, and any non-geopy exception will be caught and turned into this. The exception's message will be that of the original exception.

class geopy.exc.GeocoderQueryError

Bases: geopy.exc.GeocoderServiceError

Either geopy detected input that would cause a request to fail, or a request was made and the remote geocoding service responded that the request was bad.

class geopy.exc.GeocoderQuotaExceeded

Bases: geopy.exc.GeocoderServiceError

The remote geocoding service refused to fulfill the request because the client has used its quota.

class geopy.exc.GeocoderAuthenticationFailure

Bases: geopy.exc.GeocoderServiceError

The remote geocoding service rejected the API key or account credentials this geocoder was instantiated with.

class geopy.exc.GeocoderInsufficientPrivileges

Bases: geopy.exc.GeocoderServiceError

The remote geocoding service refused to fulfill a request using the account credentials given.

class geopy.exc.GeocoderTimedOut

Bases: geopy.exc.GeocoderServiceError

The call to the geocoding service was aborted because no response has been received within the timeout argument of either the geocoding class or, if specified, the method call. Some services are just consistently slow, and a higher timeout may be needed to use them.

class geopy.exc.GeocoderUnavailable

Bases: geopy.exc.GeocoderServiceError

Either it was not possible to establish a connection to the remote geocoding service, or the service responded with a code indicating it was unavailable.

class geopy.exc.GeocoderParseError

Bases: geopy.exc.GeocoderServiceError

Geopy could not parse the service's response. This is probably due to a bug in geopy.

class geopy.exc.GeocoderNotFound

Bases: geopy.exc.GeopyError

Caller requested the geocoder matching a string, e.g., "google" > GoogleV3, but no geocoder could be found.

$\mathsf{CHAPTER}\ 7$

Logging

geopy will log geocoding URLs with a logger name geopy at level *DEBUG*, and for some geocoders, these URLs will include authentication information.

HTTP bodies of responses with unsuccessful status codes are logged with *INFO* level.

Default logging level is NOTSET, which delegates the messages processing to the root logger. See docs for logging. Logger.setLevel() for more information.

66 Chapter 7. Logging

CHAPTER 8

Semver

geopy attempts to follow semantic versioning, however some breaking changes are still being made in minor releases, such as:

- Backwards-incompatible changes of the undocumented API. This shouldn't affect anyone, unless they extend
 geocoder classes or use undocumented features or monkey-patch anything. If you believe that something is
 missing in geopy, please consider opening an issue or providing a patch or a PR instead of hacking around
 geopy.
- Geocoder classes which simply don't work (usually because their service has been discontinued) might get removed. They don't work anyway, so that's hardly a breaking change, right? :)
- Geocoding services sometimes introduce new APIs and deprecate the previous ones. We try to upgrade without breaking the geocoder's API interface, but the geopy.location.Location.raw value might change in a backwards-incompatible way.
- Behavior for invalid input and peculiar edge cases might be altered. For example, *geopy.point.Point* instances did coordinate values normalization, though it's not documented, and it was completely wrong for the latitudes outside the *[-90; 90]* range. So instead of using an incorrectly normalized value for latitude, an ValueError exception is now thrown (#294).

To make the upgrade less painful, please read the changelog before upgrading.

68 Chapter 8. Semver

					\cap
\frown L	AF	D		\Box	ч
∪г	٦А	Г	ı⊏	П	J

Changelog

Changelog for 1.x.x series.

For changes in the 0.9 series, see the 0.9x changelog.

CHAPTER 10

Indices and search

- genindex
- search

Python Module Index

g

geopy, 1
geopy.distance, 55
geopy.geocoders, 7

74 Python Module Index

Symbols Α ___init___() (geopy.distance.geodesic method), 57 address (geopy.location.Location attribute), 59 __init__() (geopy.distance.great_circle method), 57 altitude (geopy.location.Location attribute), 59 ___init___() (geopy.distance.vincenty method), 57 ArcGIS (class in geopy.geocoders), 12 ___init___() (geopy.extra.rate_limiter.RateLimiter AzureMaps (class in geopy.geocoders), 14 method), 11 В __init___() (geopy.geocoders.ArcGIS method), 12 __init___() (geopy.geocoders.AzureMaps method), 14 Baidu (class in geopy.geocoders), 15 __init__() (geopy.geocoders.BANFrance method), BANFrance (class in geopy.geocoders), 16 Bing (class in geopy.geocoders), 18 __init__() (geopy.geocoders.Baidu method), 15 C __init__() (geopy.geocoders.Bing method), 18 __init__() (geopy.geocoders.DataBC method), 19 ConfigurationError (class in geopy.exc), 63 __init___() (geopy.geocoders.GeoNames method), 24 (geopy.geocoders.GeocodeEarth D ___init___() method), 20 DataBC (class in geopy.geocoders), 19 __init__() (geopy.geocoders.GeocodeFarm method), default_format_string(geopy.geocoders.options attribute), 10 __init__() (geopy.geocoders.Geolake method), 23 default proxies (geopy.geocoders.options __init__() (geopy.geocoders.GoogleV3 method), 27 tribute), 10 __init__() (geopy.geocoders.Here method), 30 default_scheme (geopy.geocoders.options attribute), __init___() (geopy.geocoders.IGNFrance method), 32 ___init___() (geopy.geocoders.LiveAddress method), default_ssl_context (geopy.geocoders.options attribute), 10 __init__() (geopy.geocoders.MapBox method), 34 (geopy.geocoders.options default_timeout __init___() (geopy.geocoders.Nominatim method), 40 tribute), 10 __init__() (geopy.geocoders.OpenCage method), 35 default_user_agent (geopy.geocoders.options at-(geopy.geocoders.OpenMapQuest ___init___() tribute), 10 method), 37 __init__() (geopy.geocoders.Pelias method), 43 F ___init___() (geopy.geocoders.Photon method), 45 from_point() (geopy.point.Point class method), 60 __init__() (geopy.geocoders.PickPoint method), 46 from_sequence() (geopy.point.Point class method), ___init___() (geopy.geocoders.TomTom method), 50 ___init___() (geopy.geocoders.What3Words method), from_string() (geopy.point.Point class method), 61 __init__() (geopy.geocoders.Yandex method), 53 G __new__() (geopy.point.Point static method), 60 geocode () (geopy.geocoders.ArcGIS method), 13 geocode () (geopy.geocoders.AzureMaps method), 14 geocode () (geopy.geocoders.Baidu method), 16

geocode() (geopy.geocoders.BANFrance method), 17 geocode() (geopy.geocoders.Bing method), 18 geocode() (geopy.geocoders.DataBC method), 20 geocode() (geopy.geocoders.GeocodeEarth method), 21 geocode() (geopy.geocoders.GeocodeFarm method), 22	L latitude (geopy.location.Location attribute), 59 LiveAddress (class in geopy.geocoders), 49 Location (class in geopy.location), 59 longitude (geopy.location.Location attribute), 59 lonlat() (in module geopy.distance), 56
geocode () (geopy.geocoders.Geolake method), 24 geocode () (geopy.geocoders.GeoNames method), 25 geocode () (geopy.geocoders.GoogleV3 method), 27 geocode () (geopy.geocoders.Here method), 30 geocode () (geopy.geocoders.IGNFrance method), 33 geocode () (geopy.geocoders.LiveAddress method), 49 geocode () (geopy.geocoders.MapBox method), 34 geocode () (geopy.geocoders.Nominatim method), 41 geocode () (geopy.geocoders.OpenCage method), 36 geocode () (geopy.geocoders.OpenMapQuest method), 38	M MapBox (class in geopy.geocoders), 34 N Nominatim (class in geopy.geocoders), 40 O OpenCage (class in geopy.geocoders), 35 OpenMapQuest (class in geopy.geocoders), 37 options (class in geopy.geocoders), 8
<pre>geocode() (geopy.geocoders.Pelias method), 44 geocode() (geopy.geocoders.Photon method), 45 geocode() (geopy.geocoders.PickPoint method), 47 geocode() (geopy.geocoders.TomTom method), 50 geocode() (geopy.geocoders.What3Words method), 52 geocode() (geopy.geocoders.Yandex method), 54 GeocodeEarth (class in geopy.geocoders), 20 GeocodeFarm (class in geopy.geocoders), 22 GeocoderAuthenticationFailure (class in geopy.exc), 63 GeocoderInsufficientPrivileges (class in</pre>	Pelias (class in geopy.geocoders), 43 Photon (class in geopy.geocoders), 45 PickPoint (class in geopy.geocoders), 46 Point (class in geopy.point), 59 point (geopy.location.Location attribute), 59 pytz_timezone (geopy.timezone.Timezone attribute), 61 R
geopy.exc), 63 GeocoderNotFound (class in geopy.exc), 64 GeocoderParseError (class in geopy.exc), 64 GeocoderQueryError (class in geopy.exc), 63 GeocoderQuotaExceeded (class in geopy.exc), 63 GeocoderServiceError (class in geopy.exc), 63 GeocoderTimedOut (class in geopy.exc), 64 GeocoderUnavailable (class in geopy.exc), 64 geodesic (class in geopy.distance), 56 Geolake (class in geopy.geocoders), 23 GeoNames (class in geopy.geocoders), 24	RateLimiter (class in geopy.extra.rate_limiter), 10 raw (geopy.location.Location attribute), 59 raw (geopy.timezone.Timezone attribute), 61 reverse() (geopy.geocoders.ArcGIS method), 13 reverse() (geopy.geocoders.AzureMaps method), 15 reverse() (geopy.geocoders.Baidu method), 16 reverse() (geopy.geocoders.BANFrance method), 17 reverse() (geopy.geocoders.Bing method), 19 reverse() (geopy.geocoders.GeocodeEarth method), 21 reverse() (geopy.geocoders.GeocodeFarm method),
<pre>geopy (module), 1 geopy.distance (module), 55 geopy.geocoders (module), 7 GeopyError (class in geopy.exc), 63 get_geocoder_for_service() (in module</pre>	reverse() (geopy.geocoders.GeoNames method), 25 reverse() (geopy.geocoders.GeoNames method), 28 reverse() (geopy.geocoders.Here method), 31 reverse() (geopy.geocoders.IGNFrance method), 33 reverse() (geopy.geocoders.MapBox method), 35 reverse() (geopy.geocoders.Nominatim method), 42 reverse() (geopy.geocoders.OpenCage method), 37 reverse() (geopy.geocoders.OpenMapQuest method), 39
Here (class in geopy.geocoders), 30 IGNFrance (class in geopy.geocoders), 32	reverse() (geopy.geocoders.Pelias method), 44 reverse() (geopy.geocoders.Photon method), 46 reverse() (geopy.geocoders.PickPoint method), 48 reverse() (geopy.geocoders.TomTom method), 51

76 Index

```
reverse() (geopy.geocoders.What3Words method), 52
reverse() (geopy.geocoders.Yandex method), 54
reverse_timezone() (geopy.geocoders.GeoNames
        method), 26
reverse_timezone() (geopy.geocoders.GoogleV3
        method), 28
Т
Timezone (class in geopy.timezone), 61
timezone() (geopy.geocoders.GoogleV3 method), 29
TomTom (class in geopy.geocoders), 50
V
vincenty (class in geopy.distance), 57
W
```

What 3Words (class in geopy.geocoders), 51

Υ

Yandex (class in geopy.geocoders), 53

Index 77