

# ANDROID SDK V2.6

# **Contents**

3
3
3
3
4
6
7
8
9
12
13
13
13

### Introduction

Mimopay Android SDK is designed to help you integrate your android application or games to Mimopay's payment gateway. Mimopay Android SDK equipped with a built-in UI as well as quiet mode operation. Quiet mode means that after you initiate execution, the SDK will do the payment process in background instead of popping up its built-in UI. This will allow you to continue with other process that you want to do. All information, whether an error occurs or a successful payment, will be notified via 'onReturn' callback method.

# **Supported Channels**

#### Topup:

- 1. Smartfren
- 2. Sevelin

#### ATM:

- 1. BCA
- 2. Bersama

#### Airtime (Telkomsel):

1. UPoint

XL:

- 1. Airtime
- 2. HRN (Voucher)

#### Maxis:

1. Airtime

#### Digi:

1. DPoint

# **Prerequisites**

Before you begin, you need to make sure that you are a registerred merchant at Mimopay payment gateway since the SDK will be useless without user ID, merchant code, and secret key that required to pass at initialization


### **Download the SDK**

The SDK is available at <a href="https://github.com/mimopay/Mimopay-Android-SDK">https://github.com/mimopay/Mimopay-Android-SDK</a>. You can clone it with whatever git tool you have or use command line as shown below

git clone https://github.com/mimopay/Mimopay-Android-SDK.git

# **The Flow**

### <u>UI Mode Flow Illustration</u>




#### Where:

- (a) User choose to do some payment.
- (b) Merchant's app to activate SDK's built-in UI.

In this stage, merchant's app is become inactive. All interaction only between user and the SDK. The SDK provides necessary UI controls to simplify user to do the payment

- (c) User choose some payment channel and method
- (d) The SDK's UI pass all necessary things that user has choosen or input, to mimopay server
- (e) Mimopay server replies back the results
- (f) The SDK display the results
- (g) Mimopay server than apply callback to merchant's server

### **Quiet Mode Flow Illustration**



#### Where:

(a) User choose to do some payment.

Merchant's app provides some fancy, interactive payment UI to user. In this stage, the SDK running behind its scene.

- (b) Merchant's app to execute process according to what payment method that user has choosen.
- (c) The SDK pass all values or inputs to mimopay server
- (d) Mimopay server replies back the results
- (e) The SDK will filtering them, and pass necessary things to merchant's app
- (f) Merchant's app display the filterred results to user
- (g) Mimopay server than apply callback to merchant's server

## Integrating the SDK

Before you start, you need to follow these steps below

- 1. You need to copy the Mimopay.jar into libs directory of your project.
- 2. The SDK require several android permissions so you need to add lines of codes below into the AndroidManifest.xml file of your project

```
<uses-permission android:name="android.permission.INTERNET" />
<uses-permission android:name="android.permission.WRITE EXTERNAL STORAGE" />
<uses-permission android:name="android.permission.READ_PHONE_STATE" />
<uses-permission android:name="android.permission.SEND SMS"/>
<uses-permission android:name="android.permission.READ SMS" />
```

3. The SDK has it own built-in UI that will pops up during execution, so you need to add several line of codes below into the AndroidManifest.xml file of your project

```
<activity
       android:name="com.mimopay.MimopayActivity"
       android:theme="@android:style/Theme.Translucent.NoTitleBar.Fullscreen"
       android:windowSoftInputMode="stateUnspecified|adjustPan"
</activity>
```

4. You also need to add these three line of codes into your java source.

```
import com.mimopay.Mimopay;
import com.mimopay.MimopayInterface;
import com.mimopay.merchant.Merchant;
```

note:

Note: Since library V2.0 it is no longer needed

- 5. Please pay attention closely that since ADT 17, all JAR libraries better to be placed in 'libs' directory instead of lib.
- 6. For developer that using proguard, please add below in your proguard config file

```
-keep class org.jsoup.** {*;}
```

Note: Since library V2.0 it is no longer needed

### Class and Interface

The following is the description of the SDK class and interface that you have imported in your java source code

```
public class Mimopay {
        public Mimopay(Context context,
               String emailOrUserId, String merchantCode, String productName,
               String transactionId, String secretKey, String currency,
               MimopayInterface mimopayinterface
        public void executeTopup()
        public void executeTopup(String channel)
        public void executeTopup(String channel, String code)
        public void executeATMs()
        public void executeATMs(String channel)
        public void executeATMs(String channel, String amount)
        public void executeUPointAirtime()
        public void executeUPointAirtime(String amount, String phoneNumber,
               boolean autosendsms)
        public void executeMPointAirtime()
        public void executeMPointAirtime(String amount, String phoneNumber,
               boolean autosendsms)
        public void executeDPointAirtime()
        public void executeDPointAirtime(String amount, String phoneNumber,
               boolean autosendsms)
        public String getSdkVersion()
        public void enableGateway(boolean enable)
        public void enableLog(boolean enable)
        public String[] getLastResult()
public interface MimopayInterface {
        public void onReturn(String info, ArrayList<String> params);
```

### **Initialization**

The SDK initialization require you to fill all your merchant stuffs into its parameters. Please refer to <a href="http://staging.mimopay.com/api">http://staging.mimopay.com/api</a>.

```
Mimopay mimopay = new Mimopay(
       Context context,
                                      // your android application context
       String emailOrUserId,
       String merchantCode,
       String productName,
       String transactionId,
       String secretKeyStaging,
       String secretKeyGateway,
       String currency,
       MimopayInterface mi
                                     // your callback interface
);
```

transactionId may set to empty (transactioID = "") which cause the library to generate a unique value based on unix timestamp.

In the sample source codes, the secretKeyStaging and secretKeyGateway is managed as string of encrypted keys.

```
try {
       secretKeyStaging = Merchant.get(true, "zLdLLbLX7xi2E4zxcbGMPg==");
       secretKeyGateway = Merchant.get(false, "5aSkczdhkk4ukFsZEHykkA==");
} catch(Exception e) {
```

The encrypted values are bundled in a java JAR file that should be placed in the lib directory along with the SDK jar to make the final build. This will allow you to avoid your secretKey written in your java source codes.

Please contact us and we will generate for you a text file (encrypted keys) and JAR file (encrypted values).

### **Callback**

To obtain any information from the SDK during and after execution, you need to use MimopayInterface interface and override its oReturn method as decribed below.

```
MimopayInterface mimopayinterface = new MimopayInterface()
        public void onReturn(String info, ArrayList<String> params)
               if(info.equals("SUCCESS")) {
                       // do what you want to do
               } else if(info.equals("ERROR")) {
                       // do what you want to do
               } else if(info.equals("FATALERROR")) {
                       // do what you want to do
};
```

Use 'info' as indicator whether it is success, error, or fatal error status. Use 'params' to obtain the details. Be noticed that 'params' may set to null so you need to test first whether it equal to null or not. After that, you should obtain its size. Here is the ilustration

```
if(params != null) {
         int j = params.size();
         // ....
}
```

Please pay attention closely when using quiet mode. Since it is actualy running on background task, then onReturn definetely called within background task. If you don't have any codes that update your own UI, it will not be a problem. However if you do have, please use android's runOnUiThread function to avoid fatal error. Please refer to example codes below:

```
if(mQuietMode) {
       runOnUiThread(new Runnable() { public void run() {
               Toast.makeText(getApplicationContext(), "SDK onReturn",
                       Toast.LENGTH_LONG).show();
       }});
```

### The following table visualize on Return's info and params string

Info	Params		Meaning		
	0	UserCancelled	User was cancelling the transaction		
	0	MerchantLoadUrlNull	You pass the channel string other		
			than listed in this document		
	0	ErrorConnectingToMimopayServer	Internet connection problem		
		ErrorValidatingVoucherCode	Occurs when SDK receive other then		
	0		'ok' status from server in during		
			transaction process		
	0	ErrorInternetConnectionProblem	Internet connection problem		
	0	Unsupported Payment Method	Requested payment method does not		
			exist		
	0	UnspecifiedChannelRequest	Requested payment channel does not		
		·	exist		
	0	ErrorHTTP404NotFound	Server return 404 error code.		
ERROR	0	ErrorUnderMaintenance	The current payment channel is		
			under maintenance		
		ErrorInvalidPhoneNumber	Phone number that you've supplied is		
			in invalid format		
	0 E	ErrorInvalidDenomValue	The denom value that you've		
			supplied is in invalid format		
	0	ErrorInvalidAmountValue	The amount value that you've		
			supplied is in invalid format		
	Notes				
	Those error listed above are errors that occurs during transaction process. Since all				
	transactions are done by Mimopay's server and also depend on the input, at the end of				
	transaction, server might return an error or failed. Therefore since it is considerred as the				
	end of the transaction (not 'during' transaction), then SDK will always return SUCCESS once				
	it received status=200 . In other word, the transaction success but the result is failed				
SUCCESS	03	Depends on the channel	Message retrieved from server		
FATALERROR	TALERROR 0	Depends on the uncaughtException message	Occurs when the SDK suddenly force		
TATALLINION		2 aparta on the undugitereption message	closed by the Android OS		

Pymt Method	Mode	:.nfa	params				
		info	0	1	2	3	
Smartfren	B/Q		CHCCECC	smartfren	OK	Sukses	
		SUCCESS	smartfren	FAILED	*SF1		
		ERROR	LE	*HST	*JEM		
Sevelin	B/Q		SUCCESS	sevelin	ОК	Sukses	
		SUCCESS	sevelin	FAILED	*SV1		
		ERROR	LE	*HST	*JEM		
ATM DCA	D / O	SUCCESS	atm_bca	*AT1	*AT2	*AT3	
ATM BCA	B/Q	ERROR	LE	*HST	*JEM		
ATN 4 D	2/0	SUCCESS	atm_bersama	*AT1	*AT2	*AT3	
ATM Bersama	B/Q	ERROR	LE	*HST	*JEM		
	D	SUCCESS	upoint_airtime	*UP1	*AT1	*AT2	
II i.t Aintina	В	ERROR	LE	*HST	*JEM		
Upoint Airtime	Q	SUCCESS	upoint_airtime	*UP1	*AT1		
		ERROR	LE	*HST	*JEM		
	В	SUCCESS	xl_airtime	*XL1	*AT1	*AT2	
XL Airtime		ERROR	LE	*HST	*JEM		
AL AII time	Q	SUCCESS	xl_airtime	OK	Sukses		
		ERROR	LE	*HST	*JEM		
	B/Q	SUCCESS	xl_hrn	OK	Sukses		
XL Voucher		SUCCESS	xl_hrn	FAILED	*XV1		
		ERROR	LE	*HST	*JEM		
	D	SUCCESS	mpoint_airtime	OK	*AT2		
Maxis Airtime	В	ERROR	LE	*HST	*JEM		
IVIAXIS AITUINE	Q	SUCCESS	mpoint_airtime	OK	*MP1		
		ERROR	LE	*HST	*JEM		
	В	SUCCESS	dpoint_airtime_charge	OK	*AT2		
Digi Dooin+		ERROR	LE	*HST	*JEM		
Digi Dpoint	Q	SUCCESS	dpoint_airtime	OK	*DG1		
		ERROR	LE	*HST	*JEM		

B = build-in UI

Q = quiet mode

Empty cell on params column means equals to **null** 

LE = Listed Errors. Please refer to previous table

\* = Please refer to table below

_				
SF1	Kode voucher sudah digunakan (voucher code has been used already)			
SV1	Kode Voucher salah (wrong voucher code)			
AT1	Company Code			
AT2	Total Amount			
AT3	Transaction ID			
UP1	6-digit UP Code (upoint)			
AT1	Destination Number for the for sending the shortcode			
AT2	User phone number			
XL1	4-digit XL's shortcode			
XV1	Reload Gagal			
MP1	You will receive a sms soon, please follow the instruction in it to complete this payment			
DG1	SMS CODE is comming in			
HST	Http status code or Java Exception (-1)			
JEM	Java Exception status			

# **Executing Payment**

The following table will help you to understand the SDK's methods and how they are categorized.

Pymt Method	Channel	Built-in UI	Quiet
Торир	smartfren sevelin	executeTopup() executeTopup(String channel)	executeTopup(String channel, String code)
ATM	atm_bca atm_bersama	executeATMs() executeATMs(String channel)	executeATMs(String channel, String code)
Airtime	upoint	executeUPointAirtime()	<ul> <li>executeUPointAirtime(String amount)</li> <li>executeUPointAirtime(String amount, String phoneNumber, boolean autosendsms)</li> </ul>
XL	xl_airtime xl_hrn	public void executeXL() public void executeXLAirtime() public void executeXLHrn()	<ul> <li>public void executeXLHrn(String code)</li> <li>public void executeXLAirtime(String amount, String phoneNumber, boolean autosendsms)</li> <li>public void executeXLAirtime(String amount)</li> </ul>
Maxis	mpoint	executeMPointAirtime()	executeMPointAirtime(String amount, String phoneNumber, boolean autosendsms)
Digi	dpoint	void executeDPointAirtime();	void executeDPointAirtime(     String amount,     String phoneNumber, boolean     autosendsms)     boolean isDPointPaymentIncomplete()     void completeDPointPayment(String smscode)

On Airtime UPoint, the result that received from mimopay server would be SMS content: up <code> and the destination phone number. The SDK would not go automatically send SMS without user intervention. So for Airtime UPoint, the quiet mode operation will not be completely quiet. The built-in UI will pops up to allow user to type that codes

### Parameter explanation:

```
String channel
```

channel should be one of the followings

smartfren sevelin atm\_bca atm\_bersama upoint xl\_airtime

xl hrn mpoint dpoint

#### String code

A voucher code string for smartfren or sevelin topup

### String amount

A mimocard value for atm bca & atm bersama

#### String phoneNumber

A phone number for UPoint & XL

#### boolean autosendsms

It will send an SMS automatically when it is set to 'true'.

Please note that due to Indonesia Telco policy, fully automatic sending SMS is not allowed. When it is set to 'true', it will redirected to Mimopay's built-in UI. It then will confirm to user to re-type the SMS code then the SMS will be sent.

# **Other Important Methods**

- For some reason you may want to know the current SDK version. You may call getSdkVersion() to obtain the current SDK version
- By default, the SDK points to staging.mimopay.com during execution. On your production release, you should use gateway.mimopay.com instead of staging. To enable it you call enableGateway(boolean enable) with enable sets to true
- The last successful transaction always be recorded. You can call getLastResult() to obtain those transaction messages.
- Sometimes we need to visualize SDK's log activities during process. You may enable it by calling enableLog(boolean enable) with enable sets to true
- Since version v2.2 SDK's built-in UI is now support custom language. Please refer to CustomLang.java source code, it shows you how to manage all words of your desired language in a single array of strings. After that then you need to call setUiLanguage(String[] slang)

## **SDK Build**

The SDK builds with Android API Level 17

### Queries

If you have any queries or issues please email me at jimmy@mimopay.com or skype to <u>jimmybas</u>