Chapter 3 outline


- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer

3-3

Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
 - send side: breaks app messages into segments, passes to network layer
 - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
 - Internet: TCP and UDP



Transport Layer

Transport vs. network layer

- network layer: logical communication between hosts
- transport layer: logical communication between processes
 - relies on, enhances, network layer services

Household analogy:

12 kids sending letters to 12 kids


- processes = kids
- app messages = letters in envelopes
- hosts = houses
- transport protocol = Ann and Bill
- network-layer protocol = postal service

Transport Layer

3-5

Internet transport-layer protocols

- reliable, in-order delivery (TCP)
 - congestion control
 - flow control
 - connection setup
- unreliable, unordered delivery: UDP
 - basic extension of "besteffort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees




Transport Layer

Chapter 3 outline


- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer



How demultiplexing works

- host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - each datagram carries 1 transport-layer segment
 - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

Transport Layer

3-9

Connectionless demultiplexing

 Create sockets with port numbers:

DatagramSocket mySocket1 = new
 DatagramSocket(12534);


DatagramSocket mySocket2 = new
 DatagramSocket(12535);


 UDP socket identified by two-tuple:

(dest IP address, dest port number)

- When host receives UDP segment:
 - checks destination port number in segment
 - directs UDP segment to socket with that port number
- IP datagrams with different source IP addresses and/or source port numbers directed to same socket

Transport Layer








Connection-oriented demux

- TCP socket identified by 4-tuple:
 - source IP address
 - source port number
 - dest IP address
 - dest port number
- recv host uses all four values to direct segment to appropriate socket
- Server host may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
- Web servers have different sockets for each connecting client
 - non-persistent HTTP will have different socket for each request

Transport Layer







Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer

3-17


UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones"
 Internet transport protocol
- "best effort" service, UDP segments may be:
 - lost
 - delivered out of order to app
- connectionless:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others

Why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small segment header
- no congestion control: UDP can blast away as fast as desired

Transport Layer



UDP checksum

<u>Goal:</u> detect "errors" (e.g., flipped bits) in transmitted segment

Sender:

- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field


Receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - NO error detected
 - YES no error detected.
 But maybe errors
 nonetheless? More later

Transport Layer

Internet Checksum Example

- Note
 - When adding numbers, a carryout from the most significant bit needs to be added to the result
- Example: add two 16-bit integers




Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer

Principles of Reliable data transfer

- important in app., transport, link layers top-10 list of important networking topics!




- (a) provided service
- characteristics of unreliable channel will determine complexity of reliable data transfer

Transport Layer

3-23

Principles of Reliable data transfer

- important in app., transport, link layers
- top-10 list of important networking topics!




(a) provided service

(b) service implementation

characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Transport Layer

Principles of Reliable data transfer important in app., transport, link layers top-10 list of important networking topics! application proces process data data rdt_send() data deliver data() reliable channel reliable data reliable data transfer protoco transfer protocol (sending side) (receiving side) udt_send()1 rdt_rcv() unreliable channel) (b) service implementation (a) provided service characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt) 3-25 Transport Layer



Reliable data transfer: getting started

We'll:

- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- · consider only unidirectional data transfer
 - but control info will flow on both directions!
- use finite state machines (FSM) to specify sender, receiver

event causing state transition
actions taken on state transition
state: when in this
"state" next state
uniquely determined
by next event

event

event


event

actions

state
2

Rdt1.0: reliable transfer over a reliable channel

- · underlying channel perfectly reliable
 - no bit errors
 - no loss of packets
- separate FSMs for sender, receiver:
 - sender sends data into underlying channel
 - receiver read data from underlying channel



Transport Layer

3-28

3-27

Transport Layer


Rdt2.0: channel with bit errors(ARQ)


- underlying channel may flip bits in packet
 - checksum to detect bit errors
- the question: how to recover from errors:
 - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
 - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
 - sender retransmits pkt on receipt of NAK
- new mechanisms in rdt2.0 (beyond rdt1.0):
 - error detection
 - receiver feedback: control msgs (ACK,NAK) rcvr->sender

Transport Layer

3-29


rdt2.0: FSM specification(Stop&wait) rdt_send(data) snkpkt = make_pkt(data, checksum) receiver udt_send(sndpkt) rdt rcv(rcvpkt) && isNAK(rcvpkt) Wait for Wait for rdt rcv(rcvpkt) && call from ACK or udt_send(sndpkt) corrupt(rcvpkt) NAK above udt_send(NAK) rdt_rcv(rcvpkt) && isACK(rcvpkt) Wait for call from below sender rdt rcv(rcvpkt) && notcorrupt(rcvpkt) extract(rcvpkt,data) deliver_data(data) udt_send(ACK) Transport Layer 3-30





Stop and Wait

- · source transmits frame
- destination receives frame and replies with acknowledgement (ACK)
- source waits for ACK before sending next
- destination can stop flow by not send ACK
- works well for a few large frames
- Stop and wait becomes inadequate if large block of data is split into small frames



rdt2.0 has a fatal flaw!

What happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate

Handling duplicates:

- sender retransmits current pkt if ACK/NAK garbled
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt


stop and wait

Sender sends one packet, then waits for receiver response


Transport Layer

3-35

rdt2.1: sender, handles garbled ACK/NAKs



Transport Layer




Stop and Wait

- · source transmits single frame
- wait for ACK
- · if received frame damaged, discard it
 - transmitter has timeout
 - if no ACK within timeout, retransmit
- · if ACK damaged,transmitter will not recognize it
 - transmitter will retransmit
 - receive gets two copies of frame
 - use alternate numbering and ACK0 / ACK1

Stop and Wait

- see example with both types of errors
- pros and cons
 - simple
 - inefficient



rdt2.1: discussion

Sender:

- seq # added to pkt
- two seq. #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
 - state must "remember" whether "current" pkt has 0 or 1 seq. #

Receiver:


- must check if received packet is duplicate
 - state indicates whether 0 or1 is expected pkt seq #
- note: receiver can not know if its last ACK/NAK received OK at sender


Transport Layer


rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
 - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

Transport Layer







rdt3.0: channels with errors and loss


New assumption: underlying Approach: sender waits channel can also lose packets (data or ACKs)


checksum, seq. #, ACKs, retransmissions will be of help, but not enough


"reasonable" amount of time for ACK

- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but use of seq. #'s already handles this
 - receiver must specify seq # of pkt being ACKed
- requires countdown timer

Transport Layer







Performance of rdt3.0

- rdt3.0 works, but performance stinks
- example: 1 Gbps link, 15 ms e-e prop. delay, 1KB packet:


$$T_{transmit} = \frac{L \text{ (packet length in bits)}}{R \text{ (transmission rate, bps)}} = \frac{8kb/pkt}{10**9 \text{ b/sec}} = 8 \text{ microsec}$$

O U sender: utilization - fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- o 1KB pkt every 30 msec → 33kB/sec thruput over 1 Gbps link
- o network protocol limits use of physical resources!


Transport Layer 3-49



Pipelined protocols


Pipelining: sender allows multiple, "in-flight", yet-to-beacknowledged pkts

- range of sequence numbers must be increased
- buffering at sender and/or receiver



 Two generic forms of pipelined protocols: go-Back-N, selective repeat

Transport Layer



Go-Back-N

Sender:

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack'ed pkts allowed




- ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
 may receive duplicate ACKs (see receiver)
- timer for each in-flight pkt
- timeout(n): retransmit pkt n and all higher seq # pkts in window

Transport Layer 3-53

GBN: sender extended FSM rdt_send(data) if (nextseqnum < base+N) { sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum) udt_send(sndpkt[nextseqnum]) if (base == nextseqnum) start timer nextseqnum++ else refuse_data(data) base=1 nextseqnum=1 timeout start timer Wait udt_send(sndpkt[base]) udt_send(sndpkt[base+1]) rdt_rcv(rcvpkt) && corrupt(rcvpkt) udt_send(sndpkt[nextseqnum-1]) rdt_rcv(rcvpkt) && notcorrupt(rcvpkt) base = getacknum(rcvpkt)+1 If (base == nextseqnum) stop_timer else start_timer Transport Layer 3-54


GBN: receiver extended FSM



ACK-only: always send ACK for correctly-received pkt with highest *in-order* seq

- may generate duplicate ACKs
- need only remember expectedseqnum
- out-of-order pkt:
 - discard (don't buffer) -> no receiver buffering!
 - Re-ACK pkt with highest in-order seq #


Transport Layer 3-55



Selective Repeat

- receiver individually acknowledges all correctly received pkts
 - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
 - sender timer for each unACKed pkt
- sender window
 - N consecutive seq #'s
 - again limits seq #s of sent, unACKed pkts

Transport Layer



Selective repeat

-sender

data from above :

 if next available seq # in window, send pkt

timeout(n):

· resend pkt n, restart timer

ACK(n) in [sendbase,sendbase+N]:

- · mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seg #

-receiver —

pkt n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt

pkt n in [rcvbase-N,rcvbase-1]

ACK(n)

otherwise:


ignore

Transport Layer

3-59


Selective repeat in action pkt0 sent 0 1 2 3 4 5 6 7 8 9 pkt0 rcvd, delivered, ACKO sent pkt1 sent 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 ▶ pkt1 rovd, delivered, ACK1 sent 0 1 2 3 4 5 6 7 8 9 pkt2 sent 0 1 2 3 4 5 6 7 8 9 pkt3 sent, window full 0 1 2 3 4 5 6 7 8 9 pkt3<u>rcvd</u>, buffered, ACK3 sent 0 1 2 3 4 5 6 7 8 9 ACKO rovd, pkt4 sent 🖊 0 1 2 3 4 5 6 7 8 9 pkt4_rcvd, buffered, ACK4 sent ACK1 rovd, pkt5 sent 🗲 0 1 2 3 4 5 6 7 8 9 pkt5 rcvd, buffered, ACK5 sent 0 1 2 3 4 5 6 7 8 9 pkt2 TIMEOUT, pkt2 resent 0 1 2 3 4 5 6 7 8 9 pkt2 rovd, pkt2,pkt3,pkt4,pkt5 delivered, ACK2 sent 0 1 2 3 4 5 6 7 8 9 ACK3 rovd, nothing sent 0 1 2 3 4 5 6 7 8 9 3-60

sender window receiver window Selective repeat: (after receipt) 0 1 2 3 0 1 2 pkt0 0 1 2 3 0 1 2 pkt1 dilemma 0 1 2 3 0 1 2 pkt2 Example: timeout retransmit pkt0 0 1 2 3 0 1 2 seq #'s: 0, 1, 2, 3 receive packet with seq number 0 window size=3 receiver sees no difference in two sender window receiver window (after receipt) scenarios! (after receipt) 0 1 2 3 0 1 2 pkt0 incorrectly passes 0 1 2 3 0 1 2 pktl duplicate data as new in (a) 0 1 2 3 0 1 Q: what relationship 0 1 2 3 0 1 receive packet with seq number 0 between seq # size and window size? Transport Layer 3-61




Stop and Wait


- · source transmits frame
- destination receives frame and replies with acknowledgement (ACK)
- source waits for ACK before sending next
- destination can stop flow by not send ACK
- works well for a few large frames
- Stop and wait becomes inadequate if large block of data is split into small frames



Sliding Windows Flow Control

- allows multiple numbered frames to be in transit
- receiver has buffer W long
- transmitter sends up to W frames without ACK
- ACK includes number of next frame expected
- sequence number is bounded by size of field (k)
 - frames are numbered modulo 2k
 - giving max window size of up to 2k 1
- receiver can ack frames without permitting further transmission (Receive Not Ready)
- · must send a normal acknowledge to resume
- if have full-duplex link, can piggyback ACks





Error Control

- detection and correction of errors such as:
 - lost frames
 - damaged frames
- · common techniques use:
 - error detection
 - positive acknowledgment
 - retransmission after timeout
 - negative acknowledgement & retransmission

Automatic Repeat Request (ARQ)


- collective name for such error control mechanisms, including:
- stop and wait
- go back N
- selective reject (selective retransmission)

Stop and Wait

- · source transmits single frame
- wait for ACK
- · if received frame damaged, discard it
 - transmitter has timeout
 - if no ACK within timeout, retransmit
- · if ACK damaged, transmitter will not recognize it
 - transmitter will retransmit
 - receive gets two copies of frame
 - use alternate numbering and ACK0 / ACK1

Stop and Wait

- see example with both types of errors
- pros and cons
 - simple
 - inefficient



Go Back N

- · based on sliding window
- · if no error, ACK as usual
- use window to control number of outstanding packet
- if error, reply with rejection
 - discard that packet and all future packet until error packet received correctly
 - transmitter must go back and retransmit that packet and all subsequent packets

Go Back N - Handling


- Damaged Frame
 - error in packet i so receiver rejects packet i
 - transmitter retransmits packets from i
- Lost Frame
 - packet i lost and either
 - transmitter sends i+1 and receiver gets packet i+1 out of seq and rejects packet i
 - or transmitter times out and send ACK with P bit set which receiver responds to with ACK i
 - transmitter then retransmits packets from i

Go Back N - Handling

- Damaged Acknowledgement
 - receiver gets packet i, sends ack (i+1) which is lost
 - acks are cumulative, so next ack (*i*+*n*) may arrive before transmitter times out on frame *i*
 - if transmitter times out, it sends ack with P bit set
 - can be repeated a number of times before a reset procedure is initiated
- Damaged Rejection
 - reject for damaged frame is lost
 - handled as for lost frame when transmitter times out

Selective Reject

- also called selective retransmission
- · only rejected frames are retransmitted
- subsequent frames are accepted by the receiver and buffered
- minimizes retransmission
- · receiver must maintain large enough buffer
- · more complex logic in transmitter
- hence less widely used
- useful for satellite links with long propagation delays



Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- · 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer

3-77

TCP: Overview

RFCs: 793, 1122, 1323, 2018,

 bi-directional data flow in same connection

MSS: maximum segment

handshaking (exchange

of control msgs) init's

· full duplex data:

size

2581

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- pipelined:
 - TCP congestion and flow control set window size
- send & receive buffers


sender, receiver state before data exchange flow controlled:


connection-oriented:



- sender will not overwhelm receiver

Transport Layer






- If the SYN flag is set, then this is the initial sequence number. The sequence number of the actual first data byte will then be this sequence number plus 1.
- If the SYN flag is not set, then this is the sequence number of the first data byte
- Acknowledgement number (32 bits) if the ACK flag is set then the value of this field is the next expected sequence number that the receiver is expecting.
- Data offset (4 bits) specifies the size of the TCP header in 32-bit words.
 The minimum size header is 5 words and the maximum is 15 words thus
 giving the minimum size of 20 bytes and maximum of 60 bytes. This field
 gets its name from the fact that it is also the offset from the start of the TCP
 segment to the actual data.
- Reserved (4 bits) for future use and should be set to zero
- Flags (8 bits) (aka Control bits) contains 8 1-bit flags

- CWR (1 bit) Congestion Window Reduced (CWR) flag is set by the sending host to indicate that it received a TCP segment with the ECE flag set (added to header by RFC 3168).
- ECE (ECN-Echo) (1 bit) indicate that the TCP peer is <u>ECN</u> capable during 3-way handshake (added to header by <u>RFC 3168</u>).
- URG (1 bit) indicates that the URGent pointer field is significant
- ACK (1 bit) indicates that the ACKnowledgment field is significant
- PSH (1 bit) Push function
- RST (1 bit) Reset the connection
- SYN (1 bit) Synchronize sequence numbers
- FIN (1 bit) No more data from sender

- Window (16 bits) the size of the receive window, which specifies the number of bytes (beyond
 the sequence number in the acknowledgment field) that the receiver is currently willing to receive
 (see <u>Flow control</u>)
- Checksum (16 bits) The 16-bit checksum field is used for error-checking of the header and data
- Urgent pointer (16 bits) if the URG flag is set, then this 16-bit field is an offset from the sequence number indicating the last urgent data byte
- Options (Variable bits) the total length of the option field must be a multiple of a 32-bit word and the data offset field adjusted appropriately
- 0 End of options list
- 1 No operation (NOP, Padding)
- 2 Maximum segment size (see <u>maximum segment size</u>)
- 3 Window scale (see window scaling for details)
- 4 Selective Acknowledgement ok (see selective acknowledgments for details)
- 5 -
- 6-
- 7-
- 8 Timestamp (see TCP Timestamps for details)



TCP Round Trip Time and Timeout

- Q: how to set TCP timeout value?
- longer than RTT
 - but RTT varies
- too short: premature timeout
 - unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT

Transport Layer

3-85


TCP Round Trip Time and Timeout

EstimatedRTT = $(1-\alpha)*$ EstimatedRTT + $\alpha*$ SampleRTT

- Exponential weighted moving average
- influence of past sample decreases exponentially fast
- \square typical value: $\alpha = 0.125$ or (1/8)

EstimatedRTT = 0.875*EstimatedRTT + 0.125*SampleRTT

Transport Layer



TCP Round Trip Time and Timeout

Setting the timeout

- EstimtedRTT plus "safety margin"
 - large variation in EstimatedRTT -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

Then set timeout interval:

TimeoutInterval = EstimatedRTT + 4*DevRTT

Transport Layer

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer

3-89

TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
- Pipelined segments
- Cumulative acks
- TCP uses single retransmission timer
- Retransmissions are triggered by:
 - timeout events
 - duplicate acks
- Initially consider simplified TCP sender:
 - ignore duplicate acks
 - ignore flow control, congestion control

Transport Layer

TCP sender events:

data rcvd from app:

- Create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running (think of timer as for oldest unacked segment)
- expiration interval: TimeOutInterval

timeout:

- retransmit segment that caused timeout
- restart timer

Ack rcvd:

- If acknowledges previously unacked segments
 - update what is known to be acked
 - start timer if there are outstanding segments

Transport Layer

3-91

```
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum
loop (forever) {
  switch(event)
  event: data received from application above
      create TCP segment with sequence number NextSeqNum
      if (timer currently not running)
          start timer
      pass segment to IP
      NextSeqNum = NextSeqNum + length(data)
   event: timer timeout
      retransmit not-yet-acknowledged segment with
           smallest sequence number
   event: ACK received, with ACK field value of y
      if (y > SendBase) {
          SendBase = y
         if (there are currently not-yet-acknowledged segments)
              start timer
 } /* end of loop forever */
```


TCP sender


(simplified)

Comment:

- SendBase-1: last cumulatively ack'ed byte Example:
- SendBase-1 = 71;
 y= 73, so the rcvr
 wants 73+;
 y > SendBase, so
 that new data is
 acked

Transport Layer





TCP ACK generation [RFC 1122, RFC 2581]

Event at Receiver	TCP Receiver action		
Arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	Delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK		
Arrival of in-order segment with expected seq #. One other segment has ACK pending	Immediately send single cumulative ACK, ACKing both in-order segments		
Arrival of out-of-order segment higher-than-expect seq. # . Gap detected	Immediately send <i>duplicate ACK</i> , indicating seq. # of next expected byte		
Arrival of segment that partially or completely fills gap	Immediate send ACK, provided that segment startsat lower end of gap		
	Transport Layer 3-9		

Fast Retransmit

- Time-out period often relatively long:
 - long delay before resending lost packet
- Detect lost segments via duplicate ACKs.
 - Sender often sends many segments back-to-back
 - If segment is lost, there will likely be many duplicate ACKs.
- If sender receives 3
 ACKs for the same data, it supposes that segment after ACKed data was lost:
 - <u>fast retransmit:</u> resend segment before timer expires

Transport Layer

Fast retransmit algorithm:

```
event: ACK received, with ACK field value of y

if (y > SendBase) {
    SendBase = y
    if (there are currently not-yet-acknowledged segments)
        start timer
    }
    else {
        increment count of dup ACKs received for y
        if (count of dup ACKs received for y = 3) {
            resend segment with sequence number y
        }

a duplicate ACK for
already ACKed segment
```

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP

Transport Layer


- segment structure
- reliable data transfer
- flow control
- connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer

3-98

TCP Flow Control

 receive side of TCP connection has a receive buffer:



 app process may be slow at reading from buffer flow control


sender won't overflow receiver's buffer by transmitting too much, too fast

speed-matching service: matching the send rate to the receiving app's drain rate

Transport Layer

3-99

TCP Flow control: how it works



(Suppose TCP receiver discards out-of-order segments)

- spare room in buffer
- = RcvWindow
- = RcvBuffer-[LastByteRcvd LastByteRead]

- Rcvr advertises spare room by including value of RcvWindow in segments
- Sender limits unACKed data to RcvWindow
 - guarantees receive buffer doesn't overflow

Transport Layer

3-

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer

3-101

TCP Connection Management

Recall: TCP sender, receiver establish "connection" before exchanging data segments

- · initialize TCP variables:
 - seq. #s
 - buffers, flow control info (e.g. RcvWindow)
- client: connection initiator
 Socket clientSocket = new
 Socket("hostname", "port
 number");
- server: contacted by client socket connectionSocket = welcomeSocket.accept();

Three way handshake:

Step 1: client host sends TCP SYN segment to server

- specifies initial seq #
- no data


<u>Step 2:</u> server host receives SYN, replies with SYNACK segment


- server allocates buffers
- specifies server initial seq. #


Step 3: client receives SYNACK, replies with ACK segment, which may contain data

Transport Layer

3-







Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer


Principles of Congestion Control

Congestion:

- informally: "too many sources sending too much data too fast for *network* to handle"
- · different from flow control!
- · manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- a top-10 problem!


Transport Layer


ა-<u>სე</u>z




Causes/costs of congestion: scenario 2 one router, finite buffers sender retransmission of lost packet Host A Ain: original data, plus retransmitted data finite shared output link buffers

Transport Layer







Approaches towards congestion control

Two broad approaches towards congestion control:

End-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

Network-assisted congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate sender should send at

Transport Layer

3-

Case study: ATM ABR congestion control

ABR: available bit rate:

- · "elastic service"
- if sender's path "underloaded":
 - sender should use available bandwidth
- if sender's path congested:
 - sender throttled to minimum guaranteed rate


RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
 - NI bit: no increase in rate (mild congestion)
 - Cl bit: congestion indication
- RM cells returned to sender by receiver, with bits intact

Transport Layer

3-

Case study: ATM ABR congestion control



- · two-byte ER (explicit rate) field in RM cell
 - congested switch may lower ER value in cell
 - sender' send rate thus maximum supportable rate on path
- EFCI bit in data cells: set to 1 in congested switch
 - if data cell preceding RM cell has EFCI set, sender sets CI bit in returned RM cell

Transport Layer

3-115

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer
- 3.5 Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport Layer

3-

TCP congestion control: additive increase, multiplicative decrease Approach: increase transmission rate (window size), probing for usable bandwidth, until loss occurs additive increase: increase CongWin by 1 MSS every RTT until loss detected multiplicative decrease: cut CongWin in half after loss congestion window 4 Kbytes 16 Kbytes Saw tooth behavior: probing for bandwidth 8 Kbytes Transport Layer 3117

TCP Congestion Control: details

- sender limits transmission:
 LastByteSent-LastByteAcked
 ≤ CongWin
- Roughly,

rate =
$$\frac{CongWin}{RTT}$$
 Bytes/sec

 CongWin is dynamic, function of perceived network congestion

<u>How does sender</u> <u>perceive congestion?</u>

- loss event = timeout or 3 duplicate acks
- TCP sender reduces rate (CongWin) after loss event

three mechanisms:

- AIMD
- slow start
- conservative after timeout events

Transport Layer

TCP Slow Start

- When connection begins,
 Congwin = 1 MSS
 - Example: MSS = 500 bytes& RTT = 200 msec
 - initial rate = 20 kbps
- available bandwidth may be >> MSS/RTT
 - desirable to quickly ramp up to respectable rate


 When connection begins, increase rate exponentially fast until first loss event

Transport Layer

3-


TCP Slow Start (more)

- When connection begins, increase rate exponentially until first loss event:
 - double Congwin every RTT
 - done by incrementing CongWin for every ACK received
- <u>Summary:</u> initial rate is slow but ramps up exponentially fast



Refinement

- Q: When should the exponential incresswitch to linear?
- A: When Congwin (to 1/2 of its value before timeout.



Implementation:

- · Variable Threshoid
- At loss event, Threshold is set to 1/2 of CongWin just before loss event

Transport Layer

3-

Refinement: inferring loss

- · After 3 dup ACKs:
 - CongWin is cut in half
 - window then grows linearly
- But after timeout event:
 - CongWin instead set to 1 MSS;
 - window then grows exponentially
 - to a threshold, then grows linearly

- Philosophy: –

- 3 dup ACKs indicates network capable of delivering some segments
 timeout indicates a
- "more alarming"
 congestion scenario

Transport Layer

3-

Summary: TCP Congestion Control

- When CongWin is below Threshold, sender in slow-start phase, window grows exponentially.
- When CongWin is above Threshold, sender is in congestion-avoidance phase, window grows linearly.
- When a triple duplicate ACK occurs, Threshold set to CongWin/2 and CongWin set to Threshold.
- When timeout occurs, Threshold set to CongWin/2 and CongWin is set to 1 MSS.

Transport Layer

123

TCP sender congestion control

State	Event	TCP Sender Action	Commentary
Slow Start (SS)	ACK receipt for previously unacked data	CongWin = CongWin + MSS, If (CongWin > Threshold) set state to "Congestion Avoidance"	Resulting in a doubling of CongWin every RTT
Congestion Avoidance (CA)	ACK receipt for previously unacked data	CongWin = CongWin+MSS * (MSS/CongWin)	Additive increase, resulting in increase of CongWin by 1 MSS every RTT
SS or CA	Loss event detected by triple duplicate ACK	Threshold = CongWin/2, CongWin = Threshold, Set state to "Congestion Avoidance"	Fast recovery, implementing multiplicative decrease. CongWin will not drop below 1 MSS.
SS or CA	Timeout	Threshold = CongWin/2, CongWin = 1 MSS, Set state to "Slow Start"	Enter slow start
SS or CA	Duplicate ACK	Increment duplicate ACK count for segment being acked	CongWin and Threshold not changed

Transport Layer

24

TCP throughput

- What's the average throughout of TCP as a function of window size and RTT?
 - Ignore slow start
- Let W be the window size when loss occurs.
- When window is W, throughput is W/RTT
- Just after loss, window drops to W/2, throughput to W/2RTT.
- Average throughout: .75 W/RTT

Transport Layer

3-125

TCP Futures: TCP over "long, fat pipes"

- Example: 1500 byte segments, 100ms RTT, want 10 Gbps throughput
- Requires window size W = 83,333 in-flight segments
- Throughput in terms of loss rate:

$$\frac{1.22 \cdot MSS}{DTT \sqrt{I}}$$


- \rightarrow L = 2·10⁻¹⁰ Wow^{RTT} \sqrt{L}
- New versions of TCP for high-speed

Transport Layer

3-

TCP Fairness

Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K




Transport Layer

3-127

Why is TCP fair?

Two competing sessions:

- Additive increase gives slope of 1, as throughout increases
- · multiplicative decrease decreases throughput proportionally



Transport Layer

Fairness (more)

Fairness and UDP

- Multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- Instead use UDP:
 - pump audio/video at constant rate, tolerate packet loss
- Research area: TCP friendly

<u>Fairness and parallel TCP</u> <u>connections</u>

- nothing prevents app from opening parallel connections between 2 hosts.
- Web browsers do this
- Example: link of rate R supporting 9 connections;
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2!

Transport Layer

3-120

Chapter 3: Summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation and implementation in the Internet
 - UDP
 - TCP

Next:

- leaving the network "edge" (application, transport layers)
- · into the network "core"

Transport Layer

3-