# **LAB 04**

# Working with Data related Operator and Directives, Addressing



Syed Muhammad Faheem STUDENT NAME  $\frac{20\text{K-}1054}{\text{ROLL NO}}$ 

3<u>E</u> SEC

LAB ENGINEER'S SIGNATURE & DATE

## MARKS AWARDED: /

NATIONAL UNIVERSITY OF COMPUTER AND EMERGING SCIENCES (NUCES), KARACHI

Prepared by: Qurat ul ain & Rabia Ansari

#### Lab Session 04: Working with Data Related Operators and Directives, Addressing

#### **OBJECTIVES:**

- Observing effect of Arithmetic Instructions on Flag Register
- Direct-offset operands
- OFFSET operator
- PTR operator
- TYPE operator
- LENGTHOF operator
- SIZEOF operator
- Indirect operands
- Indexed operands

#### **Effect of Arithmetic Instructions on Flag Registers**

- Status flags are updated to indicate certain properties of the result
- Once a flag is set, it remains in that state until another instruction that affects the flags is executed

#### **Z-Zero Flag:**

The Zero flag is set when the result of an operation produces zero in the destination operand.

```
mov cx,1
sub cx,1 ; CX = 0, ZF = 1
mov ax,0FFFFh
inc ax ; AX = 0, ZF = 1
inc ax ; AX = 1, ZF = 0
```

#### Remember...

- A flag is set when it equals 1.
- A flag is clear when it equals 0.

#### C-Carry Flag:



This flag is set, when there is a carry out of MSB in case of addition and borrow in case of subtraction.

The Carry flag is set when the result of an operation generates an unsigned value that is out of range (too big or too small for the destination operand).

```
mov al, 0FFh
add al,1 ; CF = 1, AL = 00
; Try to go below zero:

mov al, 0
sub al, 1 ; CF = 1, AL = FF
```

#### S-Sign Flag:

This flag indicates the sign of the result of an operation. A 0 for positive number and 1 for a negative number.

mov	AL, 15	mov	AL,15
add	AL,97	sub	AL,97
clears the sign flag as		sets the sign flag as	
the result is 112		the result is -82	
(or 0111000 in binary)		(or 10101110 in binary)	

#### AC-Auxilary Carry Flag:

This flag is set, if there is a carry from the lowest nibble, i.e., bit three during addition, or borrow for the lowest nibble, i.e. bit three, during subtraction.

Suppose we add 1 to 0Fh. The sum (10h) contains a 1 in bit position 4 that was carried out of bit position 3:

```
mov al,0Fh add al,1 ; AC = 1
```

#### P Parity Flag:

The Parity flag (PF) is set when the least significant byte of the destination has an even number of 1 bits. The following ADD and SUB instructions alter the parity of AL:

```
mov al,10001100b

add al,00000010b ; AL = 10001110, PF = 1

sub al,10000000b ; AL = 00001110, PF = 0
```



#### O-Over flow Flag:

The Overflow flag is set when the result of a signed arithmetic operation over-flows or underflows the destination operand. For example, the largest possible integer signed byte value is +127; adding 1 to it causes overflow:

```
mov al,+127
add al,1 ; OF = 1
```

Similarly, the smallest possible negative integer byte value is 128. Subtracting 1 from it causes underflow. The destination operand value does not hold a valid arithmetic result, and the Over- flow flag is set:

#### **Direct-offset Operands:**

You can add a displacement to the name of a variable, creating a direct-offset operand. <u>Example:</u> .data

```
arrayB BYTE
10h,20h,30h,40h,50h arrayW WORD
100h,200h,300h

.code

mov al,arrayB ; AL = 10h
mov al farrayB+11 ; AL = 20h
```

 $\begin{array}{lll} \text{mov al,} [\text{arrayB+1}] & ; \text{AL} = 20\text{h} \\ \text{mov ax,arrayW} & ; \text{AX} = 100\text{h} \\ \text{mov ax,} [\text{arrayW+2}] & ; \text{AX} = 200\text{h} \end{array}$ 

Similarly, the second element in a doubleword array is 4 bytes beyond the first one.

#### **DATA-RELATED OPERATORS AND DIRECTIVES**

#### **OFFSET Operator:**



The OFFSET operator returns the offset of a data label.

#### Syntax:

MOV reg32, OFFSET mem ; reg32 points to count

#### Example:

```
.data bVal BYTE ?
wVal WORD ?
dVal DWORD
? dVal2
DWORD ?

If bVal is located at offset 00404000h, we would get:
mov esi, OFFSET bval ; ESI = 00404000
```

mov esi, OFFSET dVal ; ESI = 00404000mov esi, OFFSET dVal ; ESI = 00404003mov esi, OFFSET dVal2 ; ESI = 00404003

#### PTR Operator:

We can use the PTR operator to override the declared size of an operand. Note PTR must be used in combination with one of the standard assembler data types.

**For example**, that we would like to move the lower 16 bits of a doubleword variable named myDouble into AX. The assembler will not permit the following move because the operand sizes do not match:

```
.data
myDouble DWORD 12345678h
.code
mov ax, myDouble ; error
```

But the WORD PTR operator makes it possible to move the low-order word (5678h) to AX:

```
mov ax, word ptr myDouble ; AX = 5678H and higher word (1234h) to AX: mov dx, word ptr myDouble+2 ; DX = 1234H
```



#### **Moving Smaller Values into Larger Destinations**

We might want to move two smaller values from memory to a larger destination operand. In the next example, the first word is copied to the lower half of EAX and the second word is copied to the upper half.

The DWORD PTR operator makes this possible:

```
.data

wordList WORD 5678h, 1234h

.code

mov eax, DWORD PTR wordList ; EAX = 12345678h
```

#### **TYPE Operator:**

The TYPE operator returns the size, in bytes, of a single element of a variable.

#### Syntax:

```
MOV reg16, TYPE mem

Example 1:

.data
```

```
var1 BYTE ? ; TYPE var1 = 1
var2 WORD ? ; TYPE var2 =
2 var3 DWORD ? ; TYPE var3 =
4 var4 QWORD ? ; TYPE var4 = 8
```

#### Example 2:

```
.data
var1 BYTE 20h var2
WORD 1000h
var3 DWORD ?
var4 BYTE 10, 20, 30, 40, 50
msg BYTE 'File not found', 0
.code
mov ax, type var1 ; AX = 0001
mov ax, type var2 ; AX = 0002
```



```
mov ax, type var3 ; AX = 0004
mov ax, type var4 ; AX = 0001
mov ax, type msg ; AX = 0001
```

#### **LENGTHOF Operator:**

The LENGTHOF operator counts the number of individual elements in a variable that has been defined using DUP.

#### Syntax:

MOV reg16, LENGTHOF mem

#### Example:

```
.data
val1 WORD 1000h val2 SWORD
10, 20, 30 array WORD 10
DUP(?),0 array2 WORD 5 DUP(3
DUP(0)) message BYTE 'File not
found', 0

.code
mov ax, LENGTHOF val1 ; AX = 1 mov
ax, LENGTHOF val2 ; AX = 3 mov ax, LENGTHOF
array ; AX = 11 mov ax, LENGTHOF array2 ; AX = 15
mov ax, LENGTHOF message ; AX = 15 SIZEOF
Operator:
```

The SIZEOF operator returns the number of bytes an array takes up. It is similar in effect to multiplying LENGTHOF with TYPE.

#### Syntax:

MOV reg16/32, SIZEOF mem

#### Example:

```
.data
intArray WORD 32 DUP(0)
.code
mov eax,SIZEOF intArray ; EAX = 64
```



#### **Indirect Operands**

In protected mode, an indirect operand can be any 32-bit general-purpose register (EAX, EBX, ECX, EDX, ESI, EDI, EBP, and ESP) surrounded by brackets. The register is assumed to contain the address of some data.

#### Example:

```
.data
byteVal BYTE 10h
.code
mov esi,OFFSET byteVal
mov al,[esi]; AL = 10h
```

If the destination operand uses indirect addressing, a new value is placed in memory at the location pointed to by the register. mov [esi],bl

Using PTR with Indirect Operands

```
inc [esi] ; error: operand must have size
```

The assembler does not know whether ESI points to a byte, word, doubleword, or some other size. The PTR operator confirms the operand size: inc BYTE PTR [esi]

#### **Arrays**

Indirect operands are ideal tools for stepping through arrays.

#### Example:

```
.data
```

arrayB BYTE 10h,20h,30h

.code

mov esi,OFFSET arrayB

mov al,[esi]; AL = 10h

inc esi

mov al, [esi]; AL = 20h

If we use an array of 16-bit integers, we add 2 to ESI to address each subsequent array element.



.data
arrayW WORD 1000h,2000h,3000h
.code
mov esi,OFFSET arrayW mov
ax,[esi]; AX = 1000h
add esi,2
mov ax,[esi]; AX = 2000h



If we use an array of 32-bit integers, we add 4 to ESI to address each subsequent array element.

#### **Indexed Operands**

An indexed operand adds a constant to a register to generate an effective address. Any of the 32-bit general-purpose registers may be used as index registers.

```
SYNTAX:
```

```
constant [reg32] ; reg32 can be any of the 32-bit general registers
```

```
[ constant + reg32 ]
```

#### **EXAMPLE:**

.data

```
arrayB BYTE 20, 40, 60, 80
```

```
.code mov esi, 1
```

mov al, arrayB[esi]

inc esi

mov al, arrayB[esi]

mov esi, 3 mov al,

[arrayB + esi]

Adding Displacements: The second type of indexed addressing combines a register with a constant offset. The index register holds the base address of an array.

#### INCLUDE Irvine32.inc

.data

arrayW WORD 1000h,2000h,3000h

.code

main PROC

mov eax,0

mov ebx,0

mov ecx,0 mov



```
esi,OFFSET
arrayW mov
ax,[esi]; AX =
1000h mov
bx,[esi+2]; AX
= 2000h mov
cx,[esi+4]; AX
= 3000h
```

#### **Scale Factors in Indexed Operands**

Indexed operands must take into account the size of each array element when calculating offsets.

```
SYNTAX:

constant [ reg32 * TYPE constant]

EXAMPLE:

INCLUDE Irvine32.inc

.data

arrayW WORD 1000h, 2000h, 3000h, 4000h

.code

main PROC

mov eax,0 mov

ebx,0 mov

ecx,0 mov esi,

1

mov ax, arrayW[esi * TYPE arrayW]

mov esi, 2
```

```
mov bx, arrayW[esi * TYPE arrayW]
mov esi, 3
mov cx, arrayW[esi * TYPE arrayW]
call DumpRegs
```

#### **Exercises:**

- 1. Declare a 32-bit signed integer val1 and initialize it with the eight thousand. If val1 is incremented by 1 using the ADD instruction, what will be the values of the Carry and Sign flags?
- 2. Write down the values of the Carry, Sign, Zero, and Overflow flags after each instruction has executed:

```
mov ax,7FF0h add al,10h ; a. CF = SF = ZF = OF = add ah,1 ; b. CF = SF = ZF = OF = add ax,2 ; c. CF = SF = ZF = OF =
```

- 3. Initialize a double word array consisting of elements 8, 5, 1, 2, 6. Sort the given array in ascending order directly with the help of registers. Use direct-offset addressing to access the elements.
- 4. Use following array declarations:

```
arrayB BYTE 10, 20, 30 arrayW WORD 150, 250, 350 arrayD DWORD 600, 1200, 1800
```

Now initialize three double word variables SUM1, SUM2, SUM3 and perform following operations (expressed in pseudo-code here):

```
SUM1 = arrayB[0] + arrayW[0] + arrayD[0] SUM2 = arrayB[1] + arrayW[1] + arrayD[1] SUM3 = arrayB[2] + arrayW[2] + arrayD[2]
```

5. Initialize two arrays:



array1 BYTE 10, 20, 30, 40 array2 BYTE 4 DUP (?)

Copy elements of array1 into array2 in reverse order using either indirect addressing or direct-offset addressing.

- 6. Subtract an array of 5 doublewords using indirect operands.
- 7. Use following array declarations:

)

arrayB BYTE 60, 70, 80 arrayW

WORD 150, 250, 350


arrayD DWORD 600, 1200, 1800

For each array, add its 1st and last element using scale factors and display the result in a separate register.



## **COAL Lab 4 Tasks**

### **Task # 1:**



## Task # 2:

```
Registers
 EAX = 00CF7FF0 EBX = 00A88000 ECX = 00FC1005 EDX = 00FC1005
 OV = 0 UP = 0 EI = 1 PL = 0 ZR = 1 AC = 0 PE = 1 CY = 0
Memory 1 Memory 2 Registers Processes Modules
Task 3.asm → X
          include Irvine32.inc
          .model small
          .stack 100h
          .data
          val1 DWORD 8000h
          .code
          main proc
          mov ax,7FF0h
          add al,10 ≤1ms elapsed
     10
          add ah,1
     11
          add ax,2
     12
          invoke exitprocess,0
     13
          main endp
          end main
```

```
Registers
 EAX = 00CF7FFA EBX = 00A88000 ECX = 00FC1005 EDX = 00FC1005
 OV = 0 UP = 0 EI = 1 PL = 1 ZR = 0 AC = 0 PE = 1 CY = 0
132 %
Memory 1 Memory 2 Registers Processes Modules
Task 3.asm     ⊅     X
           include Irvine32.inc
      2
           .model small
           .stack 100h
           .data
           val1 DWORD 8000h
           .code
          main proc
      8
          mov ax,7FF0h
      9
           add al,10
          add ah,1 ≤1ms elapsed
     10
           add ax,2
     11
           invoke exitprocess,0
     12
           main endp
     13
           end main
     14
```

```
Registers
 EAX = 00CF80FA EBX = 00A88000 ECX = 00FC1005 EDX = 00FC1005
 OV = 1 UP = 0 EI = 1 PL = 1 ZR = 0 AC = 1 PE = 0 CY = 0
132 %
Memory 1 Memory 2 Registers Processes Modules
Task 3.asm     ⊅     X
           include Irvine32.inc
           .model small
           .stack 100h
           .data
          val1 DWORD 8000h
           .code
          main proc
      8
          mov ax,7FF0h
      9
          add al,10
     10
         add ah,1
          add ax,2 ≤1ms elapsed
     11
          invoke exitprocess,0
     12
     13
          main endp
          end main
     14
```

```
Registers
 EAX = 00CF80FC EBX = 00A88000 ECX = 00FC1005 EDX = 00FC1005
 OV = 0 UP = 0 EI = 1 PL = 1 ZR = 0 AC = 0 PE = 1 CY = 0
132 %
Memory 1 Memory 2 Registers Processes Modules
Task 3.asm     ⊅     X
           include Irvine32.inc
           .model small
           .stack 100h
           .data
          val1 DWORD 8000h
          .code
          main proc
          mov ax,7FF0h
          add al,10
          add ah,1
     11
          add ax,2
          invoke exitprocess,0 ≤1ms elapsed
     12
     13
          main endp
     14
          end main
```

## Task # 3:

```
include Irvine32.inc
    .model small
    .stack 100h
    .data
    array DWORD 8,5,1,2,6
    .code
    main proc
                                     Microsoft Visual Studio Debug Console
    mov eax,array
                                    +8
    call WriteInt
                                    +5
    call Crlf
                                    +1
    mov eax,array+4
    call WriteInt
                                    +2
                                    +6
    call Crlf
    mov eax,array+8
    call WriteInt
                                    1
    call Crlf
                                    2
    mov eax,array+12
    call WriteInt
                                    6
19
    call Crlf
                                    8
    mov eax,array+16
                                   C:\Users\Faheem\source\repos\Lab 1\Debug\Lab 1.exe (process 2214
    call WriteInt
                                    Press any key to close this window . . .
    call Crlf
    call Crlf
    mov eax,[array+8]
    mov ebx,[array]
    mov array,eax
    mov [array+8],ebx
    mov eax,[array+8]
    mov ebx,[array+16]
    mov [array+16],eax
    mov [array+8],ebx
    mov eax,[array+4]
    mov ebx,[array+8]
    mov [array+8],eax
    mov [array+4],ebx
    mov eax,[array+4]
    mov ebx,[array+12]
    mov [array+12],eax
    mov [array+4],ebx
    mov eax, array
    call WriteDec
    call Crlf
    mov eax,[array+4]
call WriteDec
    call Crlf
    mov eax,[array+8]
    call WriteDec
    call Crlf
    mov eax,[array+12]
    call WriteDec
    call Crlf
    mov eax,[array+16]
    call WriteDec
    invoke exitprocess,0
    main endp
    end main
```

## **Task # 4:**

```
include Irvine32.inc
     .model small
     .stack 100h
     .data
     arrayB BYTE 10,20,30
                                     Microsoft Visual Studio Debug Console
                                                                                    arrayW WORD 150,250,350
                                     +760
     arrayDW DWORD 600,1200,1800
                                     +1470
                                     +2180
     SUM1 DWORD ?
                                     C:\Users\Faheem\source\repos\Lab 1\Debug\Lab 1.exe (p
     SUM2 DWORD ?
                                     rocess 19512) exited with code 0.
     SUM3 DWORD ?
                                     Press any key to close this window . . .
     .code
12
    main proc
     mov eax,0
     mov al, arrayB
     add ax,arrayW
    add eax,arrayDW
17
    mov SUM1,eax
    mov eax,0
    mov al,[arrayB+1]
     add ax,[arrayW+2]
     add eax,[arrayDW+4]
    mov SUM2,eax
    mov eax,0
    mov al,[arrayB+2]
     add ax,[arrayW+4]
     add eax,[arrayDW+8]
27
    mov SUM3,eax
    mov eax, SUM1
     call WriteInt
    call Crlf
    mov eax, SUM2
     call WriteInt
33
    call Crlf
    mov eax, SUM3
    call WriteInt
    invoke exitprocess,0
     main endp
     end main
```



## **Task # 5:**

```
include Irvine32.inc
.model small
.stack 100h
.data
array1 BYTE 10, 20, 30, 40
array2 BYTE 4 DUP (?)
                                                                           Microsoft Visual Studio Debug Console
.code
                            +40
main proc
                            +30
+20
mov al,array1+3
                            +10
mov array2,al
                            C:\Users\Faheem\source\repos\Lab 1\Debug\Lab 1.exe (pr
mov al, array1+2
                            ocess 16844) exited with code -2147483645.
Press any key to close this window . . .
mov array2+1,al
mov al,array1+1
mov array2+2,al
mov al, array1
mov array2+3,al
mov eax,0
mov al, array2
call WriteInt
call Crlf
mov eax,0
mov al, array2+1
call WriteInt
call Crlf
mov eax,0
mov al,array2+2
call WriteInt
call Crlf
mov eax,0
mov al,array2+3
call WriteInt
main endp
end main
```

## Task # 6:

```
include Irvine32.inc
.model small
.stack 100h
.data
array DWORD 8,5,1,2,6
.code
main proc
mov esi,offset array
                          Microsoft Visual Studio Debug Console
add esi,4
mov eax,[esi]
                          +4
sub array,eax
                          +5
mov eax, array
call WriteInt
                         C:\Users\Faheem\source\repos\Lab 1\Debug\Lab 1.exe (process 29356) exited with code 0.
                         Press any key to close this window . . .
call Crlf
add esi,4
mov eax,[esi]
sub array+4,eax
mov eax,array+4
call WriteInt
call Crlf
mov eax,[esi]
sub array+12,eax
mov eax,array+12
call WriteInt
call Crlf
add esi,4
mov eax,[esi]
sub array+16,eax
mov eax,array+16
call WriteInt
call Crlf
invoke exitprocess,0
main endp
end main
```

## Task # 7:

