VISHNU - Le guide de l'administrateur



COLLABORATORS

	TITLE : VISHNU - Le guide de	l'administrateur	
ACTION	NAME	DATE	SIGNATURE
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	September 4, 2012	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
1	08/03/2011	Version initiale pour le module UMS uniquement	K. COULOMB
2	18/03/2011	Ajout du lancement manuel avec forwarder et d'image de fichiers de configuration exemple	K. COULOMB
3	22/03/2011	Ajout des web services	K. COULOMB
4	11/05/2011	Réécriture du lancement avec fichier de configuration. Ajout d'un paragraphe pour le sendmail. Ajout de l'administration de TMS.	K. COULOMB, B.ISNARD
5	18/05/2011	Ajout du parametre de configuration dbConnectionsNb.	B.ISNARD
6	10/06/2011	Documentation pour IMS.	K.COULOMB
7	15/06/2011	Documentation pour FMS.	I.CISSE
8	22/06/2011	Ajout de l'option ENABLE_SWIG.	B.ISNARD
9	24/06/2011	Ajout de l'option vishnuMachineld dans les fichiers de configuration de UMS, IMS et FMS.	I.CISSE

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
10	13/07/2011	Mise à jour du document suites aux premiers retours .	K.COULOMB
11	11/08/2011	Prise en compte du gestionnaire de resources SLURM	D.TRAORE
12	23/08/2011	Ajout d'un lien sur des sites expliquant comment installer une base de données postgresql/mysql. Suppression des informations de mise à jour de la base (maintenant le script de création contient tout). Ajout d'une référence vers 'VISHNU_API'	K.COULOMB
13	14/12/2011	Mise à j <mark>our pou</mark> r l <mark>es no</mark> uveaux forwarder de DIET.	K.COULOMB
14	15/12/2011	Mise à jour de la section configuration des clés ssh requises pour FMS.	I.CISSE
15	16/12/2011	Ajout de la section configuration des clés ssh requises pour TMS.	D.TRAORE
16	30/01/2012	Modifie les requirements en fonction de la version de DIET	K. COULOMB
17	27/02/2012	Liste les libs de boost nécessaire	K. COULOMB
18	02/03/2012	Prise en compte du gestionnaire de resources LSF	D.TRAORE
19	22/03/2012	Ajout pour le support de LDAP	K. COULOMB
20	11/04/2012	Prise en compte du gestionnaire de resources Grid Engine	E. PAMBA CAPO-CHICHI
21	30/05/2012	Ajout des versions de LoadLeveler, GLIBC pour libcrypt et ssh	E. PAMBA CAPO-CHICHI
22	27/08/2012	Nouvelle compilation avec les batchs	K. COULOMB

Contents

1	Prés	sentation du document	1
	1.1	Objectifs du document	
	1.2	Structure du document	1
2	Défi	nitions	2
	2.1	Acronymes	2
	2.2	Références	2
	2.3	Glossaire	2
3	Inst	allation à partir des sources	4
	3.1	Objectifs	4
	3.2	Prérequis	4
	3.3	Compilation des sources	5
4	Con	figuration de la base de données	7
	4.1	Utilisation d'une base de données PostGreSQL	7
	4.2	Utilisation d'une base de données MySQL	7
	4.3	Utilisation de LDAP	7
5	Inst	allation des web services	9
	5.1	Pré-requis	9
	5.2	Installation de JBoss	9
	5.3	Installation des modules WS dans JBoss	10
		5.3.1 Fichiers à installer	10
		5.3.2 Variables d'environnement à définir	10
		5.3.3 Lancement du serveur JBoss avec le module WS	10
6	Dép	loiement de VISHNU	11
	6.1	Lancement sur un même réseau	11
	6.2	Lancement sur plusieurs réseaux avec une version de DIET supérieure ou égale à 2.8	13
	6.3	Lancement sur plusieurs réseaux avec une version de DIET inférieure à 2.8	14
	6.4	Exemple de fichier de configuration d'un MA	16

	6.5	Exemple de fichier de configuration pour un SeD DIET	
	6.6	Exemple de fichier de configuration d'un SeD UMS	16
	6.7	Exemple de fichier de configuration d'un SeD TMS	17
	6.8	Exemple de fichier de configuration d'un SeD FMS	17
	6.9	Exemple de fichier d'un forwarder	17
	6.10	Exemple de fichier du LogCentral	18
	6.11	Configuration de l'envoi des emails par VISHNU	18
	6.12	Configuration des clés privées/publiques ssh requises pour FMS	18
	6.13	Configuration des clés privées/publiques ssh requises pour TMS	19
	6.14	Test d'exécution d'un service depuis une machine client par shell	19
_			••
7		ninistration	20
	7.1	Présentation	
	7.2	Gestion des utilisateurs (UMS)	
	7.3	Gestion des machines (UMS+IMS)	
	7.4	Gestion de la plateforme (UMS)	
	7.5	Options propres à l'administrateur dans les commandes utilisateurs(UMS+FMS)	
	7.6	Gestion des processus VISHNU et délestage (IMS)	
	7.7	Surveillance de l'état des machines (IMS)	22
	7.8	Définition des formats des identifian <mark>ts (IMS</mark>)	22
8	IIMS	S Command reference	24
U	8.1	vishnu_add_user	
	8.2	vishnu_update_user	
	8.3	vishnu_delete_user	
	8.4	vishnu reset password	
	8.5	vishnu_save_configuration	
	8.6	vishnu_restore_configuration	
	8.7	vishnu_add_machine	
		vishnu_update_machine	
	8.8	vishnu_delete_machine	
	8.9		
		vishnu_list_users	
		vishnu_configure_default_option	
		vishnu_add_auth_system	
		vishnu_update_auth_system	
	8.14	vishnu_delete_auth_system	39

9	UMS	S C++ API Reference	41
	9.1	addUser	41
	9.2	updateUser	42
	9.3	deleteUser	43
	9.4	resetPassword	43
	9.5	saveConfiguration	44
	9.6	restoreConfiguration	45
	9.7	addMachine	46
	9.8	updateMachine	46
	9.9	deleteMachine	47
	9.10	listUsers	48
	9.11	configureDefaultOption	49
	9.12	addAuthSystem	50
		updateAuthSystem	
	9.14	deleteAuthSystem	51
10		S Python API Reference	53
		VISHNU.addUser	
		VISHNU.updateUser	
		VISHNU.deleteUser	
		VISHNU.resetPassword	
		VISHNU.saveConfiguration	
	10.6	VISHNU.restoreConfiguration	57
		VISHNU.addMachine	
	10.8	VISHNU.updateMachine	59
	10.9	VISHNU.deleteMachine	60
	10.10	OVISHNU.listUsers	61
	10.11	VISHNU.configureDefaultOption	62
	10.12	2VISHNU.addAuthSystem	63
	10.13	3VISHNU.updateAuthSystem	64
	10.14	VISHNU.deleteAuthSystem	65
	TMC		
11		Command reference	67
		vishnu_get_processes	67
		vishnu_set_system_info	
			69
			69
		vishnu_define_user_identifier	
	11.6	vishnu_define_machine_identifier	71

11.8 vishnu_deline_transfer_identifier 73 11.9 vishnu_deline_auth_identifier 74 11.10vishnu_load_shed 75 11.11vishnu_set_update_frequency 76 11.11vishnu_set_update_frequency 77 11.13vishnu_restart 78 11.14vishnu_deline_work_identifier 79 12 IMS C++ API Reference 81 12.1 getProcesses 81 12.2 setSystemInfo 81 12.3 setSystemThreshold 82 12.4 getSystemThreshold 83 12.5 defineUserIdentifier 84 12.6 defineMachineIdentifier 84 12.7 defineIobldentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10badShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13. VISHNU_setSystemInfo 91 13.3 VISHNU_setSystemInfo 91 13.4 VISHNU_defineCoblemtifier 93 13.5 VISHNU_defineCoblemtifier 94 1		11.7 vishnu_define_job_identifier	72
11.10vishnu_load_shed 75 11.11vishnu_set_update_frequency 76 11.12vishnu_tstop 77 11.13vishnu_restart 78 11.14vishnu_define_work_identifier 78 11.14vishnu_define_work_identifier 81 12. IMS C++ API Reference 81 12.1 getProcesses 81 12.2 setSystemInfo 81 12.3 setSystemThreshold 82 12.4 gctSystemThreshold 83 12.5 defineUserIdentifier 83 12.6 defineAdhineIdentifier 84 12.7 defineJobIdentifier 84 12.8 defineAuthIdentifier 86 12.9 defineAuthIdentifier 86 12.1 setUpdateFrequency 87 12.12stop 88 12.11setUpdateFrequency 87 12.12stop 88 13.1 VISHNU.getProcesses 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.getProcesses 90 13.3 VISHNU.getProcesses 90 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineUserIdentifier 93 13.7 VISHNU.defineUserId		11.8 vishnu_define_transfer_identifier	73
11.11 vishnu_stop 76 11.12 vishnu_stop 77 11.13 vishnu_restart 78 11.14 vishnu_define_work_identifier 79 12 IMS C++ API Reference 81 12.1 getProcesses 81 12.2 setSystemInfo 81 12.3 setSystemThreshold 82 12.4 getSystemThreshold 33 12.5 defineUserIdentifier 83 12.6 defineUserIdentifier 84 12.7 definelobleIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuchIdentifier 86 12.10 loadSysted 86 12.11 setUpdateFrequency 87 12.12 stop 88 12.13 restart 88 12.14 defineWorkIdentifier 88 13 IMS Python API Reference 90 13.1 VISHNU_setSystemInfo 91 13.4 VISHNU_getSystemThreshold 91 13.5 VISHNU.defineLobIdentifier 93 13.6 VISHNU.defineLobIdentifier 93 13.7 VISHNU.defineInerTransferIdentifier 94 13.8 VISHNU.defineLobIdentifier 96 13.1 VISH		11.9 vishnu_define_auth_identifier	74
11.12vishnu_stop 77 11.13vishnu_restart 78 11.14vishnu_define_work_identifier 79 12 IMS C++ API Reference 81 12.1 getProcesses 81 12.2 setSystemInfo 81 12.3 setSystemThreshold 82 12.4 getSystemThreshold 82 12.5 defineUserIdentifier 33 12.6 defineMachineIdentifier 84 12.7 defineJobIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10 loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.13restart 88 13.1 WISHNU.getProcesses 90 13.1 VISHNU.getSystemInfo 91 13.2 VISHNU.getSystemThreshold 91 13.3 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineMachineIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineAuthIdentifier 94 13.8 VISHNU.defineAuthIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 <td< td=""><th></th><td>11.10vishnu_load_shed</td><td>75</td></td<>		11.10vishnu_load_shed	75
11.13vishnu_testart 78 11.14vishnu_define_work_identifier 79 12 IMS C++ API Reference 81 12.1 getProcesses 81 12.2 setSystemInfo 81 12.3 setSystemThreshold 82 12.4 getSystemThreshold 33 12.5 defineUserIdentifier 83 12.6 defineMachineIdentifier 84 12.7 defineJobIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10dodShed 86 12.11setUpdateFrequency 37 12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU_setSystemInfo 91 13.2 VISHNU.setSystemThreshold 92 13.5 VISHNU_defineJobIdentifier 93 13.6 VISHNU_defineJobIdentifier 93 13.7 VISHNU_defineAuthIdentifier 94 13.8 VISHNU_defineAuthIdentifier 95 13.10VISHNU_loadShed 96 13.11VISHNU_setUpdateFrequency 97 13.11VISH		11.11 vishnu_set_update_frequency	76
11. 14vishnu_define_work_identifier 79 12 IMS C++ API Reference 81 12.1 getProcesses 81 12.2 setSystemInfo 81 12.3 setSystemThreshold 82 12.4 getSystemThreshold 83 12.5 defineUserIdentifier 83 12.6 defineMachineIdentifier 84 12.7 defineJobIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.14restart 88 12.14reineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU_getFystemThreshold 91 13.3 VISHNU_setSystemInfo 91 13.3 VISHNU_setSystemThreshold 92 13.5 VISHNU_defineJobIdentifier 93 13.6 VISHNU_defineJobIdentifier 93 13.7 VISHNU_defineAuthIdentifier 93 13.8 VISHNU_defineAuthIdentifier 96 13.10VISHNU_loadShed 96 13.11VISHNU_setUpdateFrequency 97 <		11.12vishnu_stop	77
12 IMS C++ API Reference \$1 12.1 getProcesses \$1 12.2 setSystemInfo \$1 12.3 setSystemThreshold \$2 12.4 getSystemThreshold \$3 12.5 defineUserIdentifier \$3 12.6 defineMachineIdentifier \$4 12.7 defineJobIdentifier \$4 12.8 defineTransferIdentifier \$5 12.9 defineAuthIdentifier \$6 12.10loadShed \$6 12.11setUpdateFrequency \$7 12.12stop \$8 12.13restart \$8 12.14defineWorkIdentifier \$9 13 IMS Python API Reference \$9 13.1 VISHNU_getProcesses 90 13.2 VISHNU_setSystemInfo 91 13.3 VISHNU_setSystemThreshold 91 13.4 VISHNU_defineUserIdentifier 93 13.5 VISHNU_defineMachineIdentifier 93 13.6 VISHNU_defineMachineIdentifier 94 13.8 VISHNU_defineFransferIdentifier 94 13.8 VISHNU_defineAuthIdentifier 96 13.10 VISHNU_defineAuthIdentifier 96 13.10 VISHNU_defineAuthIdentifier 96 </td <th></th> <td>11.13 vishnu_restart</td> <td>78</td>		11.13 vishnu_restart	78
12.1 getProcesses 81 12.2 setSystemInfo 81 12.3 setSystemThreshold 82 12.4 getSystemThreshold 83 12.5 defineUserIdentifier 83 12.6 defineMachineIdentifier 84 12.7 defineJobIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.14defineWorkIdentifier 88 12.14defineWorkIdentifier 89 13. IVISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getIneUserIdentifier 93 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineUserIdentifier 93 13.7 VISHNU.defineMachineIdentifier 93 13.8 VISHNU.defineAuchineIdentifier 94 13.8 VISHNU.defineAuchineTransferIdentifier 96 13.1 VISHNU.setUpdateFrequency 96 13.11 VISHNU.setUpdateFrequency 97 13.12 VISHNU.setUpdateFrequency <th></th> <td>11.14vishnu_define_work_identifier</td> <td>79</td>		11.14vishnu_define_work_identifier	79
12.2 setSystemInfo 81 12.3 setSystemThreshold 82 12.4 getSystemThreshold 83 12.5 defineUserIdentifier 83 12.6 defineMachineIdentifier 84 12.7 defineIobIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.14defineWorkIdentifier 88 13.1 VISHNU getProcesses 90 13.1 VISHNU getProcesses 90 13.2 VISHNU setSystemInfo 91 13.3 VISHNU getSystemThreshold 91 13.4 VISHNU getSystemThreshold 92 13.5 VISHNU defineUserIdentifier 93 13.6 VISHNU defineIneMachineIdentifier 93 13.7 VISHNU defineMachineIdentifier 94 13.8 VISHNU defineMachineIdentifier 95 13.9 VISHNU defineFransferIdentifier 95 13.9 VISHNU defineIneMachineIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop	12	IMS C++ API Reference	81
12.3 setSystemThreshold 82 12.4 getSystemThreshold 83 12.5 defineUserIdentifier 83 12.6 defineMachineIdentifier 84 12.7 defineJobIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.getSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineMachineIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.trestart 99		12.1 getProcesses	81
12.4 getSystemThreshold 83 12.5 defineUserIdentifier 83 12.6 defineMachineIdentifier 84 12.7 defineJobIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.defineUserIdentifier 93 13.5 VISHNU.defineMachineIdentifier 93 13.6 VISHNU.defineJobIdentifier 93 13.8 VISHNU.defineAuthIdentifier 93 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.2 setSystemInfo	81
12.5 defineUserIdentifier 83 12.6 defineMachineIdentifier 84 12.7 defineJobIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 93 13.8 VISHNU.defineAuthIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.3 setSystemThreshold	82
12.6 defineMachineIdentifier 84 12.7 defineJobIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineMachineIdentifier 93 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.top 98 13.13VISHNU.restart 99		12.4 getSystemThreshold	83
12.7 defineJobIdentifier 84 12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineMachineIdentifier 94 13.8 VISHNU.defineAuthIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.5 defineUserIdentifier	83
12.8 defineTransferIdentifier 85 12.9 defineAuthIdentifier 86 12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineJobIdentifier 93 13.7 VISHNU.defineJobIdentifier 93 13.8 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineAuthIdentifier 95 13.9 VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.6 defineMachineIdentifier	84
12.9 defineAuthIdentifier 86 12.10 loadShed 86 12.11 setUpdateFrequency 87 12.12 stop 88 12.13 restart 88 12.14 defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.getSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineUserIdentifier 93 13.7 VISHNU.defineMachineIdentifier 93 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.7 defineJobIdentifier	84
12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineBachineIdentifier 93 13.7 VISHNU.defineAuthIdentifier 93 13.8 VISHNU.defineFransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.8 defineTransferIdentifier	85
12.10loadShed 86 12.11setUpdateFrequency 87 12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineBachineIdentifier 93 13.7 VISHNU.defineAuthIdentifier 93 13.8 VISHNU.defineFransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.9 defineAuthIdentifier	86
12.12stop 88 12.13restart 88 12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineJobIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99			
12.13 restart 88 12.14 define Work Identifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.11 setUpdateFrequency	87
12.14defineWorkIdentifier 89 13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineFolbIdentifier 94 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.12stop	88
13 IMS Python API Reference 90 13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineJobIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.13 restart	88
13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		12.14defineWorkIdentifier	89
13.1 VISHNU.getProcesses 90 13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99	13	IMS Python API Reference	90
13.2 VISHNU.setSystemInfo 91 13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99			90
13.3 VISHNU.setSystemThreshold 91 13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99			
13.4 VISHNU.getSystemThreshold 92 13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99			
13.5 VISHNU.defineUserIdentifier 93 13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99			
13.6 VISHNU.defineMachineIdentifier 93 13.7 VISHNU.defineJobIdentifier 94 13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99			
13.8 VISHNU.defineTransferIdentifier 95 13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99			
13.9 VISHNU.defineAuthIdentifier 96 13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		13.7 VISHNU.defineJobIdentifier	94
13.10VISHNU.loadShed 96 13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		13.8 VISHNU.defineTransferIdentifier	95
13.11VISHNU.setUpdateFrequency 97 13.12VISHNU.stop 98 13.13VISHNU.restart 99		13.9 VISHNU.defineAuthIdentifier	96
13.12VISHNU.stop		13.10VISHNU.loadShed	96
13.12VISHNU.stop		13.11VISHNU.setUpdateFrequency	97
		13.12VISHNU.stop	98
13.14VISHNU.defineWorkIdentifier		13.13VISHNU.restart	99
		13.14VISHNU.defineWorkIdentifier	99

Présentation du document

1.1 Objectifs du document

Ce document présente l'administration de la plateforme VISHNU.

1.2 Structure du document

Ce document contient les parties suivantes:

- Définitions
- Installation
- Installation des web services
- Déploiement
- Administration
- Référence des commandes (en anglais)
- Référence de l'API C++ (en anglais)
- Référence de l'API Python (en anglais)

Définitions

2.1 Acronymes

- DB : Base de données: elle est centralisée et utilisée pour sauvegarder toutes les données manipulées par les divers modules.
- FMS : File Management Service
- IMS: Information Management Service
- LDAP : Lightweight Directory Access Protocol, protocole de gestion d'annuaires
- MA: "Master Agent": élément de Sysfera-DS distribuant les requêtes entre les clients et les services désirés.
- SQL : Langage de requêtes sur les bases de données
- TMS: Task Management Service
- UMS : User Management Service
- WS: Web Services

2.2 Références

- [ARCH] D1.1g-VISHNU Technical Architecture : description de l'architecture de l'application VISHNU
- [DIET_USERGUIDE] DIET User Guide : guide de l'utilisateur DIET (nom du projet OpenSource de l'application SysFera-DS)
- [VISHNU_USERMANUAL] VISHNU User Manual : guide de l'utilisateur VISHNU.
- [VISHNU_API] VISHNU API : API VISHNU contenant les signatures et la définition des objets.

2.3 Glossaire

- Client FMS: Cela désigne les programmes permettant un accès à distance aux services du SeD FMS.
- Client IMS: Cela désigne les programmes permettant un accès à distance aux services du SeD IMS.
- Client TMS: Cela désigne les programmes permettant un accès à distance aux services du SeD TMS.
- Client UMS : Cela désigne les programmes permettant un accès à distance aux services du SeD UMS.

- Préfrontale : Cela désigne une machine mise avant la(les) frontale(s) des calculateurs.
- SeD fMS : Cela désigne le programme contenant et exécutant les services du module IMS.
- SeD IMS : Cela désigne le programme contenant et exécutant les services du module IMS.
- SeD TMS : Cela désigne le programme contenant et exécutant les services du module TMS.
- SeD UMS : Cela désigne le programme contenant et exécutant les services du module UMS.
- Sysfera-DS : Intergiciel open source développé par SysFera.

Installation à partir des sources

3.1 Objectifs

Ce chapitre présentera comment installer VISHNU à partir des sources.

Nous décrirons comment installer et configurer la partie serveur et la partie client. L'installation de la partie client est indépendante de la partie serveur. Mais, à l'inverse, l'installation de la partie serveur nécessite l'installation de la partie client. Par ailleurs, il faut noter que le module UMS est requis pour faire fonctionner les modules FMS, IMS et TMS. Même si ces derniers peuvent être installés sur des machines indépendantes. Toutefois, pour qu'IMS puisse gérer le délestage, les différents modules doivent être installés sur la même machine.

3.2 Prérequis

La compilation des sources de Vishnu dépend d'un ensemble de bibliothèques présentées ci-dessous. Sur la plupart des distributions GNU/Linux tels que Debian, Ubuntu, Redhat, Fedora ou SuSE Linux, ces bibliothèques peuvent être facilement installées à partir du gestionnaire de paquets (apt-get, yum ou zypper). Vous pouvez également les installer à partir des sources téléchargeables sur leur site respectif.

- Dépendances requises:
 - GCC: Version 4.4.3 ou ultérieure.
 - CMAKE: Version 2.8 ou ultérieure.
 - BOOST: Version 1.46.1 ou ultérieure. Au moins les modules *program_options*, date_time, thread, filesystem, system, unit_test_framework, serialization, random et regex doivent être installés
 - OMNIORB : Version 4.1.4 ou ultérieure.
 - GLIBC : Version 2.7 ou ultérieure.
 - openSSH: Version 4.2 ou ultérieure.
 - DIET : version 2.8 ou ultérieure. Le module *LOG SERVICE* doit être activé.
- Dépendances optionelles pour le module UMS:
 - OpenLDAP: Version 2.4
- En fonction du Batch Scheduler sous-jacent à TMS, vous devez installer les APIs correspondantes :
 - Torque API: Version 2.3.6.
 - IBM LoadLeveler API: Version 3.5.1.14
 - SLURM API: Versions 2.2.x, 2.3.x ou 2.4.x. Non testé avec les versions inférieures ou supérieures.

- LSF API : Version 7.0.6.134609Grid Engine API : Version 2011.11
- Dépendances optionnelles:
 - SWIG : Version 1.3.40 (ATTENTION : la version 2 de SWIG n'est pas supporté).
 - JAVA SDK: Version 1.6.
 - Python: Version 2.x, x>=5.
 - Base de données, à mettre sur les machines avec des serveurs, au choix :
 - * PGSQL-API (api PostGreSQL) : Version 8.0 minimum.
 - * MYSQL-API (api MySQL) : Version 5.1 minimum.

3.3 Compilation des sources

VISHNU utilise CMake comme système de construction et se conforme aux pratiques communément admises. Les options principales utilisables sont les suivantes:

- BUILD_TESTING, compile les tests si le flag est activé (OFF par défaut).
- CLIENT_ONLY, qui permet de ne compiler que les clients si le flag est activé (OFF par défaut). Sinon les clients et les serveurs sont compilés.
- CMAKE_INSTALL_PREFIX, répertoire d'installation (/usr/local par défaut sur les plateformes *nix)
- COMPILE_TMS, compile le module TMS si le flag est activé (OFF par défaut). Si ON, COMPILE_UMS doit aussi être à ON et les options VISHNU_BATCH et VISHNU_BATCH_VERSION doivent être remplies.
- COMPILE_IMS, compile le module IMS si le flag est activé (OFF par défaut). Si ON, COMPILE_UMS, COMPILE_TMS et COMPILE_FMS doivent aussi être à ON.
- COMPILE_FMS, compile le module FMS si le flag est activé (OFF par défaut). Si ON, COMPILE_UMS doit aussi être à ON.
- COMPILE_UMS, compile le module UMS si le flag est activé (ON par défaut).
- ENABLE_PYTHON, qui permet d'activer la compilation du code PYTHON (OFF par défaut).
- ENABLE_JAVA, qui permet d'activer la compilation des sources JAVA pour les web services (OFF par défaut).
- VISHNU_USE_LDAP, qui permet d'activer le support LDAP pour l'authentification (OFF par défaut).
- ENABLE_SWIG, qui permet d'activer la generation du code des adapteurs Python et Java (OFF par défaut). Cette option doit obligatoirement être activée si on choisit de ne pas compiler tous les modules VISHNU c'est-à-dire si au moins l'une des options COMPILE_UMS, COMPILE_TMS, COMPILE_FMS ou COMPILE_IMS est à OFF. Si l'option ENABLE_SWIG est activée, le package SWIG (voir paragraphe 'Prérequis') est nécessaire pour compiler.
- VISHNU_BATCH, compile le SeD TMS avec le batch correspondant (TORQUE par défaut). Les variables (BATCHNAME)_INCLUE et (BATCHNAME)_LIB doivent être renseignées.
 - LOADLEVELER_INCLUDE_DIR indique le chemin absolu vers le fichier llapi.h
 - LOADLEVELER LIB indique le chemin absolu jusqu'à la librairie llapi.so
 - TORQUE_INCLUDE_DIR indique le chemin absolu vers le fichier pbs_ifl.h
 - TORQUE_LIB indique le chemin absolu jusqu'à la librairie libtorque.so
 - SLURM_INCLUDE_DIR indique le chemin absolu vers le fichier slurm/slurm.h
 - SLURM_LIB indique le chemin absolu jusqu'à la librairie libslurm.so
 - LSF_INCLUDE_DIR indique le chemin absolu vers le fichier lsf/lsbatch.h
 - LSBATCH_LIB indique le chemin absolu jusqu'à la librairie libbat.so

- LSF_LIB indique le chemin absolu jusqu'à la librairie liblsf.so
- SGE_ROOT indique le chemin absolu jusqu'au répertoire d'installation de Grid Engine
- SGE_INCLUDE_DIR indique le chemin absolu vers le fichier drmaa.h
- SGE_BIN_DIR indique le chemin absolu jusqu'aux binaires de Grid Engine
- SGE_LIB indique le chemin absolu jusqu'à la librairie libdrmaa.so
- VISHNU_BATCH_VERSION indique la version du batch scheduler utilisée

Par exemple, pour compiler VISHNU (clients et serveurs) avec UMS et TMS (torque) avec l'API Python puis l'installer dans le répertoire /opt/vishnu sous *nix:

- 1. créer un répertoire build à la racine du projet et se placer dedans
 - \$ mkdir build
 - \$ cd build
- 2. générer le Makefile
 - \$ cmake -DENABLE_PYTHON=ON -DENABLE_SWIG=ON -DCMAKE_INSTALL_PREFIX=/opt/vishnu/
 -DCOMPILE_UMS=ON -DCOMPILE_TMS=ON -DVISHNU_BATCH=TORQUE -DVISHNU_BATCH_VERSION=2.3
 -DTORQUE_DIR=/opt/torque ..
- 3. lancer la compilation avec 2 jobs
 - \$ make -j 2
- 4. installation (en mode super-utilisateur)
 - # make install

Note: pensez à ajouter le répertoire d'installation dans le \$PATH utilisateur pour avoir accès à la commande.

Configuration de la base de données

Les fichiers de configuration de la DB sont disponibles dans le répertoire core/database du package d'installation VISHNU. Les seules bases de données actuellement supportées sont PostgreSQL et MySQL. Les bases de type Oracle ne sont pas supportées. Lors de l'installation toutes les machines doivent avoir soit PostgreSQL, soit MySQL, mais pas certaines machines une base et d'autres une autre, cela ne fonctionnerait pas.

4.1 Utilisation d'une base de données PostGreSQL

Un guide pour installer une base PostGreSLQ peut être trouvé à cette addresse : http://beuss.developpez.com/tutoriels/postgres/install.

Pour une installation d'une nouvelle base de données, les scripts 'postgre_create.sql' et 'database_init.sql' doivent être utilisés par l'administrateur de la DB.

Pour la mise à jour de la base de données lors d'un passage de la release VISHNU précédente à la nouvelle release VISHNU, les scripts 'postgre_update.sql' et 'database_update.sql' doivent être utilisés par l'administrateur de la DB. Le détail des numéros de release est indiqué dans les commentaires au début du script.

4.2 Utilisation d'une base de données MySQL

Un guide pour installer une base MySQL peut être trouvé à cette adresse : http://dev.mysql.com/doc/refman/5.0/fr/unix-post-installation.html

Pour une installation d'une nouvelle base de données, les scripts 'mysql_create.sql' et 'database_init.sql' doivent être utilisés par l'administrateur de la DB.

4.3 Utilisation de LDAP

Un guide pour installer un serveur LDAP est disponible à cette adresse: http://ferry.eof.eu.org/lesjournaux/jar/public_html/x5073.ht

Pour pouvoir utiliser l'authentification avec LDAP, le flag de compilation VISHNU_USE_LDAP doit avoir été activé. Sous debian, les paquets suivants sont nécessaires : slapd libldap-2.4-2 libldap2-dev ldap-utils. Une fois VISHNU compilé, une option de configuration du serveur UMS doit être mise dans le fichier de configuration. Cette option est nommée 'authenticationType' et peut actuellement supporter 4 valeurs :

- UMS : Authentifie uniquement en utilisant la base de données
- LDAPUMS: Pour chaque couple (nom d'utilisateur, mot de passe), essaye d'authentifier avec LDAP en premier puis avec UMS

IMCIDAD. Dans about and distribution and de many) again d'authorif a sur IMC as again air a	
• UMSLDAP : Pour chaque couple (nom d'utilisateur, mot de passe), essaye d'authentifier avec UMS en premier puis av LDAP	/ec
• LDAP : Authentifie uniquement en utilisant LDAP	

Installation des web services

5.1 Pré-requis

- Installer **Java 1.6** (commande 'sudo apt-get install openjdk-6-jdk' ou bien 'sudo apt-get install sun-java6-jdk' sur Linux Debian) et vérifier que la variable JAVA_HOME est bien définie et contient le répertoire racine de l'installation de java.
- Installer les modules désirés avec les options -DENABLE_JAVA=ON et -DENABLE_SWIG (**Note** : Ce pré-requis est optionnel car les jars sont déjà fournis dans la distribution des web services).
- Installer Maven 2 pour compiler les jars (Note : Ce pré-requis est optionnel car les jars sont déjà fournis dans la distribution des web services. Par ailleurs la compilation avec maven nécessite une connexion internet).

5.2 Installation de JBoss

- Télécharger le package JBOSSAS : (la version binaire est disponible) sur http://www.jboss.org/jbossas/downloads => version 5.1.0.GA
- Télécharger le package JBOSSWS : (la version binaire est disponible) sur http://www.jboss.org/jbossws/downloads/ => version 3.3.1.GA
- Décompresser l'archive du package JBOSSAS 5.1.0
- Définir la variable d'environement JBOSS_HOME sur le répertoire décompressé. Par exemple dans le .bashrc : 'export JBOSS_HOME=/home/toto/jboss-5.1.0.GA'
- Décompresser l'archive du package JBOSSWS 3.3.1 et aller dans le répertoire créé
- Copier le fichier 'ant.properties.example' en 'ant.properties'
- Editer le fichier nouvellement créé 'ant.properties'. Mettre la valeur de la variable jboss510.home à la valeur du répertoire de JBOSSAS (même valeur que dans la variable JBOSS_HOME). Il faut noter que si une autre version que la 5.1.0 de jboss a été prise, il faut modifier la variable correspondant à cette version
- Lancer la commande 'ant deploy-jboss510'. Si une autre version de jboss a été prise, il faut faire la commande de la version correspondante
- Le lancement du serveur se fait en lançant le script JBOSS_HOME/bin/run.sh. Pour que le serveur jboss soit accessible depuis une autre machine, utiliser l'option '-b adresseIP' où adresseIP représente l'adresse IP du serveur, et vérifier que le firewall du serveur autorise l'accès au port 8080.
- **Vérification de l'installation:** Pour vérifier que le serveur JBoss est bien démarré et que le module web services est activé, lancer un navigateur internet sur le serveur et se connecter sur l'adresse 'http://localhost:8080/jbossws' (ou 'http://adresseIP:8080/jboss et vérifier que la page affiche bien la version du module web services (jbossws-cxf-3.3.1.GA).

5.3 Installation des modules WS dans JBoss

5.3.1 Fichiers à installer

- VISHNULib-1.0-SNAPSHOT.jar
 - Contient les classes internes faisant le lien JAVA(JNI)/C++.
 - A copier dans JBOSS_HOME/server/default/lib.
 - Le changer implique un redémarrage du serveur JBOSS.
 - Compilation (si nécessaire)
 - * Aller dans le répertoire VISHNULib
 - * Faire 'mvn install' (peut être long la première fois)
 - * Le fichier .jar produit se trouve dans le répertoire target/

· WSAPI.jar

- Contient les classes issues du WSDL et l'implémentation des WS.
- A mettre dans JBOSS_HOME/server/default/deploy.
- Peut être mis à jour sans redémarrer le serveur JBOSS.
- Compilation (si nécessaire)
 - * Aller dans le répertoire WSAPI, avoir le jar VISHNULib-1.0-SNAPSHOT.jar de déjà fait
 - * Faire 'mvn install' (peut être long la première fois)
 - * Le fichier .jar produit se trouve dans le répertoire target
 - * Renommer le jar en WSAPI.jar avant de le mettre dans jboss, ceci est nécessaire

• libVISHNU.so

- Nécessaire pour le fonctionnement des WS, cette librairie dynamique est obtenue en compilant les modules VISHNU désirés avec l'option ENABLE_JAVA.
- Le fichier est installé par défaut par le package VISHNU UMS dans '/usr/local/lib' et il n'est pas nécessaire de le copier.
- S'il y a un problème de déploiement dans le serveur jboss, vérifier qu'elle est bien accessible et dans le LD_LIBRARY_PATH.

5.3.2 Variables d'environnement à définir

- VISHNU_CONFIG_FILE : contient le chemin complet du fichier de configuration client de VISHNU. Se référer au guide d'installation du client [VISHNU_USER_GUIDE] pour connaître le contenu de ce fichier. Si l'exécution échoue avec un message d'erreur lié à initialisation de la librairie lors du connect, vérifier le contenu de cette variable.
- LD_LIBRARY_PATH: contient les chemins des répertoires contenant les librairies VISHNU, notamment libVISHNU.so.

5.3.3 Lancement du serveur JBoss avec le module WS

- Après installation des fichiers définis au paragraphe précédent, le serveur JBoss doit être redémarré en lançant le script JBOSS_HOME/bin/run.sh (avec les options indiquées au paragraphe sur le serveur JBoss).
- Vérification de l'installation: Pour vérifier que le serveur JBoss est bien démarré et que le module UMS WS est activé, lancer un navigateur internet sur le serveur et se connecter sur l'adresse 'http://localhost:8080/jbossws/services' (ou 'http://adresseIP:8080/jbossws/services') et vérifier que le "service endPoint": VISHNUUMSPortImpl est actif.

Déploiement de VISHNU

6.1 Lancement sur un même réseau

Les modules peuvent être lancés manuellement. Le déploiement se fera en suivant la configuration montrée sur la figure 4.1 du document [ARCH]. Pour simplier les choses, on supposera que les divers éléments dans le carré "dedicated to VISHNU" vont être déployés sur la même machine que l'on va nommer **préfrontale**.

NOTE: Il est préférable d'éviter de lancer le même SeD sur la même machine.

NOTE: Il existe un bug connu sur debian (entre autre) avec boost file system, utilisé par VISHNU. Le rapport de bug est ici et le bug est actuellement ouvert: https://syn.boost.org/trac/boost/ticket/4688. Si lors du lancement d'un SeD, le message d'erreur suivant apparait : std::runtime_error: locale::facet::_S_create_c_locale name not valid, faire un "export LANG=C" et cela devrait régler le problème.

NOTE: L'utilisateur VISHNU 'root' doit av<mark>oir un</mark> compt<mark>e loca</mark>l sur chaque machine ou il y a un serveur IMS. Le compte UNIX correspondant sera utilisé pour le redémarrage automatique des SeD.

Pour mieux comprendre l'architecture de déploiement, se référer au document [ARCH], le chapitre 4, 'Technical Architecture'.

- Avoir une base de données PostGreSQL accessible et initialisée (tables créées et premières données créées). Des scripts SQL sont fournis pour cela. Avoir la base PostGreSQL configurée pour qu'elle soit accessible par VISHNU (voir le fichier de configuration pg_hba.conf qui se situe dans un répertoire de la forme '/etc/postgresql/8.3/main' pour configurer la base).
- 2. Lancer le service de nommage CORBA sur la machine préfrontale. La commande est **omniNames -start** pour la première fois, sinon **omniNames** suffit. Attention, dans la configuration de l'omninames, bien utiliser l'adresse de l'hôte et non pas 'localhost' ou '127.0.0.1'.
- 3. Lancer le log service de DIET sur la machine préfrontale. La commande est LogCentral --config config.cfg avec config.cfg un fichier de configuration pour le log central.
- 4. Lancer le MA avec son fichier de configuration sur la machine préfrontale : **dietAgent config.cfg**. Voir le paragraphe 6.3 pour avoir un exemple de configuration. Ce fichier de configuration peut contenir les 3 lignes suivantes :
 - 'traceLevel = 0': Le niveau de verbosité du master agent, cette valeur peut être entre 0 et 10 compris.
 - 'agentType = DIET_MASTER_AGENT' : Le type de l'agent, l'autre type disponible est DIET_LOCAL_AGENT mais dans notre cas il faut DIET_MASTER_AGENT.
 - 'name = MA0' : Le nom que l'on veut donner à l'agent, par exemple on le nomme MA0 ici.
- 5. Lancer le SeD UMS sur la préfrontale avec la commande **umssed ~/ums_sed.cfg**. Le paramètre est un fichier de configuration VISHNU. Voir le paragraphe 6.6 pour un exemple de fichier de configuration. Les paramètres à fournir correspondent à :
 - 'dietConfigFile=/usr/local/etc/SeD.cfg': le chemin jusqu'au fichier de configuration DIET du SeD. Voir le paragraphe 6.4 pour un exemple de configuration. Ce fichier peut par exemple contenir les 2 lignes suivantes:

- 'traceLevel = 0' : Le niveau de verbosité du SeD UMS, ce niveau peut être entre 0 (minimum) et 10 compris.
- 'parentName = MA0' : Le nom du MA auquel le SeD UMS doit se lier. Ce doit être exactement le même nom que celui donné au même dans le champs 'name' du MA en question, sur cet exemple c'est MA0.
- 'useLogService = 1': Pour utiliser le service de log dans DIET (sinon les SeD n'émettent aucun message).
- 'vishnuId=1' : L'id de VISHNU à utiliser dans la DB (valeur '1' par défaut) .
- 'databaseType=postgresql' : Pour utiliser une base postgreSQL. Pour utiliser une base MySQL, il faut mettre 'mysql' comme type.
- 'databaseHost=localhost': Le nom DNS du serveur de bases de données, ou 'localhost' si la base est locale.
- 'databaseName=vishnu' : Le nom de la base de données
- 'databaseUserName=vishnu user' : Le nom d'utilisateur pour se connecter à la DB.
- 'databaseUserPassword=vishnu_user' : Le mot de passe pour se connecter à la DB.
- 'databaseConnectionsNb=5' : Le nombre de connexions ouvertes sur la base de données par le SeD afin de traiter des requêtes en parallèle. (le nombre par défaut est 10). Si le nombre d'utilisateurs simultané du SeD est grand, cette valeur doit être augmentée dans la limite du nombre de connections simultanées autorisées par le serveur de base de données.
- 'sendmailScriptPath=/usr/local/vishnu/sbin/sendmail.py': Le script à utiliser pour envoyer les mails. Il est installé avec le module UMS dans le sous-répertoire sbin/ du répertoire d'installation.
- 'authenticationType=LDAP': Utilise uniquement LDAP pour authentifier un utilisateur.
- 'vishnuMachineId=machine_1' : Optionnel, ce paramètre indique l'identifiant de la machine associée au SeD.

 IMPORTANT : Lors de la première initialialisation, c'est-à-dire lorsqu'il n'y a pas encore de machine créée dans le système, vous devez laisser ce paramètre vide. En effet, lorsque définie, sa valeur doit correspondre à une machine VISHNU, sinon le démarrage du SeD échoue.
- 6. Sur la machine hôte de Torque, lancer le serveur (pbs_serv), le scheduler (pbs_sched) et l'ordonnanceur (pbs_mom) de Torque.
- 7. Lancer le SeD TMS sur la machine hôte de Torque. La commande de lancement est : tmssed ~/tms_sed.cfg. Le paramètre est un fichier de configuration VISHNU. Voir le paragraphe 6.6 pour un exemple de fichier de configuration. Les paramètres à fournir correspondent à ceux de UMS avec de plus :
 - 'intervalMonitor = 1': La fréquence (en secondes) de mise à jour des données dans la base concernant les états des jobs.
 - 'batchSchedulerType=TORQUE' : Le type du batch scheduler utilisé.
 - 'vishnuMachineId=machine_1' : L'identifiant VISHNU de la machine ou le SeD TMS est lancé (obtenu en utilisant la commande vishnu_list_machines).
- 8. Sur la machine hôte de SLURM, lancer les serveurs slurmd, slurmctld et slurmdbd.
- 9. Lancer le SeD TMS sur la machine hôte de SLURM. La commande de lancement est: tmssed ~/tms_sed.cfg. Le paramètre est un fichier de configuration VISHNU. Voir le paragraphe 6.6 pour un exemple de fichier de configuration. Les paramètres à fournir correspondent à ceux de UMS avec de plus:
 - 'intervalMonitor = 1': La fréquence (en secondes) de mise à jour des données dans la base concernant les états des jobs.
 - 'batchSchedulerType=SLURM' : Le type du batch scheduler utilisé.
 - 'vishnuMachineId=machine_2' : L'identifiant VISHNU de la machine ou le SeD TMS est lancé (obtenu en utilisant la commande vishnu_list_machines).
- 10. Sur la machine hôte de LSF, lancer les exécutables hostsetup *lsfstartup*.
- 11. Lancer le SeD TMS sur la machine hôte de LSF. La commande de lancement est : tmssed ~/tms_sed.cfg. Le paramètre est un fichier de configuration VISHNU. Voir le paragraphe 6.6 pour un exemple de fichier de configuration. Les paramètres à fournir correspondent à ceux de UMS avec de plus :
 - 'intervalMonitor = 1': La fréquence (en secondes) de mise à jour des données dans la base concernant les états des jobs.
 - 'batchSchedulerType=LSF' : Le type du batch scheduler utilisé.
 - 'vishnuMachineId=machine_2' : L'identifiant VISHNU de la machine ou le SeD TMS est lancé (obtenu en utilisant la commande vishnu_list_machines).

- 12. Sur la machine hôte de Grid Engine, lancer les exécutables sge_qmaster_et sge_execd.
- 13. Lancer le SeD TMS sur la machine hôte de Grid Engine. La commande de lancement est : tmssed ~/tms_sed.cfg. Le paramètre est un fichier de configuration VISHNU. Voir le paragraphe 6.6 pour un exemple de fichier de configuration. Les paramètres à fournir correspondent à ceux de UMS avec de plus :
 - 'intervalMonitor = 1': La fréquence (en secondes) de mise à jour des données dans la base concernant les états des jobs.
 - 'batchSchedulerType=SGE' : Le type du batch scheduler utilisé.
 - 'vishnuMachineId=machine_2' : L'identifiant VISHNU de la machine ou le SeD TMS est lancé (obtenu en utilisant la commande vishnu_list_machines).
- 14. Lancer le SeD IMS sur toutes la machine préfrontale. La commande de lancement est : imssed ~/ims_sed.cfg. Le paramètre est un fichier de configuration VISHNU. Voir le paragraphe 6.5 pour un exemple de fichier de configuration. Les paramètres à fournir correspondent à ceux de UMS. Il faut noter que IMS doit être lancé sur toutes les machines à monitorer.
- 15. Lancer le SeD FMS sur une machine (sur la figure exemple 4.1 elle est différente de la préfrontale et de la machine avec le batch, mais cela peut être n'importe laquelle). La commande de lancement est : fmssed ~/fms_sed.cfg. Le paramètre est un fichier de configuration VISHNU. Voir le paragraphe 6.7 pour un exemple de fichier de configuration. Les paramètres à fournir correspondent à ceux de UMS avec de plus :
 - 'intervalMonitor = 1' : La fréquence (en secondes) de mise à jour des données dans la base concernant les états des transferts de fichiers.
- 16. Les modules de VISHNU sont prêts à être utilisés. Pour ce faire, un client doit se connecter et soumettre des requêtes à VISHNU au moyen des commandes UMS, TMS, FMS et IMS (voir le manuel de l'utilisateur VISHNU pour plus d'informations sur les commandes utilisateurs disponibles).

6.2 Lancement sur plusieur<mark>s ré</mark>seau<mark>x av</mark>ec une version de DIET supérieure ou égale à 2.8

Un module VISHNU peut être lancé manuellement. Pour le déploiement on se base sur le modèle de la figure 4.2 du document [ARCH] en supposant pour simplifier que sur un réseau tout est lancé sur la même machine et que les réseaux "Network C" et "Network D" sont confondus (pas de forwarder à mettre entre eux).

- Avoir une base de données PostgreSQL accessible et initialisée (tables créées et premières données créées). Des scripts SQL sont fournis pour cela. Avoir la base PostGreSQL configurée pour qu'elle soit accessible par VISHNU (voir le fichier de configuration pg_hba.conf qui se situe dans un répertoire de la forme '/etc/postgresql/8.3/main' pour configurer la base).
- 2. Lancer le service de nommage CORBA sur les différents réseaux. La commande est **omniNames** -start pour la première fois, sinon **omniNames** suffit. Attention, dans la configuration de l'omninames, bien utiliser l'adresse de l'hôte et non pas 'localhost' ou '127.0.0.1'.
- 3. Lancer un démon forwarder sur le reseau 2 (Network B) :

dietForwarder --name forwarder2

- forwarder2 : nom qui identifie le démon forwarder sur ce réseau
- 4. Lancer un démon forwarder sur le reseau 1 (network C):

dietForwarder --peer-name forwarder2 --ssh-host nom_DNS_machine_distante --remote-port 50005 --name forwarder --remote-host localhost --ssh-login login

- --peer-name : le nom donné au forwarder de l'autre coté, ici forwarder2.
- --ssh-host : la nom DNS de la machine distante pour connecter le tunnel SSH.
- --remote-port : le port à utiliser pour le tunnel ssh, ici 50005.
- --name : le nom identifiant ce démon forwarder, c'est-à-dire 'forwarder1'.

- --remote-host : le nom de l'adresse loopback, c'est-à-dire 'localhost'.
- --ssh-login : le login de connection sur la machine distante.
- 5. Si la clé ssh est accessible (le chemin par défaut est le répertoire \$HOME/.ssh/) et que la clé est protégée par une passphrase, la passphrase est demandée et la connexion ssh s'établit.
- 6. Lancer un démon forwarder pour le log service sur le reseau 2 (network B) :

logForwarder --name logforwarder2

- logforwarder2 : nom qui identifie le démon forwarder sur ce réseau
- 7. Lancer un démon log forwarder sur le reseau 1 (network C) :

logForwarder --peer-name logforwarder2 --ssh-host nom_DNS_machine_distante --remote-port 50005 --name logforwarder --remote-host localhost --ssh-login login

- --peer-name : le nom donné au forwarder de l'autre coté, ici forwarder2.
- --ssh-host : la nom DNS de la machine distante pour connecter le tunnel SSH.
- --remote-port : le port à utiliser pour le tunnel ssh, ici 50005.
- --name : le nom identifiant ce démon forwarder, c'est-à-dire 'forwarder1'.
- --remote-host : le nom de l'adresse loopback, c'est-à-dire 'localhost'.
- --ssh-login : le login de connection sur la machine distante.
- 8. Si la clé ssh est accessible (le chemin par défaut est le répertoire \$HOME/.ssh/) et que la clé est protégée par une passphrase, la passphrase est demandée et la connexion ssh s'établit.
- 9. Lancer le log service de DIET sur la machine du network B. La commande est LogCentral --config config.cfg avec config.cfg un fichier de configuration pour le log central.
- 10. Lancer le MA avec son fichier de config<mark>uratio</mark>n sur le <mark>réseau</mark> network B : **dietAgent config.cf**. Voir le paragraphe 6.3 pour un exemple de configuration. Ce fichier de configuration peut contenir les 3 lignes suivantes :
 - 'traceLevel = 0' : Le niveau de verbosité du master agent, cette valeur peut être entre 0 et 10 compris.
 - 'agentType = DIET_MASTER_AGENT': Le type de l'agent, l'autre type disponible est DIET_LOCAL_AGENT mais dans notre cas il faut DIET_MASTER_AGENT.
 - 'name = MA0': Le nom que l'on veut donner à l'agent, dans notre exemple on va l'appeller MA0.
- 11. Lancer le SeD, par exemple un UMS sur le réseau network C. Un exemple de commande de lancement est : umssed ~/ums_sed.cfg. Se référer au chapitre de déploiement pour le contenu du fichier, c'est le même à utiliser que dans un déploiement sur un seul réseau.
- 12. Le module, ici UMS, de VISHNU est prêt à être utilisé. Pour ce faire, un client doit se connecter et soumettre des requêtes à VISHNU au moyen de clients UMS. Si le client est encore sur un autre réseau il faudra mettre la paire de dietForwarder entre le réseau client et l'un des réseaux connecté à la hierarchie déployée.

6.3 Lancement sur plusieurs réseaux avec une version de DIET inférieure à 2.8

Un module VISHNU peut être lancé manuellement. Pour le déploiement on se base sur le modèle de la figure 4.2 du document [ARCH] en supposant pour simplifier que sur un réseau tout est lancé sur la même machine et que les réseaux "Network C" et "Network D" sont confondus (pas de forwarder à mettre entre eux).

 Avoir une base de données PostgreSQL accessible et initialisée (tables créées et premières données créées). Des scripts SQL sont fournis pour cela. Avoir la base PostGreSQL configurée pour qu'elle soit accessible par VISHNU (voir le fichier de configuration pg_hba.conf qui se situe dans un répertoire de la forme '/etc/postgresql/8.3/main' pour configurer la base).

- 2. Lancer le service de nommage CORBA sur les différents réseaux. La commande est **omniNames** -start pour la première fois, sinon **omniNames** suffit. Attention, dans la configuration de l'omninames, bien utiliser l'adresse de l'hôte et non pas 'localhost' ou '127.0.0.1'.
- 3. Lancer un démon forwarder sur le reseau 2 (Network B) :

dietForwarder --name forwarder2 --net-config forwarder2.cfg

- forwarder2 : nom qui identifie le démon forwarder sur ce réseau
- forwarder2.cfg: fichier de configuration (voir le paragraphe 6.8 pour un exemple de configuration) contenant des règles appliquées aux connections entre agents de l'intergiciel. Les règles sont de deux sortes: 'accept:' ou 'reject:'. Dans l'exemple de le paragraphe 6.8, les règles utilisées sont:
 - une règle 'accept' correspondant au filtre sur la source des connections acceptées. '.*' signifie les connections provenant de n'importe quelle adresse IP.
 - deux règles 'reject' contenant les adresses destination à rejeter. Il est nécessaire que l'adresse IP du serveur sur lequel tourne le démon forwarder soit indiquée dans une règle de ce type. Dans l'exemple le serveur ayant deux adresses IP on a indiqué une règle pour chaque adresse.
- 4. Lancer un démon forwarder sur le reseau 1 (network C):

dietForwarder -C --peer-name forwar<mark>der2 --</mark>ssh-h<mark>ost nom_DNS_machine_distante --remote-port 50005 --name forwarder --remote-host localhost --net-config forwarder1.cfg --ssh-login login</mark>

- -C : indique que c'est ce démon forwarder qui crée le tunnel SSH.
- --net-config : le fichier de configuration, ici forwarder1.cfg. Ce fichier doit contenir des règles 'reject' et 'accept' également, sur le même modèle que forwarder2.cfg.
- --peer-name : le nom donné au forwarder de l'autre coté, ici forwarder2.
- --ssh-host : la nom DNS de la machine distante pour connecter le tunnel SSH.
- --remote-port : le port à utiliser pour le tunnel ssh, ici 50005.
- --name : le nom identifiant ce démon forwarder, c'est-à-dire 'forwarder1'.
- --remote-host : le nom de l'adresse loopback, c'est-à-dire 'localhost'.
- --ssh-login : le login de connection sur la machine distante.
- 5. Si la clé ssh est accessible (le chemin par défaut est le répertoire \$HOME/.ssh/) et que la clé est protégée par une passphrase, la passphrase est demandée et la connexion ssh s'établit.
- 6. Lancer un démon forwarder pour le log service sur le reseau 2 (network B) :

logForwarder --name logforwarder2 --net-config logforwarder2

- logforwarder2 : nom qui identifie le démon forwarder sur ce réseau
- logforwarder2.cfg: fichier de configuration (voir le paragraphe 6.8 pour un exemple de fichier de configuration) contenant des règles appliquées aux connections entre agents de l'intergiciel. Les règles sont de deux sortes: 'accept:' ou 'reject:'. Dans l'exemple de le paragraphe 6.8, les règles utilisées sont:
 - une règle 'accept' correspondant au filtre sur la source des connections acceptées. '.*' signifie les connections provenant de n'importe quelle adresse IP.
 - deux règles 'reject' contenant les adresses destination à rejeter. Il est nécessaire que l'adresse IP du serveur sur lequel tourne le démon forwarder soit indiquée dans une règle de ce type. Dans l'exemple le serveur ayant deux adresses IP on a indiqué une règle pour chaque adresse.
- 7. Lancer un démon log forwarder sur le reseau 1 (network C) :

logForwarder -C --peer-name logforwarder2 --ssh-host nom_DNS_machine_distante --remote-port 50005 --name logforwarder --remote-host localhost --net-config logforwarder1.cfg --ssh-login login

- -C : indique que c'est ce démon forwarder qui crée le tunnel SSH.
- --peer-name : le nom donné au forwarder de l'autre coté, ici forwarder2.

- --net-config : le fichier de configuration, ici forwarder1.cfg. Ce fichier doit contenir des règles 'reject' et 'accept' également, sur le même modèle que forwarder2.cfg.
- --ssh-host : la nom DNS de la machine distante pour connecter le tunnel SSH.
- --remote-port : le port à utiliser pour le tunnel ssh, ici 50005.
- --name : le nom identifiant ce démon forwarder, c'est-à-dire 'forwarder1'.
- --remote-host : le nom de l'adresse loopback, c'est-à-dire 'localhost'.
- --ssh-login : le login de connection sur la machine distante.
- 8. Si la clé ssh est accessible (le chemin par défaut est le répertoire \$HOME/.ssh/) et que la clé est protégée par une passphrase, la passphrase est demandée et la connexion ssh s'établit.
- 9. Lancer le log service de DIET sur la machine du network B. La commande est LogCentral --config config.cfg avec config.cfg un fichier de configuration pour le log central.
- 10. Lancer le MA avec son fichier de configuration sur le réseau network B : **dietAgent config.cf**. Voir le paragraphe 6.3 pour un exemple de configuration. Ce fichier de configuration peut contenir les 3 lignes suivantes :
 - 'traceLevel = 0' : Le niveau de verbosité du master agent, cette valeur peut être entre 0 et 10 compris.
 - 'agentType = DIET_MASTER_AGENT': Le type de l'agent, l'autre type disponible est DIET_LOCAL_AGENT mais dans notre cas il faut DIET_MASTER_AGENT.
 - 'name = MA0': Le nom que l'on veut donner à l'agent, dans notre exemple on va l'appeller MA0.
- 11. Lancer le SeD, par exemple un UMS sur le réseau network C. Un exemple de commande de lancement est : umssed ~/ums_sed.cfg. Se référer au chapitre de déploiement pour le contenu du fichier, c'est le même à utiliser que dans un déploiement sur un seul réseau.
- 12. Le module, ici UMS, de VISHNU est prêt à être utilisé. Pour ce faire, un client doit se connecter et soumettre des requêtes à VISHNU au moyen de clients UMS. Si le client est encore sur un autre réseau il faudra mettre la paire de dietForwarder entre le réseau client et l'un des réseaux connecté à la hierarchie déployée.

6.4 Exemple de fichier de configuration d'un MA

```
traceLevel = 0
name = MA0
agentType = DIET_MASTER_AGENT
```

6.5 Exemple de fichier de configuration pour un SeD DIET

```
traceLevel = 0
parentName = MA0
useLogService = 1
```

6.6 Exemple de fichier de configuration d'un SeD UMS

```
# Configuration of the VISHNU UMS SeD
dietConfigFile=/usr/local/etc/SeD.cfg
vishnuId=1
databaseType=postgresql
databaseHost=localhost
databaseName=vishnu
databaseUserName=vishnu_user
```

```
databaseUserPassword=vishnu_user
databaseConnectionsNb=5
sendmailScriptPath=/usr/local/sbin/sendmail.py
vishnuMachineId=machine_1
    authenticationType=LDAP
```

6.7 Exemple de fichier de configurat<mark>ion d</mark>'un <mark>SeD</mark> TMS

```
# Configuration of the VISHNU TMS SeD
dietConfigFile=/usr/local/etc/SeD.cfg
vishnuId=1
databaseType=postgresql
databaseHost=localhost
databaseName=vishnu
databaseUserName=vishnu_user
databaseUserPassword=vishnu_user
databaseConnectionsNb=5
sendmailScriptPath=/usr/local/sbin/sendmail.py
vishnuMachineId=machine_1
# Configuration propres à TMS
# batchSchedulerType=SLURM si le batchScheduler est de type SLURM
# batchSchedulerType=LSF si le batchScheduler est de type LSF
# batchSchedulerType=SGE si le batchScheduler est de type Grid Engine
batchSchedulerType=TORQUE
intervalMonitor = 1
```

6.8 Exemple de fichier de configuration d'un SeD FMS

```
# Configuration of the VISHNU FMS SeD
dietConfigFile=/usr/local/etc/SeD.cfg
vishnuId=1
databaseType=postgresql
databaseHost=localhost
databaseName=vishnu
databaseUserName=vishnu_user
databaseUserPassword=vishnu_user
databaseConnectionsNb=5
vishnuMachineId=machine_1
# Configuration propres à FMS
intervalMonitor = 1
```

6.9 Exemple de fichier d'un forwarder

```
# accept everything from everyone
accept:.*

# reject its own ip
reject:192\.168\.1\.6
```

6.10 Exemple de fichier du LogCentral

```
# an empty configuration file for LogService
[General]

[DynamicTagList]
[StaticTagList]
[UniqueTagList]
[VolatileTagList]
```

6.11 Configuration de l'envoi des emails par VISHNU

Le processus UMS SeD utilise le fichier 'sendmail.py' (fourni dans l'installation VISHNU, dans le sous-répertoire sbin/) pour envoyer des emails aux utilisateurs lors de certaines opérations. Ce fichier peut être modifié par l'administrateur afin de s'adapter à la méthode d'envoi d'email propre au serveur sur lequel est installé le SeD. Par défaut, la configuration fournie se connecte sur le serveur SMTP de 'localhost' sur le port 25, sans authentification.

Les paramètres suivants peuvent être configurés dans le script sendmail.py :

Option	Ligne du script sendmai <mark>l.py à m</mark> odifier
login	<pre>parser.add_option("login", dest="login", help="", default="[← login_utilisateur]")</pre>
password	<pre>parser.add_option("password", dest="password", help="smtp password", ← default="[password_utilisateur]")</pre>
hostname	<pre>parser.add_option("hostname", dest="host", help="smtp host", default="[←</pre>
port	<pre>parser.add_option("port", dest="port", help="smtp port [default: 25]", ←</pre>
SSL	<pre>parser.add_option("ssl", action="store_true", dest="use_ssl", help="enable ← ssl support [default: %default - default port: 587]", default=True)</pre>

6.12 Configuration des clés privées/publiques ssh requises pour FMS

Toutes les commandes éxécutées par le SeD FMS sont lancées via ssh sous le nom de l'utilisateur ayant émis la requête. Les services FMS sont de deux types : il y a ceux qui n'impliquent qu'une machine distante : Exemple getFilesInfo,listDir,etc.. et ceux qui impliquent au moins deux machines distantes : machine source et destination pour les transferts de fichiers.

- Dans le premier cas le SeD se connecte sur la machine distante et effectue la commande. Par conséquent la clé publique du SeD doit être ajoutée au fichier authorized_keys (\$HOME/.ssh/authorized_keys) de l'utilisateur de la machine distante concernée.
- Dans le second cas, deux connexions ssh sont nécessaires. Le SeD se connecte sur la machine source et lance le transfert (seconde connexion) vers la machine destination. Par conséquent:

- la clé publique du SeD doit être ajoutée au fichier authorized_key de la machine source pour permettre la première connexion.
- La machine source doit pouvoir se connecter sur la machine destination par ssh, avec la clé privée enregistrée dans la base de VISHNU lors de l'ajout du compte (local account) liant la machine source à VISHNU. Par ailleurs si le mécanisme d'agent forwarding (de ssh) est activée entre ces différentes machines, il n'est alors plus nécessaire qu'il y ait un autre couple de clés entre la machine source et destination.

En somme, il est alors obligatoire que la clé publique du SeD soit ajoutée à tous les comptes utilisateurs des machines impliquées par les requêtes FMS. Toutes les clés protégées par des passphrases devront être stockées par un agent ssh pour permettre les authentifications automatiques.

6.13 Configuration des clés privées/publiques ssh requises pour TMS

Les commandes de soumission, d'annulation et de récupération des résultats de jobs éxécutées par le SeD TMS sont lancées via ssh sous le nom de l'utilisateur ayant émis la requête. Pour pouvoir exécuter ces commandes correctement, la clé publique du compte dédié au SeD TMS doit être ajoutée au fichier authorized_keys (\$HOME/.ssh/authorized_keys) de l'utilisateur. Toutes les clés protégées par des passphrases devront être stockées par un agent ssh pour permettre les authentifications automatiques.

6.14 Test d'exécution d'un service depuis une machine client par shell

- 1. Une fois que la plateforme a été installée, se mettre sur un poste client avec VISHNU d'installé. Se référer au document [VISHNU_USERMANUAL] pour l'installation de la partie client.
- 2. Exporter la variable d'environnement VISHNU_CONFIG_FILE dans un script de configuration client. Se référer au guide d'installation du client [VISHNU_USER_GUIDE] pour connaître le contenu d'un fichier client.
- 3. Lancer la commande dans le shell 'vish<mark>nu_co</mark>nnect u<mark>ser', ou</mark> user représente un nom d'utilisateur dans la base de données vishnu
- 4. Taper le mot de passe associé correspondant à l'utilisateur 'user'
- 5. Sur le client, un affichage doit signaler que le service a réussi. Dans le terminal ou le SeD UMS a été lancé et dans le terminal ou le MA tourne, selon le niveau de verbosité, plus ou moins d'informations, concernant le service effectué, doivent apparaître. Le message affiché contient au moins une ligne similaire : sessionId: root-2011-Jul-11-14:22:14.403491:86690, qui indique l'identifiant de la session ouverte.
- 6. Fermer la session avec 'vishnu_close'. Aucune erreur ne doit être remontée lors de ces tests.

Administration

7.1 Présentation

Le module UMS correspond à la gestion des utilisateurs et des machines de VISHNU. Il permet aussi de sauvegarder la configuration de VISHNU à chaud et de la restaurer si besoin est. Dans toute la suite du chapitre, on supposera que l'utilisateur est déjà connecté avec un compte administrateur de VISHNU pour pouvoir réaliser ces manipulations. De plus, on présentera l'utilisation des commandes depuis le shell, mais cela reste valable depuis les API Python ou C++.

L'API est disponible dans le document [VISHNU_API]

7.2 Gestion des utilisateurs (UMS)

- 1. L'ajout d'un utilisateur se fait à l'aide de la commande vishnu_add_user'. Elle prend en paramètre le prénom de l'utilisateur, son nom de famille, les droits qui lui sont associés dans VISHNU (administrateur ou simple utilisateur) et son adresse de couriel. Tout ces paramètres sont obligatoires. Un privilège à 1 signifie administrateur, un privilège à 0 signifie un utilisateur. L'identifiant de l'utilisateur est généré et renvoyé.
- 2. La mise à jour d'un utilisateur ne peut être faite que par un administrateur. Cette mise à jour se fait avec un appel à la commande 'vishnu_update_user' et permet de modifier les paramètres de l'ajout (nom, prénom, statut, couriel). Il faut avoir l'identifiant de l'utilisateur (généré lors de la création de l'utilisateur) pour le désigner lors de la mise à jour.
 - Note: le changement du statut d'un utilisateur à l'état "INACTIVE" correspond à un blocage de son compte.
- 3. La suppression d'un utilisateur efface toutes les informations liées à l'utilisateur de la base de donnée. Cette suppression se fait à l'aide de la commande 'vishnu_delete_user'.
- 4. La liste des utilisateurs ne peut être faite que par un administrateur. Cela se fait avec la commande 'vishnu_list_user'. Cette commande peut prendre en paramètre l'identifiant d'un utilisateur pour n'avoir les informations que concernant cet utilisateur.
- 5. Seul un administrateur peut réinitialiser le mot de passe d'un utilisateur de VISHNU. Pour ce faire, il doit appeller la commande 'vishnu_reset_password' en fournissant l'identifiant de l'utilisateur dont l'administrateur veut réinitialiser le mot de passe. Le nouveau mot de passe est temporaire et renvoyé par la commande. Lors de la prochaine connexion, l'utilisateur devra changer son mot de passe avec 'vishnu_change_password'.

7.3 Gestion des machines (UMS+IMS)

1. L'ajout d'une machine se fait à l'aide de la commande 'vishnu_add_machine'. Cette commande prend en paramètre le nom de la machine, le site ou elle se trouve, le language de la description qui sera donnée pour la machine, le fichier contenant la clé publique et la description. Ces paramètres sont obligatoires, en passant par le shell, la description n'a pas besoin

- d'être fournie en paramètre mais elle est alors demandée à l'administrateur avant d'ajouter la machine. A la fin de l'ajout, l'identifiant généré pour la machine est renvoyé.
- 2. La mise à jour d'une machine se fait à l'aide de la commande 'vishnu_update_machine' et permet de modifier les paramètres mis lors de l'ajout de la machine. Il faut utiliser l'identifiant de la machine pour l'identifier lors de la mise à jour.
 - Note : le changement du statut d'une machine à l'état "INACTIVE" correspond à un blocage de la machine. Cela rend la machine inaccessible aux utilisateurs de VISHNU mais toujours visible pour les administrateurs.
- 3. La suppression d'une machine se fait à l'aide de la commande 'vishnu_delete_machine' avec l'identifiant de la machine à supprimer. Cela supprime la machine de la base de données, ainsi que toutes les informations qui y sont attachées (Attention : cette commande est irréversible).
- 4. Les utilisateurs peuvent lister les machines, mais un administrateur a en plus une option qui est l'identifiant d'un utilisateur. Ceci lui permet de lister les machines sur lesquelles l'utilisateur a un compte VISHNU.
- 5. La mise à jour d'informations système d'une machine se fait à l'aide de la commande 'vishnu_set_system_info' et permet d'ajouter ou modifier des informations système d'une machine. Il faut utiliser l'identifiant de la machine pour l'identifier lors de la mise à jour.

7.4 Gestion de la plateforme (UMS)

- 1. L'administrateur peut faire une sauvegarde à chaud à un moment donné de VISHNU. Ceci sauvegarde les utilisateurs, les machines et les comptes des utilisateurs. Le fichier, dans lequel la configuration est, est retourné par la fonction. La fonction est 'vishnu_save_configuration', pas besoin de paramètres.
- 2. L'administrateur peut recharger une configuration précédente de VISHNU à l'aide de la commande 'vishnu_restore_configuration' qui a besoin du fichier de sauvegarde pour recharger la base. Avant de pouvoir lancer cette restauration, tous les utilisateurs de VISHNU doivent être déconnectés.
- 3. Un administrateur peut également définir les valeurs par défaut des options de VISHNU pour tout les utilisateurs (ces options sont le temps de déconnexion par défaut et le type de fermeture d'une session par défaut). Cela se fait en appellant 'vishnu_configure_default_option' en donnant le nom de l'option et sa nouvelle valeur.
- 4. Un administrateur peut ajouter ou modifier un système d'authentification. Par exemple il peut ajouter différents LDAP pour authentifier ses utilisateurs. Actuellement, pour un même LDAP, si les utilisateurs sont dans des branches différentes il faut ajouter un système d'authentification par branche. Ceci afin de faciliter la connexion de l'utilisateur, pour qu'il ne donne aucune information concernant son arbre LDAP, juste son login. C'est l'administrateur lorsqu'il crée son système d'authentification qui doit remplir le champs ldapbase avec le chemin complet dans l'arbre LDAP à utiliser pour authentifier un utilisateur. Lorsqu'un administrateur rempli le chemin menant aux utilisateurs, il doit remplacer le nom de l'utilisateur par la chaîne de caractère \\$USERNAME, cette chaîne sera remplacée par vishnu par le login de l'utilisateur que l'on cherche à authentifier. Fonctions associées : vishnu_add_auth_system, vishnu_update_auth_system, vishnu_delete_auth_system

7.5 Options propres à l'administrateur dans les commandes utilisateurs (UMS+FMS)

- 1. Dans la fonction 'vishnu_connect', un administrateur peut donner l'identifiant d'un utilisateur pour se connecter sous le nom de cet utilisateur dans VISHNU.
- 2. Dans la fonction 'vishnu_list_history_cmd', l'administrateur peut lister toutes les commandes de tout les utilisateurs ou les commandes d'un utilisateur en particulier en fournissant l'identifiant de l'utilisateur.
- 3. Dans la fonction 'vishnu_list_local_accounts', l'administrateur peut lister toutes les comptes de tout les utilisateurs ou les comptes d'un utilisateur particulier en fournissant l'identifiant de l'utilisateur.
- 4. Dans la fonction 'vishnu_list_options', l'administrateur peut lister les toutes les options de tout les utilisateurs ou les options d'un utilisateur en particulier en fournissant l'identifiant de l'utilisateur.

- 5. Dans la fonction 'vishnu_list_sessions', l'administrateur peut lister les toutes les sessions de tous les utilisateurs ou les sessions d'un utilisateur en particulier en fournissant l'identifiant de l'utilisateur, ou les sessions sur une machine particulière en fournissant l'identifiant de la machine.
- 6. Dans la fonction 'vishnu_list_file_transfers', l'administrateur peut lister tous les transferts de fichiers de tous les utilisateurs ou ceux d'un utilisateur en particulier en fournissant l'identifiant de l'utilisateur, ou lister les transferts impliquant une machine particulière (qui peut être source ou destination du transfert) en fournissant l'identifiant de la machine.
- 7. Dans la fonction 'vishnu_stop_file_transfers', l'administrateur peut annuler tous les transferts de fichiers de tous les utilisateurs ou ceux d'un utilisateur en particulier en fournissant l'identifiant de l'utilisateur, ou annuler les transferts impliquant une machine particulière (qui peut être source ou destination du transfert) en fournissant l'identifiant de la machine.

7.6 Gestion des processus VISH<mark>NU e</mark>t dé<mark>lesta</mark>ge (IMS)

- L'administrateur peut lister les processus VISHNU, sur toute la plateforme ou sur une machine particulière. Fonction associée : vishnu_get_processes.
- L'administrateur peut arrêter un processus VISHNU, ce processus ne sera pas redémarrer automatiquement. Attention : l'administrateur doit avoir un compte sur la machine Fonction associée : vishnu_stop
- L'administrateur peut redémarrer un proces<mark>sus VI</mark>SHNU sur une machine, ce processus doit avoir déjà tourné pour VISHNU sur cette machine et l'administrateur doit avoir un compte sur la machine. Fonction associée : vishnu_restart
- L'administrateur peut délester une machine selon deux modes. Dans le mode HARD, tout les processus VISHNU de la machine sont arretés. Dans le mode SOFT, seul FMS et TMS sont touchés, on arrête tout leurs transferts et jobs en cours. Fonction associée : vishnu_load_shed

7.7 Surveillance de l'état des machin<mark>es (I</mark>MS)

- Un administrateur peut fixer la fréquence de mise à jour de l'enregistrement de l'état des machines. Fonction associée : vishnu_set_update_frequency
- Un administrateur peut obtenir la fréquence de mise à jour de l'enregistrement de l'état des machines. Fonction associée : vishnu_get_update_frequency
- Un administrateur peut fixer un seuil sur une machine. Ce seuil peut être l'utilisation du CPU, la mémoire libre restante ou l'espace disque restant. Lors de l'enregistrement de l'état d'une machine, si un seuil est atteint sur cette machine, l'administrateur est notifié par mail de ce dépassement. Fonction associée : vishnu_set_threshold
- Un administrateur peut obtenir les seuils fixés sur une machine. Pour plus d'informations sur les seuils voir la partie pour fixer les seuils ci-dessus. Fonction associée : vishnu_get_threshold

7.8 Définition des formats des identifiants (IMS)

- Un administrateur peut fixer le format des identifiants VISHNU automatiquement générés pour les utilisateurs, les machines, les jobs soumis aux batchs scheduler et les transferts de fichiers. Ces identifiants peuvent contenir plusieurs variables :
 - '\$DAY': Variable qui sera remplacée par le jour de création (1-31)
 - '\$MONTH': Variable qui sera remplacée par le mois de création (1-12)
 - '\$YEAR': Variable qui sera remplacé par l'année de création (0-99)
 - '\$CPT': Variable compteur qui est automatiquement incrémentée
 - '\$SITE': Pour les utilisateurs ou machine, une information sur le lieu
 - '\$UNAME': Pour les utilisateurs, variable remplacée par le nom de l'utilisateur

- '\$MANAME': Pour les machines, variable remplacée par le nom de la machine

Attention la variable conteur est obligatoire pour éviter la génération d'un identifiant déjà existant. Fonctions associées : define_file_format, define_machine_format, define_user_format, define_auth_format.

UMS Command reference

8.1 vishnu add user

vishnu_add_user — adds a new VISHNU user

Synopsis

vishnu_add_user [-h] firstname lastname privilege email

DESCRIPTION

This command allows an admin to add a new user in VISHNU. Several user information are necessary such as: lastname, firtsname and email address. The admin also gives a VISHNU privilege to the new user and a new userId and password are sent to the user by email.

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for **VISHNU**.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

"Vishnu not available (Service bus failure)" [1]

"Vishnu not available (Database error)" [2]

"Vishnu not available (Database connection)" [3]

"Vishnu not available (System)" [4]

"Internal Error: Undefined exception" [9]

- "There is no open session in this terminal" [13]
- "Missing parameters" [14]
- "Vishnu initialization failed" [15]
- "Undefined error" [16]
- "The userId already exists in the database" [22]
- "The user is locked" [23]
- "The user is not an administrator" [25]
- "The mail adress is invalid" [27]
- "The session key is unrecognized" [28]
- "The sessionKey is expired. The session is closed." [29]
- "The machine is locked" [34]

EXAMPLE

To add the user Jean DUPONT as a simple user and with the mail dupont@gmail.com: vishnu_add_user Jean DUPONT 0 dupont@gmail.com

8.2 vishnu update user

vishnu_update_user — updates the user information except the userId and the password

Synopsis

vishnu_update_user[-h][-f firstname][-l lastname][-p privilege][-m email][-s status]userId

DESCRIPTION

This command allows an admin to update a VISHNU user information or to lock a user. When a user is locked, she/he can not uses VISHNU. However, it is not possible to change the privilege of another admin.

OPTIONS

- -h help help about the command.
- **-f** *firstname* represents the updated firstname of the user.
- **-1** *lastname* represents the updated lastname of the user.
- -p privilege represents the updated privilege of the user. The value must be an integer. Predefined values are: 0 (USER), 1 (ADMIN).
- -m email represents the updated email address of the user.
- -s status represents the status of the user (LOCKED or ACTIVE). The value must be an integer. Predefined values are: -1 (UNDEFINED), 0 (INACTIVE), 1 (ACTIVE).

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"Vishnu not available (Service bus failure)" [1]
```

EXAMPLE

To update the mail address of a user user_1 to jdupont@gmail.com: vishnu_update_user -m jdupont@gmail.com user_1

8.3 vishnu_delete_user

vishnu_delete_user — removes a user from VISHNU

Synopsis

```
vishnu_delete_user[-h] userId
```

DESCRIPTION

This command allows an admin to delete a user from VISHNU. When a user is deleted from VISHNU all of her/his information are deleted from VISHNU. However, it is not possible to delete the VISHNU root user.

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The userId is unknown" [21]

[&]quot;The user is locked" [23]

[&]quot;Trying to lock a user account that is already locked" [24]

[&]quot;The user is not an administrator" [25]

[&]quot;The mail adress is invalid" [27]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"Vishnu not available (Service bus failure)" [1]
```

EXAMPLE

```
Tu delete the user user_1: vishnu_delete_user user_1
```

8.4 vishnu_reset_password

vishnu_reset_password — resets the password of a user

Synopsis

```
vishnu_reset_password[-h] userId
```

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The userId is unknown" [21]

[&]quot;The user is locked" [23]

[&]quot;The user is not an administrator" [25]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

DESCRIPTION

This command allows an admin to reset the password of the user. The password generated is temporary and must be changed for using VISHNU.

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"Vishnu not available (Service bus failure)" [1]
```

EXAMPLE

```
To reset the password of the user user_1: vishnu_reset_password user_1
```

8.5 vishnu_save_configuration

vishnu_save_configuration — saves the configuration of VISHNU

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The userId is unknown" [21]

[&]quot;The user is locked" [23]

[&]quot;The user is not an administrator" [25]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

Synopsis

vishnu_save_configuration[-h]

DESCRIPTION

This commands allows an admin to save the VISHNU configuration. This configuration contains the list of users, the lists of machines and the list of local user configurations. It is saved on a xml format on a file registered on the directory \$HOME/.vishnu/configurations.

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"Vishnu not available (Service bus failure)" [1]
```

EXAMPLE

To save the current configuration:

vishnu_save_configuration

8.6 vishnu_restore_configuration

vishnu_restore_configuration — restores the configuration of VISHNU

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The user is not an administrator" [25]

[&]quot;A problem occurs during the configuration saving " [39]

Synopsis

vishnu_restore_configuration[-h] filePath

DESCRIPTION

This function must be used carefully as it replaces all the content of the VISHNU central database with the information stored in the provided file. This file contains the list of users, the lists of machines and the list of local user configurations. It can be created using the vishnu_save_configuration command. The "root" VISHNU user is the only user authorized to call this function, and this action must be done without any other user connected to VISHNU. After restoring, the vishnu database is re-initialized.

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"Vishnu not available (Service bus failure)" [1]
```

EXAMPLE

To restore the configuration in /tmp/toto.cfg: vishnu_restore_configuration /tmp/toto.cfg

8.7 vishnu_add_machine

vishnu_add_machine — adds a new machine in VISHNU

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The user is not an administrator" [25]

[&]quot;A problem occurs during the configuration restoring" [40]

Synopsis

vishnu_add_machine[-h] name site language sshPublicKeyFile machineDescription

DESCRIPTION

This command allows an admin to add a new machine in VISHNU. Several machine information are mandatory such as: name, site, language and the public ssh key of the VISHNU system account on the machine. This public key will be provided automatically to all new VISHNU users who will have to add it to the authorized keys of their own account on the machine.

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"Vishnu not available (Service bus failure)" [1]
```

EXAMPLE

To add the machine perceval in paris with the description in french "ceci est une description" with the public key in /tmp/key.pub: vishnu_add_machine perceval paris fr /tmp/key.pub "ceci est une description"

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The user is not an administrator" [25]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

[&]quot;The machineId already exists in the database" [33]

[&]quot;The closure policy is unknown" [42]

8.8 vishnu_update_machine

vishnu_update_machine — updates machine description

Synopsis

vishnu_update_machine[-h][-n name][-s site][-d machineDescription][-l language][-t status][-k sshPublicKeyFile] machineId

DESCRIPTION

This command allows an admin to update a VISHNU machine or to locked it. A machine locked is not usable.

OPTIONS

- **-h** help help about the command.
- **-n** name represents the name of the machine.
- -s site represents the location of the machine.
- -d machineDescription represents the description of the machine.
- -1 language represents the language used for the description of the machine.
- -t status represents the status of the machine. The value must be an integer. Predefined values are: -1 (UNDEFINED), 0 (INACTIVE), 1 (ACTIVE).
- -k sshPublicKeyFile contains the path to the SSH public key used by VISHNU to access local user accounts.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

- "Vishnu not available (Service bus failure)" [1]
- "Vishnu not available (Database error)" [2]
- "Vishnu not available (Database connection)" [3]
- "Vishnu not available (System)" [4]
- "Internal Error: Undefined exception" [9]
- "There is no open session in this terminal" [13]
- "Missing parameters" [14]
- "Vishnu initialization failed" [15]
- "Undefined error" [16]

```
"The user is not an administrator" [25]
```

EXAMPLE

To change the name of the machine whose id is machine_1 to provencal: vishnu_update_machine machine_1 -n provencal

8.9 vishnu_delete_machine

vishnu_delete_machine — removes a machine from VISHNU

Synopsis

vishnu_delete_machine[-h] machineId

DESCRIPTION

This command allows an admin to delete a machine from VISHNU. When a machine is deleted all of its information are deleted from VISHNU.

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

[&]quot;The machine id is unknown" [32]

[&]quot;The closure policy is unknown" [42]

[&]quot;Vishnu not available (Service bus failure)" [1]

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

```
"Missing parameters" [14]
```

EXAMPLE

```
To delete the machine machine_1: vishnu_delete_machine machine_1
```

8.10 vishnu_list_users

```
vishnu_list_users — lists VISHNU users
```

Synopsis

```
vishnu_list_users[-h][-u userId][-i authSystemId]
```

DESCRIPTION

This command allows an admin to display all users information except the passwords.

OPTIONS

- -h help help about the command.
- -u userId allows an admin to get information about a specific user identified by his/her userId.
- -i authSystemId is an option to list users who have local user-authentication configurations on a specific user-authentication system.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The user is not an administrator" [25]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

[&]quot;The machine id is unknown" [32]

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"Vishnu not available (Service bus failure)" [1]
```

EXAMPLE

To list all the users:

vishnu_list_users

8.11 vishnu_configure_default_option

vishnu_configure_default_option — configures a default option value

Synopsis

vishnu_configure_default_option[-h] optionName value

DESCRIPTION

Options in VISHNU corresponds to parameters of some VISHNU commands (e.g. the close policy for vishnu_connect) that can be preset in the user configuration stored by the VISHNU system. This command allows an administrator to configure the default value of an option; this is the value that will be applied when the user has no configuration defined for that option using the vishnu_configure_option command.

OPTIONS

-h help help about the command.

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The userId is unknown" [21]

[&]quot;The user is not an administrator" [25]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

- "Vishnu not available (Service bus failure)" [1]
- "Vishnu not available (Database error)" [2]
- "Vishnu not available (Database connection)" [3]
- "Vishnu not available (System)" [4]
- "Internal Error: Undefined exception" [9]
- "There is no open session in this terminal" [13]
- "Missing parameters" [14]
- "Vishnu initialization failed" [15]
- "Undefined error" [16]
- "The user is not an administrator" [25]
- "The session key is unrecognized" [28]
- "The sessionKey is expired. The session is closed." [29]
- "The name of the user option is unknown" [41]
- "The value of the timeout is incorrect" [43]
- "The value of the transfer command is incorrect" [44]

EXAMPLE

To configure the option VISHNU_TIMEOUT with the value 42: vishnu_configure_default_option VISHNU_TIMEOUT 42

8.12 vishnu_add_auth_system

vishnu_add_auth_system — adds a new user-authentication system in VISHNU

Synopsis

vishnu_add_auth_system [-h] [-b ldapBase] name URI authLogin authPassword userPasswordEncryption type

DESCRIPTION

This command allows an admin to add a new user-authentication system in VISHNU. Several user-authentication system's information are mandatory such as: URI, login, password, type and optionally for LDAP the DN of the root entry. By default, the type of the user-authentication system is LDAP.

OPTIONS

- -h help help about the command.
- -b 1dapBase is an option for user-authentication system based on LDAP which specifies the DN of the root entry.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"Vishnu not available (Service bus failure)" [1]
```

EXAMPLE

To add an LDAP's user-authentication system on VISHNU named CLAMART with the parameters which follows: URI ldap://127.0.0.1:3, login cn=ldapadmin,dc=sysfera,dc=fr, password secret and DN root entry dc=sysfera,dc=fr:

vishnu_add_auth_system CLAMART ldap://127.0.0.1:389/ cn=ldapadmin,dc=sysfera,dc=fr secret -b uid=\\$USERNAME,ou=users,dc=

8.13 vishnu_update_auth_system

vishnu_update_auth_system — updates a user-authentication system in VISHNU

Synopsis

vishnu_update_auth_system[-h][-n name][-i URI][-u authLogin][-w authPassword][-e userPasswordEncryption][-t type][-s status][-b ldapBase]authSystemId

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The user is not an administrator" [25]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

[&]quot;The identifier (name or generated identifier) of the user-authentication system already exists" [50]

[&]quot;The encryption method is unknown" [53]

DESCRIPTION

This command allows an admin to update a user-authentication system in VISHNU. It is possible to change the parameters which follow: URI, login, password, type and optionally for LDAP the DN of the root entry. By default, the type of the user-authentication system is LDAP.

OPTIONS

- -h help help about the command.
- **-n** name corresponds to the user-authentication system's name.
- -i URI is the URI of the user-authentication systems (by the form host:port for LDAP).
- -u authLogin is the login used to connect to the user-authentication system.
- -w authPassword is the password used to connect to the user-authentication system.
- -e userPasswordEncryption represents the encryption method used to encrypt user's password. The value must be an integer. Predefined values are: -1 (UNDEFINED), 0 (SSHA).
- -t type represents the type of the user-authentication system. The value must be an integer. Predefined values are: -1 (UN-DEFINED), 0 (LDAP).
- -s status represents the status of the user-authentication system. The value must be an integer. Predefined values are: -1 (UNDEFINED), 0 (INACTIVE), 1 (ACTIVE).
- -b 1dapBase is an option for user-authentication system based on LDAP which specifies the DN of the root entry.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"Vishnu not available (Service bus failure)" [1]
```

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The user is not an administrator" [25]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

[&]quot;The user-authentication system is unknown or locked" [48]

[&]quot;The user-authentication system is already locked" [49]

[&]quot;The encryption method is unknown" [53]

EXAMPLE

To change the address of a user-authentication system whose identifier is AUTHENLDAP_1: vishnu_update_auth_system -i ldap://192.128.1.1:389/ AUTHENLDAP_1

8.14 vishnu_delete_auth_system

vishnu_delete_auth_system — removes a user-authentication system from VISHNU

Synopsis

vishnu_delete_auth_system[-h] authSystemId

DESCRIPTION

This command allows an admin to remove a user-authentication system from VISHNU.

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"Vishnu not available (Service bus failure)" [1]
```

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;The user is not an administrator" [25]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

[&]quot;The user-authentication system is unknown or locked" [48]

EXAMPLE

To remove a user-authentication system whose identifier is AUTHENLDAP_1: vishnu_delete_auth_system AUTHENLDAP_1

Chapter 9

UMS C++ API Reference

9.1 addUser

addUser — adds a new VISHNU user

Synopsis

int **vishnu::addUser**(const string& sessionKey, User& newUser);

DESCRIPTION

This command allows an admin to add a new user in VISHNU. Several user information are necessary such as: lastname, firtsname and email address. The admin also gives a VISHNU privilege to the new user and a new userId and password are sent to the user by email.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

newUser Input/Output argument. Object containing the new user information.

EXCEPTIONS

The following exceptions may be thrown:

- "Vishnu not available (Service bus failure)" [1]
- "Vishnu not available (Database error)" [2]
- "Vishnu not available (Database connection)" [3]
- "Vishnu not available (System)" [4]
- "Internal Error: Undefined exception" [9]
- "The userId already exists in the database" [22]
- "The user is locked" [23]

```
"The user is not an administrator" [25]
```

9.2 updateUser

updateUser — updates the user information except the userId and the password

Synopsis

int vishnu::updateUser(const string& sessionKey, const User& user);

DESCRIPTION

This command allows an admin to update a VISHNU user information or to lock a user. When a user is locked, she/he can not uses VISHNU. However, it is not possible to change the privilege of another admin.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

user Input argument. Object containing user information.

EXCEPTIONS

The following exceptions may be thrown:

```
"Vishnu not available (Service bus failure)" [1]
```

[&]quot;The mail adress is invalid" [27]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

[&]quot;The machine is locked" [34]

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;The userId is unknown" [21]

[&]quot;The user is locked" [23]

[&]quot;Trying to lock a user account that is already locked" [24]

[&]quot;The user is not an administrator" [25]

[&]quot;The mail adress is invalid" [27]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

9.3 deleteUser

deleteUser — removes a user from VISHNU

Synopsis

int vishnu::deleteUser(const string& sessionKey, const string& userId);

DESCRIPTION

This command allows an admin to delete a user from VISHNU. When a user is deleted from VISHNU all of her/his information are deleted from VISHNU. However, it is not possible to delete the VISHNU root user.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

userId Input argument. UserId represents the VISHNU user identifier of the user who will be deleted from VISHNU.

EXCEPTIONS

The following exceptions may be thrown:

"Vishnu not available (Service bus failure)" [1]

"Vishnu not available (Database error)" [2]

"Vishnu not available (Database connection)" [3]

"Vishnu not available (System)" [4]

"Internal Error: Undefined exception" [9]

"The userId is unknown" [21]

"The user is locked" [23]

"The user is not an administrator" [25]

"The session key is unrecognized" [28]

"The sessionKey is expired. The session is closed." [29]

9.4 resetPassword

resetPassword — resets the password of a user

Synopsis

int vishnu::resetPassword(const string& sessionKey, const string& userId, string& tmpPassword);

DESCRIPTION

This command allows an admin to reset the password of the user. The password generated is temporary and must be changed for using VISHNU.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

userId Input argument. UserId represents the VISHNU user identifier of the user whose password will be reset.

tmpPassword Output argument. The temporary password generated by VISHNU.

EXCEPTIONS

The following exceptions may be thrown:

"Vishnu not available (Service bus failure)" [1]

"Vishnu not available (Database error)" [2]

"Vishnu not available (Database connection)" [3]

"Vishnu not available (System)" [4]

"Internal Error: Undefined exception" [9]

"The userId is unknown" [21]

"The user is locked" [23]

"The user is not an administrator" [25]

"The session key is unrecognized" [28]

"The sessionKey is expired. The session is closed." [29]

9.5 saveConfiguration

saveConfiguration — saves the configuration of VISHNU

Synopsis

int vishnu::saveConfiguration(const string& sessionKey, Configuration& configuration);

DESCRIPTION

This commands allows an admin to save the VISHNU configuration. This configuration contains the list of users, the lists of machines and the list of local user configurations. It is saved on a xml format on a file registered on the directory \$HOME/.vishnu/configurations.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.configuration Output argument. The configuration is an object which encapsulates the configuration description.

The following exceptions may be thrown:

- "Vishnu not available (Service bus failure)" [1]
- "Vishnu not available (Database error)" [2]
- "Vishnu not available (Database connection)" [3]
- "Vishnu not available (System)" [4]
- "Internal Error: Undefined exception" [9]
- "The user is not an administrator" [25]
- "A problem occurs during the configuration saving" [39]

9.6 restoreConfiguration

restoreConfiguration — restores the configuration of VISHNU

Synopsis

int vishnu::restoreConfiguration(const string& sessionKey, const string& filePath);

DESCRIPTION

This function must be used carefully as it replaces all the content of the VISHNU central database with the information stored in the provided file. This file contains the list of users, the lists of machines and the list of local user configurations. It can be created using the vishnu_save_configuration command. The "root" VISHNU user is the only user authorized to call this function, and this action must be done without any other user connected to VISHNU. After restoring, the vishnu database is re-initialized.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU. filePath Input argument. The filePath is the path of the file used to restore VISHNU configuration.

EXCEPTIONS

The following exceptions may be thrown:

- "Vishnu not available (Service bus failure)" [1]
- "Vishnu not available (Database error)" [2]
- "Vishnu not available (Database connection)" [3]
- "Vishnu not available (System)" [4]
- "Internal Error: Undefined exception" [9]
- "The user is not an administrator" [25]
- "A problem occurs during the configuration restoring" [40]

9.7 addMachine

addMachine — adds a new machine in VISHNU

Synopsis

int vishnu::addMachine(const string& sessionKey, Machine& newMachine);

DESCRIPTION

This command allows an admin to add a new machine in VISHNU. Several machine information are mandatory such as: name, site, language and the public ssh key of the VISHNU system account on the machine. This public key will be provided automatically to all new VISHNU users who will have to add it to the authorized keys of their own account on the machine.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

newMachine Input/Output argument. Is an object which encapsulates the information of the machine which will be added in VISHNU except the machine id which will be created automatically by VISHNU.

EXCEPTIONS

The following exceptions may be thrown:

"Vishnu not available (Service bus failure)" [1]

"Vishnu not available (Database error)" [2]

"Vishnu not available (Database connection)" [3]

"Vishnu not available (System)" [4]

"Internal Error: Undefined exception" [9]

"The user is not an administrator" [25]

"The session key is unrecognized" [28]

"The sessionKey is expired. The session is closed." [29]

"The machineId already exists in the database" [33]

"The closure policy is unknown" [42]

9.8 updateMachine

updateMachine — updates machine description

Synopsis

int vishnu::updateMachine(const string& sessionKey, const Machine& machine);

DESCRIPTION

This command allows an admin to update a VISHNU machine or to locked it. A machine locked is not usable.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

machine Input argument. Existing machine information.

EXCEPTIONS

The following exceptions may be thrown:

- "Vishnu not available (Service bus failure)" [1]
- "Vishnu not available (Database error)" [2]
- "Vishnu not available (Database connection)" [3]
- "Vishnu not available (System)" [4]
- "Internal Error: Undefined exception" [9]
- "The user is not an administrator" [25]
- "The session key is unrecognized" [28]
- "The sessionKey is expired. The session is closed." [29]
- "The machine id is unknown" [32]
- "The closure policy is unknown" [42]

9.9 deleteMachine

deleteMachine — removes a machine from VISHNU

Synopsis

int vishnu::deleteMachine(const string& sessionKey, const string& machineId);

DESCRIPTION

This command allows an admin to delete a machine from VISHNU. When a machine is deleted all of its information are deleted from VISHNU.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.machineId Input argument. MachineId represents the identifier of the machine.

The following exceptions may be thrown:

- "Vishnu not available (Service bus failure)" [1]
- "Vishnu not available (Database error)" [2]
- "Vishnu not available (Database connection)" [3]
- "Vishnu not available (System)" [4]
- "Internal Error: Undefined exception" [9]
- "The user is not an administrator" [25]
- "The session key is unrecognized" [28]
- "The sessionKey is expired. The session is closed." [29]
- "The machine id is unknown" [32]

9.10 listUsers

listUsers — lists VISHNU users

Synopsis

int **vishnu::listUsers**(const string& sessionKey, ListUsers& listuser, const ListUsersOptions& options = ListUsersOptions());

DESCRIPTION

This command allows an admin to display all users information except the passwords.

ARGUMENTS

sessionKey Input argument. The sessionKey is the identifier of the session generated by VISHNU.

listuser Output argument. Listuser is the list of users .

options Input argument. Allows an admin to get information about a specific user identified by his/her userId or to get information about users authenticated by a specific user-authentication system.

EXCEPTIONS

The following exceptions may be thrown:

- "Vishnu not available (Service bus failure)" [1]
- "Vishnu not available (Database error)" [2]
- "Vishnu not available (Database connection)" [3]
- "Vishnu not available (System)" [4]
- "Internal Error: Undefined exception" [9]

```
"The userId is unknown" [21]
```

9.11 configureDefaultOption

configureDefaultOption — configures a default option value

Synopsis

int vishnu::configureDefaultOption(const string& sessionKey, const OptionValue& optionValue);

DESCRIPTION

Options in VISHNU corresponds to parameters of some VISHNU commands (e.g. the close policy for vishnu_connect) that can be preset in the user configuration stored by the VISHNU system. This command allows an administrator to configure the default value of an option; this is the value that will be applied when the user has no configuration defined for that option using the vishnu_configure_option command.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

optionValue Input argument. The optionValue is an object which encapsulates the option information.

EXCEPTIONS

The following exceptions may be thrown:

```
"Vishnu not available (Service bus failure)" [1]
```

[&]quot;The user is not an administrator" [25]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

[&]quot;Vishnu not available (Database error)" [2]

[&]quot;Vishnu not available (Database connection)" [3]

[&]quot;Vishnu not available (System)" [4]

[&]quot;Internal Error: Undefined exception" [9]

[&]quot;The user is not an administrator" [25]

[&]quot;The session key is unrecognized" [28]

[&]quot;The sessionKey is expired. The session is closed." [29]

[&]quot;The name of the user option is unknown" [41]

[&]quot;The value of the timeout is incorrect" [43]

[&]quot;The value of the transfer command is incorrect" [44]

9.12 addAuthSystem

addAuthSystem — adds a new user-authentication system in VISHNU

Synopsis

int vishnu::addAuthSystem(const string& sessionKey, AuthSystem& newAuthSys);

DESCRIPTION

This command allows an admin to add a new user-authentication system in VISHNU. Several user-authentication system's information are mandatory such as: URI, login, password, type and optionally for LDAP the DN of the root entry. By default, the type of the user-authentication system is LDAP.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

newAuthSys Input/Output argument. Is an object which encapsulates the information of the user-authentication system which will be added in VISHNU.

EXCEPTIONS

The following exceptions may be thrown:

"Vishnu not available (Service bus failure)" [1]

"Vishnu not available (Database error)" [2]

"Vishnu not available (Database connection)" [3]

"Vishnu not available (System)" [4]

"Internal Error: Undefined exception" [9]

"The user is not an administrator" [25]

"The session key is unrecognized" [28]

"The sessionKey is expired. The session is closed." [29]

"The identifier (name or generated identifier) of the user-authentication system already exists" [50]

"The encryption method is unknown" [53]

9.13 updateAuthSystem

updateAuthSystem — updates a user-authentication system in VISHNU

Synopsis

int vishnu::updateAuthSystem(const string& sessionKey, const AuthSystem& AuthSys);

DESCRIPTION

This command allows an admin to update a user-authentication system in VISHNU. It is possible to change the parameters which follow: URI, login, password, type and optionally for LDAP the DN of the root entry. By default, the type of the user-authentication system is LDAP.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

AuthSys Input argument. Is an object which encapsulates the information of the user-authentication system which will be added in VISHNU.

EXCEPTIONS

The following exceptions may be thrown:

"Vishnu not available (Service bus failure)" [1]

"Vishnu not available (Database error)" [2]

"Vishnu not available (Database connection)" [3]

"Vishnu not available (System)" [4]

"Internal Error: Undefined exception" [9]

"The user is not an administrator" [25]

"The session key is unrecognized" [28]

"The sessionKey is expired. The session is closed." [29]

"The user-authentication system is unknown or locked" [48]

"The user-authentication system is already locked" [49]

"The encryption method is unknown" [53]

9.14 deleteAuthSystem

deleteAuthSystem — removes a user-authentication system from VISHNU

Synopsis

int vishnu::deleteAuthSystem(const string& sessionKey, const string& authSystemId);

DESCRIPTION

This command allows an admin to remove a user-authentication system from VISHNU.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU. authSystemId Input argument. AuthSystemId is the identifier of the user-authentication system.

The following exceptions may be thrown:

- "Vishnu not available (Service bus failure)" [1]
- "Vishnu not available (Database error)" [2]
- "Vishnu not available (Database connection)" [3]
- "Vishnu not available (System)" [4]
- "Internal Error: Undefined exception" [9]
- "The user is not an administrator" [25]
- "The session key is unrecognized" [28]
- "The sessionKey is expired. The session is closed." [29]
- "The user-authentication system is unknown or locked" [48]

Chapter 10

UMS Python API Reference

10.1 VISHNU.addUser

VISHNU.addUser — adds a new VISHNU user

Synopsis

ret=VISHNU.addUser(string sessionKey, User newUser);

DESCRIPTION

This command allows an admin to add a new user in VISHNU. Several user information are necessary such as: lastname, firtsname and email address. The admin also gives a VISHNU privilege to the new user and a new userId and password are sent to the user by email.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

newUser Input/Output argument. Object containing the new user information.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The userId already exists in the database" [22])

UMSVishnuException("The user is locked" [23])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The mail adress is invalid" [27])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

UMSVishnuException("The machine is locked" [34])

10.2 VISHNU.updateUser

VISHNU.updateUser — updates the user information except the userId and the password

Synopsis

ret=VISHNU.updateUser(string sessionKey, User user);

DESCRIPTION

This command allows an admin to update a VISHNU user information or to lock a user. When a user is locked, she/he can not uses VISHNU. However, it is not possible to change the privilege of another admin.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU. user Input argument. Object containing user information.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The userId is unknown" [21])

UMSVishnuException("The user is locked" [23])

UMSVishnuException("Trying to lock a user account that is already locked" [24])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The mail adress is invalid" [27])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

10.3 VISHNU.deleteUser

VISHNU.deleteUser — removes a user from VISHNU

Synopsis

ret=VISHNU.deleteUser(string sessionKey, string userId);

DESCRIPTION

This command allows an admin to delete a user from VISHNU. When a user is deleted from VISHNU all of her/his information are deleted from VISHNU. However, it is not possible to delete the VISHNU root user.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

userId Input argument. UserId represents the VISHNU user identifier of the user who will be deleted from VISHNU.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The userId is unknown" [21])

UMSVishnuException("The user is locked" [23])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

10.4 VISHNU.resetPassword

VISHNU.resetPassword — resets the password of a user

Synopsis

ret, tmpPassword=VISHNU.resetPassword(string sessionKey, string userId);

DESCRIPTION

This command allows an admin to reset the password of the user. The password generated is temporary and must be changed for using VISHNU.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

userId Input argument. UserId represents the VISHNU user identifier of the user whose password will be reset.

tmpPassword Output argument. The temporary password generated by VISHNU.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

tmpPassword(string) The temporary password generated by VISHNU

EXCEPTIONS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The userId is unknown" [21])

UMSVishnuException("The user is locked" [23])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

10.5 VISHNU.saveConfiguration

VISHNU.saveConfiguration — saves the configuration of VISHNU

Synopsis

ret=VISHNU.saveConfiguration(string sessionKey, Configuration configuration);

DESCRIPTION

This commands allows an admin to save the VISHNU configuration. This configuration contains the list of users, the lists of machines and the list of local user configurations. It is saved on a xml format on a file registered on the directory \$HOME/.vishnu/configurations.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

configuration Output argument. The configuration is an object which encapsulates the configuration description.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("A problem occurs during the configuration saving "[39])

10.6 VISHNU.restoreConfiguration

VISHNU.restoreConfiguration — restores the configuration of VISHNU

Synopsis

ret=VISHNU.restoreConfiguration(string sessionKey, string filePath);

DESCRIPTION

This function must be used carefully as it replaces all the content of the VISHNU central database with the information stored in the provided file. This file contains the list of users, the lists of machines and the list of local user configurations. It can be created using the vishnu_save_configuration command. The "root" VISHNU user is the only user authorized to call this function, and this action must be done without any other user connected to VISHNU. After restoring, the vishnu database is re-initialized.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

filePath Input argument. The filePath is the path of the file used to restore VISHNU configuration.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("A problem occurs during the configuration restoring" [40])

10.7 VISHNU.addMachine

VISHNU.addMachine — adds a new machine in VISHNU

Synopsis

ret=VISHNU.addMachine(string sessionKey, Machine newMachine);

DESCRIPTION

This command allows an admin to add a new machine in VISHNU. Several machine information are mandatory such as: name, site, language and the public ssh key of the VISHNU system account on the machine. This public key will be provided automatically to all new VISHNU users who will have to add it to the authorized keys of their own account on the machine.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

newMachine Input/Output argument. Is an object which encapsulates the information of the machine which will be added in VISHNU except the machine id which will be created automatically by VISHNU.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

UMSVishnuException("The machineId already exists in the database" [33])

UMSVishnuException("The closure policy is unknown" [42])

10.8 VISHNU.updateMachine

VISHNU.updateMachine — updates machine description

Synopsis

ret=VISHNU.updateMachine(string sessionKey, Machine machine);

DESCRIPTION

This command allows an admin to update a VISHNU machine or to locked it. A machine locked is not usable.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

machine Input argument. Existing machine information.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

UMSVishnuException("The machine id is unknown" [32])

UMSVishnuException("The closure policy is unknown" [42])

10.9 VISHNU.deleteMachine

VISHNU.deleteMachine — removes a machine from VISHNU

Synopsis

ret=VISHNU.deleteMachine(string sessionKey, string machineId);

DESCRIPTION

This command allows an admin to delete a machine from VISHNU. When a machine is deleted all of its information are deleted from VISHNU.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

machineId Input argument. MachineId represents the identifier of the machine.

RETURNED OBJECTS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

UMSVishnuException("The machine id is unknown" [32])

10.10 VISHNU.listUsers

VISHNU.listUsers — lists VISHNU users

Synopsis

ret, listuser=VISHNU.listUsers(string sessionKey, ListUsersOptions options = ListUsersOptions());

DESCRIPTION

This command allows an admin to display all users information except the passwords.

ARGUMENTS

sessionKey Input argument. The sessionKey is the identifier of the session generated by VISHNU.

listuser Output argument. Listuser is the list of users .

options Input argument. Allows an admin to get information about a specific user identified by his/her userId or to get information about users authenticated by a specific user-authentication system.

RETURNED OBJECTS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The userId is unknown" [21])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

10.11 VISHNU.configureDefaultOption

VISHNU.configureDefaultOption — configures a default option value

Synopsis

ret=VISHNU.configureDefaultOption(string sessionKey, OptionValue optionValue);

DESCRIPTION

Options in VISHNU corresponds to parameters of some VISHNU commands (e.g. the close policy for vishnu_connect) that can be preset in the user configuration stored by the VISHNU system. This command allows an administrator to configure the default value of an option; this is the value that will be applied when the user has no configuration defined for that option using the vishnu_configure_option command.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU. optionValue Input argument. The optionValue is an object which encapsulates the option information.

RETURNED OBJECTS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

UMSVishnuException("The name of the user option is unknown" [41])

UMSVishnuException("The value of the timeout is incorrect" [43])

UMSVishnuException("The value of the transfer command is incorrect" [44])

10.12 VISHNU.addAuthSystem

VISHNU.addAuthSystem — adds a new user-authentication system in VISHNU

Synopsis

ret=VISHNU.addAuthSystem(string sessionKey, AuthSystem newAuthSys);

DESCRIPTION

This command allows an admin to add a new user-authentication system in VISHNU. Several user-authentication system's information are mandatory such as: URI, login, password, type and optionally for LDAP the DN of the root entry. By default, the type of the user-authentication system is LDAP.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

newAuthSys Input/Output argument. Is an object which encapsulates the information of the user-authentication system which will be added in VISHNU.

RETURNED OBJECTS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

UMSVishnuException("The identifier (name or generated identifier) of the user-authentication system already exists" [50])

UMSVishnuException("The encryption method is unknown" [53])

10.13 VISHNU.updateAuthSystem

VISHNU.updateAuthSystem — updates a user-authentication system in VISHNU

Synopsis

ret=VISHNU.updateAuthSystem(string sessionKey, AuthSystem AuthSys);

DESCRIPTION

This command allows an admin to update a user-authentication system in VISHNU. It is possible to change the parameters which follow: URI, login, password, type and optionally for LDAP the DN of the root entry. By default, the type of the user-authentication system is LDAP.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU.

AuthSys Input argument. Is an object which encapsulates the information of the user-authentication system which will be added in VISHNU.

RETURNED OBJECTS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

UMSVishnuException("The user-authentication system is unknown or locked" [48])

UMSVishnuException("The user-authentication system is already locked" [49])

UMSVishnuException("The encryption method is unknown" [53])

10.14 VISHNU.deleteAuthSystem

VISHNU.deleteAuthSystem — removes a user-authentication system from VISHNU

Synopsis

ret=VISHNU.deleteAuthSystem(string sessionKey, string authSystemId);

DESCRIPTION

This command allows an admin to remove a user-authentication system from VISHNU.

ARGUMENTS

sessionKey Input argument. The sessionKey is the encrypted identifier of the session generated by VISHNU. authSystemId Input argument. AuthSystemId is the identifier of the user-authentication system.

RETURNED OBJECTS

EXCEPTIONS

The following exceptions may be thrown:

SystemException("Vishnu not available (Service bus failure)" [1])

SystemException("Vishnu not available (Database error)" [2])

SystemException("Vishnu not available (Database connection)" [3])

SystemException("Vishnu not available (System)" [4])

SystemException("Internal Error: Undefined exception" [9])

UMSVishnuException("The user is not an administrator" [25])

UMSVishnuException("The session key is unrecognized" [28])

UMSVishnuException("The sessionKey is expired. The session is closed." [29])

UMSVishnuException("The user-authentication system is unknown or locked" [48])

Chapter 11

IMS Command reference

11.1 vishnu get processes

vishnu_get_processes — displays the list of the VISHNU processes running on machines

Synopsis

vishnu_get_processes[-h][-p machineId]

DESCRIPTION

This command with restricted access is used to get the list of VISHNU server processes that are running on the infrastructure or on a single machine. The results contain both the VISHNU identifier of the process and the DIET underlying middleware identifier.

OPTIONS

- -h help help about the command.
- -p machineId The id of the machine.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for **VISHNU**.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

- "If a parameter is invalid" [10]
- "There is no open session in this terminal" [13]
- "Missing parameters" [14]
- "Vishnu initialization failed" [15]
- "Undefined error" [16]

EXAMPLE

To get the list of the vishnu processes that are running and monitored on machine_1: vishnu_get_processes -p machine_1

11.2 vishnu_set_system_info

vishnu_set_system_info — updates the system information of a machine

Synopsis

vishnu_set_system_info[-h][-m memory][-d diskSpace] machineId

DESCRIPTION

This command with restricted access is used to set system information on a machine in the VISHNU database. The machine must first be registered using the UMS "addMachine" call. Using the machine identifier, information such as the total memory and available diskspace on the machine can be added.

OPTIONS

- -h help help about the command.
- **-m** *memory* Amount of RAM memory available on the machine (in Bytes).
- -d diskSpace Amount of disk space available on the machine (in Bytes).

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

- "The database generated an error" [2]
- "If a parameter is invalid" [10]
- "There is no open session in this terminal" [13]
- "Missing parameters" [14]
- "Vishnu initialization failed" [15]
- "Undefined error" [16]

EXAMPLE

To set the diskspace size to 300 on machine_1: vishnu_set_system_info -d 300 machine_1

11.3 vishnu_set_system_threshold

vishnu_set_system_threshold — sets a threshold on a machine of a system

Synopsis

vishnu_set_system_threshold[-h] value machineId type handler

DESCRIPTION

This function allows an administrator to set a threshold. Each time an IMS server records the state of a machine, it checks the values defined, if a threshold is reached (over a use of the cpu or under the free memory or diskspace available), the administrator responsible for the threshold will receive an mail. These threshold will help the administrator to be aware of critical situations on a machine. Warning, a mail is sent for each time the threshold is reached, if a value swings around a threshold, the administrator may receive lots of emails depending on the update frequency.

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

- "The database generated an error" [2]
- "If a parameter is invalid" [10]
- "There is no open session in this terminal" [13]
- "Missing parameters" [14]
- "Vishnu initialization failed" [15]
- "Undefined error" [16]

EXAMPLE

To set a threshold of type use of the CPU(value=1) of value 99% on machine_1 and handled by the user admin_1: vishnu_set_system_threshold 99 machine_1 1 admin_1

11.4 vishnu_get_system_threshold

vishnu_get_system_threshold — gets a system threshold on a machine

Synopsis

vishnu_get_system_threshold[-h][-m machineId][-t metricType]

DESCRIPTION

This function allows an administrator to get the thresholds that may be defined on a machine. This may be used to check the parameters defined to monitor the machine. Each time a threshold is reached, a mail is sent. So checking the values of the threshold is important for the administrator to make sure they will not get tons of emails.

OPTIONS

- -h help help about the command.
- -m machineId The id of the machine where the metric is defined.
- -t metricType The type of the metric. The value must be an integer. Predefined values are: 0 (UNDEFINED), 1 (CPUUSE), 2 (FREEDISKSPACE), 3 (FREEMEMORY).

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

"The database generated an error" [2]

"If a parameter is invalid" [10]

"There is no open session in this terminal" [13]

"Missing parameters" [14]

"Vishnu initialization failed" [15]

"Undefined error" [16]

EXAMPLE

To get all the thresholds: vishnu_get_system_threshold

11.5 vishnu define user identifier

vishnu_define_user_identifier — defines the shape of the identifiers automatically generated for the users

Synopsis

vishnu_define_user_identifier[-h] format

This function allows an administrator to define the format of the identifier that will be automatically generated for the users. Once the format is defined, each time a user is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$NAME: The name of the user \$UNAME: The name of the user \$DAY: The day the user is added \$MONTH: The month the user is added \$YEAR: The year the user is added \$SITE: The site the user is \$TYPE: The 'U' symb to remind it is a user id

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

"The database generated an error" [2]

"If a parameter is invalid" [10]

"There is no open session in this terminal" [13]

"Missing parameters" [14]

"Vishnu initialization failed" [15]

"Undefined error" [16]

EXAMPLE

To define the format to user_\$CPT: vishnu_define_user_identifier user_\\$CPT

11.6 vishnu define machine identifier

vishnu_define_machine_identifier — defines the shape of the identifiers automatically generated for the machines

Synopsis

vishnu_define_machine_identifier[-h] format

This function allows an administrator to define the format of the identifier that will be automatically generated for the machines. Once the format is defined, each time a machine is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$MANAME: The hostname of the machine \$NAME: The hostname of the machine is added \$MONTH: The month the machine is added \$YEAR: The year the machine is added \$SITE: The site the machine is \$TYPE: The 'M' symb to remind it is a machine id

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

"The database generated an error" [2]

"If a parameter is invalid" [10]

"There is no open session in this terminal" [13]

"Missing parameters" [14]

"Vishnu initialization failed" [15]

"Undefined error" [16]

EXAMPLE

To define the format to machine_\$CPT: vishnu_define_machine_identifier machine_\\$CPT

11.7 vishnu define job identifier

vishnu_define_job_identifier — defines the shape of the identifiers automatically generated for the jobs

Synopsis

vishnu_define_job_identifier[-h] format

This function allows an administrator to define the format of the identifier that will be automatically generated for the jobs submitted through TMS. Once the format is defined, each time a job is submitted, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the job is submitted \$MONTH: The month the job is submitted \$YEAR: The year the job is submitted \$TYPE: The 'J' symb to remind it is a job id

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

"The database generated an error" [2]

"If a parameter is invalid" [10]

"There is no open session in this terminal" [13]

"Missing parameters" [14]

"Vishnu initialization failed" [15]

"Undefined error" [16]

EXAMPLE

To define the format to job_\$CPT: vishnu_define_job_identifier job_\\$CPT

11.8 vishnu_define_transfer_identifier

vishnu_define_transfer_identifier — defines the shape of the identifiers automatically generated for the file transfers

Synopsis

vishnu_define_transfer_identifier[-h] format

This function allows an administrator to define the format of the identifier that will be automatically generated for the file transfers. Once the format is defined, each time a file transfer is done, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the file transfer is done \$MONTH: The month the file transfer is done \$YEAR: The year the file transfer is done \$TYPE: The 'F' symb to remind it is a file transfer id

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

"The database generated an error" [2]

"If a parameter is invalid" [10]

"There is no open session in this terminal" [13]

"Missing parameters" [14]

"Vishnu initialization failed" [15]

"Undefined error" [16]

EXAMPLE

To define the format to transfer_\$CPT: vishnu_define_transfer_identifier transfer_\\$CPT

11.9 vishnu define auth identifier

vishnu_define_auth_identifier — defines the shape of the identifiers automatically generated for the authentication system

Synopsis

vishnu_define_auth_identifier[-h] format

This function allows an administrator to define the format of the identifier that will be automatically generated for the authentication. Once the format is defined, each time an authentication system is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the file transfer is done \$MONTH: The month the file transfer is done \$YEAR: The year the file transfer is done \$TYPE: The 'F' symb to remind it is a file transfer id

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

- "The database generated an error" [2]
- "If a parameter is invalid" [10]
- "There is no open session in this terminal" [13]
- "Missing parameters" [14]
- "Vishnu initialization failed" [15]
- "Undefined error" [16]

EXAMPLE

To define the format to transfer_\$CPT: vishnu_define_auth_identifier LDAP_\\$CPT

11.10 vishnu load shed

vishnu_load_shed — sheds load on a machine

Synopsis

vishnu_load_shed[-h] machineId loadShedType

DESCRIPTION

This function allows an administrator to shed load on a machine. Two modes are available: SOFT mode will cancel all the submitted jobs and file transfers for all VISHNU users (Note that jobs and file transfers not initiated through VISHNU will not be impacted). HARD mode will additionally stop all the VISHNU processes on the machine. If a user without administrator rights uses this function, all the user's jobs and file transfers will be cancelled on the machine. In the HARD mode, the stopped processes will not be automatically restarted. Type values: HARD = 1 SOFT = 2

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"The database generated an error" [2]
```

EXAMPLE

To make a hard load shedding on machine_1: vishnu_load_shed machine_1 1

11.11 vishnu_set_update_frequency

vishnu_set_update_frequency — sets the update frequency of the IMS tables

Synopsis

vishnu_set_update_frequency[-h] freq

DESCRIPTION

This function allows an admin to set the update frequency. This frequency corresponds to how often the state of the machines is automatically polled by the IMS server. The value must be in seconds.

OPTIONS

-h help help about the command.

[&]quot;If a parameter is invalid" [10]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

[&]quot;If a component is unavailable" [301]

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

"The database generated an error" [2]

"If a parameter is invalid" [10]

"There is no open session in this terminal" [13]

"Missing parameters" [14]

"Vishnu initialization failed" [15]

"Undefined error" [16]

EXAMPLE

To set the frequency to 100: vishnu_set_update_frequency 100

11.12 vishnu_stop

vishnu_stop — To stop (and do not try to relaunch) a SeD

Synopsis

vishnu_stop[-h] processName machineId

DESCRIPTION

This function allows an admin to stop a VISHNU server on a machine. The stopped process will not be restarted automatically. The important parameters in the process are the names and the machine. The processName must be UMS, TMS, IMS or FMS, in upper case.

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

```
"The database generated an error" [2]
```

EXAMPLE

```
To stop the UMS process on machine_1: vishnu_stop UMS machine_1
```

11.13 vishnu_restart

```
vishnu_restart — To restart a SeD or a MA
```

Synopsis

```
vishnu_restart[-h][-v vishnuConf][-t sedType] machineId
```

DESCRIPTION

This function allows an admin to restart a VISHNU server on a machine. Warning when restarting a server, first it is tried to stop it, so if one is running it is stopped and then another is restarted.

OPTIONS

- -h help help about the command.
- -v vishnuConf The path to the vishnu configuration file.
- -t sedType The type of the vishnu sed. The value must be an integer. Predefined values are: 0 (UNDEFINED), 1 (UMS), 2 (TMS), 3 (FMS), 4 (IMS).

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

[&]quot;If a parameter is invalid" [10]

[&]quot;There is no open session in this terminal" [13]

[&]quot;Missing parameters" [14]

[&]quot;Vishnu initialization failed" [15]

[&]quot;Undefined error" [16]

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

- "The database generated an error" [2]
- "If a parameter is invalid" [10]
- "There is no open session in this terminal" [13]
- "Missing parameters" [14]
- "Vishnu initialization failed" [15]
- "Undefined error" [16]

EXAMPLE

To restart using the configuration file ums.cfg an UMS sed on machine_1: vishnu_restart -v /tmp/ums.cfg -t 1 machine_1

11.14 vishnu_define_work_identifier

vishnu_define_work_identifier — defines the shape of the identifiers automatically generated for the work

Synopsis

vishnu_define_work_identifier[-h] format

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the work. Once the format is defined, each time a work is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the file transfer is done \$MONTH: The month the file transfer is done \$YEAR: The year the file transfer is done \$TYPE: The 'W' symb to remind it is a file transfer id \$NAME: The name of the work

OPTIONS

-h help help about the command.

ENVIRONMENT

VISHNU_CONFIG_FILE Contains the path to the local configuration file for VISHNU.

DIAGNOSTICS

The following diagnostics may be issued on stderr and the command will return the code provided within brackets:

- "The database generated an error" [2]
- "If a parameter is invalid" [10]
- "There is no open session in this terminal" [13]
- "Missing parameters" [14]
- "Vishnu initialization failed" [15]
- "Undefined error" [16]

EXAMPLE

To define the format to W_\$CPT: $vishnu_define_work_identifier\ W_\SCPT$

Chapter 12

IMS C++ API Reference

12.1 getProcesses

getProcesses — displays the list of the VISHNU processes running on machines

Synopsis

int **vishnu::getProcesses**(const string& sessionKey, ListProcesses& process, const ProcessOp& options = ProcessOp());

DESCRIPTION

This command with restricted access is used to get the list of VISHNU server processes that are running on the infrastructure or on a single machine. The results contain both the VISHNU identifier of the process and the DIET underlying middleware identifier.

ARGUMENTS

sessionKey Input argument. The session key.

process Output argument. The list of the Vishnu processes on the machine.

options Input argument. The options to search for the processes.

EXCEPTIONS

The following exceptions may be thrown:

"If a parameter is invalid" [10]

12.2 setSystemInfo

setSystemInfo — updates the system information of a machine

Synopsis

int vishnu::setSystemInfo(const string& sessionKey, const SystemInfo& systemInfo);

This command with restricted access is used to set system information on a machine in the VISHNU database. The machine must first be registered using the UMS "addMachine" call. Using the machine identifier, information such as the total memory and available diskspace on the machine can be added.

ARGUMENTS

sessionKey Input argument. The session key.

systemInfo Input argument. Contains system information to store in Vishnu database.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.3 setSystemThreshold

setSystemThreshold — sets a threshold on a machine of a system

Synopsis

int vishnu::setSystemThreshold(const string& sessionKey, const Threshold& threshold);

DESCRIPTION

This function allows an administrator to set a threshold. Each time an IMS server records the state of a machine, it checks the values defined, if a threshold is reached (over a use of the cpu or under the free memory or diskspace available), the administrator responsible for the threshold will receive an mail. These threshold will help the administrator to be aware of critical situations on a machine. Warning, a mail is sent for each time the threshold is reached, if a value swings around a threshold, the administrator may receive lots of emails depending on the update frequency.

ARGUMENTS

sessionKey Input argument. The session key.

threshold Input argument. The threshold to set.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.4 getSystemThreshold

getSystemThreshold — gets a system threshold on a machine

Synopsis

int vishnu::getSystemThreshold(const string& sessionKey, ListThreshold& value, const ThresholdOp& options);

DESCRIPTION

This function allows an administrator to get the thresholds that may be defined on a machine. This may be used to check the parameters defined to monitor the machine. Each time a threshold is reached, a mail is sent. So checking the values of the threshold is important for the administrator to make sure they will not get tons of emails.

ARGUMENTS

sessionKey Input argument. The session key.value Output argument. The thresholds value.options Input argument. The options for the threshold.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.5 defineUserIdentifier

defineUserIdentifier — defines the shape of the identifiers automatically generated for the users

Synopsis

int vishnu::defineUserIdentifier(const string& sessionKey, const string& format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the users. Once the format is defined, each time a user is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$NAME: The name of the user \$UNAME: The name of the user \$DAY: The day the user is added \$MONTH: The month the user is added \$YEAR: The year the user is added \$SITE: The site the user is \$TYPE: The 'U' symb to remind it is a user id

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.6 defineMachineldentifier

defineMachineIdentifier — defines the shape of the identifiers automatically generated for the machines

Synopsis

int vishnu::defineMachineIdentifier(const string& sessionKey, const string& format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the machines. Once the format is defined, each time a machine is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$MANAME: The hostname of the machine \$NAME: The hostname of the machine is added \$MONTH: The month the machine is added \$YEAR: The year the machine is added \$SITE: The site the machine is \$TYPE: The 'M' symb to remind it is a machine id

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.7 defineJobIdentifier

defineJobIdentifier — defines the shape of the identifiers automatically generated for the jobs

Synopsis

int vishnu::defineJobIdentifier(const string& sessionKey, const string& format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the jobs submitted through TMS. Once the format is defined, each time a job is submitted, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the job is submitted \$MONTH: The month the job is submitted \$YEAR: The year the job is submitted \$TYPE: The 'J' symb to remind it is a job id

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.8 defineTransferIdentifier

defineTransferIdentifier — defines the shape of the identifiers automatically generated for the file transfers

Synopsis

int vishnu::defineTransferIdentifier(const string& sessionKey, const string& format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the file transfers. Once the format is defined, each time a file transfer is done, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the file transfer is done \$MONTH: The month the file transfer is done \$YEAR: The year the file transfer is done \$TYPE: The 'F' symb to remind it is a file transfer id

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.9 defineAuthIdentifier

defineAuthIdentifier — defines the shape of the identifiers automatically generated for the authentication system

Synopsis

int vishnu::defineAuthIdentifier(const string& sessionKey, const string& format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the authentication. Once the format is defined, each time an authentication system is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the file transfer is done \$MONTH: The month the file transfer is done \$YEAR: The year the file transfer is done \$TYPE: The 'F' symb to remind it is a file transfer id

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.10 loadShed

loadShed - sheds load on a machine

Synopsis

int vishnu::loadShed(const string& sessionKey, const string& machineId, const LoadShedType& loadShedType);

This function allows an administrator to shed load on a machine. Two modes are available: SOFT mode will cancel all the submitted jobs and file transfers for all VISHNU users (Note that jobs and file transfers not initiated through VISHNU will not be impacted). HARD mode will additionally stop all the VISHNU processes on the machine. If a user without administrator rights uses this function, all the user's jobs and file transfers will be cancelled on the machine. In the HARD mode, the stopped processes will not be automatically restarted. Type values: HARD = 1 SOFT = 2

ARGUMENTS

sessionKey Input argument. The session key.

machineId Input argument. The id of the machine to stop.

loadShedType Input argument. Selects a load shedding mode (SOFT: stops all services and they can be restarted, HARD: stops all services, they cannot be restarted).

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

"If a component is unavailable" [301]

12.11 setUpdateFrequency

setUpdateFrequency — sets the update frequency of the IMS tables

Synopsis

int vishnu::setUpdateFrequency(const string& sessionKey, const int& freq);

DESCRIPTION

This function allows an admin to set the update frequency. This frequency corresponds to how often the state of the machines is automatically polled by the IMS server. The value must be in seconds.

ARGUMENTS

sessionKey Input argument. The session key.

freq Input argument. Frequency the data are updated, in second.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.12 stop

stop — To stop (and do not try to relaunch) a SeD

Synopsis

int vishnu::stop(const string& sessionKey, const Process& process);

DESCRIPTION

This function allows an admin to stop a VISHNU server on a machine. The stopped process will not be restarted automatically. The important parameters in the process are the names and the machine. The processName must be UMS, TMS, IMS or FMS, in upper case.

ARGUMENTS

sessionKey Input argument. The session key.

process Input argument. The process to stop and do not try to restart anymore.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.13 restart

restart — To restart a SeD or a MA

Synopsis

int vishnu::restart(const string& sessionKey, const string& machineId, const RestartOp& options);

DESCRIPTION

This function allows an admin to restart a VISHNU server on a machine. Warning when restarting a server, first it is tried to stop it, so if one is running it is stopped and then another is restarted.

ARGUMENTS

sessionKey Input argument. The session key.

machineId Input argument. The id of the machine where to restart.

options Input argument. The option for the restart.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

12.14 defineWorkIdentifier

defineWorkIdentifier — defines the shape of the identifiers automatically generated for the work

Synopsis

int vishnu::defineWorkIdentifier(const string& sessionKey, const string& format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the work. Once the format is defined, each time a work is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the file transfer is done \$MONTH: The month the file transfer is done \$YEAR: The year the file transfer is done \$TYPE: The 'W' symb to remind it is a file transfer id \$NAME: The name of the work

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

EXCEPTIONS

The following exceptions may be thrown:

"The database generated an error" [2]

"If a parameter is invalid" [10]

Chapter 13

IMS Python API Reference

13.1 VISHNU.getProcesses

VISHNU.getProcesses — displays the list of the VISHNU processes running on machines

Synopsis

ret, **process=VISHNU.getProcesses**(string sessionKey, ProcessOp options = ProcessOp());

DESCRIPTION

This command with restricted access is used to get the list of VISHNU server processes that are running on the infrastructure or on a single machine. The results contain both the VISHNU identifier of the process and the DIET underlying middleware identifier.

ARGUMENTS

sessionKey Input argument. The session key.

process Output argument. The list of the Vishnu processes on the machine.

options Input argument. The options to search for the processes.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

UserException("If a parameter is invalid" [10])

13.2 VISHNU.setSystemInfo

VISHNU.setSystemInfo — updates the system information of a machine

Synopsis

ret=VISHNU.setSystemInfo(string sessionKey, SystemInfo systemInfo);

DESCRIPTION

This command with restricted access is used to set system information on a machine in the VISHNU database. The machine must first be registered using the UMS "addMachine" call. Using the machine identifier, information such as the total memory and available diskspace on the machine can be added.

ARGUMENTS

sessionKey Input argument. The session key.

systemInfo Input argument. Contains system information to store in Vishnu database.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.3 VISHNU.setSystemThreshold

VISHNU.setSystemThreshold — sets a threshold on a machine of a system

Synopsis

ret=VISHNU.setSystemThreshold(string sessionKey, Threshold threshold);

DESCRIPTION

This function allows an administrator to set a threshold. Each time an IMS server records the state of a machine, it checks the values defined, if a threshold is reached (over a use of the cpu or under the free memory or diskspace available), the administrator responsible for the threshold will receive an mail. These threshold will help the administrator to be aware of critical situations on a machine. Warning, a mail is sent for each time the threshold is reached, if a value swings around a threshold, the administrator may receive lots of emails depending on the update frequency.

ARGUMENTS

sessionKey Input argument. The session key.

threshold Input argument. The threshold to set.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.4 VISHNU.getSystemThreshold

VISHNU.getSystemThreshold — gets a system threshold on a machine

Synopsis

ret, value=VISHNU.getSystemThreshold(string sessionKey, ThresholdOp options);

DESCRIPTION

This function allows an administrator to get the thresholds that may be defined on a machine. This may be used to check the parameters defined to monitor the machine. Each time a threshold is reached, a mail is sent. So checking the values of the threshold is important for the administrator to make sure they will not get tons of emails.

ARGUMENTS

sessionKey Input argument. The session key.

value Output argument. The thresholds value.

options Input argument. The options for the threshold.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.5 VISHNU.defineUserIdentifier

VISHNU.defineUserIdentifier — defines the shape of the identifiers automatically generated for the users

Synopsis

ret=VISHNU.defineUserIdentifier(string sessionKey, string format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the users. Once the format is defined, each time a user is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$NAME: The name of the user \$UNAME: The name of the user \$DAY: The day the user is added \$MONTH: The month the user is added \$YEAR: The year the user is added \$SITE: The site the user is \$TYPE: The 'U' symb to remind it is a user id

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.6 VISHNU.defineMachineIdentifier

VISHNU.defineMachineIdentifier — defines the shape of the identifiers automatically generated for the machines

Synopsis

ret=VISHNU.defineMachineIdentifier(string sessionKey, string format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the machines. Once the format is defined, each time a machine is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$MANAME: The hostname of the machine \$NAME: The hostname of the machine is added \$MONTH: The month the machine is added \$YEAR: The year the machine is added \$SITE: The site the machine is \$TYPE: The 'M' symb to remind it is a machine id

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.7 VISHNU.defineJobIdentifier

VISHNU.defineJobIdentifier — defines the shape of the identifiers automatically generated for the jobs

Synopsis

ret=VISHNU.defineJobIdentifier(string sessionKey, string format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the jobs submitted through TMS. Once the format is defined, each time a job is submitted, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the job is submitted \$MONTH: The month the job is submitted \$YEAR: The year the job is submitted \$TYPE: The 'J' symb to remind it is a job id

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.8 VISHNU.defineTransferIdentifier

VISHNU.defineTransferIdentifier — defines the shape of the identifiers automatically generated for the file transfers

Synopsis

ret=VISHNU.defineTransferIdentifier(string sessionKey, string format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the file transfers. Once the format is defined, each time a file transfer is done, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the file transfer is done \$MONTH: The month the file transfer is done \$YEAR: The year the file transfer is done \$TYPE: The 'F' symb to remind it is a file transfer id

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.9 VISHNU.defineAuthIdentifier

VISHNU.defineAuthIdentifier — defines the shape of the identifiers automatically generated for the authentication system

Synopsis

ret=VISHNU.defineAuthIdentifier(string sessionKey, string format);

DESCRIPTION

This function allows an administrator to define the format of the identifier that will be automatically generated for the authentication. Once the format is defined, each time an authentication system is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the file transfer is done \$MONTH: The month the file transfer is done \$YEAR: The year the file transfer is done \$TYPE: The 'F' symb to remind it is a file transfer id

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.10 VISHNU.loadShed

 $VISHNU.loadShed -\!\!\!\!\!-- sheds \ load \ on \ a \ machine$

Synopsis

ret=VISHNU.loadShed(string sessionKey, string machineId, LoadShedType);

DESCRIPTION

This function allows an administrator to shed load on a machine. Two modes are available: SOFT mode will cancel all the submitted jobs and file transfers for all VISHNU users (Note that jobs and file transfers not initiated through VISHNU will not be impacted). HARD mode will additionally stop all the VISHNU processes on the machine. If a user without administrator rights uses this function, all the user's jobs and file transfers will be cancelled on the machine. In the HARD mode, the stopped processes will not be automatically restarted. Type values: HARD = 1 SOFT = 2

ARGUMENTS

sessionKey Input argument. The session key.

machineId Input argument. The id of the machine to stop.

loadShedType Input argument. Selects a load shedding mode (SOFT: stops all services and they can be restarted, HARD: stops all services, they cannot be restarted).

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

IMSVishnuException("If a component is unavailable" [301])

13.11 VISHNU.setUpdateFrequency

VISHNU.setUpdateFrequency — sets the update frequency of the IMS tables

Synopsis

ret=VISHNU.setUpdateFrequency(string sessionKey, int freq);

DESCRIPTION

This function allows an admin to set the update frequency. This frequency corresponds to how often the state of the machines is automatically polled by the IMS server. The value must be in seconds.

ARGUMENTS

sessionKey Input argument. The session key.

freq Input argument. Frequency the data are updated, in second.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.12 VISHNU.stop

VISHNU.stop — To stop (and do not try to relaunch) a SeD

Synopsis

ret=VISHNU.stop(string sessionKey, Process process);

DESCRIPTION

This function allows an admin to stop a VISHNU server on a machine. The stopped process will not be restarted automatically. The important parameters in the process are the names and the machine. The processName must be UMS, TMS, IMS or FMS, in upper case.

ARGUMENTS

sessionKey Input argument. The session key.

process Input argument. The process to stop and do not try to restart anymore.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.13 VISHNU.restart

VISHNU.restart — To restart a SeD or a MA

Synopsis

ret=VISHNU.restart(string sessionKey, string machineId, RestartOp options);

DESCRIPTION

This function allows an admin to restart a VISHNU server on a machine. Warning when restarting a server, first it is tried to stop it, so if one is running it is stopped and then another is restarted.

ARGUMENTS

sessionKey Input argument. The session key.machineId Input argument. The id of the machine where to restart.

options Input argument. The option for the restart.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])

13.14 VISHNU.defineWorkIdentifier

VISHNU.defineWorkIdentifier — defines the shape of the identifiers automatically generated for the work

Synopsis

ret=VISHNU.defineWorkIdentifier(string sessionKey, string format);

This function allows an administrator to define the format of the identifier that will be automatically generated for the work. Once the format is defined, each time a work is added, the format will be used to define its identifier. The format can contain various variables, a variable is preceded by the '\$' symbol. Moreover, the counter variable '\$CPT' MUST be present in the format, otherwise it will be rejected. The available variables are: \$CPT: a counter \$DAY: The day the file transfer is done \$MONTH: The month the file transfer is done \$YEAR: The year the file transfer is done \$TYPE: The 'W' symb to remind it is a file transfer id \$NAME: The name of the work

ARGUMENTS

sessionKey Input argument. The session key.

format Input argument. The new format to use.

RETURNED OBJECTS

errorCode (integer) Output parameter. Contains 0 on success and the error code on failure.

EXCEPTIONS

The following exceptions may be thrown:

SystemException("The database generated an error" [2])

UserException("If a parameter is invalid" [10])