D1.1d - VISHNU Command-line
interface specifications

D1.1d - VISHNU Command-line interface specifications



COLLABORATORS

	TITLE : D1.1d - VISHNU Co specifications	ommand-line interface		
ACTION	NAME	DATE	SIGNATURE	
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	January 22, 2013		

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
0	05/01/2011	Formatting example	SysFera
1	13/01/2011	First release	SysFera
2	10/02/2011	Removed UMS::SessionStateType. Added UMS::StatusType, UMS::PrivilegeType. Modified UMS::addVishnuUser, UMS::updateUser, UMS::addLocalAccount, UMS::addMachine, UMS::updateMachine, UMS::listSessions, UMS::restoreConfiguration.	SysFera
3	18/02/2011	Renamed all commands to follow C-style command names with vishnu prefix. Added the help option to all commands. Modified update_machine and export_commands. Removed the VISHNU_SESSION_KEY environment variable on all commands.	SysFera

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
4	15/04/2011	Updates for TMS: Modified description of machineld parameter, vishnu_submit_job service. Modified name of get_all_jobs_output to get_completed_jobs_output. Added input parameter outDir to get_job_output and get_completed_jobs_output. Added vishnu_get_machine_refresh_period service. Removed set_machine_env service. Removed jobPriority option in submit_job. Updates for IMS: Add option in exportCommand, getMetricCurrentValue, getProcesses, getMetricHistory, restart and getSystemThreshold. Add services stop and getSystemInfo.	SysFera
5	21/04/2011	Updates for TMS: Removed vishnu_get_machine_refresh_period and vishnu_set_machine_refresh_period services. Added UNDEFINED status of JobStatus Enum. Added UNDEFINED priority of JobPriority Enum. Removed of outputPah and errorPath of ListJobsOptions. Removed scriptContent in Job class. Added ERRCODE_ALREADY_TERMINATED, ERRCODE_ALREADY_CANCELED, ERRCODE_JOB_IS_NOT_TERMINATED in exception list. Modified values of JobPriority Enum. Modified values of QueuePriority and QueueStatus. Added UNDEFINED priority of QueuePriority. Added option queueName in vishnu_list_queues.	SysFera
6	24/05/2011	Updates of UMS: Added new error code for addLocalAccount and updateLocalAccount.	SysFera
10	15/12/2011	Updates of TMS: Extended vishnu_submit_job options. Updates of FMS: Added recursive option to vishnu_create_dir command. Updates of UMS: Added vishnu_current_session_id command. Added -w option to connect and reconnect command.	SysFera

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
11	10/01/2012	Updates of TMS: Modified decription of vishnu_submit_job command (to take into account automatic submission). Extended vishnu_submit_job options (added load criterion option for automatic submission, added option to select a queue automatically). Modified decription of vishnu_list_jobs command (to take into account listing of jobs on all machines). Extended vishnu_list_jobs options (added multipleStatus option for combination of several job states, added option to list all jobs submitted by the underlying batch scheduler (VISHNU jobs and jobs submitted out of VISHNU).	SysFera
12	20/01/2012	Updates of UMS: Added vishnu_connect_m and vishnu_reconnect_m respectively for connection and reconnection using multiple VISHNU accounts defined on the .netrc file. Modified vishnu_list_users option -u to -i for userId and added a new option for user-authentication system. Added vishnu_add_authentication_system, vishnu_update_authentication_system, vishnu_delete_authentication_system, vishnu_list_authentication_system, vishnu_add_auth_account, vishnu_update_auth_account, vishnu_delete_auth_account, vishnu_list_auth_account. Updates of IMS: Added vishnu_define_auth_identifier	SysFera
13	21/08/2012	Updates of TMS: Extended vishnu_list_jobs options (added -l option for listing all information about jobs). Extended vishnu_submit_job options (added -w option for associating a job at a work).	SysFera
14	04/12/2012	Rename of FMS commands according to Posix names.	SysFera

Contents

1	Docu	cument presentation	1
	1.1	Document objectives	. 1
	1.2	Document structure	. 1
	1.3	References	. 1
	1.4	Glossary	. 1
	1.5	Generic command definition format	. 2
	1.6	Environment variables and options	. 2
2	Com	mmands specification for User Man <mark>ageme</mark> nt Service (UMS)	4
	2.1	Command definitions	
		2.1.1 vishnu_connect	. 4
		2.1.2 vishnu_connect_m	. 5
		2.1.3 vishnu_reconnect	. 5
		2.1.4 vishnu_reconnect_m	. 6
		2.1.5 vishnu_add_user	. 6
		2.1.6 vishnu_update_user	. 6
		2.1.7 vishnu_delete_user	. 7
		2.1.8 vishnu_close	. 7
		2.1.9 vishnu_change_password	. 8
		2.1.10 vishnu_reset_password	. 8
		2.1.11 vishnu_add_local_account	. 8
		2.1.12 vishnu_update_local_account	. 9
		2.1.13 vishnu_delete_local_account	. 9
		2.1.14 vishnu_save_configuration	. 10
		2.1.15 vishnu_restore_configuration	. 10
		2.1.16 vishnu_add_machine	. 11
		2.1.17 vishnu_update_machine	. 11
		2.1.18 vishnu_delete_machine	. 12
		2.1.19 vishnu_list_local_accounts	. 12
		2.1.20 vishnu_list_machines	. 13

		2.1.21	vishnu_list_history_cmd	13
		2.1.22	vishnu_list_options	14
		2.1.23	vishnu_list_users	14
		2.1.24	vishnu_list_sessions	14
		2.1.25	vishnu_configure_default_option	15
		2.1.26	vishnu_configure_option	16
		2.1.27	vishnu_current_session_id	16
		2.1.28	vishnu_add_auth_system	16
		2.1.29	vishnu_update_auth_system	17
		2.1.30	vishnu_delete_auth_system	18
		2.1.31	vishnu_list_auth_systems	18
		2.1.32	vishnu_add_auth_account	18
		2.1.33	vishnu_update_auth_account	19
		2.1.34	vishnu_delete_auth_account	19
		2.1.35	vishnu_list_auth_accounts	20
		2.1.36	vishnu_set_ssh_key	20
	2.2	Parame	eters definitions	21
3	Corr	mands	specification for Tasks Management Service (TMS)	22
J	3.1	Comm	and definitions	
	3.1	3.1.1	vishnu_submit_job	
		3.1.2	vishnu_get_job_info	
		3.1.3	vishnu_get_job_progress	
		3.1.4	vishnu_list_queues	
		3.1.5	vishnu list jobs	
		3.1.6	vishnu_get_job_output	
		3.1.7	vishnu_get_job_output	
		3.1.8	vishnu_cancel_job	
		3.1.9	vishnu_add_work	
	3.2		eters definitions	
	3.2	1 drame	acis definitions	20
4	Con		specification for Information Management Service (IMS)	30
	4.1	Comm	and definitions	30
		4.1.1	vishnu_export_commands	30
		4.1.2	vishnu_get_metric_current_value	30
		4.1.3	vishnu_get_metric_history	31
		4.1.4	vishnu_get_processes	31
		4.1.5	vishnu_set_system_info	31
		4.1.6	vishnu_set_system_threshold	32

		4.1.7	vishnu_get_system_threshold	32
		4.1.8	vishnu_define_user_identifier	
		4.1.9	vishnu_define_machine_identifier	33
		4.1.10	vishnu_define_job_identifier	33
		4.1.11	vishnu_define_transfer_identifier	34
		4.1.12	vishnu_define_auth_identifier	34
		4.1.13	vishnu_load_shed	35
			vishnu_set_update_frequency	
		4.1.15	vishnu_get_update_frequency	35
			vishnu_stop	
		4.1.17	vishnu_get_system_info	36
			vishnu_restart	
			vishnu_define_work_identifi <mark>er</mark>	
	4.2	Parame	eters definitions	37
5	Com	ımands	specification for File Management Service (FMS)	39
	5.1	Comma	and definitions	39
		5.1.1	vishnu_touch	39
		5.1.2	vishnu_mkdir	39
		5.1.3	vishnu_rm	40
		5.1.4	vishnu_rmdir	40
		5.1.5	vishnu_chgrp	41
		5.1.6	vishnu_chmod	41
		5.1.7	vishnu_head	41
		5.1.8	vishnu_tail	42
		5.1.9	vishnu_more	42
		5.1.10	vishnu_ls	42
		5.1.11	vishnu_cp	43
		5.1.12	vishnu_acp	43
		5.1.13	vishnu_mv	44
				44
				45
		5.1.16	vishnu_list_file_transfers	45
		5.1.17	vishnu_stat	46
	5.2	Parame	eters definitions	46

Chapter 1

Document presentation

1.1 Document objectives

This document presents the detailed specifications of the VISHNU command line user interface.

These specifications include the definition of all commands including administration commands.

1.2 Document structure

The document is divided into 4 parts corresponding to the 4 modules that compose the Vishnu system:

- UMS: Users Management Service
- TMS: Tasks Management Service
- FMS: Files Management Service
- IMS: Information Management Service

Each module corresponds to a chapter in the document, and each chapter contains the following sections:

- A first section describing the definition of all commands provided by the package.
- A second section describing the definition of all enumerated values used as command parameters.

1.3 References

• D1.1a: VISHNU General specifications

1.4 Glossary

• VISHNU admin: any user having the administrator privilege

1.5 Generic command definition format

This section presents the generic format used in the following chapters to describe the commands. It also details the environment variables required and the user options.

A commands is defined as follows:

Access

Here is detailed the access level of the command line (i.e. the privilege required to use this command)

Description

Here is detailed the purpose of the command line.

Example of use

Here is detailed an example of the use of the command line which starts by optional arguments preceded by a short letter and the required arguments at the end.

myCommand -l acLogin -s sshKeyPath userId

Parameters

The following table contains all the input argu<mark>ments</mark> of the command with their type and description, their short letter for options and a required flag.

Parameter	Type	Option	Description	Required
userId	string		This is an example of a required argument	YES
acLogin	string	1	This is an example of an optional argument	NO
sshKeyPath	string	S	This is an example of an optional argument	NO

The following table contains the list of environment variables information. These environment variables can be mandatory or optional and the value will be overriden by the corresponding command-line option if applicable. When the user option flag is true, the value for this variable can be defined persistently as a user option stored in the database (see the "vishnu_configure_option" command.

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_CONFIG_FILE	N/A	string	This is an example of an environment variable	YES	NO

Note:

For each command line the -h option can be used for help.

1.6 Environment variables and options

Here is detailed the way to use the user options which are stored in the database and environment variables in VISHNU.

Example 1.1 Pseudo code

```
if (the option is provided in the command line) {
    optionValue = option
} else {
    if (an environment variable exists) {
        optionValue = EnVariable_Value

    } else {

        if (a value has been defined in the user configuration) {
            optionValue = user_Option
        }
        else {
            //The default value of the option defined by VISHNU admin is used optionValue = defaultValueOption
        }
    }
}
```

Chapter 2

Commands specification for User Management Service (UMS)

2.1 Command definitions

2.1.1 vishnu connect

Access

This command line can be used by any VISHNU user

Description

The vishnu_connect command opens a session

Example of use

vishnu_connect[-h][-p closePolicy][-d sessionInactivityDelay][-s substituteUserId][-u userId]
[-w password]

Parameters

Parameter Type		Option	Description	Required
closePolicy	SessionCloseType	p	is an option for closing session automatically	NO
			is the maximum delay in seconds between two	
sessionInactivityDelay	int	d	user requests when the CLOSE_ON_TIMEOUT	NO
			policy is set	
			is an admin option which allows an admin to	
substituteUserId	string	S	open a session as if she was another user	NO
			identified by her userId	
userId	string	u	userId represents the VISHNU user identifier	NO
password	string	W	password represents the password of the user	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_CLOSE_POLICY	closePolicy	SessionCloseType	is an option for closing session automatically	NO	YES

2.1.2 vishnu_connect_m

Access

This command line can be used by any VISHNU user

Description

The vishnu_connect_m command opens a session by trying multiple couples (userId, password) each in turn

Example of use

vishnu_connect_m[-h][-p closePolicy][-d sessionInactivityDelay][-s substituteUserId]userIdp-wd

Parameters

Parameter	Type	Option	Description	Required
closePolicy	SessionCloseType	p	is an option for closing session automatically	NO
			is the maximum delay in seconds between two	
sessionInactivityDelay	int	d	user requests when the CLOSE_ON_TIMEOUT	NO
			policy is set	
			is an admin option which allows an admin to	
substituteUserId	string	S	open a session as if she was another user	NO
			identified by her userId	
		7	userId represents the VISHNU user identifier.	
userId	string		There may be various users id used set	YES
			alternatively with the corresponding password.	
			represents the password of the user. There may	
pwd	string		be various password used set alternatively with	YES
			the corresponding userId.	

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_CLOSE_POLICY	closePolicy	SessionCloseType	is an option for closing session automatically	NO	YES

2.1.3 vishnu_reconnect

Access

This command line can be used by any VISHNU user

Description

The vishnu_reconnect command reconnects to a session that is still active

Example of use

vishnu_reconnect[-h][-u userId][-w password] sessionId

Parameter	Type	Option	Description	Required
sessionId	string		sessionId is the identifier of the session defined in	YES
	string		the database	
userId	string	u	userId represents the VISHNU user identifier	NO
password	string	W	password represents the password of the user	NO

This command defines no environment variables.

2.1.4 vishnu_reconnect_m

Access

This command line can be used by any VISHNU user

Description

The vishnu_reconnect_m command reconnects to a session that is still active by trying multiple couples (userId, password) each in turn

Example of use

vishnu_reconnect_m [-h] sessionId userId pwd

Parameters

Parameter	Type	Opti	n Description	Required
sessionId	string		sessionId is the identifier of the session defined the database	in YES
userId	string		userId represents the VISHNU user identifier	YES
pwd	string		represents the password of the user	YES

Environment variables

This command defines no environment variables.

2.1.5 vishnu_add_user

Access

This command line can be used by ADMIN users only

Description

The vishnu_add_user command adds a new VISHNU user

Example of use

vishnu_add_user[-h] firstname lastname privilege email

Parameters

Parameter	Type	Option	Description	Required
firstname	string		is the firstname of the user	YES
lastname	string		is the lastname of the user	YES
privilege	PrivilegeType		is the privilege of the user (admin or simple user)	YES
email	string		is the email of the user	YES

Environment variables

This command defines no environment variables.

2.1.6 vishnu_update_user

Access

This command line can be used by ADMIN users only

Description

The vishnu_update_user command updates the user information except the userId and the password

Example of use

vishnu_update_user[-h][-f firstname][-l lastname][-p privilege][-m email][-s status]userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		represents the VISHNU user identifier	YES
firstname	string	f	represents the updated firstname of the user	NO
lastname	string	1	represents the updated lastname of the user	NO
privilege	PrivilegeType	p	represents the updated privilege of the user	NO
email	string	m	represents the updated email address of the user	NO
status	StatusType	S	represents the status of the user (LOCKED or ACTIVE)	NO

Environment variables

This command defines no environment variables.

2.1.7 vishnu_delete_user

Access

This command line can be used by ADMIN users only

Description

The vishnu_delete_user command removes a user from VISHNU

Example of use

vishnu_delete_user[-h] userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user who will be deleted from VISHNU	YES

Environment variables

This command defines no environment variables.

2.1.8 vishnu_close

Access

This command line can be used by any VISHNU user

Description

The vishnu_close command closes the session

Example of use

vishnu_close[-h]

This command defines no arguments.

Environment variables

This command defines no environment variables.

2.1.9 vishnu_change_password

Access

This command line can be used by any VISHNU user

Description

The vishnu_change_password command changes the password

Example of use

vishnu_change_password[-h] userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
passwordNew	string		passwordNew represents the new password of the user, it is an interactive parameter	YES

Environment variables

This command defines no environment variables.

2.1.10 vishnu_reset_password

Access

This command line can be used by ADMIN users only

Description

The vishnu_reset_password command resets the password of a user

Example of use

vishnu_reset_password[-h] userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user whose password will be reset	YES

Environment variables

This command defines no environment variables.

2.1.11 vishnu_add_local_account

Access

This command line can be used by any VISHNU user

Description

The vishnu_add_local_account command adds a new local user configuration

Example of use

vishnu_add_local_account [-h] userId machineId acLogin sshKeyPath homeDirectory

Parameters

Parameter	Туре	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier	YES YES YES YES
useria	sumg		of the user of the local user configuration	
machineId	string		The MachineId represents the identifier of the	VEC
machinera	sumg		machine associated to the local user configuration	1123
acLogin	string		accLogin represents the login of the user on the	VEC
acLogin			associated machine	ILS
sshKeyPath	string		sshKeyPath is the path of the ssh key of the user	VES
SSHIXCYI atti	sumg		on the associated machine	1125
homeDirectory	etring		HomeDirectory is the path of the home directory	YES
homeDirectory	string		of the user on the associated machine	IES

Environment variables

This command defines no environment variables.

2.1.12 vishnu_update_local_account

Access

This command line can be used by any VISHNU user

Description

The vishnu_update_local_account command updates a local user configuration

Example of use

vishnu_update_local_account[-h][-l acLogin][-s sshKeyPath][-d homeDirectory]userId machineId

Parameters

Parameter	Type	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier	YES
useria	sumg		of the user of the local user configuration	163
machineId	string		The MachineId represents the identifier of the	YES
macminerd	Sumg		machine associated to the local user configuration	1 E3
acLogin	string	1	acLogin represents the login of the user on the	NO
acLogiii	Sumg	1	associated machine	NO
sshKeyPath	string	S	sshKeyPath is the path of the ssh key of the user	NO
SSIIICYI atti	Sumg	8	on the associated machine	NO
homeDirectory	string	d	HomeDirectory is the path of the home directory	NO
	Sumg	l u	of the user on the associated machine	110

Environment variables

This command defines no environment variables.

2.1.13 vishnu_delete_local_account

Access

This command line can be used by any VISHNU user

Description

The vishnu_delete_local_account command removes a local user configuration (for a given user on a given machine) from VISHNU

Example of use

vishnu_delete_local_account [-h] userId machineId

Parameters

Parameter	Type	Option	Description	Required
			userId represents the VISHNU user identifier of	
userId	string		the user whose local configuration will be deleted	YES
			for the given machine	
			machineId represents the identifier of the	
machineId	string		machine whose local configuration will be	YES
			deleted for the given user	

Environment variables

This command defines no environment variables.

2.1.14 vishnu_save_configuration

Access

This command line can be used by ADMIN users only

Description

The vishnu_save_configuration command saves the configuration of VISHNU

Example of use

vishnu_save_configuration[-h]

Parameters

This command defines no arguments.

Environment variables

This command defines no environment variables.

2.1.15 vishnu_restore_configuration

Access

This command line can be used by ADMIN users only

Description

The vishnu_restore_configuration command restores the configuration of VISHNU

Example of use

vishnu_restore_configuration [-h] filePath

Parameter	Type	Option	Description	Required
filePath	string		The filePath is the path of the file used to restore VISHNU configuration	YES

This command defines no environment variables.

2.1.16 vishnu_add_machine

Access

This command line can be used by ADMIN users only

Description

The vishnu_add_machine command adds a new machine in VISHNU

Example of use

vishnu_add_machine[-h] name site language sshPublicKeyFile machineDescription

Parameters

Parameter	Type	Option	Description	Required
name	string		represents the name of the machine	YES
site	string		represents the location of the machine	YES
language	string		represents the language used for the description of the machine	YES
sshPublicKeyFile	string		contains the path to the SSH public key used by VISHNU to access local user accounts	YES
machineDescription	string		represents the description of the machine	YES

Environment variables

This command defines no environment variables.

2.1.17 vishnu_update_machine

Access

This command line can be used by ADMIN users only

Description

The vishnu_update_machine command updates machine description

Example of use

vishnu_update_machine[-h][-n name][-s site][-d machineDescription][-l language][-t status][-k sshPublicKeyFile] machineId

Parameter	Type	Option	Description	Required
machineId	string		represents the identifier of the machine	YES
name	string	n	represents the name of the machine	NO
site	string	S	represents the location of the machine	NO
machineDescription	string	d	represents the description of the machine	NO
language	string	1	represents the language used for the description of the machine	NO

Parameter	Type	Option	Description	Required
status	StatusType	t	represents the status of the machine	NO
sshPublicKeyFile	string	k	contains the path to the SSH public key used by VISHNU to access local user accounts	NO

This command defines no environment variables.

2.1.18 vishnu_delete_machine

Access

This command line can be used by ADMIN users only

Description

The vishnu_delete_machine command removes a machine from VISHNU

Example of use

vishnu_delete_machine[-h] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		machineId represents the identifier of the machine	YES

Environment variables

This command defines no environment variables.

2.1.19 vishnu_list_local_accounts

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_local_accounts command lists the local user configurations

Example of use

vishnu_list_local_accounts[-h][-a][-u userId][-i machineId]

Parameters

Parameter	Type	Option	Description	Required
adminListOption	boolean	a	is an admin option for listing all local configurations of all users	NO
userId	string	u	is an admin option for listing the local configurations of a specific user	NO
machineId	string	i	is an option for listing local user configurations on a specific machine	NO

Environment variables

This command defines no environment variables.

2.1.20 vishnu_list_machines

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_machines command lists the machines that are accessible through VISHNU

Example of use

vishnu_list_machines[-h][-u userId][-a][-m machineId]

Parameters

Parameter	Type	Option	Description	Req <mark>uired</mark>
userId	string	u	is an admin option for listing machines in which a specific user has a local configuration	NO
listAllMachine	boolean	a	is an option for listing all VISHNU machines	NO
machineId	string	m	is an option for listing information about a specific machine	NO

Environment variables

This command defines no environment variables.

2.1.21 vishnu_list_history_cmd

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_history_cmd command lists the commands

Example of use

vishnu_list_history_cmd[-h][-a][-u userId][-i sessionId][-s startDateOption][-e endDateOption]

Parameters

Parameter	Type	Option	Description	Required
adminListOption	boolean	a	is an admin option for listing all commands of all users	NO
userId	string	u	is an admin option for listing commands launched by a specific user identified by his/her userId	NO
sessionId	string	i	lists all commands launched within a specific session	NO
startDateOption	long	s	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	NO
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

Environment variables

This command defines no environment variables.

2.1.22 vishnu_list_options

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_options command lists the options of the user

Example of use

vishnu_list_options[-h][-a][-u userId][-n optionName]

Parameters

Parameter	Type	Option	Description	Req <mark>uire</mark> d
listAllDeftValue	boolean	a	is an option for listing all default option values defined by VISHNU administrator	NO
userId	string	u	is an admin option for listing the options of a specific user	NO
optionName	string	n	allows the user to get the value of a specific option identified by its name	NO

Environment variables

This command defines no environment variables.

2.1.23 vishnu_list_users

Access

This command line can be used by ADMIN users only

Description

The vishnu_list_users command lists VISHNU users

Example of use

vishnu_list_users[-h][-u userId][-i authSystemId]

Parameters

Parameter	Type	Option	Description	Required
userId	string	u	allows an admin to get information about a specific user identified by his/her userId	NO
authSystemId	string	i	is an option to list users who have local user-authentication configurations on a specific user-authentication system	NO

Environment variables

This command defines no environment variables.

2.1.24 vishnu_list_sessions

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_sessions command lists all sessions of the user

Example of use

vishnu_list_sessions[-h][-t status][-p sessionClosePolicy][-d sessionInactivityDelay][-m machineId][-a][-u userId][-i sessionId][-s startDateOption][-e endDateOption]

Parameters

Parameter	Type	Option	Description	Required
status	StatusType	t	specifies the status of the sessions which will be listed	NO
sessionClosePolicy	SessionCloseType	p	specifies the closure mode of the sessions which will be listed (CLOSE_ON_TIMEOUT or CLOSE_ON_DISCONNECT)	NO
sessionInactivityDelay	int	d	specifies the inactivity delay in seconds of the sessions which will be listed	NO
machineId	string	m	allows the user to list sessions opened on a specific client's machine by using its name	NO
adminListOption	boolean	a	is an admin option for listing all sessions of all users	NO
userId	string	u	is an admin option for listing sessions opened by a specific user	NO
sessionId	string	i	allows the user to list all commands launched within a specific session	NO
startDateOption	long	s	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	NO
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

Environment variables

This command defines no environment variables.

2.1.25 vishnu_configure_default_option

Access

This command line can be used by ADMIN users only

Description

The vishnu_configure_default_option command configures a default option value

Example of use

vishnu_configure_default_option[-h] optionName value

Parameters

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

Environment variables

This command defines no environment variables.

2.1.26 vishnu_configure_option

Access

This command line can be used by any VISHNU user

Description

The vishnu_configure_option command configures an option of the user

Example of use

vishnu_configure_option[-h] optionName value

Parameters

Parameter	Type	Option	Description	Req <mark>uire</mark> d
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

Environment variables

This command defines no environment variables.

2.1.27 vishnu_current_session_id

Access

This command line can be used by any VISHNU user

Description

The vishnu_current_session_id command display the session id

Example of use

vishnu_current_session_id[-h]

Parameters

This command defines no arguments.

Environment variables

This command defines no environment variables.

2.1.28 vishnu_add_auth_system

Access

This command line can be used by ADMIN users only

Description

The vishnu_add_auth_system command adds a new user-authentication system in VISHNU

Example of use

vishnu_add_auth_system [-h] [-b ldapBase] name URI authLogin authPassword userPasswordEncryption type

Parameter	Type	Option	Description	Required
name	string		corresponds to the user-authentication system's name	YES

Parameter	Type	Option	Description	Required	
URI	string		is the URI of the user-authentication systems (by	YES	
String			the form host:port for LDAP)	I LS	
authLogin	string		is the login used to connect to the	YES	
autilLogiii	string		user-authentication system	TLS	
authPassword	string		is the password used to connect to the	YES	
autiii ussword	sumg		user-authentication system	1 LS	
userPasswordEncryption	EncryptionMethod		represents the encryption method used to encrypt	YES	
useri usswordEneryption	Eliciyptioniviculou		user's password	TES	
type	AuthType		represents the type of the user-authentication	YES	
type	rumrype		systems	TES	
ldapBase	string	b	is an option for user-authentication system based	NO	
Таприлос	String		on LDAP which specifies the DN of the root entry	110	

This command defines no environment variables.

2.1.29 vishnu_update_auth_system

Access

This command line can be used by ADMIN users only

Description

The vishnu_update_auth_system command updates a user-authentication system in VISHNU

Example of use

vishnu_update_auth_system[-h][-n name][-i URI][-u authLogin][-w authPassword][-e userPasswordEncryption][-t type][-s status][-b ldapBase]authSystemId

Parameters

Parameter	Type	Option	Des cription	Required
authSystemId	string		is the identifier, generated by VISHNU, of the user-authentication system	YES
name	string	n	corresponds to the user-authentication system's name	NO
URI	string	i	is the URI of the user-authentication systems (by the form host:port for LDAP)	NO
authLogin	string	u	is the login used to connect to the user-authentication system	NO
authPassword	string	w	is the password used to connect to the user-authentication system	NO
userPasswordEncryption	EncryptionMethod	e	represents the encryption method used to encrypt user's password	NO
type	AuthType	t	represents the type of the user-authentication system	NO
status	StatusType	s	represents the status of the user-authentication system	NO
ldapBase	string	b	is an option for user-authentication system based on LDAP which specifies the DN of the root entry	NO

Environment variables

This command defines no environment variables.

2.1.30 vishnu_delete_auth_system

Access

This command line can be used by ADMIN users only

Description

The vishnu_delete_auth_system command removes a user-authentication system from VISHNU

Example of use

vishnu_delete_auth_system[-h] authSystemId

Parameters

Parameter	Type	Option	Descri ption	Required
authSystemId	string		authSystemId is the identifier of the user-authentication system	YES

Environment variables

This command defines no environment variables.

2.1.31 vishnu_list_auth_systems

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_auth_systems command lists VISHNU user-authentification systems

Example of use

vishnu_list_auth_systems[-h][-a][-f][-u userId][-i authSystemId]

Parameters

Parameter	Type	Option	Description	Required
listAllAuthSystems	boolean	a	is an option for listing all VISHNU user-authentication systems	NO
listFullInfo	boolean	f	is an admin option for listing full VISHNU user-authentication systems information such as all concerned only the administrator: authLogin, authPassword and userPasswordEncryption	NO
userId	string	u	is an admin option for listing all user-authentication systems in which a specific user has local user-authentication configs	NO
authSystemId	string	i	is an option for listing a specific user-authentication system	NO

Environment variables

This command defines no environment variables.

2.1.32 vishnu_add_auth_account

Access

This command line can be used by any VISHNU user

Description

The vishnu_add_auth_account command adds a new local user-authentication configuration

Example of use

vishnu_add_auth_account[-h][-u userId]authSystemId acLogin

Parameters

Parameter	Type	Option	Description	Required
authSystemId	string		is the identifier of the user-authentication system	YES
userId	string	u	represents an admin option to add a user-authentication account of a specific user	NO
acLogin	string		acLogin represents the login of the user on the associated user-authentication system	YES

Environment variables

This command defines no environment variables.

2.1.33 vishnu_update_auth_account

Access

This command line can be used by any VISHNU user

Description

The vishnu_update_auth_account command updates a local user-authentication configuration

Example of use

vishnu_update_auth_account [-h] [-u userId] [-l acLogin] authSystemId

Parameters

Parameter	Type	Option	Description	Required
authSystemId	string		is the identifier of the user-authentication system	YES
userId	string	u	represents an admin option to add a user-authentication account of a specific user	NO
acLogin	string	1	is an option to change the login of the user on the associated user-authentication system	NO

Environment variables

This command defines no environment variables.

2.1.34 vishnu_delete_auth_account

Access

This command line can be used by any VISHNU user

Description

The vishnu_delete_auth_account command removes a local user-authentication configuration from VISHNU

Example of use

vishnu_delete_auth_account[-h][-u userId] authSystemId

Parameter	Type	Option	Description	Required
authSystemId	string		authSystemId is the identifier of the	YES
aumsystemia	sumg		user-authentication system	TES
			is an admin option which represents the VISHNU	
userId	string	u	identifier of the user whose local	NO
			user-authentication configuration will be deleted	

This command defines no environment variables.

2.1.35 vishnu_list_auth_accounts

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_auth_accounts command lists local user-authentication configurations

Example of use

vishnu_list_auth_accounts[-h][-a][-u userId][-i authSystemId]

Parameters

Parameter	Type	Option	Description	Required
listAll	boolean	a	is an admin option for listing all local	NO
IISTAII	boolean	a	user-authentication configurations of VISHNU	NO
			is an admin option for listing all local	
userId	string	u	user-authentication configurations of a specific	NO
			user identified by his/her userId	
auth System Id string	atrina	;	is an option for listing local user-configuration of	NO
authSystemId	string	1	a specific user-authentication system	INO

Environment variables

This command defines no environment variables.

2.1.36 vishnu_set_ssh_key

Access

This command line can be used by any VISHNU user

Description

The vishnu_set_ssh_key command allows to add or remove a given key to/from the authorized keys of a user's remote account.

Example of use

vishnu_set_ssh_key[-h][-a][-r] rlogin sshPubKey

Parameter	Type	Option	Description	Required
rlogin	string		A ssh-compliant form of login information in the remote account (e.g. user@machine)	YES
sshPubKey	string		The key add to the remote account	YES
addOption	boolean	a	option for adding a key	NO
removeOption	boolean	r	option for removing a key	NO

This command defines no environment variables.

2.2 Parameters definitions

Enumeration UMS::AuthType Type

Name	Value
UNDEFINED	-1
LDAP	0

Enumeration UMS::CommandStatusType Type

Name	Value
FAILURE	0
SUCCESS	1

Enumeration UMS::EncryptionMethod Type

Name		Value
UNDEFIN	ED	-1
SSHA		 0

Enumeration UMS::PrivilegeType Type

Name	Value	
USER	0	
ADMIN	1	

Enumeration UMS::SessionCloseType Type

Name	V <mark>alue</mark>
DEFAULT	0
CLOSE_ON_TIMEOUT	1
CLOSE_ON_DISCONNECT	2

Enumeration UMS::StatusType Type

Name	Value
UNDEFINED	-1
INACTIVE	0
ACTIVE	1

Chapter 3

Commands specification for Tasks Management Service (TMS)

3.1 Command definitions

3.1.1 vishnu submit job

Access

This command line can be used by any VISHNU user

Description

The vishnu_submit_job command allows to submit a job consisting in running a given script on a machine.

Example of use

vishnu_submit_job[-h][-n name][-q queue][-t wallTime][-m memory][-P nbCpu][-N nbNodesAndCpu-PerNode][-o outputPath][-e errorPath][-M mailNotification][-u mailNotifyUser][-g group][-D workingDir][-T cpuTime][-Q][-L loadType][-F fileParams][-V textParams][-w workId][-S specificParams] machineId scriptFilePath

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the job must be submitted	YES
scriptFilePath	string		The path to the file containing the characteristics (job command, and batch scheduler directive required or optional) of the job to submit	YES
name	string	n	Assigns a job name. The default is the path of job	NO
queue	string	q	Assigns the queue or class of the job	NO
wallTime	int	t	The maximum wall-clock time during which the job can run (in seconds)	NO
memory	int	m	Is the memory size that the job requires (in MegaBytes)	NO
nbCpu	int	P	The number of cpu per node that the job requires	NO
nbNodesAndCpuPerNode	string	N	The number of nodes and processors per node (in the format nbNodes:nbCpuPerNode). For example if you want to use 4 nodes with 3 cpus for each node, you must specify these numbers by "4:3"	NO
outputPath	string	0	Assigns the path and file for job output	NO

Parameter	Type	Option	Description	Required
errorPath	string	e	Assigns the path and file for job error	NO
mailNotification	string	M	Assigns the notification type of the job. Valid type values are BEGIN, END, ERROR, and ALL (any state change)	NO
mailNotifyUser	string	u	The name of user to receive email notification of state changes as defined by the option mailNotification. The default value is the submitting user	NO
group	string	g	Assi <mark>gns a jo</mark> b group name.	NO
workingDir	string	D	Assigns a job remote working dir	NO
cpuTime	string	T	Assigns a job cpu limit time (in seconds or in the format [[HH:]MM:]SS)	NO
selectQueueAutom	boolean	Q	allows to select automatically a queue which has the number of nodes requested by the user	NO
loadType	LoadType	L	The criterion to automatically submit a job (for now three criterions are used: minimum number of waiting jobs, minimum number of running jobs and the total number of jobs). This option is used only if the machine identifier is equal to autom (this keyword is used to submit automatically a job)	NO
fileParams	string	F	Sets a list of local files as parameters for the script. These files will be uploaded onto the server before computing the script. At the execution time, each path can be accessed through an environment variable. E.gfileParams "PFILE1=/path/to/file1 PFILE2=/path/to/file2" or -F "PFILE1=/path/to/file1 PFILE2=/path/to/file2". At the execution, the environment variable \$PFILE1, for example, will point to the uploaded copy of the file /path/to/file1. The optionfileParam or -f allows to set each file individually. NOTE: The name of parameter as well as those of the corresponding environment are case-insensitive.	NO
textParams	string	V	Sets a list of parameters for the script so at the execution, each of parameter can be used as an environment variable. E.gtextParams "PARAM1=value1 PARAM2=value2" or -F "PARAM1=value1 PARAM2=value2", will set the environment variables named PARAM1 and PARAM2 with value1 and value2, respectively. The optiontextParam or -v allows to set each file individually. NOTE: The name of parameter as well as those of the corresponding environment are case-insensitive.	NO
workId	long	w	Sets the identifier of the Work to which the job is related	NO

Parameter	Type	Option	Description	Required
			Sets a list of specific parameters for the batch	
			scheduler so at the job submition, each of	
			parameter can be used by the batch shcheduler.	
			E.gspecificParams "PARAM1=value1	
			PARAM2=value2" or -S "PARAM1=value1	
specificParams	string	S	PARAM2=value2", will set the batch parameter	NO
			named PARAM1 and PARAM2 with value1 and	_
			value2, respectively.	
			NOTE: The name of parameter as well as those	
			of the corresponding environment are	
			case-insensitive.	

This command defines no environment variables.

3.1.2 vishnu_get_job_info

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_job_info command gets information on a job from its id

Example of use

vishnu_get_job_info[-h] machineId jobId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the job is running	YES
jobId	string		The id of the job	YES

Environment variables

This command defines no environment variables.

3.1.3 vishnu_get_job_progress

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_job_progress command gets the progression status of jobs

Example of use

vishnu_get_job_progress[-h][-i jobId][-u jobOwner] machineId

Parameter	Type	Option	Description	Required
machineId	etrina		Is the id of the machine to get the jobs	YES
macimicia	string		progression	1123

Parameter	Type	Option	Description	Required
jobId	string	i	Specifies the id of the job whose progression the user wants to see.	NO
jobOwner	string	u	Specifies the owner of the job.	NO

This command defines no environment variables.

3.1.4 vishnu_list_queues

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_queues command gets queues information

Example of use

vishnu_list_queues[-h][-q queueName] machineId

Parameters

Parameter	Туре	Option	Description	Required
machineId	string		Is the id of the machine that the user wants to list queues	YES
queueName	string	q	if it is given, listQueues gives information only of this queue	NO

Environment variables

This command defines no environment variables.

3.1.5 vishnu_list_jobs

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_jobs command gets a list of all submitted jobs on a machine.

Example of use

vishnu_list_jobs[-h][-i jobId][-P nbCpu][-d fromSubmitDate][-D toSubmitDate][-u owner][-s status][-p priority][-q queue][-S multipleStatus][-b][-w workId][-1] machineId

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the jobs are running	YES
jobId	string	i	lists the job with the specified id	NO
nbCpu	int	P	lists the jobs with the specified number of CPUs per node	NO
fromSubmitDate	long	d	lists the jobs submitted after the specified date (UNIX timestamp)	NO
toSubmitDate	long	D	lists jobs submitted before the specified date (UNIX timestamp)	NO

Parameter	Type	Option	Description	Required
owner	string	u	lists the jobs submitted by the specified owner	NO
status	JobStatus	S	lists the jobs with the specified status	NO
priority	JobPriority	p	lists the jobs with the specified priority	NO
queue	string	q	the jobs with the specified queue name	NO
multipleStatus	string	S	lists the jobs with the specified status (combination of multiple status). Its format contains the first letter or the value (interger) of each chosen status. For exemple to list the cancelled and terminated jobs, you use the format CT or 65	NO
batchJob	boolean	b	allows to select all jobs submitted through the underlying batch scheduler (jobs submitted through vishnu and out of vishnu)	NO
workId	long	w	Allows to gather information about jobs related to a given Work.	NO
listAll	boolean	1	lists all information of the job	NO

This command defines no environment variables.

3.1.6 vishnu_get_job_output

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_job_output command gets standard output and error output files of a job given its id

Example of use

vishnu_get_job_output[-h][-o outDir] machineId jobId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		gets outputPath and errorPath of a job from its id	YES
jobId	string		The Id of the job	YES
outDir	string	o	The output directory where the files will be stored (default is current directory)	NO

Environment variables

This command defines no environment variables.

3.1.7 vishnu_get_completed_jobs_output

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_completed_jobs_output command gets standard output and error output files of completed jobs (applies only once for each job)

Example of use

vishnu_get_completed_jobs_output [-h] [-o outDir] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the jobs are	YES
machinera			been submitted	
outDir string	string	0	Specifies the output directory where the files will	NO
OutDII	Sumg	О	be stored (by default, the current directory)	NO

Environment variables

This command defines no environment variables.

3.1.8 vishnu_cancel_job

Access

This command line can be used by any VISHNU user

Description

The vishnu_cancel_job command allows to cancel a job submitted on a given machine.

Example of use

vishnu_cancel_job[-h] machineId jobId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine on which the job is running	YES
jobId	string		The Id of the job	YES

Environment variables

This command defines no environment variables.

3.1.9 vishnu_add_work

Access

This command line can be used by any VISHNU user

Description

The vishnu_add_work command allows to create a work consisting in running jobs.

Example of use

vishnu_add_work[-h][-a applicationId][-n subject][-l priority][-u owner][-e estimatedHour][-d
description][-p projectId][-m machineId][-n nbCPU]

Parameter	Type	Option	Description	Required
applicationId	string	0	Is the id of the machine on which the job has	NO
аррисацопи	sumg	a	been submitted.	NO
subject	string	n	Represents the name assigned to the work.	NO
priority	int	1	Represents the work priority.	NO
owner	string	u	Represents the job owner.	NO

Parameter	Type	Option	Description	Required
estimatedHour	long	e	Is the maximum wall-clock time during which the job can run (in seconds)	NO
description	string	d	Is the textual description of the job.	NO
projectId	string	p	Is the id of the session that contained the job submission command	NO
machineId	string	m	Is the id of the session that contained the job submission command	NO
nbCPU	int	n	The current status of the job.	NO

This command defines no environment variables.

3.2 Parameters definitions

Enumeration TMS::JobPriority Type

Name	Value
UNDEFINED	-1
VERY_LOW	1
LOW	2
NORMAL	3
HIGH	4
VERY_HIGH	5

Enumeration TMS::JobStatus Type

Name	Value
UNDEFINED	-1
SUBMITTED	1
QUEUED	2
WAITING	3
RUNNING	4
TERMINATED	5
CANCELLED	6
ALREADY_DOWNLOADEI	7

Enumeration TMS::LoadType Type

Name	Value
USE_NB_WAITING_JOBS	0
USE_NB_JOBS	1
USE_NB_RUNNING_JOBS	2

Enumeration TMS::QueuePriority Type

Name	Value
UNDEFINED	-1
VERY_LOW	1
LOW	2
NORMAL	3
HIGH	4

Name	Value
VERY_HIGH	5

Enumeration TMS::QueueStatus Type

Name	Value
NOT_STARTED	0
STARTED	1
RUNNING	2

Chapter 4

Commands specification for Information Management Service (IMS)

4.1 Command definitions

4.1.1 vishnu export commands

Access

This command line can be used by any VISHNU user

Description

The vishnu_export_commands command exports all the commands made by a user during a session

Example of use

vishnu_export_commands[-h][-t exportType] oldSessionId

Parameters

Parameter	Type	Option	Description	Required
oldSessionId	string		The id of the session to export (session has ended)	YES
exportType	ExportType	t	The type to export	NO

Environment variables

This command defines no environment variables.

4.1.2 vishnu_get_metric_current_value

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_metric_current_value command displays the current values of system metrics

Example of use

vishnu_get_metric_current_value[-h][-t metricType] machineId

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
metricType	MetricType	t	The type of the metric	NO

This command defines no environment variables.

4.1.3 vishnu_get_metric_history

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_metric_history command displays the history of values of a system metric

Example of use

vishnu_get_metric_history[-h][-s startTime][-e endTime][-t type] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
startTime	long	S	The start time to get the history	NO
endTime	long	e	The end time to get the history	NO
type	MetricType	t	The type of metric searched	NO

Environment variables

This command defines no environment variables.

4.1.4 vishnu_get_processes

Access

This command line can be used by ADMIN users only

Description

The vishnu_get_processes command displays the list of the VISHNU processes running on machines

Example of use

vishnu_get_processes[-h][-p machineId]

Parameters

Parameter	Type	Option	Description	Required
machineId	string	p	The id of the machine	NO

Environment variables

This command defines no environment variables.

4.1.5 vishnu_set_system_info

Access

This command line can be used by ADMIN users only

Description

The vishnu_set_system_info command updates the system information of a machine

Example of use

vishnu_set_system_info[-h][-m memory][-d diskSpace] machineId

Parameters

Parameter	Type	Option	Description	Required
memory	long	m	Amount of RAM memory available on the machine (in Bytes)	NO
diskSpace	long	d	Amount of disk space available on the machine (in Bytes)	NO
machineId	string		The id of the machine	YES

Environment variables

This command defines no environment variables.

4.1.6 vishnu_set_system_threshold

Access

This command line can be used by ADMIN users only

Description

The vishnu_set_system_threshold command sets a threshold on a machine of a system

Example of use

vishnu_set_system_threshold[-h] value machineId type handler

Parameters

Parameter	Type	Option	Description	Required
value	long		The value of the threshold	YES
machineId	string		The machine ID the threshold is available	YES
type	MetricType		The type of the threshold	YES
handler	string		The userId of the admin responsible for handling	YES
nanarei	Sums		the threshold problems	125

Environment variables

This command defines no environment variables.

4.1.7 vishnu_get_system_threshold

Access

This command line can be used by ADMIN users only

Description

The vishnu_get_system_threshold command gets a system threshold on a machine

Example of use

vishnu_get_system_threshold[-h][-m machineId][-t metricType]

Parameter	Type	Option	Description	Required
machineId	string	m	The id of the machine where the metric is defined	NO
metricType	MetricType	t	The type of the metric	NO

This command defines no environment variables.

4.1.8 vishnu_define_user_identifier

Access

This command line can be used by ADMIN users only

Description

The vishnu_define_user_identifier command defines the shape of the identifiers automatically generated for the users

Example of use

vishnu_define_user_identifier[-h] format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Environment variables

This command defines no environment variables.

4.1.9 vishnu_define_machine_identifier

Access

This command line can be used by ADMIN users only

Description

The vishnu_define_machine_identifier command defines the shape of the identifiers automatically generated for the machines

Example of use

vishnu_define_machine_identifier[-h] format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Environment variables

This command defines no environment variables.

4.1.10 vishnu_define_job_identifier

Access

This command line can be used by ADMIN users only

Description

The vishnu_define_job_identifier command defines the shape of the identifiers automatically generated for the jobs

Example of use

vishnu_define_job_identifier[-h] format

Parameters

Parameter	Type	Option	De scription	Required
format	string		The new format to use	YES

Environment variables

This command defines no environment variables.

4.1.11 vishnu_define_transfer_identifier

Access

This command line can be used by ADMIN users only

Description

The vishnu_define_transfer_identifier command defines the shape of the identifiers automatically generated for the file transfers

Example of use

vishnu_define_transfer_identifier[-h] format

Parameters

Parameter	Туре	Option	Description	Required
format	string		The new format to use	YES

Environment variables

This command defines no environment variables.

4.1.12 vishnu_define_auth_identifier

Access

This command line can be used by ADMIN users only

Description

The vishnu_define_auth_identifier command defines the shape of the identifiers automatically generated for the authentication system

Example of use

vishnu_define_auth_identifier[-h] format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Environment variables

This command defines no environment variables.

4.1.13 vishnu_load_shed

Access

This command line can be used by ADMIN users only

Description

The vishnu_load_shed command sheds load on a machine

Example of use

vishnu_load_shed[-h] machineId loadShedType

Parameters

Parameter	Type	Option	Descri ption	Req <mark>uired</mark>
machineId	string		The id of the machine to stop	YES
			Selects a load shedding mode (SOFT: stops all	
loadShedType	LoadShedType		services and they can be restarted, HARD: stops	YES
			all services, they cannot be restarted)	

Environment variables

This command defines no environment variables.

4.1.14 vishnu_set_update_frequency

Access

This command line can be used by ADMIN users only

Description

The vishnu_set_update_frequency command sets the update frequency of the IMS tables

Example of use

vishnu_set_update_frequency[-h] freq

Parameters

Parameter	Type	Option	Description	Required
freq	int		Frequency the data are updated, in second	YES

Environment variables

This command defines no environment variables.

4.1.15 vishnu_get_update_frequency

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_update_frequency command gets the update frequency of the IMS database

Example of use

vishnu_get_update_frequency[-h]

This command defines no arguments.

Environment variables

This command defines no environment variables.

4.1.16 vishnu_stop

Access

This command line can be used by ADMIN users only

Description

The vishnu_stop command to stop (and do not try to relaunch) a SeD

Example of use

vishnu_stop[-h] processName machineId

Parameters

Parameter	Type	Option	Description	Required
processName	string		The name of the process (the name of the executable)	YES
machineId	string	7	The id of the machine	YES

Environment variables

This command defines no environment variables.

4.1.17 vishnu_get_system_info

Access

This command line can be used by any VISHNU user

Description

The vishnu_get_system_info command to get the system info on a machine

Example of use

vishnu_get_system_info[-h][-m machineId]

Parameters

Parameter	Type	Option	Description	Required
machineId	string	m	The machine id	NO

Environment variables

This command defines no environment variables.

4.1.18 vishnu_restart

Access

This command line can be used by ADMIN users only

Description

The vishnu_restart command to restart a SeD or a MA

Example of use

vishnu_restart[-h][-v vishnuConf][-t sedType] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine where to restart	YES
vishnuConf	string	v	The path to the vishnu configuration file	NO
sedType	SeDType	t	The type of the vishnu sed	NO

Environment variables

This command defines no environment variables.

4.1.19 vishnu_define_work_identifier

Access

This command line can be used by ADMIN users only

Description

The vishnu_define_work_identifier command defines the shape of the identifiers automatically generated for the work

Example of use

vishnu_define_work_identifier[-h] format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Environment variables

This command defines no environment variables.

4.2 Parameters definitions

Enumeration IMS::ExportType Type

Name	Value
UNDEFINED	0
SHELL	1

Enumeration IMS::LoadShedType Type

Name	Value
UNDEFINED	0
HARD	1
SOFT	2

Enumeration IMS::MetricType Type

Name	Value
UNDEFINED	0

Name	Value
CPUUSE	1
FREEDISKSPACE	2
FREEMEMORY	3

Enumeration IMS::ProcessState Type

Name	Value
UNDEFINED	0
RUNNING	1
DOWN	2
DELETED	3

Enumeration IMS::SeDType Type

Name	Value
UNDEFINED	0
UMS	1
TMS	2
FMS	3
IMS	4

Chapter 5

Commands specification for File Management Service (FMS)

5.1 Command definitions

5.1.1 vishnu touch

Access

This command line can be used by any VISHNU user

Description

The vishnu_touch command creates files on remote machines.

Example of use

vishnu_touch[-h] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file to create following the pattern [host:]file path	YES

Environment variables

This command defines no environment variables.

5.1.2 vishnu_mkdir

Access

This command line can be used by any VISHNU user

Description

The vishnu_mkdir command creates directories on remote machines.

Example of use

vishnu_mkdir[-h][-p]path

Parameter	Type	Option	Description	Required
path	string		The directory to create following the pattern [host:]directory path	YES
isRecursive	boolean	p	It specifies when the create command is recursive (create parent directory also) or not	NO

This command defines no environment variables.

5.1.3 vishnu_rm

Access

This command line can be used by any VISHNU user

Description

The vishnu_rm command removes files from remote hosts.

Example of use

vishnu_rm[-h][-r]path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file to remove following the pattern [host:]file path	YES
isRecursive	boolean	r	It specifies when the remove command is recursive (case of directory) or not	NO

Environment variables

This command defines no environment variables.

5.1.4 vishnu_rmdir

Access

This command line can be used by any VISHNU user

Description

The vishnu_rmdir command removes directories (and subdirectories) from remote machines.

Example of use

vishnu_rmdir[-h] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The directory to remove following the pattern [host:]directory path	YES

Environment variables

This command defines no environment variables.

5.1.5 vishnu_chgrp

Access

This command line can be used by any VISHNU user

Description

The vishnu_chgrp command changes group owner of remote files/directories.

Example of use

vishnu_chgrp [-h] group path

Parameters

Parameter	Type	Option	Description	Req <mark>uired</mark>
group	string		the new group owner of file/directory	YES
path	string		The file/directory following the pattern [host:]file path	YES

Environment variables

This command defines no environment variables.

5.1.6 vishnu_chmod

Access

This command line can be used by any VISHNU user

Description

The vishnu_chmod command changes access rights of remote files/directories.

Example of use

vishnu_chmod[-h] mode path

Parameters

Parameter	Type	Option	Option Description	
mode	mode_t		the access rigths of file/directory in octal system	YES
path	string		The file/directory following the pattern [host:]file path	YES

Environment variables

This command defines no environment variables.

5.1.7 vishnu_head

Access

This command line can be used by any VISHNU user

Description

The vishnu_head command displays a few first lines of files located on remote machines.

Example of use

vishnu_head[-h][-n nline] path

Parameter	Type	Option	Description	Required
path	string		The file following the pattern [host:]file path	YES
nline	int	n	the number of line to get	NO

This command defines no environment variables.

5.1.8 vishnu_tail

Access

This command line can be used by any VISHNU user

Description

The vishnu_tail command displays a few last lines of files located on remote machines

Example of use

vishnu_tail[-h][-n nline] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file following the pattern [host:]file path	YES
nline	int	n	the number of line to get	NO

Environment variables

This command defines no environment variables.

5.1.9 vishnu_more

Access

This command line can be used by any VISHNU user

Description

The vishnu_more command displays content of files located on remote machines

Example of use

vishnu_more[-h] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file to display following the pattern [host:]file path	YES

Environment variables

This command defines no environment variables.

5.1.10 vishnu_ls

Access

This command line can be used by any VISHNU user

Description

The vishnu_ls command displays the content of a remote directory

Example of use

 $vishnu_ls[-h][-1][-a]$ path

Parameters

Parameter	Type	Option	•	
path	string		The directory to list following the pattern [host:]directory path	YES
longFormat	boolean	1	It specifies the long display format (all available file informations)	NO
allFiles	boolean	a	Allows to display all files including hidden files	NO

Environment variables

This command defines no environment variables.

5.1.11 vishnu_cp

Access

This command line can be used by any VISHNU user

Description

The vishnu_cp command executes a synchronous copy of file.

Example of use

vishnu_cp[-h][-r][-t trCommand] src dest

Parameters

Parameter	Туре	Option	Des cription	Required	
src	string		The source file to copy following the pattern	YES	
	Sumg		[host:]file path		
dest	string		The path of the destination file	YES	
isRecursive	boolean		It specifies when the copy is recursive (case of	NO	
	boolean	1	directory) or not	NO	
trCommand	TransferCommand	t	the command to use to perform file transfer	NO	

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer	NO	YES

5.1.12 vishnu_acp

Access

This command line can be used by any VISHNU user

Description

The vishnu_acp command executes an asynchronous copy of file.

Example of use

vishnu_acp[-h][-r][-t trCommand] src dest

Parameters

Parameter	Type	Option	Description	Required
src	string		The source file to copy following the pattern [host:]file path	YES
dest	string		The path of the destination file	YES
isRecursive	boolean	r	It specifies when the copy is recursive (case of directory) or not	NO
trCommand	TransferCommand	t	the command to use to perform file transfer	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer	NO	YES

5.1.13 vishnu_mv

Access

This command line can be used by any VISHNU user

Description

The vishnu_mv command executes a synchronous move of file.

Example of use

vishnu_mv[-h][-r][-t trCommand] src dest

Parameters

Parameter	Type	Option	Description	Required
src	string		The source file to move following the pattern	YES
string		[host:]file path	1 LS	
dest	string		The path of the destination file	YES
isRecursive	isRecursive boolean	r	It specifies when the copy is recursive (case of	NO
ISRECUISIVE DOOICAII	1	directory) or not	110	
trCommand	TransferCommand	t	the command to use to perform file transfer	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer	NO	YES

5.1.14 vishnu_amv

Access

This command line can be used by any VISHNU user

Description

The vishnu_amv command executes an asynchronous move of file.

Example of use

 $\verb|vishnu_amv[-h][-r][-t|| \textit{trCommand}] src dest$

Parameters

Parameter	Type	Option	Description	Required
src	string		The source file to move following the pattern [host:]file path	YES
dest	string		The path of the destination file	YES
isRecursive	boolean	r	It specifies when the copy is recursive (case of directory) or not	NO
trCommand	TransferCommand	t	the command to use to perform file transfer	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer	NO	YES

5.1.15 vishnu_stop_file_transfer

Access

This command line can be used by any VISHNU user

Description

The vishnu_stop_file_transfer command stops an execution of a set of file transfers.

Example of use

vishnu_stop_file_transfer[-h][-i transferId][-m fromMachineId][-u userId]

Parameters

Parameter	Type	Option	Description	Required
transferId	string	i	a given transfer id	NO
fromMachineId	string	m	the machine that is the source or destination of the file transfer	NO
userId	string	u	allows an admin to stop file transfers of a specific user	NO

Environment variables

This command defines no environment variables.

5.1.16 vishnu_list_file_transfers

Access

This command line can be used by any VISHNU user

Description

The vishnu_list_file_transfers command displays the history of all file transfers submitted by User.

Example of use

vishnu_list_file_transfers[-h][-t transferId][-m fromMachineId][-u userId][-s status]

Parameters

Parameter	Type	Option	Description	Required
transferId	string	t	a given transfer id	NO
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows the admin to list file transfers initiated by a specific user	NO
status	Status	S	the file transfer status	NO

Environment variables

This command defines no environment variables.

5.1.17 vishnu_stat

Access

This command line can be used by any VISHNU user

Description

The vishnu_stat command displays the information of files.

Example of use

vishnu_stat[-h] path

Parameters

Parameter	Type	Option	D escription	Required
path	string		The file whose inode information will be displayed	YES

Environment variables

This command defines no environment variables.

5.2 Parameters definitions

Enumeration FMS::FileType Type

Name	Value
BLOCK	0
CHARACTER	1
DIRECTORY	2
SYMBOLICLINK	3
SCKT	4
FIFO	5
REGULAR	6

Enumeration FMS::Status Type

Name	Value
INPROGRESS	0
COMPLETED	1

Name	Value
CANCELLED	2
FAILED	3
UNDEFINED	4

Enumeration FMS::TransferCommand Type

Name	Value
SCP	0
RSYNC	1
UNDEFINED	2