Lecture 6: Assembly Programs

- Today's topics:
 - Control instructions
 - Procedures
 - Examples

Procedures

- Each procedure (function, subroutine) maintains a scratchpad of register values – when another procedure is called (the callee), the new procedure takes over the scratchpad – values may have to be saved so we can safely return to the caller
 - parameters (arguments) are placed where the callee can see them
 - control is transferred to the callee
 - acquire storage resources for callee
 - execute the procedure
 - place result value where caller can access it
 - return control to caller

Jump-and-Link

- A special register (storage not part of the register file) maintains the address of the instruction currently being executed – this is the program counter (PC)
- The procedure call is executed by invoking the jump-and-link (jal) instruction the current PC (actually, PC+4) is saved in the register \$ra and we jump to the procedure's address (the PC is accordingly set to this address)

return address jal NewProcedureAddress

- Since jal may over-write a relevant value in \$ra, it must be saved somewhere (in memory?) before invoking the jal instruction
- How do we return control back to the caller after completing the callee procedure? ถ้าทำฟังค์ชั่นซ้อนหลายๆชั้นมันจะ return ไม่ได้เพราะ ra ก่อนโดนเขียนทับ โลยต้องเซฟ ra ไว้ที่อื่นก่อน

The Stack

The register scratchpad for a procedure seems volatile – it seems to disappear every time we switch procedures – a procedure's values are therefore backed up in memory on a stack

High address

Proc A's values

Proc B's values

Proc C's values

Stack grows this way

Low address

Proc A call Proc B call Proc C return return return

Storage Management on a Call/Return

- A new procedure must create space for all its variables on the stack
- Before/after executing the jal, the caller/callee must save relevant values in \$s0-\$s7, \$a0-\$a3, \$ra, temps into the stack space กระดาษทดของใครของมัน หาก jal ควรเซฟตัวแปรไว้ที่อื่นด้วย
- Arguments are copied into \$a0-\$a3; the jal is executed
- After the callee creates stack space, it updates the value of \$sp
- Once the callee finishes, it copies the return value into \$v0, frees up stack space, and \$sp is incremented (เราเริ่มจากเลขมากมาน้อย)
- On return, the caller/callee brings in stack values, ra, temps into registers
- The responsibility for copies between stack and registers may fall upon either the caller or the callee

Example 1 (pg. 98)

```
int leaf_example (int g, int h, int i, int j)
{
    int f;
    f = (g + h) - (i + j);
    return f;
}
```

Notes:

In this example, the callee took care of saving the registers it needs.

The caller took care of saving its \$ra and \$a0-\$a3.

เขียนเก่งจริงไม่ต้องใช้ Stack

Could have avoided using the stack altogether.

leaf example: \$sp, \$sp, -12 addi \$t1, 8(\$sp) SW \$t0, 4(\$sp) SW sw \$s0, 0(\$sp) \$t0, \$a0, \$a1 add \$t1, \$a2, \$a3 add \$s0, \$t0, \$t1 sub \$v0 \$s0 \$zero add \$s0, 0(\$sp) W \$t0, 4(\$sp) W \$t1, 8(\$sp) W \$sp, \$sp, 12 addi \$ra jr

Saving Conventions

 Caller saved: Temp registers \$t0-\$t9 (the callee won't bother saving these, so save them if you care), \$ra (it's about to get over-written), \$a0-\$a3 (so you can put in new arguments)

- Callee saved: \$s0-\$s7 (these typically contain "valuable" data)
- Read the Notes on the class webpage on this topic

Example 2 (pg. 101)



```
int fact (int n)
{
    if (n < 1) return (1);
       else return (n * fact(n-1));
}</pre>
```

Notes:

The caller saves \$a0 and \$ra in its stack space.

Temp register \$t0 is never saved.

```
fact:
          $t0, $a0, 1
  slti
         $t0, $zero, L1
  beq
         $v0, $zero, 1
   addi
         $ra
   jr
L1:
         $sp, $sp, -8
  addi
         $ra, 4($sp) save ra
  SW
         $a0, 0($sp) save n
  SW
         $a0, $a0, -1
  addi
         fact
  ial
         $a0, 0($sp)
  W
         $ra, 4($sp)
  lw
         $sp, $sp, 8
  addi
         $v0, $a0, $v0
  mul
         $ra
  ir
```