



Advanced Service Assets

"PDTool" Promotion and Deployment Tool PDTool Studio Installer User Guide

Data Virtualization Business Unit Advanced Services
September 2015

TABLE OF CONTENTS

INTRODUCTION	4
License	4
Purpose	
Audience	
Platform Support	5
PDTOOL STUDIO (VCS INTEGRATION) INSTALLER USER GUID	DE 6
Pre-Requisite Checklist.	6
1. Network Connection:	
2. JRE7 Installed:	
3. Version Control System (VCS) Access:	6
4. Pre-Configured PDTool Studio Installer:	6
User Installation Procedure	6
1. Unzip the PDTool Studio Installer Zip File:	
2. Install Cisco PDTool Studio:	6
3. User Prompts:	
4. What Gets Executed?	
5. Logging into CIS Studio "Important":	10
6. Managing Errors:	10
7. Verify Installation:	10
CONCLUSION	12
Concluding Remarks	12
How you can help!	

DOCUMENT CONTROL

Version History

Versio n	Date	Author	Description
1.0	09/18/2015	Mike Tinius	Initial revision for Installer User Guide

Related Documents

Document	Date	Author
Cisco AS Promotion and Deployment Tool - PDTool Studio Installer Admin Guide	Cisco PDTool Studio Installer Admin.pdf	Mike Tinius

Data Virtualization Business Unit (DVBU) Products Referenced

DVBU Product Name	Version	
Composite Information Server	6.2, 7.0	

INTRODUCTION

License

(c) 2015 Cisco and/or its affiliates. All rights reserved.

This software is released under the Eclipse Public License. The details can be found in the file LICENSE. Any dependent libraries supplied by third parties are provided under their own open source licenses as described in their own LICENSE files, generally named .LICENSE.txt. The libraries supplied by Cisco as part of the Composite Information Server/Cisco Data Virtualization Server, particularly csadmin-XXXX.jar, csarchive-XXXX.jar, csbase-XXXX.jar, csclient-XXXX.jar, cscommon-XXXX.jar, csext-XXXX.jar, csjdbc-XXXX.jar, csserverutil-XXXX.jar, csserver-XXXX.jar, cswebapi-XXXX.jar, and customproc-XXXX.jar (where -XXXX is an optional version number) are provided as a convenience, but are covered under the licensing for the Composite Information Server/Cisco Data Virtualization Server. They cannot be used in any way except through a valid license for that product.

This software is released AS-IS!. Support for this software is not covered by standard maintenance agreements with Cisco. Any support for this software by Cisco would be covered by paid consulting agreements, and would be billable work.

Purpose

The User Guide provides a PDTool Studio User with the steps to install PDTool Studio on Windows using the PDTool Studio Installer.

This is the part of PDTool that provides VCS integration with CIS Studio. The other part of PDTool is simply called PDTool and is focused on deployment and testing facilities.

What gets installed?

- Cisco PDToolStudio6.2 or PDToolStudio7.0.0
- VCS Client if the Administrator chooses to pre-configure the \VCSClients folder

Where do the files get copied?

- Recommended default location:
 C:\Users\%USERNAME%\.compositesw\PDToolStudio[6.2|7.0.0]_[TFS|SVN|GIT|P4|C
 VS1
 - E.g. C:\Users\user1\.compositesw\PDToolStudio7.0.0_TFS
 - \PDToolStudio PDToolStudio VCS integration directory
 - WCSClients Pre-configured VCS clients are optional if installed elsewhere.
 - \SVN client Subversion client
 - \TFS TEE client Team Explorer Everywhere client
 - \GIT_client Git client
 - \P4 client Perforce client
 - \CVS client CVS client

Audience

This document is intended to provide guidance for the following users:

 For CIS Developers only who have Cisco Studio installed and want to connect to a version control system (VCS) such as TFS or Subversion.

Platform Support

The PDTool Studio Installer is only supported on Windows.

PDTOOL STUDIO (VCS INTEGRATION) INSTALLER USER GUIDE

Pre-Requisite Checklist

The following is a list the User will need to check before installing for PDToolStudio:

1. Network Connection:

Each user must be connected to a network and have access to the VCS server.

2. JRE7 Installed:

JRE 7 (1.7) must be pre-installed on the target computer before installing PDTool. Each user must perform this action.

If Cisco Studio 7.0 is installed, it is possible to utilize that JRE: CIS_HOME\jre or you can use the one installed in the "C:\Program Files\Java\jre7".

3. Version Control System (VCS) Access:

Each user must perform this action.

The user must submit a request in advance to their organization to get access to a version control system (VCS) repository prior to installation of PDTool.

4. Pre-Configured PDTool Studio Installer:

The PDTool Studio Administrator has "pre-configured" the PDTool Studio Installer and provided the location of the zip file to the user.

User Installation Procedure

1. Unzip the PDTool Studio Installer Zip File:

- a. This is the package that the Administrator has "pre-configured" for the organization. Unzip to any directory on your windows machine e.g. [C:\Temp].
 - i. PDToolStudio6.2_installer.zip
 - ii. PDToolStudio7.0.0_installer.zip
- b. Use PKZip and select "Extract Here" which will extract the file to the C:\Temp directory as shown below. If you use the Windows "Extract All", then it is recommended to remove the trailing folder
 - i. Location: C:\Temp\PDToolStudio6.2_Installer
 - ii. Location: C:\Temp\PDToolStudio7.0_Installer

2. Install Cisco PDTool Studio:

a. Purpose – The purpose of this is to install the "pre-configure" batch files for your organization so that you have a consistent and uniform configuration across the developer and tester user base.

b. Location

- a. [C:\Temp]\PDToolStudio6.2_installer\installer
- b. [C:\Temp]\PDToolStudio7.0.0_installer\installer

c. For any VCS [TFS,SVN,GIT,P4,CVS] Execute:

- Edit: PDToolStudio-VCS.bat and provide any default values that require modification. The variables should have been pre-configured by the PDTool Studio administrator.
- Execute by double-clicking on the following batch file from windows explorer:

PDToolStudio-VCS.bat

- Acknowledge Cisco Open Source License
- Follow the "Prompts" section below for detailed information.

3. User Prompts:

- a. Purpose The user is prompted for the following parameters unless this information is provided as parameters on the command line. The default values are provided within the square brackets. Press enter with no input to accept the default value or type your value and press enter.
- b. Prompts:

Enter

I_PDTOOL_INSTALL_SCRIPTS=[%DEF_PDTOOL_INSTALL_SCRIPTS%]:

Location of the PDTool installation scripts. E.g.
 C:\Temp\PDToolStudio7.0.0_installer

License Acknowledgement

- Use space bar to page through license
- Review and acknowledge the open source license [Y].

Enter I_JAVA_HOME=[%DEF_JAVA_HOME%]:

I_JAVA_HOME=JRE7 home folder. E.g. C:\Program Files\Java\jre7

Enter

I_PDTOOL_DESTINATION_HOME=[%DEF_PDTOOL_DESTINATION_HOME
%]:

- I_PDTOOL_DESTINATION_HOME The destination home folder for the PDTool installation and associated binaries.
- TFS: C:\Users\%USERNAME%\.compositesw\PDToolStudio7.0.0 TFS
- SVN: C:\Users\%USERNAME%\.compositesw\PDToolStudio7.0.0_SVN
- GIT: C:\Users\%USERNAME%\.compositesw\PDToolStudio7.0.0_GIT
- P4: C:\Users\%USERNAME%\.compositesw\PDToolStudio7.0.0_P4
- CVS: C:\Users\%USERNAME%\.compositesw\PDToolStudio7.0.0_CVS

Enter

I_PDTOOL_DESTINATION_DIR=[%DEF_PDTOOL_DESTINATION_DIR%]:

 The destination directory name for the PDTool Studio installation and associated binaries. e.g. PDToolStudio

Enter I_OVERWRITE_DECISION=[N]:

This prompt only comes up when the target PDTool directory exists. It allows the user to decide whether they want to overwrite that directory or not. Enter Y to overwrite the existing directory.

Enter I_VCS_TYPE=[%DEF_VCS_TYPE%]:

I VCS TYPE - The version control type [TFS|SVN|GIT|P4|CVS]

Enter I_VCS_HOME=[%DEF_VCS_HOME%]:

This is the location of the VCS script executable. E.g.
 C:\Users\%USERNAME%\.compositesw\PDToolStudio7.0.0_SVN\V
 CSClients\SVN_client

Enter I_VCS_REPOSITORY_URL=[%DEF_VCS_REPOSITORY_URL%]:

- Note: make sure the forward slashes are escaped with 4 slashes: https:///url
- TFS: The TFS repository URL pointing to the repository collection.
 e.g. http:///hostname.domain.com/tfs/DefaultCollection
- SVN: The subversion repository path at trunk or any folder designation within trunk. e.g. https:///svn.hostname.com/svnrepos/myrepo/trunk/main

Enter I_VCS_PROJECT_ROOT=[%DEF_VCS_PROJECT_ROOT%]:

E.g. SVN: cis_objects

Enter I VCS USERNAME=[%USERNAME%]:

 This is your user name regardless of whether it is TFS or Subversion and is used to connect to the VCS repository. The user must submit a request to get access to a repository prior to installation of PDTool.

Enter I_VCS_DOMAIN=[%DEF_VCS_DOMAIN%]:

When using TFS, include the VCS domain such as "@CORP". The result for the I_VCS_USERNAME would look like "username@CORP". When using subversion, put a single space in the domain so that the script accepts this and continues. The script

will remove the space later on. The I_VCS_DOMAIN will be automatically appended to I_VCS_USERNAME.

Enter I_VCS_PASSWORD=<type-your-vcs-password>

• This is your VCS password which will be encrypted.

Enter I_WORKSPACE_NAME=[%DEF_VCS_WORKSPACE_NAME%]:

 The PDToolStudio VCS workspace name such as SVNsw7 or TFSsw7.

Enter I_CIS_USERNAME=[%USERNAME%]:

 This is your user name regardless that will be used to connect to CIS.

Enter I_CIS_DOMAIN=[%DEF_CIS_DOMAIN%]:

 This is the CIS domain which is used by the I_CIS_USERNAME to connect to Composite. E.g. Idap or composite

Enter I CIS PASSWORD=<type-your-cis-password>

This is your password which will be encrypted.

Enter I CONFIG PROPERTY FILE=[%DEF CONFIG PROPERTY FILE%]

 This is the default PDTool Studio configuration property file that the user will use to set the context for which VCS environment to connect to. E.g. studio_SVN.properties or studio_TFS.properties.

The variables are displayed

Enter I_VARS_DECISION [Y or N] – If "Y", then installation commences. If "N" then the user is prompted for the variables again.

Confirmation of the network drive letter is provided

Existing PDTOOL_SUBSTITUTE_DRIVE=<drive_letter>:

PDTool network substitute drive letter.

Objective: Used to shorten the overall path to workspace folder mainly for TFS.

Do you want to use the substitute drive letter="<drive_letter>:" [Y or N]: Installation proceeds after this point.

4. What Gets Executed?

- a. Copy source files to destination folder
- b. For TFS only, TFS eula -accept

- c. Encrypt passwords:
 - C:\Users\%USERNAME%\.compositesw\PDToolStudio<ver>_<vcs>\setMyPre PDToolStudioVars.bat
- d. Enable VCS:
 - C:\Users\%USERNAME%\.compositesw\<USERNAME>.<domain>.<cishost>. properties
- e. Initialize workspace (requires the VCS credentials and repository URL).

5. Logging into CIS Studio "Important":

- a. The developer will use the same host name that was provided by the default "DEF_CIS_HOST" or the prompt "I_CIS_HOST" and the domain "DEF_CIS_DOMAIN" or the prompt "I_CIS_DOMAIN".
- b. The reason is that the combination of the username + domain + exact hostname is used to configure the CIS Studio properties file in the .compositesw directory. This gets used to configure the VCS integration for Studio which is found in Studio under "Edit→Options" tab.

6. Managing Errors:

- a. If there are any errors reported in the scripts especially during workspace initialization, try removing the workspace directory and then re-execute the installation script.
- b. If there is an error while trying to create a substitute drive then first trying removing the substitute drive which was identified as available in the script.
 - i. net use <drive>: /DELETE
- c. If Cisco Studio 6 or 7 throws this error during check-in, simply retry the check-in.
 - i. Encountered a problem during vcs export.C:\Users\%USERNAME%\.compositesw\.vcs_temp_folders\vcs_export.zip (Access is denied)
 - ii. Additionally, you can manually delete the folder"C:\Users\%USERNAME%\.compositesw\.vcs_temp_folders" and try again.

7. Verify Installation:

- a. Open Composite Studio and go to the Edit Menu and then Options
 - i. Verify that the "Enable VCS" section is set correctly.
 - ii. Example: Your paths may be different depending on the location and VCS type chosen.

vcsIncludeResourceSecurity=true enableVCS=true

vcsWorkspacePath=

C:\Users\%USERNAME%\.compositesw\PDToolStudio7.0.0_TFS\PDToolStudio\TFSsw\cis_objects

vcsScriptFolder=

C:\Users\%USERNAME%\.compositesw\PDToolStudio7.0.0_TFS\PDToolStudio\bin

- i. Verify that the corresponding property file was created in the file system for "Enable VCS":
 - C:\Users\%USERNAME%\.compositesw\<USERNAME>.<domain>.<cis host>.properties
- ii. Alternative approach: Modify with a script

Example:

ExecutePDToolStudio.bat -nopause -enablevcs -winlogin %USERNAME% - user %USERNAME% -domain ldap -host hostname.com - includeResourceSecurity true -vcsWorkspacePathOverride "C:\Users\%USERNAME%\.compositesw\PDToolStudio7.0.0\PDToolStudio\TFSsw\cis objects"

b. Verify that the workspace was created properly

Example:

- c. Check-in a resource
 - i. Locate a single resource within /shared folder structure to serve as an example to test the check-in capability.
 - ii. Right-click on the resource and select "Check-in to VCS"
 - iii. Type "update" in the box
 - iv. Click OK
 - v. A window pops up scroll to the bottom and look for the word "SUCCESSFUL"

FINISHED

CONCLUSION

Concluding Remarks

The AS Promotion and Deployment Tool is a set of pre-built modules intended to provide a turn-key experience for promoting CIS resources from one CIS instance to another. The user only requires system administration skills to operate and support. The code is transparent to operations engineers resulting in better supportability. It is easy for users to swap in different implementations of a module using the Spring framework and configuration files.

How you can help!

Build a module and donate the code back to Cisco Advanced Services for the advancement of the "AS Promotion and Deployment Tool".



Americas Headquarters Cisco Systems, Inc. San Jose, CA Asia Pacific Headquarters Cisco Systems (USA) Pte. Ltd. Singapore

Europe Headquarters
Cisco Systems International BV Amsterdam,
The Netherlands

Cisco has more than 200 offices worldwide. Addresses, phone numbers, and fax numbers are listed on the Cisco Website at www.cisco.com/go/offices.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Printed in USA CXX-XXXXX-XX 10/11