

PDTool Installer User Guide

An Open Source Asset for use with TIBCO® Data Virtualization

TIBCO Software empowers executives, developers, and business users with Fast Data solutions that make the right data available in real time for faster answers, better decisions, and smarter action. Over the past 15 years, thousands of businesses across the globe have relied on TIBCO technology to integrate their applications and ecosystems, analyze their data, and create real-time solutions. Learn how TIBCO turns data—big or small—into differentiation at www.tibco.com.

Project Name	AS Assets PDTool (Promotion and Deployment Tool)		
Document Location	This document is only valid on the day it was printed. The source of the document will be found in the PDTool and PDToolRelease folder (https://github.com/TIBCOSoftware)		
Purpose	User's Guide		



www.tibco.com

Global Headquarters 3303 Hillview Avenue Palo Alto, CA 94304 **Tel:** +1 650-846-1000 +1 800-420-8450

Fax: +1 650-846-1005

Revision History

Version	Date	Author	Comments
1.0	09/18/2015	Mike Tinius	Initial revision for Installer User Guide
4.0	12/14/2017	Mike Tinius	Initial revision with Tibco
4.1	05/29/2018	Mike Tinius	Removed reference to .compositesw folder.
5.0	08/27/2020	Mike Tinius	Updated documentation
5.1	10/20/2020	Mike Tinius	Updated documentation

Related Documents

Name	Author	
PDTool Installer Admin Guide.pdf	Mike Tinius	

Supported Versions

Name	Version
TIBCO® Data Virtualization	7.0.8 or later

Table of Contents

1	1 Introduction						
	Purpose		Δ				
	Audience						
	Platform Support						
	references						
2	PDTool (Deployment and Testing) Installer User Guide						
	Pre-Requisite C	Checklist	6				
		Connection:					
		RE requirements					
		Control System (VCS) Access:					
		igured PDTool Installer:					
	User Installation Procedure						
		PDTool Installer Zip File:					
)Tool:					
		mpts:					
		s Executed?					
		g Errors:					
		tallation:					
3	Conclusion	l	11				
Concluding Remarks							
	11						

1 Introduction

Purpose

The User Guide provides a PDTool User with the steps to install PDTool on Windows using the PDTool Installer.

This is the part of PDTool that provides deployment and testing facilities. The other part of PDTool is called PDTool Studio and is focused on version control. PDTool operates with Data Virtualization (DV) 8.x.

What gets installed?

- PDTool8.3.0
- VCS Client if the Administrator chooses to pre-configure the \VCSClients folder

Where do the files get copied?

- Recommended default location:
 - C:\Users\%USERNAME%\PDTool[7.0.0|8.0.0|8.3.0]_[NOVCS|TFS|SVN|GIT|P4]
 - E.g. C:\Users\user1\PDTool8.3.0_GIT
 - \PDTool PDTool deployment directory
 - \VCSClients Pre-configured VCS clients are optional if installed elsewhere.
 - \SVN client Subversion client
 - \TFS_TEE_client Team Explorer Everywhere client
 - \GIT client Git client
 - \P4_client Perforce client

Audience

This document is intended to provide guidance for the following users:

- Architects who want to understand how PDTool is used with Data Virtualization.
- Developers who want to deploy resources from a version control system (VCS) such as TFS or Subversion to a target DV server.
- Administrators who need to manage setup and connection with the Data Virtualization environment.
- Operations personnel who wants to encrypt a PDTool file which contains passwords.
- QA/Test personnel who want to use PDTool Regression Module for testing but do not need to connect to a VCS.

Platform Support

The PDTool Installer is only supported on Windows.

References

Product references are shown below. Any references to CIS or DV refer to the current TIBCO® Data Virtualization.

- TIBCO® Data Virtualization was formerly known as
 - o Cisco Data Virtualization (DV)
 - o Composite Information Server (CIS)

2 PDTool (Deployment and Testing) Installer User Guide

Pre-Requisite Checklist

The following is a list the User will need to check before installing PDTool:

1. Network Connection:

Each user must be connected to a network and have access to the VCS server.

2. JDK or JRE requirements

- a. JRE8 Installed for PDTool 7.0.0 or PDTool 8.0.0 [supports TDV 8.0 8.2]:

 JRE 8 (1.8) must be pre-installed on the target computer before installing PDTool.

 Each user must perform this action. Example: "C:\Program Files\Java\jre8".
- b. JDK11 Installed for PDTool 8.3.0 [supports TDV 8.3 and higher]: JDK 11 must be pre-installed on the target computer before installing PDTool. Each user must perform this action. Example: "C:\Program Files\Java\jdk-11.0.8".

3. Version Control System (VCS) Access:

Each user must perform this action.

The user must submit a request in advance to their organization to get access to a version control system (VCS) repository prior to installation of PDTool.

4. Pre-Configured PDTool Installer:

The PDTool Administrator has "pre-configured" the PDTool Installer and provided the location of the zip file to the user.

User Installation Procedure

1. Unzip the PDTool Installer Zip File:

- a. This is the package that the Administrator has "pre-configured" for the organization. Unzip to any directory on your windows machine e.g. [C:\Temp].
 - i. PDTool8.3.0 installer.zip
- b. Use PKZip and select "Extract Here" which will extract the file to the C:\Temp directory as shown below. If you use the Windows "Extract All", then it is recommended to remove the trailing folder
 - i. Location: C:\Temp\PDTool8.0 Installer

2. Install PDTool:

- a. Purpose The purpose of this is to install the "pre-configure" batch files for your organization so that you have a consistent and uniform configuration across the developer and tester user base.
- b. Location
 - a. [C:\Temp]\PDTool8.3.0_installer\installer

c. For any VCS [TFS,SVN,GIT,P4] Execute:

- Edit: PDTool-VCS.bat and provide any default values that require modification. The variables should have been pre-configured by the PDTool administrator.
- Execute by double-clicking on the following batch file from windows explorer:

PDTool-VCS.bat

- Acknowledge Open Source License
- o Follow the "Prompts" section below for detailed information.

d. For non-VCS Installation such as Regression testing:

- Edit: PDTool-NOVCS.bat and provide any default values that require modification. The variables should have been pre-configured by the PDTool administrator.
- Execute by double-clicking on the following batch file from windows explorer:

PDTool-NOVCS.bat

- o Acknowledge Open Source License
- Follow the "Prompts" section below for detailed information.

3. User Prompts:

- a. Purpose The user is prompted for the following parameters unless this information is provided as parameters on the command line. The default values are provided within the square brackets. Press enter with no input to accept the default value or type your value and press enter.
- b. Prompts:

Enter I_PDTOOL_INSTALL_SCRIPTS=[%DEF_PDTOOL_INSTALL_SCRIPTS%]:

Location of the PDTool installation scripts. E.g.
 C:\Temp\PDTool8.3.0_installer

License Acknowledgement

Use space bar to page through license

Review and acknowledge the open source license [Y].

Enter I JAVA HOME=[%DEF JAVA HOME%]:

 I_JAVA_HOME=JDK11 home folder. E.g. C:\Program Files\Java\idk-11.0.8

Enter

I PDTOOL DESTINATION HOME=[%DEF PDTOOL DESTINATION HOME%]:

- I_PDTOOL_DESTINATION_HOME The destination home folder for the PDTool installation and associated binaries.
- NOVCS: C:\Users\%USERNAME%\PDTool8.3.0 NOVCS
- TFS: C:\Users\%USERNAME%\PDTool8.3.0 TFS
- SVN: C:\Users\%USERNAME%\PDTool8.3.0 SVN
- GIT: C:\Users\%USERNAME%\PDTool8.3.0_GIT
- P4: C:\Users\%USERNAME%\PDTool8.3.0 P4

Enter I PDTOOL DESTINATION DIR=[%DEF PDTOOL DESTINATION DIR%]:

 The destination directory name for the PDTool installation and associated binaries. e.g. PDTool8.3.0

Enter I_OVERWRITE_DECISION=[N]:

This prompt only comes up when the target PDTool directory exists. It allows the user to decide whether they want to overwrite that directory or not. Enter Y to overwrite the existing directory.

Enter I_VCS_TYPE=[%DEF_VCS_TYPE%]:

I_VCS_TYPE - The version control type [TFS|SVN|GIT|P4]

Enter I VCS HOME=[%DEF VCS HOME%]:

This is the location of the VCS script executable. E.g.
 C:\Users\%USERNAME%\PDTool8.3.0 SVN\VCSClients\SVN client

Enter I VCS REPOSITORY URL=[%DEF VCS REPOSITORY URL%]:

- Note: make sure the forward slashes are escaped with 4 slashes: https:///url
- TFS: The TFS repository URL pointing to the repository collection.
 e.g. http:///hostname.domain.com/tfs/DefaultCollection
- SVN: The subversion repository path at trunk or any folder designation within trunk. e.g. https:///svn.hostname.com/svnrepos/myrepo/trunk/main

Enter I_VCS_PROJECT_ROOT=[%DEF_VCS_PROJECT_ROOT%]:

■ E.g. TFS: Rel

E.g. SVN: cis_objects

Enter I_RELEASE_FOLDER=[%DEF_RELEASE_FOLDER%]:

Example: RELEASE_FOLDER=20150918

Enter I VCS USERNAME=[%USERNAME%]:

This is your user name regardless of whether it is TFS or Subversion and is used to connect to the VCS repository. The user must submit a request to get access to a repository prior to installation of PDTool.

Enter I_VCS_DOMAIN=[%DEF_VCS_DOMAIN%]:

When using TFS, include the VCS domain such as "@CORP". The result for the I_VCS_USERNAME would look like "username@CORP". When using subversion, leave the domain blank. The I_VCS_DOMAIN will be automatically appended to I VCS_USERNAME.

Enter I_VCS_PASSWORD=<type-your-vcs-password>

This is your VCS password which will be encrypted.

Enter I WORKSPACE NAME=[%DEF VCS WORKSPACE NAME%]:

The PDTool VCS workspace name is derived from the VCS username and Release folder so that it is unique across usernames and releases.

Enter I CIS USERNAME=[%USERNAME%]:

 This is your user name regardless that will be used to connect to DV.

Enter I_CIS_DOMAIN=[%DEF_CIS_DOMAIN%]:

 This is the DV domain which is used by the I_CIS_USERNAME to connect to DV. E.g. Idap or composite

Enter I_CIS_PASSWORD=<type-your-cis-password>

This is your password which will be encrypted.

Enter I CONFIG PROPERTY FILE=[%DEF CONFIG PROPERTY FILE%]

 This is the default PDTool configuration property file that the user will use to set the context of which DV server to connect to. The variables are displayed

Enter I_VARS_DECISION [Y or N] – If "Y", then installation commences. If "N" then the user is prompted for the variables again.

Confirmation of the network drive letter is provided

Existing PDTOOL_SUBSTITUTE_DRIVE=<drive_letter>:

PDTool network substitute drive letter.

Objective: Used to shorten the overall path to workspace folder mainly for TFS.

Do you want to use the substitute drive letter="<drive_letter>:" [Y or N]: Installation proceeds after this point.

4. What Gets Executed?

- a. Copy source files to destination folder
- b. For TFS only, TFS eula -accept
- c. Encrypt passwords:C:\Users\%USERNAME%\PDTool<ver> <vcs>\setMyPrePDToolVars.bat
- d. Initialize workspace (requires the VCS credentials and repository URL). Note: This does not get executed for PDTool-NOVCS.bat

5. Managing Errors:

- a. If there are any errors reported in the scripts especially during workspace initialization, try removing the workspace directory and then re-execute the installation script.
- b. If there is an error while trying to create a substitute drive then first trying removing the substitute drive which was identified as available in the script. net use <drive>: /DELETE

6. Verify Installation:

a. If I CONFIGURE VCS=Y

Verify that the workspace was created properly C:\Users\%USERNAME%\PDTool8.3.0_TFS\PDTool\%I_VCS_PROJECT_ROOT %\%I_RELEASE_FOLDER%

b. If I_CONFIGURE_VCS=N

The user will need to configure a Regression Module test and execute to verify.

FINISHED

3 Conclusion

Concluding Remarks

The Promotion and Deployment Tool is a set of pre-built modules intended to provide a turn-key experience for promoting DV resources from one DV instance to another. The user only requires system administration skills to operate and support. The code is transparent to operations engineers resulting in better supportability. It is easy for users to swap in different implementations of a module using the Spring framework and configuration files.

How you can help!

Build a module and donate the code back to Professional Services for the advancement of the "*Promotion and Deployment Tool*".