

# **Aqua-Duct Documentation**

Release 0.2.25

**Tomasz Magdziarz** 

# **CONTENTS**

1	Aqua-Duct installation guide	1
2	Valve manual	7
3	Configuration file options	13
4	Valve tutorial	23
5	aquaduct	27
Рy	thon Module Index	51

# **AQUA-DUCT INSTALLATION GUIDE**

# 1.1 Overview

Aqua-Duct software is software written in Python (CPython) and comprises of two elements:

- 1. aquaduct a Python package,
- 2. valve a script that uses aquaduct to perform calculations.

#### **Download**

You can download Aqua-Duct packages directly from Aqua-Duct homepage. This page includes older versions of Aqua-Duct as well as development version.

If you follow this installation guide you will install current release.

# 1.2 Troubleshooting

If you encounter any problems with installation do not hesitate to contact us at info@aquaduct.pl. We are **RE-ALLY** willing to help!

Please, provide us with us much info as you can. In particular try to include following information:

- Operating system's name and version, and CPU architecture (if relevant).
- Python version.
- Command(s) you have used for installation.
- Any error/warning/info message(s) that emerged during or after installation.

# 1.3 Requirements

### 1.3.1 Software-wise requirements

- Python 2.7 (CPython implementation)
  - numpy >= 1.7.0
  - scipy >= 0.13.0
  - scikit-learn >= 0.16.0
  - MDAnalysis[amber]  $\geq$  0.15.0
  - roman >= 2.0.0

### 1.3.2 Hardware-wise requirements

Aqua-Duct should work on every machine on which you can install the above mentioned software. On computers older then 10 years it may work very slow though. We recommend 64bit SMP architecture, with at least 4GB RAM (32 GB RAM is recommended).

### 1.4 Installation

# 1.4.1 Generic Python installation

The easiest way to install Aqua-Duct is to install Python 2.7 and use following command:

```
pip install aquaduct
```

If *pip* is not available try to install it by typing:

```
easy_install pip
```

Depending on the settings of your system you can prepend the above command with *sudo* or *doas* or do *user* installation:

```
# sudo
sudo pip install aquaduct

# doas
doas pip install aquaduct

# 'user' installation
pip install aquaduct --user
```

It is also good idea to try to install Aqua-Duct using virtualenv:

```
virtualenv aquaduct_installation
cd aquaduct_installation
. bin/activate
pip install aquaduct
```

#### Installation of PyMOL

Under most modern GNU/Linux distributions PyMOL is available as a package in repositories. For example if you are under Ubuntu/Debian you can install it by following command:

```
sudo apt-get install pymol
```

Under Windows there are several ways to install PyMOL, for more details see PyMOL web site.

Instructions for macOS and OpenBSD are in appropriate sections below.

#### 1.4.2 GNU/Linux

Installation was tested on limited number of GNU/Linux systems. On the most of modern installations you can simply follow generic instructions, for example under Ubuntu 16.04 you can type:

```
sudo pip install aquaduct
```

Other systems may require additional work, in particular installation of NetCDF4 is sometimes cumbersome. Following is an example how to install all required packages under Ubuntu 14.04:

```
# install required python packages
sudo apt-get install python-dev python-pip python-numpy python-scipy python-
→matplotlib python-scikits-learn
# install necessary libraries and git - all required to compile netCDF4
sudo apt-get -y install libnetcdf-dev libhdf5-dev git
# clone netcdf4 python repository
qit clone https://github.com/Unidata/netcdf4-python.git
# cd to cloned repository
cd netcdf4-python
# modify setup.cfg to add paths of hdf5 and netcdf4 libraries
sed -i '/\[directories\]/a \
HDF5_dir = /usr/lib \
HDF5_libdir = /usr/lib \
HDF5_incdir = /usr/include \
netCDF4_dir = /usr/lib \
netCDF4_libdir = /usr/lib \
netCDF4_incdir = /usr/include' setup.cfg
# run setup.py
sudo python setup.py install
# install MDAnalysis
sudo pip install "MDAnalysis[amber]>=0.15"
```

If everything went fine you can follow generic instructions, type:

```
sudo pip install aquaduct
```

#### 1.4.3 MacOS

Aqua-Duct installation was tested on MacOS Sierra and is quite straightforward. It can be installed either with existing system Python or with custom Python installation. In both cases one have to install Xcode for the App Store.

#### **System native Python**

```
sudo easy_install pip
sudo pip install aquaduct
```

The drawback of using system Python installation is a lack of PyMOL. It should be, however, relatively easy to compile PyMOL on your own. Try to follow compilation instruction under BSD systems.

### **Custom Python**

This is recommended way of Aqua-Duct installation. If you do not have custom Python installation you can get it by using one of package managers available for macOS, for example homebrew. With this package manager you can do following:

```
brew install python
sudo easy_install pip
sudo pip install aquaduct
```

### Next, you can install PyMOL:

```
brew install pymol
brew cask install xquartz
```

1.4. Installation 3

Once XQuartz is installed you should reboot. The above procedure installs PyMOL, however, PyMOL Python modules are not visible. To fix it you can issue following commands:

```
cd /usr/local/lib/python2.7/site-packages
sudo ln -s /usr/local/Cellar/pymol/*/libexec/lib/python2.7/site-packages/* ./
```

The above instruction assumes that you are using brew and you have only one PyMOL installation.

#### 1.4.4 Windows

Installation under Windows is also possible. The limiting factor is MDAnalysis which is not officially available under Windows yet. You can, however, install Cygwin and perform Aqua-Duct installation in Cygwin.

First, start with Cygwin installation. During the setup select following packages:

- python (2.7)
- python-devel (2.7)
- · python-cython
- · libnetcdf-devel
- libhdf5-devel
- liblapack-devel
- libopenblas
- · python-numpy
- python-six

Another key component that have to be installed is C, C++ and Fortran compilers. You can simply install **gcc-g++** and **gcc-fortran** packages as a first choice, select following packages:

- gcc-g++
- gcc-fortran

Once Cygwin is installed with all required libraries you can perform following steps:

```
# install pip
easy_install-2.7 pip
```

First, try to install SciPy:

```
# install SciPy
pip install scipy
```

If you encounter any problems related to missing xlocale.h header file try the following workaround:

```
# prepare fake xlocale.h
ln -s /usr/include/locale.h xlocale.h
export CFLAGS="I"$( pwd )

# install SciPy
pip install scipy
```

**Note:** The above procedure for SciPy installation might not be optimal. For more information please got to SciPy web page.

Now, install scikit-learn and then Aqua-Duct:

```
# install scikit-learn
pip install scikit-learn

# finally, install aquaduct
pip install aquaduct
```

### 1.4.5 OpenBSD

Aqua-Duct can be also installed under OpenBSD (5.9 and 6.0 amd64). NetCDF-c version 4 has to be installed as OpenBSD ships only netCDF in version 3. First, install hdf5 library and GNU make:

```
# install hdf5 and GNU make
pkg_add hdf5 gmake
```

Next, download netCDF sources. Version 4.2.1.1 works out of the box but is a bit outdated. Visit NetCDF web page and select version of your choice. Older versions are available in the FTP archive. Once netCDF is downloaded and extracted go to the source directory and try following procedure:

You may now install py-scipy package:

```
pkg_add py-scipy
```

Install pip if it is missing:

```
pkg_add py-pip
```

Install netCDF4 Python:

```
# define netcdf-4 installation directory
export NETCDF4_DIR=/path/to/netCDF4/lib
pip2.7 install netCDF4
```

At this point you can follow generic Python instructions, type:

```
pip2.7 install aquaduct
```

#### PyMOL at OpenBSD

According to our knowledge it is possible to install PyMOL 1.4.1 and it is sufficient to work with Aqua-Duct. Go to SourceForge PyMOL download page and download, save, and extract sources.

PyMOL requires Python Mega Widgets. Download, for example Pmw 1.3.3b from SourceForge Pmw download page. Extract it and install by:

```
python2.7 setup.py install
```

TKinter (2.7) and several other packages are also required:

1.4. Installation 5

```
pkg_add python-tkinter freeglut glew png
```

Next, go to the extracted PyMOL sources open setup.py and modify inc\_dirs variable at line 129 by adding following paths:

```
"/usr/X11R6/include/freetype2",
"/usr/X11R6/include",
"/usr/local/include",
```

Now, you can build and install PyMOL by typing following commands:

```
python2.7 setup.py build
python2.7 setup.py install
python2.7 setup2.py install
cp pymol /usr/local/bin
```

PyMOL can be run by typing pymol or can be used as Python module.

#### Other BSDs

Installation on other BSDs might be easier. For example, Python netCDF4 is available in ports of FreeBSD and DragonFlyBSD. Try to install it and SciPy, then proceed to generic Python installation instructions.

If you are using NetBSD or other BSD try to follow OpenBSD instructions.

**CHAPTER** 

**TWO** 

# **VALVE MANUAL**

Valve application is a driver that uses aquaduct module to perform analysis of trajectories of selected residues in MD simulation.

### 2.1 Valve invocation

Once aquaduct module is installed (see Aqua-Duct installation guide) properly on the machine Valve is available as valve.py command line tool.

# 2.1.1 **Usage**

Basic help of *Valve* usage can be displayed by following command:

```
valve.py --help
```

It should display following information:

```
usage: valve.py [-h] [--dump-template-config] [-t THREADS] [-c CONFIG_FILE]
                [--max-frame MAX_FRAME]
Valve, Aqua-Duct driver
optional arguments:
 -h, --help
                       show this help message and exit
  --dump-template-config
                       Dumps template config file. Suppress all other output
                       or actions. (default: False)
 -t THREADS
                       Limit Aqua-Duct calculations to given number of
                       threads. (default: None)
 -c CONFIG_FILE Config file filename. (default: None)
  --max-frame MAX_FRAME
                       Limit number of frames. (default: None)
                       Prints versions and exits.. (default: False)
  --version
```

# 2.1.2 Configuration file template

Configuration file used by *Valve* is of moderate length and complexity. It can be easily prepared with a template file that can be printed by *Valve*. Use following command to print configuration file template on the screen:

```
valve.py --dump-template-config
```

Configuration file template can also be easily saved in to a file with:

```
valve.py --dump-template-config > config.txt
```

Where config.txt is a configuration file template.

For detailed description of configuration file and available options see Configuration file options

#### 2.1.3 Valve calculation run

Once configuration file is ready Valve calculations can be run with a following simple command:

```
valve.py -c config.txt
```

Some of *Valve* calculations can be run in parallel. By default all available CPU cores are used. This is not always desired - limitation of used CPU cores can be done with -t option which limits number of concurrent threads used by *Valve*. If it equals 1 no parallelism is used.

**Note:** Specifying number of threads greater then available CPU cores is generally not optimal.

However, in order to maximize usage of available CPU power it is recommended to set it as number of cores + 1. The reason is that *Valve* uses one thread for the main process and the excess over one for processes for parallel calculations. When parallel calculations are executed the main threads waits for results.

**Note:** Option —max-frame can be used for testing or debugging purposes. It allows to limit number of frames processed by *Valve*. If it set, for example, to 1000 only first 1000 frames will be processed making all calculations very fast.

# 2.2 How does Valve work

Application starts with parsing input options. If --help or --dump-template-config options are provided appropriate messages are printed on the screen and *Valve* quits with signal 0.

**Note:** In current version *Valve* does not check the validity of the config file.

If config file is provided *Valve* parse it quickly and regular calculations starts according to its content. Calculations performed by *Valve* are done in several stages described in the next sections.

#### 2.2.1 Traceable residues

The first stage finds all residues that should be traced and appends them to the list of *traceable residues*. It is done in a loop over all frames. In each frame residues of interest are searched and appended to the list but only if they are not already present on the list.

The search of the residues is done according to user provided definitions.. Two requirements have to be met to append residue to the list:

- 1. The residue have to be found according to the *Object* definition.
- 2. The residues have to be within the *Scope* of interest.

The *Object* definition encompasses usually the active site of the protein. The *Scope* of interest defines, on the other hand, the boundaries in which residues are traced and is usually defined as protein.

Since aquaduct in its current version uses MDAnalysis Python module for reading, parsing and searching of MD trajectory data, definitions of *Object* and *Scope* have to be given as its *Selection Commands*.

#### **Object definition**

Object definition have to comprise of two elements:

- 1. It have to define residues to trace.
- 2. It have to define spatial boundaries of the *Object* site.

For example, proper Object definition could be following:

```
(resname WAT) and (sphzone 6.0 (resnum 99 or resnum 147))
```

It defines WAT as residues that should be traced and defines spatial constrains of the *Object* site as spherical zone within 6 Angstroms of the center of masses of residues with number 99 and 147.

#### Scope definition

Scope can be defined in two ways: as Object but with broader boundaries or as the convex hull of selected molecular object.

In the first case definition is very similar to *Object* and it have to follow the same limitations. For example, proper *Scope* definition could be following:

```
resname WAT around 2.0 protein
```

It consequently have to define WAT as residues of interest and defines spatial constrains as all WAT residues that are within 2 Angstroms of the protein.

If the *Scope* is defined as the convex hull of selected molecular object (which is recommended), the definition itself have to comprise of this molecular object only, for example protein. In that case the scope is interpreted as the interior of the convex hull of atoms from the definition. Therefore, *traceable residues* would be in the scope only if they are within the convex hull of atoms of protein.

### 2.2.2 Raw paths

The second stage of calculations uses the list of all traceable residues from the first stage and finds coordinates of center of masses for each residue in each frame. As in the first stage, it is done in a loop over all frames. For each residue in each frame *Valve* calculates or checks two things:

- 1. Is the residue in the *Scope* (this is always calculated according to the Scope definition).
- 2. Is the residue in the *Object*. This information is calculated in the first stage and can be reused in the second. However, it is also possible to recalculate this data according to the new *Object* definition.

For each of the *traceable residues* a special *Path* object is created. If the residue is in the *Scope* its center of mass is added to the appropriate *Path* object together with the information if it is in the *Object* or not.

#### 2.2.3 Separate paths

The third stage uses collection of *Path* objects to create *Separate Path* objects. Each *Path* comprise data for one residue. It may happen that the residue enters and leaves the *Scope* and the *Object* many times over the entire MD. Each such an event is considered by *Valve* as a separate path.

Each separate path comprises of three parts:

- 1. *Incoming* Defined as a path that leads from the point in which residue enters the *Scope* and enters the object for the firs time.
- 2. *Object* Defined as a path that leads from the point in which residue enters the *Object* for the first time and leaves it for the last time.

3. *Outgoing* - Defined as a path that leads from the point in which residue leaves the *Object* for the last lime and leaves the *Scope*.

#### **Auto Barber**

After the initial search of *Separate Path* objects it is possible to run procedure which trims paths down to the surface of macromolecule or other molecular entity defined by the user. This is done by removing parts of raw paths that are inside spheres that originate in the points marking these ends of separate paths that end at the boundary of *Scope*. Recreation of separate paths is run automatically after Auto Barber procedure.

#### 2.2.4 Clusterization of inlets

Each of the separate paths has beginning and end. If either of them are at the boundaries of the *Scope* they are considered as *Inlets*, i.e. points that mark where the *traceable residues* enters or leaves the *Scope*. Clusters of inlets, on the other hand, mark endings of tunnels or ways in the system which was simulated in the MD.

Clusterization of inlets is performed in following steps:

- 1. Initial clusterization. Depending on the method, some of the inlets might not be arranged to any cluster and are considered as outliers.
- 2. [Optional] Outliers detection. Arrangement of inlets to clusters is sometimes far from optimal. In this step, *inlets* that do not fit to cluster are detected and annotated as outliers. This step can be executed in two modes:
  - (a) Automatic mode. Inlet is considered to be an outlier if its distance from the centroid is greater then mean distance + 4 \* standard deviation of all distances within the cluster.
  - (b) Defined threshold. Inlet is considered to be an outlier if its minimal distance from any other point in the cluster is greater then the threshold.
- 3. [Optional] Reclusterization of outliers. It may happen that the outliers form actually clusters but it was not recognized in initial clusterization. In this step clusterization is executed for outliers only and found clusters are appended to the clusters identified in the first step. Rest of the inlets are marked as outliers.

#### Potentially recursive clusterization

Both *Initial clusterization* and *Reclustarization* can be run in a recursive manner. If in the appropriate sections defining clusterization methods option *recursive\_clusterization* is used appropriate method is run for each cluster separately. Clusters of specific size can be excluded from recursive clusterization (option *recursive\_threshold*). It is also possible to limit maximal number of recursive levels - option *max\_level*. For additional information see *Clusterization sections*.

# 2.2.5 Analysis

Fifth stage of *Valve* calculations analyses results calculated in stages 1 to 4. Results of the analysis is displayed on the screen or can be save to text file and comprise of following parts:

- Tile and data stamp.
- [Optional] Dump of configuration options.
- Basic information on traceable residues and separate paths.
  - Number of traceable residues.
  - Number of separate paths.
- · Basic information on inlets.
  - Number of inlets.

- Number of clusters.
- Are outliers detected.

#### • Summary of inlets clusters. Table with 5 columns:

- 1. Nr: Row number, starting from 0.
- 2. Cluster: ID of the cluster. Outliers have 0.
- 3. Size: Size of the cluster.
- 4. **INCOMING**: Number of inlets corresponding to separate paths that enter the scope.
- 5. **OUTGOING**: Number of inlets corresponding to separate paths that leave the scope.

#### • Summary of separate paths clusters types. Table with 9 columns.

- 1. Nr: Row number, starting from 0.
- 2. **CType**: Separate path Cluster Type.
- 3. Size: Number of separate paths belonging to Cluster type.
- 4. **Inp**: Average length of incoming part of the path. If no incoming part is available it is nan.
- 5. InpStd: Standard deviation of length Inp.
- 6. **Obj**: Average length of object part of the path. If no incoming part is available it is nan.
- 7. **ObjStd**: Standard deviation of length Inp.
- 8. **Out**: Average length of outgoing part of the path. If no incoming part is available it is nan.
- 9. OutStd: Standard deviation of length Inp.

#### • List of separate paths and their properties. Table with 17 columns.

- 1. **Nr**: Row number, starting from 0.
- 2. **ID**: Separate path ID.
- 3. **BeginF**: Number of frame in which the path begins.
- 4. InpF: Number of frame in which path begins Incoming part.
- 5. **ObjF**: Number of frame in which path begins Object part.
- 6. OutF: Number of frame in which path begins Outgoing part.
- 7. **EndF**: Number of frame in which the path ends.
- 8. InpL: Length of Incoming part. If no incoming part nan is given.
- 9. **ObjL**: Length of Object part.
- 10. OutL: Length of Outgoing part. If no outgoing part nan is given.
- 11. **InpS**: Average step of Incoming part. If no incoming part nan is given.
- 12. **InpStdS**: Standard deviation of InpS.
- 13. **ObjS**: Average step of Object part.
- 14. **ObjStdS**: Standard deviation of ObjS.
- 15. **OutS**: Average step of Outgoing part. If no outgoing part nan is given.
- 16. OutStdS: Standard deviation of OutS.
- 17. **CType**: Cluster type of separate path.

#### Separate path ID

Separate Paths IDs are composed of two numbers separated by colon. First number is the residue number. Second number is consecutive number of the separate path made by the residue. Numeration starts with 0.

### **Cluster Type of separate path**

Each separate paths has two ends: beginning and end. Both of them either belong to one of the inlets clusters, or are among outliers, or are inside the scope. If an end belongs to one of the clusters (including outliers) it has ID of the cluster. If it is inside the scope it has special ID of N. Cluster type is an ID composed of IDs of both ends of separate path separated by colon charter.

#### 2.2.6 Visualization

Sixth stage of *Valve* calculations visualizes results calculated in stages 1 to 4. Visualization is done with PyMOL. *Valve* automatically starts PyMOL and loads visualizations in to it. Molecule is loaded as PDB file. Other objects like Inlets clusters or paths are loaded as CGO objects.

Following is a list of objects created in PyMOL (all of them are optional). PyMOL object names given in **bold** text or short explanation is given.

- Selected frame of the simulated system. Object name: *molecule*.
- Inlets clusters, each cluster is a separate object. Object name: **cluster\_** followed by cluster annotation: otliers are annotated as Out; regular clusters by ID.
- List of cluster types, raw paths. Each cluster type is a separate object. Object name composed of cluster type (colon replaced by underline) plus **\_raw**.
- List of cluster types, smooth paths. Each cluster type is a separate object. Object name composed of cluster type (colon replaced by underline) plus **\_smooth**.
- All raw paths. They can be displayed as one object or separated in to Incoming, Object and Outgoing part. Object name: all\_raw\_in, all\_raw\_obj, and all\_raw\_out.
- All raw paths inlets arrows. Object name: all\_raw\_paths\_io.
- All smooth paths. They can be displayed as one object or separated in to Incoming, Object and Outgoing part. Object name: all\_smooth, or all\_smooth\_in, all\_smooth\_obj, and all\_smooth\_out.
- All raw paths inlets arrows. Object name: all\_raw\_paths\_io.
- Raw paths displayed as separate objects or as one object with several states. Object name: **raw\_paths\_** plus number of path or **raw\_paths** if displayed as one object.
- Smooth paths displayed as separate objects or as one object with several states. Object name: **smooth\_paths**\_ plus number of path or **smooth\_paths** if displayed as one object.
- Raw paths arrows displayed as separate objects or as one object with several states. Object name: raw\_paths\_io\_ plus number of path or raw\_paths\_io if displayed as one object.
- Smooth paths arrows displayed as separate objects or as one object with several states. Object name: **smooth\_paths\_io** plus number of path or **smooth\_paths\_io** if displayed as one object.

#### **Color schemes**

Inlets clusters are colored automatically. Outliers are gray.

Incoming parts of paths are red, Outgoing parts are blue. Object parts in case of smooth paths are green and in case of raw paths are green if residue is precisely in the object area or yellow if is leaved object area but it is not in the Outgoing part yet.

Arrows are colored in accordance to paths colors.

# **CONFIGURATION FILE OPTIONS**

Valve Configuration file is a simple and plain text file. It has similar structure as INI files commonly used in one of the popular operating systems and is compliant with Python module ConfigParser.

Configuration file comprises of several *sections*. They can be grouped in to three categories. Names of sections given in **bold** text.

- 1. Global settings:
  - global
- 2. Stages options:
  - (a) traceable\_residues
  - (b) raw\_paths
  - (c) separate\_paths
  - (d) inlets\_clusterization
  - (e) analysis
  - (f) visualize
- 3. Methods options:
  - smooth
  - clusterization
  - reclusteriation

# 3.1 Section global

This section allows settings of trajectory data and some other future global options.

Option	Default value	Description
top	None	Path to topology file. Aqua-Duct supports PDB, PRMTOP, PFS topology files.
trj	None	Path to trajectory file. Aqua-Duct supports NC and DCD trajectory files.

**Note:** Options **top** and **trj** are mandatory.

# 3.2 Common settings of stage sections

Stages 1-4 which perform calsulations have some common options allowig for execution control and saving/loading data.

Option	Default value	Description
execute	runonce	Option controls stage execution. It
		can have one of three possible val-
		ues: run, runonce, and skip.
		If it is set to run calculations are
		always performed and if <b>dump</b> is
		set dump file is saved. If it is
		set to runonce calculations are
		performed if there is no dump file
		specified by <b>dump</b> option. If it is
		present calculations are skiped and
		data is loaded from the file. If it is
		set to skip calculations are skip
		and if <b>dump</b> is set data is loaded
		from the file.
dump	[dump file name]	File name of dump data. It is used
		to save results of calculations or
		to load previously calculated data
		- this depends on <b>execute</b> option.
		Default value of this option de-
		pends on the stage and for stages 1
		to 4 is one of the following (listed
		in order):
		•
		1_traceable_residues_data.dump
		• 2_raw_paths_data.dump
		•
		3_separate_paths_data.dump
		4_inlets_clusterization_data.dump

Stages 5-6 also uses **execute** option, however, since they do not perform calculations *per se* in stead of **dump** option they use **save**.

Option	Default value	Description
execute	run	Option controls stage execution. It can have one of three possible values: run, runonce, and skip. If it is set to run or runonce stage is executed and results is saved according to save option. If it is set to skip stage is skipped.
save	[save file name]	File name for saving results. Default value of this option depends on the stage and for stages 1 to 4 is one of the following (listed in order):  • 5_analysis_results.txt  • 6_visualize_results.py  Stage 6 can save results in two file types:  1. As Python script - extension .py plus companion archive .tar.gz,  2. As PyMOL session - extension .pse.

# 3.3 Stage traceable\_residues

Option	Default value	Description
scope	None	Definition of <i>Scope</i> of interest. See also <i>Scope definition</i> .
scope_convexhull	True	Flag to set if the <i>Scope</i> is direct or convex hull definition.
object	None	Definition of <i>Object</i> of interest. See also <i>Object definition</i> .

**Note:** Options **scope** and **object** are mandatory.

# 3.4 Stage raw\_paths

This stage also requires definition of the *Scope* and *Object*. If appropriate settings are not given, settings from the previous stage are used.

Option	De-	Description
	fault	
	value	
scope	None	Definition of <i>Scope</i> of interest. See also <i>Scope definition</i> . If None value form previous
		stage is used.
scope_con	veXbuel	Flag to set if the <i>Scope</i> is direct or convex hull definition. If None value form previous
		stage is used.
object	None	Definition of <i>Object</i> of interest. See also <i>Object definition</i> . If None, value form the
		previous stage is used
clear_in_o	bj <b>Ea</b> t <u>s</u> enfo	If it is set to True information on occupation of <i>Object</i> site by traceable residues
		calculated in the previous stage is cleared and have to be recalculated. This is useful if
		definition of <i>Object</i> was changed.

# 3.5 Stage separate\_paths

Option	De-	Description
	fault	
	value	
dis-	True	If set to True empty paths are discarded.
card_empty_	paths	
sort_by_id	True	If set to True separate paths are sorted by ID. Otherwise they are sorted in order of
		apparance.
ар-	False	If set to True smooth paths are precalculated according to <b>smooth</b> setting. This
ply_smoothin	ng	speed up access to smooth paths in later stages but makes dump data much bigger.
ар-	True	If set to True raw paths are replaced by smooth paths calculated according to
ply_soft_smo	othing	smooth section.
dis-	1	This option allows to discard paths that are shorter then the threshold.
card_short_p	aths	
auto_barber	None	This option allows to select molecular entity used in Auto Barber procedure. See
		also Auto Barber and barber_with_spheres().

# 3.6 Stage inlets\_clusterization

Option	De-	Description
	fault	
	value	
reclus-	False	If set to True reclusterization of outliers is executed according to the method defined
ter_outliers	\$	in <b>reclusterization</b> section.
de-	False	If set detection of outliers is executed. It could be set as a floating point distance
tect_outlier	rs	threshold or set tu Auto. See <i>Clusterization of inlets</i> for more details.
single-	False	Maximal size of cluster to be considered as outliers. If set to number > 0 clusters of that
tons_outlie	rs	size are removed and their objects are moved to outliers. See <i>Clusterization of inlets</i> for
		more details.
max_level	5	Maximal number of recursive clusterization levels.
cre-	False	If set to True master paths are created (fast CPU and big RAM recommended; 50k
ate_master	_paths	frames long simulation may need ca 20GB of memory)

# 3.7 Stage analysis

Option	Default value	Description
dump_config	True	If set to True configuration options, as seen by Valve, are added to the head of results.

3.7. Stage analysis

# 3.8 Stage visualize

Option	Default value	Description
simply_smooths	RecursiveVector	Option indicates linear simplifica-
		tion method to be used in plotting
		smooth paths. Simplification re-
		moves points which do not (or al-
		most do not) change the shape of
		smooth path. Possible choices are:
		• RecursiveVector (see
		LinearizeRecursiveVector
		• HobbitVector (see
		LinearizeHobbitVector),
		• OneWayVector (see
		LinearizeOneWayVector),
		• RecursiveTriangle
		(see
		LinearizeRecursiveTriang
		• HobbitTriangle (see
		LinearizeHobbitTriangle),
		• OneWayTriangle (see
		LinearizeOneWayTriangle).
		Optionally name of the method
		can be followed by a thresh-
		old value in parentheses, ie
		RecursiveVector(0.05).
		For sane values of thresholds
		see appropriate documentation
		of each method. Default val-
		ues works well. This option is
		not case sensitive. It is recom-
		mended to use default method or
		HobbitVector method.
all_paths_raw	False	If True produces one object in Py-
an_pauis_raw	1 disc	MOL that holds all paths visual-
		ized by raw coordinates.
all_paths_smooth	False	If True produces one object in Py-
an_pauis_sinooti	Taise	MOL that holds all paths visual-
		ized by smooth coordinates.
all moths smlit	False	
all_paths_split	raise	If is set True objects produced by <b>all_paths_raw</b> and
		all_paths_smooth are split into
		Incoming, Object, and Outgoing
		parts and visualized as three
all mathe many to	False	different objects.
all_paths_raw_io	False	If set True arrows pointing begin-
		ning and end of paths are displayed
		oriented accordingly to raw paths
	7.	orientation.
all_paths_smooth_io	False	If set True arrows pointing begin-
		ning and end of paths are displayed
		oriented accordingly to smooth
		paths orientation.
paths_raw	False	If set True raw paths are displayed
		as separate objects or as one object
		with states corresponding to num-
		ber of path.
paths_smooth	False	If set True smooth paths are dis-
		played as separate objects or as
8		Chaptem3.organfiguration file options
•		
		ing to number of path.
paths_raw_io	False	ing to number of path.  If set True arrows indicating be-

**Note:** Possibly due to limitations of MDAnalysis only whole molecules can be displayed. If **show\_molecule** is set to backbone complete protein will be displayed any way. This may change in future version of MDAnalysis and or aquaduct.

**Note:** If several frames are selected they are displayed as states which may interfere with other PyMOL objects displayed with several states.

**Note:** If several states are displayed protein tertiary structure data might be lost. This seems to be limitation of either MDAnalysis or PyMOL.

# 3.9 Clusterization sections

Default section for definition of clusterization method is named **clusterization** and default section for reclusterization method definition is named **reclusterization**. All clusterization sections shares some common options. Other options depends on the method.

Option	Default	Description
	value	
method	mean-	Name of clasteriation method. It have to be one of the following: dbscan, affprop,
	shift or	meanshift, birch, kmeans. Default value depends if it is <b>clusteriation</b> section
	dbscan	(meanshift) or <b>reclusterization</b> section (dbscan).
recur-	clusteri-	If it is set to name of some section that holds clusterization method settings this
sive_cluste	rization	method will be called in the next recursion of clusteriation. Default value for
	or None	reclusterization is None.
recur-	None	Allows to set threshold of that excludes clusters of certain size from reclusterization.
sive_thresh	iold	Value of this option comprises of <i>operator</i> and <i>value</i> . Operator can be one of the
		following: >, >=, <=, <. Value have to be expressed as floating number and it have to
		be in the range of 0 to 1.

#### 3.9.1 dbscan

For detailed description look at sklearn.cluster.DBSCAN documentation. Following table summarized options available in *Valve* and is a copy of original documentation.

Option	Value type	Description
eps	float	The maximum distance between
		two samples for them to be consid-
	:4	ered as in the same neighborhood.
min_samples	int	The number of samples (or total
		weight) in a neighborhood for a point to be considered as a core
		point to be considered as a core point. This includes the point it-
		self.
metric	str	The metric to use when calculat-
		ing distance between instances in
		a feature array. Can be one of the
		following:
		• cityblock,
		• cosine, • euclidean,
		• manhattan.
		mainiactan.
algorithm	str	The algorithm to be used by the
		NearestNeighbors module to com-
		pute pointwise distances and find
		nearest neighbors. Can be one of
		the following:
		• auto,
		• ball_tree,
		<ul><li>kd_tree,</li><li>brute.</li></ul>
		· Diule.
leaf_size	int	Leaf size passed to BallTree or cK-
		DTree.

# 3.9.2 affprop

For detailed description look at AffinityPropagation documentation. Following table summarized options available in *Valve* and is a copy of original documentation.

Option	Value	Description
	type	
damping	float	Damping factor between 0.5 and 1.
conver-	int	Number of iterations with no change in the number of estimated clusters that
gence_iter		stops the convergence.
max_iter	int	Maximum number of iterations.
preference	float	Points with larger values of preferences are more likely to be chosen as
		exemplars.

# 3.9.3 meanshift

For detailed description look at MeanShift documentation. Following table summarized options available in Valve and is a copy of original documentation.

Op-	Value	Description	
tion	type		
band-	Auto	Bandwidth used in the RBF kernel. If Auto or None automatic method for bandwidth	
width	or	estimation is used. See estimate_bandwidth().	
	float		
clus-	bool	If true, then all points are clustered, even those orphans that are not within any kernel.	
ter_all			
bin_see	dibnogol	If true, initial kernel locations are not locations of all points, but rather the location of the	
		discretized version of points, where points are binned onto a grid whose coarseness	
		corresponds to the bandwidth.	
min_bir	n_ifirteq	To speed up the algorithm, accept only those bins with at least min_bin_freq points as	
		seeds. If not defined, set to 1.	

### 3.9.4 birch

For detailed description look at Birch documentation. Following table summarized options available in *Valve* and is a copy of original documentation.

Option	Value	Description	
	type		
thresh-	float	The radius of the subcluster obtained by merging a new sample and the closest subcluster	
old		should be lesser than the threshold. Otherwise a new subcluster is started.	
branch-	int	Maximum number of CF subclusters in each node.	
ing_facto	r		
n_cluster	s int	Number of clusters after the final clustering step, which treats the subclusters from the	
		leaves as new samples. By default, this final clustering step is not performed and the	
		subclusters are returned as they are.	

### **3.9.5 kmeans**

For detailed description look at KMeans documentation. Following table summarized options available in *Valve* and is a copy of original documentation.

Op-	Value	Description	
tion	type		
n_clust	enisnt	The number of clusters to form as well as the number of centroids to generate.	
max_it	erint	Maximum number of iterations of the k-means algorithm for a single run.	
n_init	int	Number of time the k-means algorithm will be run with different centroid seeds. The final	
		results will be the best output of n_init consecutive runs in terms of inertia.	
init	str	Method for initialization, defaults to k-means++. Can be one of following: k-means++	
		or random.	
tol	float	Relative tolerance with regards to inertia to declare convergence.	

# 3.10 Smooth section

Section **smooth** supports following options:

3.10. Smooth section 21

Option	Value type	Description
method	str	Smoothing method. Can be one of the following:
		• window, (see
		WindowSmooth)
		• mss, (see
		MaxStepSmooth)
		• window_mss, (see
		WindowOverMaxStepSmooth)
		• awin, (see
		ActiveWindowSmooth)
		• awin_mss, (see
		ActiveWindowOverMaxStepSmooth)
		• dwin, (see
		DistanceWindowSmooth)
		• dwin_mss. (see
		DistanceWindowOverMaxStepSmooth
recursive	int	Number of recursive runs of
		smoothing method.
window	int or float	In window based method defines
		window size. In plain window it
		has to be int number.
step	int	In step based method defines size
		of the step.
function	str	In window based methods defines
		averaging function. Can be mean
		or median.

**CHAPTER** 

**FOUR** 

# **VALVE TUTORIAL**

This is a tentative *Valve* manual. Created for the sake of Aqua-Duct training we have today. Eventually, it will be rewritten to the official version.

This tutorial assumes aquaduct and Valve is already installed - see Aqua-Duct installation guide. It is also assumed that user is acquainted with Valve manual and Valve Configuration file options.

### 4.1 Valve invocation

Usually *Valve* is run by:

```
valve.py
```

To check is *Valve* is installed and works properly try to issue following commands:

```
valve.py --help
valve.py --version
```

### 4.2 Test data

#### Mouse!

We will use 10ns Amber MD simulation data of sEH protein (PDBID **1cqz**). Necessary files can be found here, see Download section:

- · Go to download server.
- Download sample data zip and extract it.

# 4.3 Inspect your system

Before we start any calculations lets have a look at the protein of interest. Start *PyMOL* and get 1cqz PDB structure (for example by typing in *PyMOL* command prompt fetch 1cqz).

To setup *Valve* calculations we need to know active site of the protein. More precisely we need to know IDs or residues that are in the active site. This would allow us to create *Object definition*.

But wait. Is it really the correct structure? How many chains there are? What is the numeration of residues?

#### 4.3.1 Create Object definition

Lets load another structure. Open file <code>lcqz\_sample\_topology.pdb</code> (see *Test data*). It is a first frame of the MD simulation and it is en example of how the frame of MD looks like. In order to create *Object definition* you have to discover following things:

- 1. What is the name of water residue?
- 2. What are numbers of residues in the active site?
- 3. What size the active site is?

Note: It is also good idea to open .pdb file in your favorite text editor and look at residue numbers and names.

# 4.3.2 Create Scope definition

*Scope definition* is easy to create. We will use *Convex hull* version so the scope definition could be simply backbone.

# 4.4 Prepare config file

Valve performs calculations according to the configuration (aka config) file.

Lets start from dumping config file template to config.txt file. Open it in your favorite editor and fill all options. If you have troubles look at *Configuration file options* (and *Valve manual*).

Things to remember:

- 1. Provide correct paths to topology and trajectory data.
- 2. Enter correct *Object* and *Scope* definitions.
- 3. Provide file name of result in analysis section, for example results.txt (for future reference).
- 4. Make sure visualization is switched on and save option points to session file name (.pse)

### 4.5 Run Valve

Make sure all necessary data is in place. Open terminal, go to your working directory and type in:

```
valve.py -c config.txt
```

Depending on your machine and current load it may take a while (matter of minutes) to complete all calculations.

# 4.5.1 Visual inspection

In the last stage *PyMOL* should pop up and *Valve* should start to feed it with visualization data. This would take a moment and if you set up save option a *PyMOL* session would be saved. Once it is done *Valve* quits and switches off *PyMOL*. Now, you can restart it and read saved session.

#### 4.5.2 Clusterization

Improve clusterization of Inlets. See Configuration file options for more hints on available clusterization options.

### 4.5.3 Analysis tables

Open 5\_analysys\_results.txt file and look at summaries and tables. See also Valve manual.

# 4.6 Feedback

Give us your opinion. Send your questions, inquires, anything to developer(s): mailto:info@aquaduct.pl. This are couple of questions that might be useful to form your opinion.

- 1. What do you like in Valve and Aqua-Duct?
- 2. What do you do not like in Valve or Aqua-Duct?
- 3. What is missing?
- 4. Do you find it useful?

4.6. Feedback 25

# **AQUADUCT**

# 5.1 aquaduct package

# 5.1.1 Subpackages

aquaduct.geom package

**Submodules** 

### aquaduct.geom.cluster module

This module provides functions for clusterization. Clusterization is done by scikit-learn module.

#### aquaduct.geom.convexhull module

```
_vertices_ids (convexhull)
_vertices_points (convexhull)
_point_within_convexhull (convexhull, point)
_facets (convexhull)
_edges (*args, **kwargs)
is_point_within_convexhull (point_chull)
```

#### aquaduct.geom.master module

```
fit_trace_to_points (trace, points)
decide_on_type (cont, s2o_treshold=0.5)
get_weights_(spaths, smooth=None)
```

```
\mathtt{get\_mean\_coord\_}(\mathit{coords}, l)
concatenate (*args)
class CTypeSpathsCollectionWorker (spaths=None, ctype=None, bias_long=5, smooth=None)
     Bases: object
     ___init___(spaths=None, ctype=None, bias_long=5, smooth=None)
     coords_types_prob_widths (sp_slices_)
      ___call___(nr_sp_slices_)
class CTypeSpathsCollection (spaths=None, ctype=None, bias_long=5, pbar=None, threads=1)
     Bases: object
     parts = (0, 1, 2)
     __init__ (spaths=None, ctype=None, bias_long=5, pbar=None, threads=1)
     beat()
     update()
     lens()
     lens_norm()
     lens_real()
     full_size()
     static simple_types_distribution (types)
     types_distribution()
     types_prob_to_types (types_prob)
     get_master_path (smooth=None, resid=0)
create_master_spath (spaths, smooth=None, resid=0, ctype=None, bias_long=5, pbar=None)
calculate_master (spaths_resid_ctype_smooth)
aquaduct.geom.pca module
class Center (X)
     Bases: object
     \__init\_(X)
      \underline{\phantom{a}}call\underline{\phantom{a}}(X)
     undo (X)
class Normalize (X)
     Bases: object
     \_\_\mathtt{init}\_\_(X)
     \mathtt{call} (X)
     undo (X)
class Standartize (X)
     Bases: aquaduct.geom.pca.Center, aquaduct.geom.pca.Normalize
      \underline{\hspace{1cm}}init\underline{\hspace{1cm}} (X)
     \_\_\mathtt{call}\_\_(X)
     undo (X)
```

```
\mathbf{class} \ \mathbf{PCA} \ (X, prepro=None)
     Bases: object
     ___init___(X, prepro=None)
     preprocess(X)
     preprocess undo(X)
     \underline{\phantom{a}}call\underline{\phantom{a}}(X)
     undo(T)
aquaduct.geom.smooth module
class Smooth (recursive=None, **kwargs)
     Bases: object
     __init__ (recursive=None, **kwargs)
     smooth (coords)
     call (coords)
class GeneralWindow
     static max_window_at_pos (pos, size)
     check bounds at max window at pos (lb, ub, pos, size)
class WindowSmooth (window=5, function=<function mean>, **kwargs)
     Bases: aquaduct.geom.smooth.Smooth, aquaduct.geom.smooth.GeneralWindow
     __init__ (window=5, function=<function mean>, **kwargs)
     smooth (*args, **kwargs)
class DistanceWindowSmooth (window=5, function=<function mean>, **kwargs)
     Bases: aquaduct.geom.smooth.Smooth, aquaduct.geom.smooth.GeneralWindow
     ___init___(window=5, function=<function mean>, **kwargs)
     smooth (*args, **kwargs)
class ActiveWindowSmooth (window=5, function=<function mean>, **kwargs)
     \textbf{Bases:} \ a \textit{quaduct.geom.smooth.Smooth}, \textit{aquaduct.geom.smooth.GeneralWindow}
     ___init___(window=5, function=<function mean>, **kwargs)
     smooth (*args, **kwargs)
class MaxStepSmooth (step=1.0, **kwargs)
     Bases: aquaduct.geom.smooth.Smooth
     ___init___(step=1.0, **kwargs)
     smooth (*args, **kwargs)
class WindowOverMaxStepSmooth (**kwargs)
     Bases: aquaduct.geom.smooth.Smooth
     ___init___(**kwargs)
     smooth (coords)
class ActiveWindowOverMaxStepSmooth (**kwargs)
     Bases: aquaduct.geom.smooth.Smooth
     ___init___(**kwargs)
```

```
smooth (coords)
```

#### class DistanceWindowOverMaxStepSmooth (\*\*kwargs)

```
Bases: aquaduct.geom.smooth.Smooth
__init___(**kwargs)
smooth(coords)
```

#### aquaduct.geom.traces module

```
diff(trace)
```

This function calculates the distance between 2 given points.

Parameters trace – coordinates in numpy array object

**Returns** distance between points

tracepoints (start, stop, nr)

#### **Parameters**

- start coordinates of the first point as a numpy array object
- stop coordinates of the second point as a numpy array object
- nr number of elements between the first and second point

Returns two-dimentional numpy array; number of dimentions depends on nr parameter

midpoints (paths)

The function returns a tuple of numpy arrays extended with mid point spanning last and first element(column) of these arrays.

**Parameters** paths – a tuple of 2-dimentional np.arrays that hold 3D coordinates; each element holds one trace, all elements are supposed to make one path divided in to sections

Returns paths elements with additional mid points as a generator object

### ${\tt length\_step\_std}\,(\mathit{trace})$

This function calculates sum, mean and standard deviation from all segments of a trace.

Parameters trace – coordinates of points as numpy array

**Returns** a tuple with basics statistics of a trace

```
derrivative (values)
vector_norm(V)
```

Parameters V – a vector in a form of array-like object, tuple or a list

Returns normalized length of a vector

#### triangle angles (A, B, C)

Parameters are coordinates of points which are tops of triangle. The function calculates angles in a triangle formed by given coordinates.

#### **Parameters**

- A coordinates of the first point
- **B** coordinates of the second point
- **C** coordinates of the third point

**Returns** list of arguments where angle is given in radians , the output is as follow: [BAC,CAB,ABC]

#### $triangle_angles_last(A, B, C)$

Parameters are coordinates of points which are tops of triangle. The function calculates the [ABC] angle.

#### **Parameters**

- A coordinates of the first point [A top]
- **B** coordinates of the second point [B top]
- **C** coordinates of the third point [C top]

**Returns** list with one value of ABC angle in radians

#### $triangle_height(A, B, C)$

Parameters are coordinates of points which are tops of triangle. The function calculates the ABC triangle height.

#### **Parameters**

- A coordinates of the first point [A top]
- **B** coordinates of the second point [B top]
- **C** coordinates of the third point [C top]

Returns one value of ABC triangle height

#### $vectors\_angle(A, B)$

This function calculates the angle between two given vectors (starting from the [0,0,0] to the given coordinates.

#### **Parameters**

- A coordinates of the first point which is the end of the vector
- B coordinates of the second point which is the end of the vector

**Returns** the angle between vectors in question (in radians)

#### $vectors\_angle\_alt(A, B)$

This function calculates the angle between two given vectors (starting from the [0,0,0] to the given coordinates

• alternative method.

#### **Parameters**

- A coordinates of the first point which is the end of the vector
- B coordinates of the second point which is the end of the vector

**Returns** the angle between vectors in question (in radians)

```
vectors\_angle\_alt\_anorm(A, B, A\_norm)
```

This function calculates the angle between two given vectors (starting from the [0,0,0] to the given coordinates

• alternative method with additional A\_norm holding norm of A.

#### **Parameters**

- A coordinates of the first point which is the end of the vector
- B coordinates of the second point which is the end of the vector
- A\_norm additional parameter holding normalized of vector A

**Returns** the angle between vectors in question (in radians)

 $vectors\_angle\_anorm(A, B, A\_norm)$ 

This function calculates the angle between two given vectors (starting from the [0,0,0] to the given coordinates using additional A\_norm holding norm of A.

#### **Parameters**

- A coordinates of the first point which is the end of the vector
- B coordinates of the second point which is the end of the vector
- A\_norm additional parameter holding normalized of vector A

**Returns** the angle between vectors in question (in radians)

#### class LinearizeOneWay

Bases: object here (coords)

This function simplifies the trace by removing the redundant, linear points :param coords: 3D coordinates of a trace as an array-like object :return: indices of coordinates which are a staring and ending points of linear fragments and other non-linear points of the trace

#### class LinearizeHobbit

```
Bases: aquaduct.geom.traces.LinearizeOneWay
and_back_again(coords)
__call__(coords)
```

#### class LinearizeRecursive

Bases: object

Base class for linearization methods classes.

It implements recursive algorithm.

here (coords, depth=0)

Core of recursive linearization argorithm.

It checks if the first, the last and the middle point are linear according to the criterion. The middle point is a selected point that is in the middle of length of the paths made by input coordinates.

If these points are linear their indices are returned. Otherwise, coordinates are split into two parts. First part spans points from the first point to the middle point (inclusive) and the second part spans points from the middle (inclusive) to the last point. Next, these two parts are submitted recursively to here ().

Results of these recursive calls are joined, redundant indices are removed and sorted result is returned.

#### **Parameters**

- coords (numpy.ndarray) Input coordinates.
- **depth** (*int*) Depth of recurence.

**Returns** Indices of coords points that can be used instead of all points in visulatization.

Return type list of int

```
__call__(coords)

class TriangleLinearize(threshold=0.01)

Bases: object
__init__(threshold=0.01)

is_linear(coords, **kwargs)

class VectorLinearize(treshold=0.05236)
```

Bases: object

Base class for linearization methods classes.

It implements vector linearization criterion.

```
___init___(treshold=0.05236)
```

# is\_linear\_core (coords, depth=None)

Method checks if input coordinates are linear according to the threshold and depth.

It begins with calculation of the threshold. If *depth* is None it is set to 1. Current threshold is calculated with following simple equation:

```
threshold_{current} = threshold_{initial} * (2 - 0.9^{depth})
```

Next, in a loop over all points but the first and the last the angle is calculated between two vectors. The first one made by the point and the first point, and the second vector made by the last and the first point. If any of the calculated angles is bigger the the treshold methods returns False; otherwise method returns True.

#### **Parameters**

- coords (numpy.ndarray) Coordinates for which linearization criterion is checked.
- **depth** (*int*) Depth of recurence.

**Returns** True if input coordinates are linear and False otherwise.

Return type bool

# is\_linear (coords, depth=None, \*\*kwargs)

For more detail see <code>is\_linear\_core()</code> which is used as the criterion of linearity in this method.

#### **Parameters**

- coords (numpy.ndarray) Coordinates for which linearization criterion is checked.
- **depth** (*int*) Depth of recurence.

**Returns** True if input coordinates are linear and False otherwise. Criterion is checked for coordinates in normal and reverse order.

Return type bool

# class LinearizeRecursiveVector (treshold=0.05236)

Bases: aquaduct.geom.traces.LinearizeRecursive, aquaduct.geom.traces.VectorLinearize Class provides recursive linearization of coordinates with LinearizeRecursive algorithm and the criterion of linearity implemented by VectorLinearize. This is default method.

# ${\bf class\ Linearize Recursive Triangle}\ ({\it threshold} {=}\ 0.01)$

```
Bases: aquaduct.geom.traces.LinearizeRecursive, aquaduct.geom.traces. TriangleLinearize
```

Class provides recursive linearization of coordinates with LinearizeRecursive algorithm and the criterion of linearity implemented by TriangleLinearize.

# class LinearizeHobbitVector(treshold=0.05236)

```
Bases: aquaduct.geom.traces.LinearizeHobbit, aquaduct.geom.traces. 
VectorLinearize
```

Class provides recursive linearization of coordinates with LinearizeHobbit algorithm and the criterion of linearity implemented by VectorLinearize.

#### class LinearizeHobbitTriangle (threshold=0.01)

```
Bases: aquaduct.geom.traces.LinearizeHobbit, aquaduct.geom.traces.
TriangleLinearize
```

Class provides recursive linearization of coordinates with LinearizeHobbit algorithm and the criterion of linearity implemented by TriangleLinearize.

```
class LinearizeOneWayVector (treshold=0.05236)
```

```
 \begin{array}{ll} \textbf{Bases:} & \textit{aquaduct.geom.traces.LinearizeOneWay,} & \textit{aquaduct.geom.traces.} \\ \textit{VectorLinearize} \end{array}
```

Class provides recursive linearization of coordinates with LinearizeOneWay algorithm and the criterion of linearity implemented by VectorLinearize.

# class LinearizeOneWayTriangle (threshold=0.01)

```
Bases: aquaduct.geom.traces.LinearizeOneWay, aquaduct.geom.traces. TriangleLinearize
```

Class provides recursive linearization of coordinates with LinearizeOneWay algorithm and the criterion of linearity implemented by TriangleLinearize.

# **Module contents**

# aquaduct.traj package

#### **Submodules**

# aquaduct.traj.dumps module

```
class TmpDumpWriterOfMDA
    Bases: object
    __init__()
    dump_frames (reader, frames, selection='protein')
    close()
    __del__()
```

# aquaduct.traj.inlets module

```
{\bf class} \ {\tt ProtoInletTypeCodes}
```

```
surface = 'surface'
internal = 'internal'
incoming = 'inin'
outgoing = 'inout'
class InletTypeCodes
```

Bases: aquaduct.traj.inlets.ProtoInletTypeCodes

```
all_surface = [('surface', 'inin'), ('surface', 'inout')]
all_internal = [('internal', 'inin'), ('internal', 'inout')]
all_incoming = [('surface', 'inin'), ('internal', 'inin')]
all_outgoing = [('surface', 'inout'), ('internal', 'inout')]
surface_incoming = ('surface', 'inin')
internal_incoming = ('internal', 'inin')
internal_outgoing = ('internal', 'inout')
surface_outgoing = ('surface', 'inout')
itype = 'internal'
```

```
class InletClusterGenericType (inp, out)
     Bases: object
      ___init___(inp, out)
     input
     output
     static cluster2str (cl)
     __getitem__(item)
     ___len__()
     __str__()
     __repr__()
     make_val(base)
      ___cmp___(other)
      __hash___()
make_spherical(xyz)
class InletClusterExtendedType (surfin, interin, interout, surfout)
     Bases: aquaduct.traj.inlets.InletClusterGenericType
      ___init___(surfin, interin, interout, surfout)
     generic
class Inlet (coords, type, reference)
     Bases: tuple
     __getnewargs__()
          Return self as a plain tuple. Used by copy and pickle.
      __getstate__()
          Exclude the OrderedDict from pickling
     static __new__ (_cls, coords, type, reference)
          Create new instance of Inlet(coords, type, reference)
          Return a nicely formatted representation string
      __slots__ = ()
     _asdict()
          Return a new OrderedDict which maps field names to their values
     _fields = ('coords', 'type', 'reference')
     classmethod _make (iterable, new=<built-in method __new__ of type object>, len=<built-in func-
                          tion len>)
          Make a new Inlet object from a sequence or iterable
     _replace(_self, **kwds)
          Return a new Inlet object replacing specified fields with new values
     coords
          Alias for field number 0
     reference
          Alias for field number 2
     type
          Alias for field number 1
```

```
class Inlets (spaths, center_of_system=None, onlytype=[('surface', 'inin'), ('surface', 'inout')])
     Bases: object
     __init__(spaths, center_of_system=None, onlytype=[('surface', 'inin'), ('surface', 'inout')])
     extend_inlets (spath, onlytype=None)
     add_cluster_annotations (clusters)
     size
     coords
     types
     refs
     call_clusterization_method(method, data)
     perform_clustering (method)
     perform_reclustering (method, skip_outliers=False, skip_size=None)
     recluster_cluster (method, cluster)
     recluster_outliers (method)
     small_clusters_to_outliers (maxsize)
     renumber_clusters()
     sort_clusters()
     clusters_list
     clusters centers
     clusters_size
     clusters_std
     spaths2ctypes (*args, **kwargs)
     lim_to(what, towhat)
     lim2spaths (spaths)
     lim2types (types)
     lim2clusters (clusters)
     limspaths2 (*args, **kwargs)
aquaduct.traj.paths module
union (a, b)
glue(a, b)
xor (*args, **kwargs)
left(a, b)
right(a, b)
class PathTypesCodes
     path_in_code = 'i'
     path_object_code = 'c'
     path_out_code = '0'
```

```
object_name = 'c'
     scope_name = 's'
     out_name = 'n'
class GenericPaths (id_of_res, min_pf=None, max_pf=None)
    Bases: object, aquaduct.traj.paths.GenericPathTypeCodes
     ___init___(id_of_res, min_pf=None, max_pf=None)
     add_coord(coord)
     add_object (frame)
     add_scope (frame)
     add_type (frame, ftype)
    max_frame
    min_frame
    get_paths_in()
     get_paths_out()
    get_paths_for_frames_range(*args, **kwargs)
     find_paths (fullonly=False)
     find_paths_coords (fullonly=False)
    find_paths_types (fullonly=False)
     find_paths_coords_types (fullonly=False)
     get_single_path_coords(spath)
    get_single_path_types (spath)
    barber_with_spheres (spheres)
class SinglePathID (path_id=None, nr=None)
    Bases: object
    ___init___(path_id=None, nr=None)
     ___str___()
yield_single_paths (gps, fullonly=False, progress=False)
class SinglePath (path_id, paths, coords, types)
    Bases: object, aquaduct.traj.paths.PathTypesCodes, aquaduct.traj.inlets.
     InletTypeCodes
     empty_coords = array([], shape=(0, 3), dtype=float32)
     ___init___(path_id, paths, coords, types)
    coords_first_in
    coords_last_out
     coords_filo
     get_inlets()
     coords
     coords_cont
    paths
```

class GenericPathTypeCodes

```
paths_cont
    types
    types_cont
    gtypes
    gtypes_cont
    etypes
    etypes_cont
    size
    begins
    ends
    has_in
    has_object
    has_out
    get_coords (*args, **kwargs)
    get_coords_cont (smooth=None)
    _make_smooth_coords (*args, **kwargs)
    apply_smoothing(smooth)
    get_distance_cont (smooth=None, normalize=False)
    get_distance_rev_cont(*args, **kwargs)
    get_distance_both_cont(*args, **kwargs)
    get_velocity_cont(*args, **kwargs)
    get_acceleration_cont(*args, **kwargs)
class MasterPath (sp)
    Bases: aquaduct.traj.paths.SinglePath
    ___init___(sp)
    add_width(width)
aquaduct.traj.reader module
class Reader (topology, trajectory)
    Bases: object
    __init__ (topology, trajectory)
    open_trajectory()
    number_of_frames
    set_current_frame (frame)
    next_frame()
    iterate_over_frames()
    parse_selection (selection)
    select_resnum(resnum)
    select_multiple_resnum(resnum_list)
```

```
class ReadViaMDA (topology, trajectory)
    Bases: aquaduct.traj.reader.Reader
    number_of_frames
     set_current_frame (frame)
    next_frame()
    parse_selection(selection)
    select_resnum(resnum)
    select_multiple_resnum(resnum_list)
     __enter__()
     __exit__(typ, value, traceback)
     open_trajectory()
class ReadAmberNetCDFviaMDA (topology, trajectory)
    Bases: aquaduct.traj.reader.ReadViaMDA
     open_trajectory()
class ReadDCDviaMDA (topology, trajectory)
    Bases: aquaduct.traj.reader.ReadViaMDA
     open_trajectory()
aquaduct.traj.selections module
class Selection
    Bases: object
    def __init__(self,selection,selection_string=None):
         self.selection_object = selection self.selection_string = selection_string
     center_of_mass()
     iterate_over_residues()
    unique_resids()
    unique_resids_number()
     atom_positions()
     center_of_mass_of_residues()
    get_convexhull_of_atom_positions()
     contains_residues (other, convex_hull=False, map_fun=None)
     containing_residues (other, *args, **kwargs)
    uniquify()
     ___add___ (other)
     first_resid()
class SelectionMDA (atoms)
              MDAnalysis.core.AtomGroup.AtomGroup, aquaduct.traj.selections.
    Bases:
     Selection
    iterate_over_residues()
    unique_resids (ikwid=False)
     atom_positions()
```

```
__add__(other)
uniquify()

class CompactSelectionMDA(sMDA)
Bases: object
__init__(sMDA)
toSelectionMDA(reader)
```

#### **Module contents**

# aquaduct.utils package

# **Submodules**

# aquaduct.utils.clui module

Module comprises convieniences functions and definitios for different operations related to command line user interface.

```
emit_message_to_file_in_root_logger (mess)
message_special (mess)
message (mess, cont=False)
```

Prints message to standard error. If FileHandler is present in the root\_logger the same message is appended to the log file.

# **Parameters**

- mess (str) message to print
- cont (bool) if set True no new line is printed

```
class fbm (info, cont=True)
    Bases: object
    __init__ (info, cont=True)
    __enter__()
```

 $\_\mathtt{call}\_\_(info)$ 

\_\_exit\_\_(typ, value, traceback)

class tictoc (mess)

```
Bases: object
__init__(mess)
__enter__()
__exit__(typ, value, traceback)
```

# ${\tt gregorian\_year\_in\_days} = 365.2425$

Length of Gregorian year in days. Average value. Source: https://en.wikipedia.org/wiki/Year

```
smart_time_string(s, rl=0, t=1.1, maximal_length=None, maximal_units=5)
```

Function transforms time in seconds to nicely formatted string of length defined by maximal\_length. Depending on number of seconds time is represented with one or more of the following units:

Unit name	Unit abbreviation
seconds	S
minutes	m
hours	h
days	d
years	у

Maximal number of units used in time string can be set with maximal\_units.

#### **Parameters**

- **s** (*int*) Input time in seconds.
- **rl** (*int*) Number of units already used for representing time.
- t (float) Exces above standard number of current time units.
- maximal\_length (int) Maximal length of the output string. Must be greater then 0.
- maximal\_units (int) Maximal number of units used in the output string. Must be greater then 0 and lower then 6.

Returns string of nicely formated time

Return type str

```
gsep (sep='-', times=72, length=None)
```

Generic separator.

#### **Parameters**

- sep(str) Element(s) of separator.
- times (int) Number of times sep is printed.
- **length** (*int*) Optional maximal length of output.

**Returns** String separator.

Return type str

 $\texttt{tsep}\left(line\right)$ 

**Parameters** line (str) – Input line.

**Returns** Returns default gsep() of length of line.

underline (line)

**Parameters** line (str) – Input line.

**Returns** String made by concatenation of line, os.linesep, and output of tsep() called with line.

Return type str

 $\verb+thead+ (line)$ 

**Parameters** line (str) – Input line.

**Returns** String made by concatenation of output of tsep() called with line, line, os. linesep, and again output of tsep() called with line.

Return type str

class SimpleProgressBar (maxval=None, mess=None)

Bases: object

Simple progress bar displaying progress with percent indicator, progress bar and ETA. Progress is measured by iterations.

Variables

- rotate (str) String comprising characters with frames of a rotating toy.
- barlenght (int) Length of progress bar.
- maxval (int) maximal number of iterations
- **current** (*int*) current number of iterations
- **overrun\_notice** (bool) if True, overrun above **:ivar:'maxval'** iterations causes insert of newline
- overrun (bool) flag of overrun
- **begin** (*int*) time in seconds at the initialization of the *SimpleProgressBar* class.
- tcurrent (int) time in seconds of current iteration

```
rotate = '\\\/-'
```

# barlenght = 24

```
___init___ (maxval=None, mess=None)
```

#### **Parameters**

- maxval (int) Maximal number of iterations stored to maxval.
- mess(str) Optional message displayed at progress bar initialization.

#### bar()

# ETA()

Returns ETA calculated on the basis of current number of iterations current and current time tcurrent. If number of iterations is 0 returns?. Time is formated with smart\_time\_string().

**Returns** ETA as string.

Return type str

# percent()

Returns float number of precent progress calculated in the basis of current number of iterations current. Should return number between 0 and 100.

Returns percent progress number

Return type float

#### show()

Shows current progress.

If value returned by percent() is =< 100 then progres is printed as percent indicator leaded by ETA calculated by ETA().

If value returned by percent() is > 100 then progress is printed as number of iterations and total time.

Progress bar is writen to standard error.

#### heartbeat()

# update (step)

Updates number of current iterations current by one if step is > 0. Otherwise number of current iterations is not updated. In boths cases time of current iteration tcurrent is updated and show() is called.

**Parameters** step (int) – update step

#### ttime()

Calculates and returns total time string formated with smart\_time\_string().

**Returns** string of total time

# Return type str

# finish()

Finishes progress bar. First, update() is called with step = 0. Next message of total time is writen to standard error.

#### pbar

alias of SimpleProgressBar

get\_str\_timestamp()

# aquaduct.utils.helpers module

Collection of helpers - functions and decorators.

# combine (seqin)

This is an alien function. It is not extensively used.

Directly taken form http://aspn.activestate.com/ASPN/Cookbook/Python/Recipe/302478/index\_txt

Returns a list of all combinations of argument sequences. For example, following call:

```
combine(((1,2),(3,4)))
```

gives following list of combinations:

```
[[1, 3], [1, 4], [2, 3], [2, 4]]
```

Parameters seqin (tuple) - Tuple of sequences to combine.

**Returns** All possible combinations of all input sequences.

Return type list of lists

# is number(s)

# lind(l,ind)

Indexes lists using lists of integers as identificators. For example:

```
lind(['a','b','c','d','e'],[1,4,2])
```

returns:

```
['b', 'e', 'c']
```

# **Parameters**

- 1 (list) List to be indexed.
- ind (list) Integer indexes.

Returns Reindexed list.

Return type list

# class Auto

Auto type definition. The class is used as an alternative value for options (if particular option supports it). If options (or variables/parameters etc.) have value of Auto it means that an automatic process for parametrization should be performed.

For example, if the input parameter is set to Auto it is supposed that its value is calculated on the basis of input data or other parameters.

```
__repr__()
```

Returns String Auto.

Return type str

```
__str__()
Calls __repr__().
```

# create\_tmpfile(ext=None)

Creates temporary file. File is created, closed and its file name is returned.

**Note:** It is responsibility of the caller to delete the file.

**Parameters** ext (str) – Optional extension of the file.

**Returns** File name of created temporary file.

Return type str

# range2int(r, uniq=True)

Transforms a string range in to a list of integers (with added missing elements from given ranges).

For example, a following string:

```
'0:2 4:5 7 9'
```

is transformed into:

```
[0,1,2,4,5,7,9]
```

#### **Parameters**

- **r** (str) String of input range.
- uniq (bool) Optional parameter, if set to *True* only unique and sorted integers are returned.

**Returns** List of integers.

Return type list of int

# int2range(l)

Transforms a list of integers in to a string of ranges.

For example, a following list:

```
[0,1,2,4,5,7,9]
```

is transformed into:

```
0:2 4:5 7 9
```

Parameters 1 (list) – input list of int

Returns String of ranges.

Return type str

# $is\_iterable(l)$

Checks if provided object is iterable. Returns True is it is iterable, otherwise returns False.

**Parameters 1** (list) – input object

Returns True if submitted object is iterable otherwise returns False.

Return type bool

**Warning:** Current implementation cannot be used with generators!

#### Todo

Current implementation is primitive and HAVE TO be replaced.

#### sortify (gen)

Decorator to convert functions' outputs into a sorted list. If the output is iterable it is converted in to a list of appropriate length. If the output is not iterable it is converted in to a list of length 1.

Written on the basis of listify().

Returns Output of decorated function converted to a sorted list.

Return type list

# uniqify (gen)

Decorator to convert functions' outputs into a sorted list of unique objects. If the output is iterable it is converted in to a list of appropriate length. If the output is not iterable it is converted in to a list of length 1.

Written on the basis of listify().

Returns Output of decorated function converted to a sorted list of unique objects.

Return type list

#### listify (gen)

Decorator to convert functions' outputs into a list. If the output is iterable it is converted in to a list of appropriate length. If the output is not iterable it is converted in to a list of length 1.

This function was copied from:

http://argandgahandapandpa.wordpress.com/2009/03/29/python-generator-to-list-decorator/

and further improved by tljm@wp.pl.

Returns Output of decorated function converted to a list.

Return type list

# ${\tt tupleify}\,(gen)$

Decorator to convert functions' outputs into a tuple. If the output is iterable it is converted in to a tuple of appropriate length. If the output is not iterable it is converted in to a tuple of length 1.

Written on the basis of listify().

**Returns** Output of decorated function converted to a tuple.

Return type tuple

# arrayify(gen)

Decorator to convert functions' outputs into a 2D numpy array. If the output is iterable it is converted in to a 2D numpy array of appropriate shape. If the output is not iterable it is converted in to a 2D numpy array of shape 1x1.

Written on the basis of listify().

Returns Output of decorated function converted to a 2D numpy array.

**Return type** numpy.ndarray

# arrayify1 (gen)

Decorator to convert functions' outputs into a 1D numpy array. If the output is iterable it is converted in to a 2D numpy array of appropriate shape. If the output is not iterable it is converted in to a 2D numpy array of shape 1x1.

Written on the basis of listify().

**Returns** Output of decorated function converted to a 1D numpy array.

Return type numpy.ndarray

```
list\_blocks\_to\_slices(l)
```

Slices list in to block according to its elements identity. Resulting slices correspond to blocks of identical elements.

**Parameters** 1(list) – List of any objects.

Returns Generator of slices.

Return type generator

```
what2what (what, towhat)
```

This function search if elements of the one list (:attr: 'what') are present in the other list (:attr: 'towhat') and returns indices of elements form :attr:'what' list as a tuple. If elements from the first list are not present in the second list the tuple is empty. :param list what: Input list for which indices of elements present in towhat are returned. :param list towhat: List of elements which input list is indexed to. :return: Indices of what list that are present in towhat list. :rtype: tuple

# make\_iterable (something)

If input object is not iterable returns it as one element list. Otherwise returns the object.

**Parameters** something (object) – Input object.

Returns Iterable object.

**Return type** iterable or list

```
strech_zip(*args)
compress_zip(*args)
zip_zip(*args, **kwargs)
xzip_xzip(*args, **kwargs)
```

# aquaduct.utils.maths module

```
make_default_array (array_like)
```

aquaduct.utils.multip module

**Module contents** 

aquaduct.visual package

**Submodules** 

aquaduct.visual.cmaps module

aquaduct.visual.helpers module

```
 \begin{tabular}{ll} \textbf{euclidean} & (A,B) \\ \begin{tabular}{ll} \textbf{cityblock} & (A,B) \\ \begin{tabular}{ll} \textbf{cc\_safe} & (c) \\ \begin{tabular}{ll} \textbf{cc} & (c) \\ \begin{tabular}{ll} \textbf{color\_codes} & (code, custom\_codes=None) \\ \end{tabular}
```

```
get_cmap (size)
class ColorMapDistMap
    Bases: object
    grey = (0.5, 0.5, 0.5, 1)
     ___init___()
    distance(E1, E2)
    static color_distance (e1, e2)
     __call__(node)
    _ColorMapDistMap__do_cadex()
f_like(n)
aquaduct.visual.pymol_cgo module
aquaduct.visual.pymol_connector module
class BasicPymolCGO
    Bases: object
    cgo_entity_begin = []
    cgo_entity_end = []
     ___init___()
    clean()
    new()
    get()
    static make_color_triple (color_definition)
class BasicPymolCGOLines
    Bases: aquaduct.visual.pymol_connector.BasicPymolCGO
     cgo_entity_begin = [2.0, 1.0]
     cgo_entity_end = [3.0]
     add (coords=None, color=None)
class BasicPymolCGOSpheres
    Bases: a quaduct.visual.pymol\_connector.BasicPymolCGO\\
     cgo_entity_begin = []
     cgo_entity_end = []
     add (coords=None, radius=None, color=None)
class BasicPymolCGOPointers
    Bases: aquaduct.visual.pymol_connector.BasicPymolCGO
     cgo_entity_begin = []
     cgo_entity_end = []
     add_cone (coords1=None, coords2=None, radius1=None, radius2=None, color1=None,
               color2=None)
     add_pointer (point=None, direction=None, length=None, color=None, reverse=False)
class SimpleTarWriteHelper
    Bases: object
```

```
___init___()
     open (filename)
     save_object2tar(obj, name)
     save_file2tar (filename, name)
     ___del___()
class ConnectToPymol
     Bases: object
     cgo_line_width = 2.0
     ct_pymol = 'pymol'
     ct_file = 'file'
     ___init___()
     decode_color (*args, **kwargs)
     init_pymol()
     init_script (filename)
     add_cgo_object (name, cgo_object, state=None)
     del_cgo_object (name, state=None)
     load_pdb (name, filename, state=None)
     orient_on(name)
     ___del___()
class SinglePathPlotter (pymol_connector, linearize=None)
     Bases: object
     __init__ (pymol_connector, linearize=None)
                                                          smooth=None,
     add_single_path_continous_trace(spath,
                                                                              plot_in=True,
                                             plot_object=True, plot_out=True, **kwargs)
     paths_trace (spaths, smooth=None, name='paths', state=None, **kwargs)
     paths_inlets (spaths, smooth=None, color=None, plot_in=True, plot_out=True, name='in-out-
                     let', state=None, **kwargs)
     scatter (coords, radius=0.4, color='r', name='scatter', state=None)
     convexhull (chull, color='m', name='convexhull', state=None)
aquaduct.visual.quickplot module
yield_spath_len_and_smooth_diff_in_types_slices(sp,
                                                                             smooth=None.
                                                            smooth_len=None,
                                                            smooth_diff=None,
                                                            types='etypes')
plot_colorful_lines (x, y, c, **kwargs)
spaths_spectra(spaths, **kwargs)
plot_spath_spectrum(sp, **kwargs)
spath_spectrum(sp, **kwargs)
showit (gen)
get_ax3d(fig, sub=111)
```

```
class SimpleTracePlotter
    Bases: object
    plot_line (coords, color, **kwargs)
     single_trace (coords, color='r', **kwargs)
    path_trace(path, color=('r', 'g', 'b'), plot_in=True, plot_object=True, plot_out=True,
                  **kwargs)
class SimpleProteinPlotter
    Bases: aquaduct.visual.quickplot.SimpleTracePlotter
    protein_trace (protein, smooth=None, color=('c', 'm', 'y'), **kwargs)
class SimplePathPlotter
    Bases: aquaduct.visual.quickplot.SimpleTracePlotter
     single_path_traces (spaths, smooth=None, color=('r', 'g', 'b'), **kwargs)
class MPLTracePlotter
    Bases: aquaduct.visual.quickplot.SimplePathPlotter, aquaduct.visual.
     quickplot.SimpleProteinPlotter
     init_ax (*args, **kwargs)
    plot_line(*args, **kwargs)
     scatter (*args, **kwargs)
Module contents
```

# 5.1.2 Module contents

Aqua-Duct - a collection of tools to trace residues in MD simulation.

# version()

Returns aquaduct version number.

**Returns** 3 element tuple of int numbers

Return type tuple

#### version\_nice()

Returns aquaduct version number as nicely formatted string.

**Returns** string composed on the basis of the number returned by version ().

Return type str

# greetings()

Returns fancy greetings of aquaduct. It has a form of ASCII-like graphic. Currently it returns following string:

```
\sim A Q U A - D U C T \sim \sim
####
        #######
                 ########
                   ####
##
         ####
                    ##
         ##
          ##
                    ##
         ##
                    ##
```

**Returns** aquaduct fancy greetings.

# Return type str

Documentation for other versions of Aqua-Duct:

• development version (use with care)

# **PYTHON MODULE INDEX**

# а

```
aquaduct, 49
aquaduct.geom, 34
aquaduct.geom.cluster, 27
aquaduct.geom.convexhull, 27
aquaduct.geom.master, 27
aquaduct.geom.pca, 28
aquaduct.geom.smooth, 29
aquaduct.geom.traces, 30
aquaduct.traj,40
aquaduct.traj.dumps, 34
aquaduct.traj.inlets, 34
aquaduct.traj.paths,36
aquaduct.traj.reader,38
aquaduct.traj.selections, 39
aquaduct.utils,46
aquaduct.utils.clui,40
aquaduct.utils.helpers,43
aquaduct.utils.maths, 46
aquaduct.utils.multip,46
aquaduct.visual,49
aquaduct.visual.cmaps,46
aquaduct.visual.helpers,46
aquaduct.visual.pymol_cgo, 47
aquaduct.visual.pymol_connector,47
aquaduct.visual.quickplot,48
```

# **INDEX**

Symbols	init() (Inlets method), 36
_ColorMapDistMapdo_cadex() (ColorMapDistMap	init() (MasterPath method), 38
method), 47	init() (MaxStepSmooth method), 29
add() (Selection method), 39	init() (Normalize method), 28
add() (SelectionMDA method), 40	init() (PCA method), 29
call() (CTypeSpathsCollectionWorker method), 28	init() (PerformClustering method), 27
call() (Center method), 28	init() (Reader method), 38
call() (ColorMapDistMap method), 47	init() (SimpleProgressBar method), 42
call() (LinearizeHobbit method), 32	init() (SimpleTarWriteHelper method), 47
call() (LinearizeRecursive method), 32	init() (SinglePath method), 37
call() (Normalize method), 28	init() (SinglePathID method), 37
call() (PCA method), 29	init() (SinglePathPlotter method), 48
call() (PerformClustering method), 27	init() (Smooth method), 29
call() (Smooth method), 29	init() (Standartize method), 28
call() (Standartize method), 28	init() (TmpDumpWriterOfMDA method), 34
call() (fbm method), 40	init() (TriangleLinearize method), 32
cmp() (InletClusterGenericType method), 35	init() (VectorLinearize method), 33
del() (ConnectToPymol method), 48	init() (WindowOverMaxStepSmooth method), 29
del() (SimpleTarWriteHelper method), 48	init() (WindowSmooth method), 29
del() (TmpDumpWriterOfMDA method), 34	init() (fbm method), 40
enter() (ReadViaMDA method), 39	init() (tictoc method), 40
enter() (fbm method), 40	len() (InletClusterGenericType method), 35
enter() (tictoc method), 40	new() (Inlet static method), 35
exit() (ReadViaMDA method), 39	<u>repr()</u> (Auto method), 43
exit() (fbm method), 40	<u>repr()</u> (Inlet method), 35
exit() (tictoc method), 40	repr() (InletClusterGenericType method), 35
getitem() (InletClusterGenericType method), 35	slots (Inlet attribute), 35
getnewargs() (Inlet method), 35	str() (Auto method), 44
getstate() (Inlet method), 35	str() (InletClusterGenericType method), 35
hash() (InletClusterGenericType method), 35	str() (SinglePathID method), 37
init() (ActiveWindowOverMaxStepSmooth	_asdict() (Inlet method), 35
method), 29	_edges() (in module aquaduct.geom.convexhull), 27
init() (ActiveWindowSmooth method), 29	_facets() (in module aquaduct.geom.convexhull), 27
init() (BasicPymolCGO method), 47	_fields (Inlet attribute), 35
init() (CTypeSpathsCollection method), 28	_get_noclusters() (PerformClustering method), 27
init() (CTypeSpathsCollectionWorker method), 28	_make() (aquaduct.traj.inlets.Inlet class method), 35
init() (Center method), 28	_make_smooth_coords() (SinglePath method), 38
init() (ColorMapDistMap method), 47	_point_within_convexhull() (in module
init() (CompactSelectionMDA method), 40	aquaduct.geom.convexhull), 27
init() (ConnectToPymol method), 48	_replace() (Inlet method), 35
init() (DistanceWindowOverMaxStepSmooth	_vertices_ids() (in module aquaduct.geom.convexhull),
method), 30	27
init() (DistanceWindowSmooth method), 29	_vertices_points() (in module
init() (GenericPaths method), 37	aquaduct.geom.convexhull), 27
init() (InletClusterExtendedType method), 35	
init () (InletClusterGenericType method) 35	

A	barlenght (SimpleProgressBar attribute), 42
ActiveWindowOverMaxStepSmooth (class in	BasicPymolCGO (class in
aquaduct.geom.smooth), 29	aquaduct.visual.pymol_connector), 47
ActiveWindowSmooth (class in	BasicPymolCGOLines (class in
aquaduct.geom.smooth), 29	aquaduct.visual.pymol_connector), 47
add() (BasicPymolCGOLines method), 47	BasicPymolCGOPointers (class in
add() (BasicPymolCGOSpheres method), 47	aquaduct.visual.pymol_connector), 47
add_cgo_object() (ConnectToPymol method), 48	BasicPymolCGOSpheres (class in
add_cluster_annotations() (Inlets method), 36	aquaduct.visual.pymol_connector), 47
add_cone() (BasicPymolCGOPointers method), 47	beat() (CTypeSpathsCollection method), 28
add_coord() (GenericPaths method), 37	begins (SinglePath attribute), 38
add_object() (GenericPaths method), 37	С
add_pointer() (BasicPymolCGOPointers method), 47	
add_scope() (GenericPaths method), 37	calculate_master() (in module aquaduct.geom.master),
add_single_path_continous_trace() (SinglePathPlotter	28
method), 48	call_clusterization_method() (Inlets method), 36
add_type() (GenericPaths method), 37	cc() (in module aquaduct.visual.helpers), 46
add_width() (MasterPath method), 38	cc_safe() (in module aquaduct.visual.helpers), 46
all_incoming (InletTypeCodes attribute), 34	Center (class in aquaduct.geom.pca), 28
all_internal (InletTypeCodes attribute), 34	center_of_mass() (Selection method), 39
all_outgoing (InletTypeCodes attribute), 34	center_of_mass_of_residues() (Selection method), 39
all_surface (InletTypeCodes attribute), 34	centers() (PerformClustering method), 27 cgo_entity_begin (BasicPymolCGO attribute), 47
and_back_again() (LinearizeHobbit method), 32 apply_smoothing() (SinglePath method), 38	cgo_entity_begin (BasicPymolCGOLines attribute), 47
aquaduct (module), 49	cgo_entity_begin (BasicPymolCGOPointers attribute), 47
aquaduct (module), 49	47
aquaduct.geom.cluster (module), 27	cgo_entity_begin (BasicPymolCGOSpheres attribute),
aquaduct.geom.convexhull (module), 27	47
aquaduct.geom.master (module), 27	cgo_entity_end (BasicPymolCGO attribute), 47
aquaduct.geom.pca (module), 28	cgo_entity_end (BasicPymolCGOLines attribute), 47
aquaduct.geom.smooth (module), 29	cgo_entity_end (BasicPymolCGOPointers attribute),
aquaduct.geom.traces (module), 30	47
aquaduct.traj (module), 40	cgo_entity_end (BasicPymolCGOSpheres attribute), 47
aquaduct.traj.dumps (module), 34	cgo_line_width (ConnectToPymol attribute), 48
aquaduct.traj.inlets (module), 34	check_bounds_at_max_window_at_pos() (General-
aquaduct.traj.paths (module), 36	Window method), 29
aquaduct.traj.reader (module), 38	cityblock() (in module aquaduct.visual.helpers), 46
aquaduct.traj.selections (module), 39	clean() (BasicPymolCGO method), 47
aquaduct.utils (module), 46	close() (TmpDumpWriterOfMDA method), 34
aquaduct.utils.clui (module), 40	cluster2str() (InletClusterGenericType static method),
aquaduct.utils.helpers (module), 43	35
aquaduct.utils.maths (module), 46	clusters_centers (Inlets attribute), 36
aquaduct.utils.multip (module), 46	clusters_list (Inlets attribute), 36
aquaduct.visual (module), 49	clusters_size (Inlets attribute), 36
aquaduct.visual.cmaps (module), 46	clusters_std (Inlets attribute), 36
aquaduct.visual.helpers (module), 46	color_codes() (in module aquaduct.visual.helpers), 46 color_distance() (ColorMapDistMap static method), 47
aquaduct.visual.pymol_cgo (module), 47 aquaduct.visual.pymol_connector (module), 47	ColorMapDistMap (class in aquaduct.visual.helpers),
aquaduct.visual.quickplot (module), 48	47
arrayify() (in module aquaduct.utils.helpers), 45	combine() (in module aquaduct.utils.helpers), 43
arrayify1() (in module aquaduct.utils.helpers), 45	CompactSelectionMDA (class in
atom_positions() (Selection method), 39	aquaduct.traj.selections), 40
atom_positions() (SelectionMDA method), 39	compress_zip() (in module aquaduct.utils.helpers), 46
Auto (class in aquaduct.utils.helpers), 43	concatenate() (in module aquaduct.geom.master), 28
_	ConnectToPymol (class in
В	aquaduct.visual.pymol_connector), 48
bar() (SimpleProgressBar method), 42	containing_residues() (Selection method), 39
barber_with_spheres() (GenericPaths method), 37	contains_residues() (Selection method), 39

convexhull() (SinglePathPlotter method), 48	G
coords (Inlet attribute), 35	GeneralWindow (class in aquaduct.geom.smooth), 29
coords (Inlets attribute), 36	generic (InletClusterExtendedType attribute), 35
coords (SinglePath attribute), 37	GenericPaths (class in aquaduct.traj.paths), 37
coords_cont (SinglePath attribute), 37	GenericPathTypeCodes (class in aquaduct.traj.paths),
coords_filo (SinglePath attribute), 37 coords_first_in (SinglePath attribute), 37	36
coords_last_out (SinglePath attribute), 37	get() (BasicPymolCGO method), 47
coords_types_prob_widths() (CTypeSpathsCollection-	get_acceleration_cont() (SinglePath method), 38
Worker method), 28	get_ax3d() (in module aquaduct.visual.quickplot), 48 get_cmap() (in module aquaduct.visual.helpers), 46
create_master_spath() (in module aquaduct.geom.master), 28	get_convexhull_of_atom_positions() (Selection method), 39
create_tmpfile() (in module aquaduct.utils.helpers), 44	get_coords() (SinglePath method), 38
ct_file (ConnectToPymol attribute), 48	get_coords_cont() (SinglePath method), 38
ct_pymol (ConnectToPymol attribute), 48	get_distance_both_cont() (SinglePath method), 38
CTypeSpathsCollection (class in	get_distance_cont() (SinglePath method), 38
aquaduct.geom.master), 28 CTypeSpathsCollectionWorker (class in	get_distance_rev_cont() (SinglePath method), 38
CTypeSpathsCollectionWorker (class in aquaduct.geom.master), 28	get_inlets() (SinglePath method), 37
n aquaduct.geom.master), 20	get_master_path() (CTypeSpathsCollection method), 28
decide_on_type() (in module aquaduct.geom.master),	get_mean_coord_() (in module aquaduct.geom.master), 27
27 decode_color() (ConnectToPymol method), 48	get_paths_for_frames_range() (GenericPaths method), 37
del_cgo_object() (ConnectToPymol method), 48	get_paths_in() (GenericPaths method), 37
derrivative() (in module aquaduct.geom.traces), 30	get_paths_out() (GenericPaths method), 37
diff() (in module aquaduct.geom.traces), 30	get_single_path_coords() (GenericPaths method), 37
distance() (ColorMapDistMap method), 47	get_single_path_types() (GenericPaths method), 37
DistanceWindowOverMaxStepSmooth (class in	get_str_timestamp() (in module aquaduct.utils.clui), 43
aquaduct.geom.smooth), 30	get_velocity_cont() (SinglePath method), 38
DistanceWindowSmooth (class in	get_weights_() (in module aquaduct.geom.master), 27
aquaduct.geom.smooth), 29 dump_frames() (TmpDumpWriterOfMDA method), 34	glue() (in module aquaduct.traj.paths), 36 greetings() (in module aquaduct), 49
dump_names() (1mpbamp wheronvib) t method), 54	gregorian_year_in_days (in module
E	aquaduct.utils.clui), 40
emit_message_to_file_in_root_logger() (in module	grey (ColorMapDistMap attribute), 47
aquaduct.utils.clui), 40	gsep() (in module aquaduct.utils.clui), 41
empty_coords (SinglePath attribute), 37	gtypes (SinglePath attribute), 38
ends (SinglePath attribute), 38	gtypes_cont (SinglePath attribute), 38
ETA() (SimpleProgressBar method), 42	ш
etypes (SinglePath attribute), 38	Н
etypes_cont (SinglePath attribute), 38	has_in (SinglePath attribute), 38
euclidean() (in module aquaduct.visual.helpers), 46	has_object (SinglePath attribute), 38
extend_inlets() (Inlets method), 36	has_out (SinglePath attribute), 38
F	heartbeat() (SimpleProgressBar method), 42 here() (LinearizeOneWay method), 32
f_like() (in module aquaduct.visual.helpers), 47	here() (LinearizeRecursive method), 32
fbm (class in aquaduct.utils.clui), 40	nere() (EmeanZerceursive medica), 32
find_paths() (GenericPaths method), 37	1
find_paths_coords() (GenericPaths method), 37	incoming (ProtoInletTypeCodes attribute), 34
find_paths_coords_types() (GenericPaths method), 37	init_ax() (MPLTracePlotter method), 49
find_paths_types() (GenericPaths method), 37	init_pymol() (ConnectToPymol method), 48
finish() (SimpleProgressBar method), 43	init_script() (ConnectToPymol method), 48
first_resid() (Selection method), 39	Inlet (class in aquaduct.traj.inlets), 35
fit() (PerformClustering method), 27	InletClusterExtendedType (class in
fit_trace_to_points() (in module	aquaduct.traj.inlets), 35
aquaduct.geom.master), 27 full_size() (CTypeSpathsCollection method), 28	InletClusterGenericType (class in aquaduct.traj.inlets), 34
isii_bizo() (C i ) pospunisconotion inculou), 20	J 1

Inlets (class in aquaduct.traj.inlets), 35	make_val() (InletClusterGenericType method), 35
InletTypeCodes (class in aquaduct.traj.inlets), 34	MasterPath (class in aquaduct.traj.paths), 38
input (InletClusterGenericType attribute), 35	max_frame (GenericPaths attribute), 37
int2range() (in module aquaduct.utils.helpers), 44	max_window_at_pos() (GeneralWindow static
internal (ProtoInletTypeCodes attribute), 34	method), 29
internal_incoming (InletTypeCodes attribute), 34	MaxStepSmooth (class in aquaduct.geom.smooth), 29
internal_outgoing (InletTypeCodes attribute), 34	MeanShiftBandwidth() (in module
is_iterable() (in module aquaduct.utils.helpers), 44	aquaduct.geom.cluster), 27
is_linear() (TriangleLinearize method), 32	message() (in module aquaduct.utils.clui), 40
is_linear() (VectorLinearize method), 33	message_special() (in module aquaduct.utils.clui), 40
is_linear_core() (VectorLinearize method), 33	midpoints() (in module aquaduct.geom.traces), 30
is_number() (in module aquaduct.utils.helpers), 43	min_frame (GenericPaths attribute), 37
is_point_within_convexhull() (in module	MPLTracePlotter (class in aquaduct.visual.quickplot),
aquaduct.geom.convexhull), 27	49
iterate_over_frames() (Reader method), 38	A I
iterate_over_residues() (Selection method), 39	N
iterate_over_residues() (SelectionMDA method), 39	new() (BasicPymolCGO method), 47
itype (InletTypeCodes attribute), 34	next_frame() (Reader method), 38
	next_frame() (ReadViaMDA method), 39
L	Normalize (class in aquaduct.geom.pca), 28
left() (in module aquaduct.traj.paths), 36	number_of_frames (Reader attribute), 38
length_step_std() (in module aquaduct.geom.traces), 30	number_of_frames (ReadViaMDA attribute), 39
lens() (CTypeSpathsCollection method), 28	
lens_norm() (CTypeSpathsCollection method), 28	0
lens_real() (CTypeSpathsCollection method), 28	object_name (GenericPathTypeCodes attribute), 37
lim2clusters() (Inlets method), 36	open() (SimpleTarWriteHelper method), 48
lim2spaths() (Inlets method), 36	open_trajectory() (ReadAmberNetCDFviaMDA
lim2types() (Inlets method), 36	method), 39
lim_to() (Inlets method), 36	open_trajectory() (ReadDCDviaMDA method), 39
limspaths2() (Inlets method), 36	open_trajectory() (Reader method), 38
lind() (in module aquaduct.utils.helpers), 43	open_trajectory() (ReadViaMDA method), 39
LinearizeHobbit (class in aquaduct.geom.traces), 32	orient_on() (ConnectToPymol method), 48
LinearizeHobbitTriangle (class in	out_name (GenericPathTypeCodes attribute), 37
aquaduct.geom.traces), 33	outgoing (ProtoInletTypeCodes attribute), 34
LinearizeHobbitVector (class in aquaduct.geom.traces),	output (InletClusterGenericType attribute), 35
33	
LinearizeOneWay (class in aquaduct.geom.traces), 32	P
LinearizeOneWayTriangle (class in	P (PCA attribute), 29
aquaduct.geom.traces), 34	parse_selection() (Reader method), 38
LinearizeOneWayVector (class in	parse_selection() (ReadViaMDA method), 39
aquaduct.geom.traces), 33	parts (CTypeSpathsCollection attribute), 28
LinearizeRecursive (class in aquaduct.geom.traces), 32	path_in_code (PathTypesCodes attribute), 36
LinearizeRecursiveTriangle (class in	path_object_code (PathTypesCodes attribute), 36
aquaduct.geom.traces), 33	path_out_code (PathTypesCodes attribute), 36
LinearizeRecursiveVector (class in	path_trace() (SimpleTracePlotter method), 49
aquaduct.geom.traces), 33	paths (SinglePath attribute), 37
list_blocks_to_slices() (in module	paths_cont (SinglePath attribute), 38
aquaduct.utils.helpers), 46	paths_inlets() (SinglePathPlotter method), 48
listify() (in module aquaduct.utils.helpers), 45	paths_trace() (SinglePathPlotter method), 48
load_pdb() (ConnectToPymol method), 48	PathTypesCodes (class in aquaduct.traj.paths), 36
	pbar (in module aquaduct.utils.clui), 43
M	PCA (class in aquaduct.geom.pca), 28
make_color_triple() (BasicPymolCGO static method),	percent() (SimpleProgressBar method), 42
47	perform_clustering() (Inlets method), 36
make_default_array() (in module aquaduct.utils.maths),	perform_reclustering() (Inlets method), 36
46	PerformClustering (class in aquaduct.geom.cluster), 27
make_iterable() (in module aquaduct.utils.helpers), 46	plot_colorful_lines() (in module
make_spherical() (in module aquaduct.traj.inlets), 35	aquaduct.visual.quickplot), 48

plot_line() (MPLTracePlotter method), 49 plot_line() (SimpleTracePlotter method), 49 plot_spath_spectrum() (in module aquaduct.visual.quickplot), 48 preprocess() (PCA method), 29 preprocess_undo() (PCA method), 29 protein_trace() (SimpleProteinPlotter method), 49 ProtoInletTypeCodes (class in aquaduct.traj.inlets), 34	size (SinglePath attribute), 38 small_clusters_to_outliers() (Inlets method), 36 smart_time_string() (in module aquaduct.utils.clui), 40 Smooth (class in aquaduct.geom.smooth), 29 smooth() (ActiveWindowOverMaxStepSmooth method), 30 smooth() (ActiveWindowSmooth method), 29 smooth() (DistanceWindowOverMaxStepSmooth
R	method), 30 smooth() (DistanceWindowSmooth method), 29
range2int() (in module aquaduct.utils.helpers), 44 ReadAmberNetCDFviaMDA (class in aquaduct.traj.reader), 39 ReadDCDviaMDA (class in aquaduct.traj.reader), 39 Reader (class in aquaduct.traj.reader), 38 ReadViaMDA (class in aquaduct.traj.reader), 38 recluster_cluster() (Inlets method), 36 recluster_outliers() (Inlets method), 36 reference (Inlet attribute), 35 refs (Inlets attribute), 36 renumber_clusters() (Inlets method), 36	smooth() (MaxStepSmooth method), 29 smooth() (Smooth method), 29 smooth() (Smooth method), 29 smooth() (WindowOverMaxStepSmooth method), 29 smooth() (WindowSmooth method), 29 sort_clusters() (Inlets method), 36 sortify() (in module aquaduct.utils.helpers), 45 spath_spectrum() (in module aquaduct.visual.quickplot), 48 spaths2ctypes() (Inlets method), 36 spaths_spectra() (in module aquaduct.visual.quickplot), 48 Standartize (class in aquaduct.geom.pca), 28
right() (in module aquaduct.traj.paths), 36 rotate (SimpleProgressBar attribute), 42	strech_zip() (in module aquaduct.utils.helpers), 46
	surface (ProtoInletTypeCodes attribute), 34
S	surface_incoming (InletTypeCodes attribute), 34
save_file2tar() (SimpleTarWriteHelper method), 48	surface_outgoing (InletTypeCodes attribute), 34
save_object2tar() (SimpleTarWriteHelper method), 48	T
scatter() (MPLTracePlotter method), 49 scatter() (SinglePathPlotter method), 48 scope_name (GenericPathTypeCodes attribute), 37 select_multiple_resnum() (Reader method), 38 select_multiple_resnum() (ReadViaMDA method), 39 select_resnum() (Reader method), 38	thead() (in module aquaduct.utils.clui), 41 tictoc (class in aquaduct.utils.clui), 40 TmpDumpWriterOfMDA (class in aquaduct.traj.dumps), 34 toSelectionMDA() (CompactSelectionMDA method), 40
select_resnum() (ReadViaMDA method), 39 Selection (class in aquaduct.traj.selections), 39	tracepoints() (in module aquaduct.geom.traces), 30
Selection (class in aquaduct.traj.selections), 39 set_current_frame() (Reader method), 38 set_current_frame() (ReadViaMDA method), 39	triangle_angles() (in module aquaduct.geom.traces), 30 triangle_angles_last() (in module aquaduct.geom.traces), 30
show() (SimpleProgressBar method), 42	triangle_height() (in module aquaduct.geom.traces), 31 TriangleLinearize (class in aquaduct.geom.traces), 32
showit() (in module aquaduct.visual.quickplot), 48 simple_types_distribution() (CTypeSpathsCollection static method), 28 SimplePathPlotter (class in aquaduct.visual.quickplot), 49	tsep() (in module aquaduct.utils.clui), 41 ttime() (SimpleProgressBar method), 42 tupleify() (in module aquaduct.utils.helpers), 45 type (Inlet attribute), 35
SimpleProgressBar (class in aquaduct.utils.clui), 41	types (Inlets attribute), 36 types (SinglePath attribute), 38
SimpleProteinPlotter (class in	types_cont (SinglePath attribute), 38
aquaduct.visual.quickplot), 49 SimpleTarWriteHelper (class in aquaduct.visual.pymol_connector), 47	types_distribution() (CTypeSpathsCollection method), 28
SimpleTracePlotter (class in aquaduct.visual.quickplot), 48	types_prob_to_types() (CTypeSpathsCollection method), 28
single_path_traces() (SimplePathPlotter method), 49 single_trace() (SimpleTracePlotter method), 49 SinglePath (class in aquaduct.traj.paths), 37	U underline() (in module aquaduct.utils.clui), 41
SinglePathID (class in aquaduct.traj.paths), 37	undo() (Center method), 28
SinglePathPlotter (class in	undo() (Normalize method), 28
aquaduct.visual.pymol_connector), 48 size (Inlets attribute), 36	undo() (PCA method), 29 undo() (Standartize method), 28

```
union() (in module aquaduct.traj.paths), 36
uniqify() (in module aquaduct.utils.helpers), 45
unique_resids() (Selection method), 39
unique_resids() (SelectionMDA method), 39
unique_resids_number() (Selection method), 39
uniquify() (Selection method), 39
uniquify() (SelectionMDA method), 40
update() (CTypeSpathsCollection method), 28
update() (SimpleProgressBar method), 42
vector_norm() (in module aquaduct.geom.traces), 30
VectorLinearize (class in aquaduct.geom.traces), 32
vectors_angle() (in module aquaduct.geom.traces), 31
vectors_angle_alt() (in module aquaduct.geom.traces),
         31
vectors_angle_alt_anorm()
                                  (in
                                              module
         aquaduct.geom.traces), 31
                                              module
vectors_angle_anorm()
                                (in
         aquaduct.geom.traces), 31
version() (in module aquaduct), 49
version_nice() (in module aquaduct), 49
what2what() (in module aquaduct.utils.helpers), 46
Window Over Max Step Smooth \\
                                     (class
                                                   in
         aquaduct.geom.smooth), 29
WindowSmooth (class in aquaduct.geom.smooth), 29
X
xor() (in module aquaduct.traj.paths), 36
xzip_xzip() (in module aquaduct.utils.helpers), 46
Υ
yield_single_paths() (in module aquaduct.traj.paths),
yield_spath_len_and_smooth_diff_in_types_slices()
         (in module aquaduct.visual.quickplot), 48
Z
zip_zip() (in module aquaduct.utils.helpers), 46
```