

# Smart Contract Audit Report

Safe State

Low Risk





# Version description

Revised man	<b>Revised content</b>	Revised	version number	Reviewer
Yifeng Luo	Document creation and editing	2020/9/22	V1.0	Haojie Xu

#### **Document information**

Name	<b>Document version</b>	Number	Privacy
	number		level
SMinter		Tan C . Di tar	
Smart Contract Audit	V1.0	SMinter-DMSJ-	Open project
Report		20200922 🕽	team

## **Copyright statement**

Any text descriptions, document formats, illustrations, photographs, methods, procedures, etc. appearing in this document, unless otherwise specified, are copyrighted by Beijing Known Chuangyu Information Technology Co., Ltd. and are protected by relevant property rights and copyright laws. No individual or institution may copy or cite any fragment of this document in any way without the written permission of Beijing Chuangyu Information Technology Co., Ltd.

# 目录

1.	Review	1
2.	Analysis of code vulnerability	2
2.1.	Distribution of vulnerability Levels	2
2.2.	Audit result summary	3
3.	Result analysis	4
3.1.	Reentrancy [Low]	4
3.2.	Arithmetic Issues 【Pass】	4
3.3.	Access Control [Pass]	5
3.4.	Unchecked Return Values For Low Level Calls [Pass]	5
3.5.	Bad Randomness [Pass]	6
3.6.	Transaction ordering dependence [Low]	6
3.7.	Denial of service attack detection [Pass]	7
3.8.	Logical design Flaw 【Pass 】	7
3.9.		7
3.10		8
3.11	1. Freezing accounts bypassed [Pass]	8
4.	Appendix A: Contract code	9
5.	Appendix B: vulnerability risk rating criteria	31
6.	Appendix C: Introduction of test tool	31
6.1.	Manticore	31
6.2.	Oyente	32
6.3.	securify.sh	32
6.4.	Echidna	32
6.5.	MAIAN	32
6.6.	ethersplay	32
6.7.	ida-evm	33
6.8.	Remix-ide	33
6.9.	Knownsec Penetration Tester Special Toolkit	33

# 1. Review

The effective testing time of this report is from **September 19,2020** to **September 22,2020**. During this period, the Knownsec engineers audited the safety and regulatory aspects of **SMinter** smart contract code.

In this test, engineers comprehensively analyzed common vulnerabilities of smart contracts (Chapter 3) and It was discovered that reentrancy, transaction ordering dependence, adding tokens risk; so it's evaluated as low-risk.

## The result of the safety auditing: Pass

Since the test process is carried out in a non-production environment, all the codes are the latest backups. We communicates with the relevant interface personnel, and the relevant test operations are performed under the controllable operation risk to avoid the risks during the test..


Target information for this test:

Module name	content
Token name	SMinter
Code type	Token code
Code language	solidity

# 2. Analysis of code vulnerability

# 2.1. Distribution of vulnerability Levels

Vulnerability statistics			
high	Middle	low	pass
0	0	3	8



# 2.2. Audit result summary

Result			
Test project	Test content	status	description
	Reentrancy	Low	Check the call.value() function for security
	Arithmetic Issues	Pass	Check add and sub functions
	Access Control	Pass	Check the operation access control
	Unchecked Return Values For Low Level Calls	Pass	Check the currency conversion method.
	Bad Randomness	Pass	Check the unified content filter
	Transaction ordering dependence	Low	Check the transaction ordering dependence
	Denial of service	Pass	Check whether the code has a resource
C ,	attack detection		abuse problem when using a resource
Smart Contract	Logic design Flaw	Pass	Examine the security issues associated with business design in intelligent contract codes.
	USDT Fake Deposit Issue	Pass	Check for the existence of USDT Fake Deposit Issue
	Adding tokens	Low	It is detected whether there is a function in
			the token contract that may increase the total amounts of tokens
	Freezing accounts bypassed	Pass	It is detected whether there is an unverified token source account, an originating account, and whether the target account is frozen.

# 3. Result analysis

# 3.1. Reentrancy Low

The Reentrancy attack, probably the most famous Ethereum vulnerability, led to a hard fork of Ethereum.

When the low level call() function sends ether to the msg.sender address, it becomes vulnerable; if the address is a smart contract, the payment will trigger its fallback function with what's left of the transaction gas.

**Detection results:** After testing, there are related call external contract calls in the smart contract code.

```
function sendValue(address payable recipient, uint256 amount) internal {
    require(address(this).balance >= amount, "Address: insufficient balance");

    // solhint-disable-next-line avoid-low-level-calls, avoid-call-value
    (bool success,) = recipient.call{ value: amount }("");
    require(success, "Address: unable to send value, recipient may have reverted");
}
```

#### Safety advice:

- (1) Try to use send() and transfer() functions.
- (2) If you use a low-level calling function like the call() function, you should perform the internal state change first, and then use the low-level calling function.
  - (3) Try to avoid calling external contracts when writing smart contracts.

# 3.2. Arithmetic Issues [Pass]

Also known as integer overflow and integer underflow. Solidity can handle up to 256 digits (2^256-1), The largest number increases by 1 will overflow to 0. Similarly, when the number is an unsigned type, 0 minus 1 will underflow to get the maximum numeric value.

Integer overflows and underflows are not a new class of vulnerability, but they are especially dangerous in smart contracts. Overflow can lead to incorrect results,

Smart contract audit report

especially if the probability is not expected, which may affect the reliability and

security of the program.

Test results: No related vulnerabilities in smart contract code

Safety advice: None

3.3. Access Control (Pass)

Access Control issues are common in all programs, Also smart contracts. The

famous Parity Wallet smart contract has been affected by this issue.

**Test results**: No related vulnerabilities in smart contract code

Safety advice: None.

3.4. Unchecked Return Values For Low Level Calls

(Pass)

Also known as or related to silent failing sends, unchecked-send. There are

transfer methods such as transfer(), send(), and call.value() in Solidity and can be used

to send Ether to an address. The difference is: transfer will be thrown when failed to

send, and rollback; only 2300gas will be passed for call to prevent reentry attacks;

send will return false if send fails; only 2300gas will be passed for call to prevent

reentry attacks; If .value fails to send, it will return false; passing all available gas

calls (which can be restricted by passing in the gas\_value parameter) cannot

effectively prevent reentry attacks.

If the return value of the send and call value switch functions is not been

checked in the code, the contract will continue to execute the following code, and it

may have caused unexpected results due to Ether sending failure.

Test results: No related vulnerabilities in smart contract code

Safety advice: None.

5

## 3.5. Bad Randomness [Pass]

Smart Contract May Need to Use Random Numbers. While Solidity offers functions and variables that can access apparently hard-to-predict values just as block.number and block.timestamp. they are generally either more public than they seem or subject to miners' influence. Because these sources of randomness are to an extent predictable, malicious users can generally replicate it and attack the function relying on its unpredictability.

Test results: No related vulnerabilities in smart contract code

**Safety advice:** None •

# 3.6. Transaction ordering dependence Low

Since miners always get rewarded via gas fees for running code on behalf of externally owned addresses (EOA), users can specify higher fees to have their transactions mined more quickly. Since the Ethereum blockchain is public, everyone can see the contents of others' pending transactions.

This means if a given user is revealing the solution to a puzzle or other valuable secret, a malicious user can steal the solution and copy their transaction with higher fees to preempt the original solution.

**Test results**: After testing, there are related vulnerabilities in the smart contract code.

contracts\ERC20.sol lines 74

```
function _approve(address owner, address spender, uint256 amount) internal virtual {
    require(owner != address(0), "ERC20: approve from the zero address");
    require(spender != address(0), "ERC20: approve to the zero address");

_allowances[owner][spender] = amount;
    emit Approval(owner, spender, amount);
}
```

Safety advice:

- 1. When the approve function changes the quota from N to M, it can only be changed from N to 0, and then from 0 to M: require((\_value == 0)  $\parallel$  (allowance[msg.sender][\_spender] == 0));
- 2. Use increaseApproval function and decreaseApproval function instead of approve function.

### 3.7. Denial of service attack detection [Pass]

In the ethernet world, denial of service is deadly, and smart contracts under attack of this type may never be able to return to normal. There may be a number of reasons for a denial of service in smart contracts, including malicious behavior as a recipient of transactions, gas depletion caused by artificially increased computing gas, and abuse of access control to access the private components of the intelligent contract. Take advantage of confusion and neglect, etc.

Test results: No related vulnerabilities in smart contract code.

Safety advice: None.

# 3.8. Logical design Flaw Pass

Detect the security problems related to business design in the contract code.

Test results: No related vulnerabilities in smart contract code.

Safety advice: None.

# 3.9. USDT Fake Deposit Issue **Pass**

In the transfer function of the token contract, the balance check of the transfer initiator (msg.sender) is judged by if. When balances[msg.sender] < value, it enters the else logic part and returns false, and finally no exception is thrown. We believe that only the modest judgment of if/else is an imprecise coding method in the sensitive function scene such as transfer.

**Detection results**: No related vulnerabilities in smart contract code...

Safety advice: none

# 3.10. Adding tokens [Low]

It is detected whether there is a function in the token contract that may increase the total amount of tokens after the total amount of tokens is initialized.

**Detection results:** After testing, there are related vulnerabilities in the smart contract code.

```
function _mint(address account, uint256 amount) internal virtual {
    require(account != address(0), "ERC20: mint to the zero address");

    _beforeTokenTransfer(address(0), account, amount);

    _totalSupply = _totalSupply.add(amount);
    _balances[account] = _balances[account].add(amount);
    emit Transfer(address(0), account, amount);
}
```

#### Safety advice:

This issue is not a security issue, but some exchanges will restrict the use of additional issuance functions, and the specific circumstances need to be determined according to the requirements of the exchange.

# 3.11. Freezing accounts bypassed [Pass]

In the token contract, when transferring the token, it is detected whether there is an unverified token source account, an originating account, and whether the target account is frozen.

**Detection results:** No related vulnerabilities in smart contract code.

Safety advice: none.

# 4. Appendix A: Contract code

```
• // SPDX-License-Identifier: MIT
   pragma solidity ^0.6.0;
    //pragma experimental ABIEncoderV2;
    import "./SToken.sol";
   import "./Governable.sol";
   import "./TransferHelper.sol";
   interface Minter {
       event Minted(address indexed recipient, address reward_contract, uint minted);
       function token() external view returns (address);
       function controller() external view returns (address);
       function minted(address, address) external view returns (uint);
       function allowed_to_mint_for(address, address) external view returns
                                                                                     (bool);
       function mint(address gauge) external;
       function mint many(address[8] calldata gauges) external;
       function mint_for(address gauge, address _for) external;
       function toggle approve mint(address minting user) external;
   interface LiquidityGauge {
       event Deposit (address indexed provider, uint value);
       event Withdraw(address indexed provider, uint value);
event UpdateLiquidityLimit(address user, uint original_balance, uint
original_supply, uint working_balance, uint working_supply);
       function user_checkpoint (address addr) external returns (bool);
       function claimable tokens (address addr) external view returns (uint);
       function claimable_reward(address addr) external view returns (uint); function integrate checkpoint() external view returns (uint);
       function kick(address addr) external;
function set_approve_deposit(address addr, bool can_deposit) external;
       function deposit(uint value) external; function deposit(uint value, address addr) external; function withdraw(uint value) external; function withdraw(uint value, bool claim_rewards) external;
       function claim_rewards() external; function claim_rewards(address addr) external;
       function minter()
                                                external view returns (address);
       function crv token()
                                                external view returns (address);
       function lp_token()
function controller()
                                                external view returns (address);
                                                external view returns (address);
       function voting escrow()
                                                external view returns (address);
       function balanceOf(address)
                                                 external view returns (uint);
       function totalSupply()
                                                external view returns (uint);
       function future_epoch_time()
                                                 external view returns (uint);
       function approved_to_deposit(address, address)
                                                             external view returns (bool);
       function working_balances(address) external view returns (uint);
       function working_supply()
                                                 external view returns (uint);
       function period()
                                                external view returns (int128);
                                                 external view returns (uint);
       function period_timestamp(uint)
       function integrate_inv_supply(uint)
                                                   external view returns (uint);
       function integrate_inv_supply_of(address) external view returns (uint);
       function integrate_checkpoint_of(address) external view returns (uint);
       function integrate fraction(address) external view returns (uint);
       function inflation rate()
                                                 external view returns (uint);
       function reward contract()
                                                 external view returns (address);
                                                 external view returns (address);
       function rewarded token()
       function reward_integral()
                                                 external view returns (uint);
       function reward integral for (address) external view returns (uint);
       function rewards for (address)
                                                 external view returns (uint);
       function claimed_rewards_for(address) external view returns (uint);
```

```
contract SSimpleGauge is LiquidityGauge, Configurable {
       using SafeMath for uint;
       using TransferHelper for address;
       address override public minter;
       address override public crv token;
       address override public lp_token;
       address override public controller;
       address override public voting escrow;
       mapping(address => uint) override public balanceOf;
       uint override public totalSupply;
       uint override public future_epoch_time;
       // caller -> recipient -> can deposit?
       {\it mapping (address => mapping (address => bool)) \ override \ public}
approved_to_deposit;
       mapping(address => uint) override public working balances;
       uint override public working_supply;
       // The goal is to be able to calculate \int (rate * balance / total Supply dt) from
0 till checkpoint
       // All values are kept in units of being multiplied by 1e18
       int128 override public period;
       uint256[1000000000000000000000000000] override public period timestamp;
       // le18 * \int (rate(t) / totalSupply(t) dt) from 0 till checkpoint
       uint256[10000000000000000000000000000000] override public integrate inv supply;
// bump epoch when rate() changes
       // le18 * \int (rate(t) / totalSupply(t) dt) from (last_action) till checkpoint
       mapping(address => uint) override public integrate inv supply of;
       mapping(address => uint) override public integrate checkpoint of;
       // \int (balance * rate(t) / totalSupply(t) dt) from 0 till checkpoint // Units: rate * t = already number of coins per address to issue mapping(address => uint) override public integrate_fraction;
       uint override public inflation_rate;
       // For tracking external rewards
address override public reward_contract;
       address override public rewarded_token;
       uint override public reward_integral;
      mapping(address => uint) override public reward_integral_for;
mapping(address => uint) override public rewards_for;
       mapping(address => uint) override public claimed_rewards_for;
     uint public span;
     uint public end;
    function initialize (address governor, address minter, address 1p token) public
initializer {
        super.initialize(governor);
        minter
                       minter;
                   = Minter(_minter).token();
= _lp_token;
        crv_token
        lp token
        IERC20(lp token).totalSupply();
                                                   // just check
       function setSpan(uint span, bool isLinear) virtual external governance {
           span = _span;
           if(isLinear)
              end = now + \_span;
           else
              end = 0;
       function kick(address addr) virtual override external {
           _checkpoint(addr, true);
```

```
function set approve deposit (address addr, bool can deposit) virtual override
external {
          approved to deposit[addr][msg.sender] = can deposit;
       function deposit (uint amount) virtual override external {
          deposit(amount, msg.sender);
       function deposit (uint amount, address addr) virtual override public {
          require(addr == msg.sender || approved_to_deposit[msg.sender][addr], 'Not
approved');
          checkpoint(addr, true);
          _deposit(addr, amount);
          balanceOf[addr] = balanceOf[addr].add(amount);
          totalSupply = totalSupply.add(amount);
          emit Deposit(addr, amount);
       function deposit(address addr, uint amount) virtual internal
          lp_token.safeTransferFrom(addr, address(this), amount);
       function withdraw() virtual external {
          withdraw(balanceOf[msg.sender], true);
       function withdraw(uint amount) virtual override external {
          withdraw(amount, true);
       function withdraw(uint amount, bool claim rewards) virtual override public {
         _checkpoint(msg.sender, claim_rewards);
          totalSupply = totalSupply.sub(amount);
          balanceOf[msg.sender] = balanceOf[msg.sender].sub(amount);
          withdraw (msg.sender, amount);
          emit Withdraw(msg.sender, amount);
       function _withdraw(address to, uint amount) virtual internal {
          lp_token.safeTransfer(to, amount);
       function claimable_reward(address) virtual override public view returns (uint)
          return 0:
       function claim_rewards() virtual override public {
          return claim rewards (msg.sender);
       function claim_rewards(address) virtual override public {
          return;
       function checkpoint rewards(address, bool) virtual internal {
          return:
       function claimable tokens (address addr) virtual override public view returns
(uint amount) {
          if(span == 0 \mid \mid totalSupply == 0)
             return 0;
          amount = SMinter(minter).quotas(address(this));
          amount = amount.mul(balanceOf[addr]).div(totalSupply);
          uint lasttime = integrate_checkpoint_of[addr];
          if(end == 0) {
                                                                         //
isNonLinear, endless
             if(now.sub(lasttime) < span)</pre>
                 amount = amount.mul(now.sub(lasttime)).div(span);
          }else if(now < end)
             amount = amount.mul(now.sub(lasttime)).div(end.sub(lasttime));
          else if(lasttime >= end)
             amount = 0;
```

```
function checkpoint(address addr, uint amount) virtual internal {
           if(amount > 0) {
              integrate fraction[addr] = integrate fraction[addr].add(amount);
              address teamAddr = address(config['teamAddr']);
              uint teamRatio = config['teamRatio'];
              if(teamAddr != address(0) && teamRatio != 0)
                  integrate fraction[teamAddr] =
integrate_fraction[teamAddr].add(amount.mul(teamRatio).div(1 ether));
       function _checkpoint(address addr, bool _claim_rewards) virtual internal {
          uint amount = claimable_tokens(addr);
          _checkpoint(addr, amount);
          __checkpoint_rewards(addr, _claim_rewards);
           integrate checkpoint of[addr] = now;
       function user checkpoint (address addr) virtual override external returns (bool)
           checkpoint(addr, true);
           return true;
       function integrate checkpoint() override external view returns
                                                                            (uint)
          return now;
   contract SExactGauge is LiquidityGauge, Configurable {
       using SafeMath for uint;
       using TransferHelper for address;
       bytes32 internal constant _devAddr_
                                                        'devAddr';
       bytes32 internal constant devRatio
bytes32 internal constant ecoAddr
                                                      = 'devRatio';
                                                        'ecoAddr';
                                                        'ecoRatio';
       bytes32 internal constant _ecoRatio
       address override public minter;
       address override public crv_token; address override public lp_token;
       address override public controller;
       address override public voting_escrow;
       mapping(address => uint) override public balanceOf;
       uint override public totalSupply;
uint override public future_epoch_time;
          caller -> recipient -> can deposit?
       mapping(address => mapping(address => bool)) override public
approved to deposit;
       mapping(address => uint) override public working balances;
       uint override public working supply;
       // The goal is to be able to calculate \int (rate * balance / totalSupply dt) from
0 till checkpoint
       // All values are kept in units of being multiplied by 1e18
       int128 override public period;
       uint256[10000000000000000000000000000] override public period timestamp;
       // le18 * \int (rate(t) / totalSupply(t) dt) from 0 till checkpoint
       uint256[1000000000000000000000000000000] override public integrate_inv_supply;
// bump epoch when rate() changes
       // le18 * \int (rate(t) / totalSupply(t) dt) from (last_action) till checkpoint mapping(address => uint) override public integrate_inv_supply_of;
       mapping(address => uint) override public integrate_checkpoint_of;
       // \int (balance * rate(t) / totalSupply(t) dt) from 0 till checkpoint
       // Units: rate * t = already number of coins per address to issue
       mapping(address => uint) override public integrate fraction;
```

```
uint override public inflation rate;
       // For tracking external rewards
      address override public reward_contract;
      address override public rewarded token;
      uint override public reward integral;
      mapping (address => uint) override public reward integral for;
      mapping(address => uint) override public rewards for;
      mapping(address => uint) override public claimed_rewards_for;
    uint public span;
    uint public end:
    mapping(address => uint) public sumMiningPerOf;
    uint public sumMiningPer;
    uint public bufReward;
    uint public lasttime;
    function initialize (address governor, address minter, address lp token) public
initializer {
       super.initialize(governor);
       minter = _minter;
crv_token = Minter(_minter).token();
lp_token = _lp_token;
       minter
        IERC20(lp token).totalSupply();
                                                       // just check
       function setSpan(uint _span, bool isLinear) virtual external governance {
          span = _span;
          if (isLinear)
             end = now + \_span;
          else
             end = 0;
          lasttime = now;
       function kick(address addr) virtual override external {
          _checkpoint(addr, true);
       function \ set\_approve\_deposit(address \ addr, \ bool \ can\_deposit) \ virtual \ override
          approved to deposit[addr][msg.sender] = can deposit;
       function deposit(uint amount) virtual override external {
          deposit(amount, msg.sender);
       function deposit(uint amount, address addr) virtual override public {
          require(addr == msg.sender || approved_to_deposit[msg.sender][addr], 'Not
approved');
           checkpoint(addr, true);
          deposit (addr, amount);
          balanceOf[msg.sender] = balanceOf[msg.sender].add(amount);
          totalSupply = totalSupply.add(amount);
          emit Deposit(msg.sender, amount);
       function _deposit(address addr, uint amount) virtual internal {
          lp_token.safeTransferFrom(addr, address(this), amount);
       function withdraw() virtual external {
          withdraw(balanceOf[msg.sender], true);
       function withdraw(uint amount) virtual override external {
          withdraw(amount, true);
       function withdraw(uint amount, bool claim rewards) virtual override public {
          checkpoint(msg.sender, claim rewards);
          totalSupply = totalSupply.sub(amount);
          balanceOf[msg.sender] = balanceOf[msg.sender].sub(amount);
```

```
withdraw (msg.sender, amount);
          emit Withdraw (msg.sender, amount);
       function _withdraw(address to, uint amount) virtual internal {
          lp token.safeTransfer(to, amount);
      function claimable reward(address addr) virtual override public view returns
(uint) {
          addr:
          return 0;
       function claim_rewards() virtual override public {
          return claim rewards (msg.sender);
       function claim_rewards(address) virtual override public {
       function checkpoint rewards(address, bool) virtual internal {
          return:
       function claimable tokens(address addr) virtual override public
                                                                         view returns
(uint) {
          return _claimable_tokens(addr, claimableDelta(), sumMiningPer,
sumMiningPerOf[addr]);
       function _claimable_tokens(address addr, uint delta, uint sumPer, uint
lastSumPer) virtual internal view returns (uint amount)
          if(span == 0 \mid \mid totalSupply == 0)
             return 0;
          amount = sumPer.sub(lastSumPer);
          amount = amount.add(delta.mul(1 ether).div(totalSupply));
          amount = amount.mul(balanceOf[addr]).div(1 ether);
       function claimableDelta() virtual internal view returns(uint amount) {
          amount = SMinter(minter).quotas(address(this)).sub(bufReward);
          if(end == 0) {
isNonLinear, endless
              if(now.sub(lasttime) < span)</pre>
                 amount = amount.mul(now.sub(lasttime)).div(span);
          }else if(now < end)
             amount = amount.mul(now.sub(lasttime)).div(end.sub(lasttime));
          else if(lasttime >= end)
              amount = 0;
       function
                checkpoint(address addr, uint amount) virtual internal {
          if(amount > 0)
              integrate fraction[addr] = integrate fraction[addr].add(amount);
              addr = address(config[ devAddr ]);
             uint ratio = config[_devRatio_];
if(addr != address(0) && ratio != 0)
                 integrate fraction[addr] =
integrate fraction[addr].add(amount.mul(ratio).div(1 ether));
              addr = address(config[_ecoAddr_]);
              ratio = config[_ecoRatio_];
              if (addr != address(0) && ratio != 0)
                 integrate fraction[addr] =
integrate_fraction[addr].add(amount.mul(ratio).div(1 ether));
       function checkpoint(address addr, bool claim rewards) virtual internal {
          if(span == 0 \mid \mid totalSupply == 0)
             return;
          uint delta = claimableDelta();
          uint amount = _claimable_tokens(addr, delta, sumMiningPer,
sumMiningPerOf[addr]);
```

```
if(delta != amount)
              bufReward = bufReward.add(delta).sub(amount);
          if(delta > 0)
              sumMiningPer = sumMiningPer.add(delta.mul(1 ether).div(totalSupply));
          if(sumMiningPerOf[addr] != sumMiningPer)
              sumMiningPerOf[addr] = sumMiningPer;
          lasttime = now;
          _checkpoint(addr, amount);
          _checkpoint_rewards(addr, _claim_rewards);
       function user checkpoint (address addr) virtual override external returns (bool)
           _checkpoint(addr, true);
          return true;
       function integrate_checkpoint() override external view returns (uint)
         return lasttime;
   contract SNestGauge is SExactGauge {
    address[] public rewards;
    mapping(address => mapping(address =>uint)) public sumRewardPerOf;
recipient => rewarded_token => can sumRewardPerOf
    mapping(address => uint) public sumRewardPer;
rewarded token => can sumRewardPerOf
function initialize(address governor, address _minter, address _lp_token, address _nestGauge, address[] memory _moreRewards) public initializer {
                                             _lp_token);
       super.initialize(governor, minter,
        reward contract = nestGauge;
        rewarded token = LiquidityGauge( nestGauge).crv token();
                       = moreRewards;
        rewards.push (rewarded token);
        address rewarded_token2 = LiquidityGauge(_nestGauge).rewarded_token();
        if(rewarded_token2 != address(0))
            rewards.push(rewarded token2);
        LiquidityGauge(_nestGauge).integrate_checkpoint();
                                                                // just check
        for(uint i=0; i<_moreRewards.length; i++)</pre>
           IERC20(_moreRewards[i]).totalSupply();
                                                               // just check
       function _deposit(address from, uint amount) virtual override internal {
          super._deposit(from, amount);
lp token.safeTransferFrom(from, address(this), amount);
          lp token.safeApprove(reward contract, amount);
          LiquidityGauge(reward_contract).deposit(amount);
                 withdraw(address to, uint amount) virtual override internal {
          LiquidityGauge (reward contract).withdraw(amount);
          super._withdraw(to, amount);
lp token.safeTransfer(to, amount);
       function claim_rewards(address to) virtual override public {
          if(span == 0 \mid \mid totalSupply == 0)
              return;
          uint[] memory bals = new uint[](rewards.length);
          for(uint i=0; i<bals.length; i++)</pre>
             bals[i] = IERC20(rewards[i]).balanceOf(address(this));
          Minter(LiquidityGauge(reward contract).minter()).mint(reward contract);
          LiquidityGauge(reward contract).claim rewards();
          for(uint i=0; i<bals.length; i++) {</pre>
              uint delta = IERC20(rewards[i]).balanceOf(address(this)).sub(bals[i]);
              uint amount = _claimable_tokens(msg.sender, delta,
sumRewardPer[rewards[i]], sumRewardPerOf[msg.sender][rewards[i]]);
```

```
if(delta > 0)
                sumRewardPer[rewards[i]] = sumRewardPer[rewards[i]].add(delta.mul(1))
ether).div(totalSupply));
             if(sumRewardPerOf[msg.sender][rewards[i]] != sumRewardPer[rewards[i]])
                sumRewardPerOf[msg.sender][rewards[i]] = sumRewardPer[rewards[i]];
             if(amount > 0) {
                rewards[i].safeTransfer(to, amount);
                if(rewards[i] == rewarded token) {
                    rewards_for[to] = rewards_for[to].add(amount);
                    claimed rewards for[to] = claimed rewards for[to].add(amount);
      function claimable reward(address addr) virtual override public view returns
(uint) {
          uint delta =
LiquidityGauge(reward_contract).claimable_tokens(address(this));
         return claimable tokens (addr, delta, sumRewardPer[rewarded token],
sumRewardPerOf[addr][rewarded token]);
      function claimable reward2 (address addr) virtual public view returns (uint) {
         uint delta =
LiquidityGauge(reward_contract).claimable_reward(address(this));
         address reward2 = LiquidityGauge(reward_contract).rewarded_token();
          return claimable tokens(addr, delta, sumRewardPer[reward2],
sumRewardPerOf[addr][reward2]);
   contract SMinter is Minter, Configurable
      using SafeMath for uint;
      using Address for address payable;
      using TransferHelper for address;
    bytes32 internal constant _allowContract_
                                                 'allowContract';
                                               = 'allowlist';
    bytes32 internal constant _allowlist_
    bytes32 internal constant blocklist
                                              = 'blocklist';
      address override public token;
      address override public controller;
     mapping(address => mapping(address => uint)) override public minted;
// user => reward contract => value
      mapping(address => mapping(address => bool)) override public
// minter => user => can mint?
// reward contract => quota;
      function initialize (address governor, address token ) public initializer {
          super.initialize(governor);
          token = token_;
      function setGaugeQuota(address gauge, uint quota) public governance {
        quotas[gauge] = quota;
      function mint(address gauge) virtual override public {
         mint for(gauge, msg.sender);
      function mint_many(address[8] calldata gauges) virtual override external {
          for(uint i=0; i<gauges.length; i++)</pre>
             mint(gauges[i]);
      function mint for (address gauge, address for) virtual override public {
         require( for == msg.sender || allowed to mint for[msg.sender][ for], 'Not
approved');
          require(quotas[gauge] > 0, 'No quota');
```

```
require\left( getConfig\left( \_blocklist\_, \ msg.sender \right) \ == \ 0, \ 'In \ blocklist' \right);
          bool isContract = msg.sender.isContract();
          require(!isContract || config[_allowContract_] != 0 ||
getConfig(_allowlist_, msg.sender) != 0, 'No allowContract');
          LiquidityGauge(gauge).user_checkpoint(_for);
          uint total mint = LiquidityGauge(gauge).integrate fraction( for);
          uint to mint = total mint.sub(minted[ for][gauge]);
          if(to mint != 0) {
              quotas[gauge] = quotas[gauge].sub(to_mint);
              token.safeTransfer(_for, to_mint);
              minted[ for][gauge] = total mint;
              emit Minted(_for, gauge, total_mint);
       function toggle approve mint(address minting user) virtual override external {
          allowed to mint for[minting user][msg.sender]
= !allowed_to_mint_for[minting_user][msg.sender];
   // helper methods for interacting with ERC20 tokens and sending ETH that do not
consistently return true/false
   library TransferHelper {
       function safeApprove(address token, address to, uint value) internal {
          // bytes4(keccak256(bytes('approve(address,uint256)')));
          (bool success, bytes memory data) =
token.call(abi.encodeWithSelector(0x095ea7b3, to, value));
require(success && (data.length == 0 \mid \mid abi.decode(data, (bool))),
'TransferHelper: APPROVE FAILED');
       function safeTransfer(address token, address to, uint value) internal {
          // bytes4(keccak256(bytes('transfer(address,uint256)')));
          (bool success, bytes memory data) =
token.call(abi.encodeWithSelector(0xa9059cbb, to, value));
          require(success && (data.length == 0 || abi.decode(data, (bool))),
'TransferHelper: TRANSFER FAILED');
       function safeTransferFrom(address token, address from, address to, uint value)
internal {
          // bytes4(keccak256(bytes('transferFrom(address,address,uint256)')));
          (bool success, bytes memory data) =
token.call(abi.encodeWithSelector(0x23b872dd, from, to, value));
          require(success && (data.length == 0 || abi.decode(data, (bool))),
TransferHelper: TRANSFER_FROM_FAILED');
       function safeTransferETH(address to, uint value) internal {
           (bool success,) = to.call{value:value} (new bytes(0));
          require(success, 'TransferHelper: ETH TRANSFER FAILED');
   // SPDX-License-Identifier: MIT
   pragma solidity ^0.6.0;
    * @title Initializable
    * @dev Helper contract to support initializer functions. To use it, replace
     the constructor with a function that has the `initializer` modifier.
    * WARNING: Unlike constructors, initializer functions must be manually
    * invoked. This applies both to deploying an Initializable contract, as well
    * as extending an Initializable contract via inheritance.
    ^{\star} WARNING: When used with inheritance, manual care must be taken to not invoke
     a parent initializer twice, or ensure that all initializers are idempotent,
    * because this is not dealt with automatically as with constructors.
   contract Initializable {
```

```
* @dev Indicates that the contract has been initialized.
     bool private initialized;
      ^{\star} @dev Indicates that the contract is in the process of being initialized.
     bool private initializing;
      ^{\star} @dev Modifier to use in the initializer function of a contract.
     modifier initializer() {
       require(initializing || isConstructor() || !initialized, "Contract instance has
already been initialized");
       bool isTopLevelCall = !initializing;
       if (isTopLevelCall) {
         initializing = true;
         initialized = true;
       if (isTopLevelCall) {
        initializing = false;
      * Odev Modifier to use in the initializer function of a contract when upgrade
EVEN times.
     modifier initializerEven() {
       require(initializing || isConstructor() || initialized,
                                                                    "Contract instance has
already been initialized EVEN times");
       bool isTopLevelCall = !initializing;
       if (isTopLevelCall) {
         initializing = true;
         initialized = false;
       if (isTopLevelCall)
         initializing = false;
        / @dev Returns true if and only if the function is running in the constructor
     function isConstructor() private view returns (bool) {
// extcodesize checks the size of the code stored in an address, and
// address returns the current address. Since the code is still not
       // deployed when running a constructor, any checks on its code size will
       // yield zero, making it an effective way to detect if a contract is
       // under construction or not.
       address self = address(this);
       uint256 cs;
       assembly { cs := extcodesize(self) }
       return cs == 0;
     // Reserved storage space to allow for layout changes in the future.
     uint256[50] private ____gap;
   contract Governable is Initializable {
       address public governor;
       event GovernorshipTransferred(address indexed previousGovernor, address indexed
newGovernor);
        * @dev Contract initializer.
```

```
* called once by the factory at time of deployment
       function initialize(address governor) virtual public initializer {
          governor = governor ;
          emit GovernorshipTransferred(address(0), governor);
       modifier governance() {
          require(msg.sender == governor);
        * @dev Allows the current governor to relinquish control of the contract.
        ^{\star} @notice Renouncing to governorship will leave the contract without an
governor.
        ^{\star} It will not be possible to call the functions with the `governance`
        * modifier anymore.
       function renounceGovernorship() public governance {
          emit GovernorshipTransferred(governor, address(0));
          governor = address(0);
        * @dev Allows the current governor to transfer control of the contract to a
newGovernor.
        ^{\star} @param newGovernor The address to transfer governorship to.
       function transferGovernorship(address newGovernor) public governance {
          _transferGovernorship(newGovernor);
        * @dev Transfers control of the contract to a newGovernor.
        ^{\star} @param newGovernor The address to transfer governorship to.
       function transferGovernorship(address newGovernor) internal {
          require (newGovernor != address(0));
          emit GovernorshipTransferred(governor, newGovernor);
          governor = newGovernor;
   contract Configurable is Governable {
     mapping (bytes32 => uint) internal config;
       function getConfig(bytes32 key) public view returns (uint) {
          return config[key];
       function getConfig(bytes32 key, uint index) public view returns (uint) {
          return config[bytes32(uint(key) ^ index)];
       function getConfig(bytes32 key, address addr) public view returns (uint) {
          return config[bytes32(uint(key) ^ uint(addr))];
       function setConfig(bytes32 key, uint value) internal {
          if(config[key] != value)
              config[key] = value;
       function _setConfig(bytes32 key, uint index, uint value) internal {
    _setConfig(bytes32(uint(key) ^ index), value);
       function _setConfig(bytes32 key, address addr, uint value) internal {
   _setConfig(bytes32(uint(key) ^ uint(addr)), value);
       function setConfig(bytes32 key, uint value) external governance {
          _setConfig(key, value);
       function setConfig(bytes32 key, uint index, uint value) external governance {
          _setConfig(bytes32(uint(key) ^ index), value);
       function setConfig(bytes32 key, address addr, uint value) external governance {
```

```
_setConfig(bytes32(uint(key) ^ uint(addr)), value);
   // SPDX-License-Identifier: MIT
   pragma solidity ^0.6.0;
    * Odev Provides information about the current execution context, including the
    * sender of the transaction and its data. While these are generally available
     t via msg.sender and msg.data, they should not be accessed in such a direct
    ^{\star} manner, since when dealing with GSN meta-transactions the account sending and
    ^{\star} paying for execution may not be the actual sender (as far as an application ^{\star} is concerned).
    * This contract is only required for intermediate, library-like contracts.
   abstract contract Context {
      function msgSender() internal view virtual returns (address payable) {
          return msg.sender;
       function _msgData() internal view virtual returns (bytes memory)
          this; // silence state mutability warning without generating bytecode
https://github.com/ethereum/solidity/issues/2691
          return msg.data;
   }
    * Odev Wrappers over Solidity's arithmetic operations with added overflow
    * checks.
    * Arithmetic operations in Solidity wrap on overflow. This can easily result
    * in bugs, because programmers usually assume that an overflow raises an
    * error, which is the standard behavior in high level programming languages.
    ^{\star} 'SafeMath' restores this intuition by reverting the transaction when an
    * operation overflows.
    ^{\star} Using this library instead of the unchecked operations eliminates an entire
    * class of bugs, so it's recommended to use it always.
   library SafeMath {
        ^{\star} 0dev Returns the addition of two unsigned integers, reverting on
         overflow.
         Counterpart to Solidity's `+` operator.
         Requirements:
          - Addition cannot overflow.
       function add(uint256 a, uint256 b) internal pure returns (uint256) {
                         + b;
          uint256 c =
          require(c >= a, "SafeMath: addition overflow");
          return c;
        ^{\star} @dev Returns the subtraction of two unsigned integers, reverting on
        ^{\star} overflow (when the result is negative).
        * Counterpart to Solidity's `-` operator.
        * Requirements:
        * - Subtraction cannot overflow.
       function sub(uint256 a, uint256 b) internal pure returns (uint256) {
          return sub(a, b, "SafeMath: subtraction overflow");
```

```
* @dev Returns the subtraction of two unsigned integers, reverting with custom
message on
        * overflow (when the result is negative).
        * Counterpart to Solidity's `-` operator.
        * Requirements:
        * - Subtraction cannot overflow.
       function sub(uint256 a, uint256 b, string memory errorMessage) internal pure
returns (uint256) {
          require(b <= a, errorMessage);
          uint256 c = a - b;
          return c:
        * @dev Returns the multiplication of two unsigned integers, reverting on
        * overflow.
        * Counterpart to Solidity's `*` operator.
        * Requirements:
        * - Multiplication cannot overflow.
       function mul(uint256 a, uint256 b) internal pure returns (uint256)
          // Gas optimization: this is cheaper than requiring 'a' not being zero, but
the
          // benefit is lost if 'b' is also tested.
           // See: https://github.com/OpenZeppelin/openzeppelin-contracts/pull/522
          if (a == 0) {
              return 0;
          uint256 c = a * b;
          require(c / a == b, "SafeMath: multiplication overflow");
          return c;
        ^{\star} @dev Returns the integer division of two unsigned integers. Reverts on
        * division by zero. The result is rounded towards zero.
        * Counterpart to Solidity's `/` operator. Note: this function uses a * `revert` opcode (which leaves remaining gas untouched) while Solidity
         uses an invalid opcode to revert (consuming all remaining gas).
         Requirements:
          - The divisor cannot be zero.
       function div(uint256 a, uint256 b) internal pure returns (uint256) {
          return div(a, b, "SafeMath: division by zero");
        * @dev Returns the integer division of two unsigned integers. Reverts with
custom message on
        * division by zero. The result is rounded towards zero.
        * Counterpart to Solidity's `/` operator. Note: this function uses a
        * `revert` opcode (which leaves remaining gas untouched) while Solidity
        * uses an invalid opcode to revert (consuming all remaining gas).
        * Requirements:
        * - The divisor cannot be zero.
       function div(uint256 a, uint256 b, string memory errorMessage) internal pure
returns (uint256) {
          require(b > 0, errorMessage);
          uint256 c = a / b;
```

```
// assert(a == b * c + a % b); // There is no case in which this doesn't
hold
          return c;
        ^{*} Odev Returns the remainder of dividing two unsigned integers. (unsigned
integer modulo),
        * Reverts when dividing by zero.
        * Counterpart to Solidity's `%` operator. This function uses a `revert`
        * opcode (which leaves remaining gas untouched) while Solidity uses an * invalid opcode to revert (consuming all remaining gas).
        * Requirements:
        * - The divisor cannot be zero.
       function mod(uint256 a, uint256 b) internal pure returns (uint256) {
          return mod(a, b, "SafeMath: modulo by zero");
        ^{\star} Odev Returns the remainder of dividing two unsigned integers. (unsigned
integer modulo),
        * Reverts with custom message when dividing by zero.
        * Counterpart to Solidity's `%` operator. This function uses a `revert
        * opcode (which leaves remaining gas untouched) while Solidity uses an
        * invalid opcode to revert (consuming all remaining gas).
        * Requirements:
        * - The divisor cannot be zero.
      function mod(uint256 a, uint256 b, string memory
                                                          errorMessage) internal pure
returns (uint256) {
          require(b != 0, errorMessage);
          return a % b;
    function sqrt(uint x)public pure returns(uint y) {
          uint z = (x + 1)
          y = x;
          while (z < y) {
    * @dev Collection of functions related to the address type
   library Address {
        * @dev Returns true if `account` is a contract.
        * [IMPORTANT]
        * It is unsafe to assume that an address for which this function returns
        ^{\star} false is an externally-owned account (EOA) and not a contract.
        * Among others, `isContract` will return false for the following
        * types of addresses:
        * - an externally-owned account
        * - a contract in construction
        * - an address where a contract will be created
        ^{\star} - an address where a contract lived, but was destroyed
        * ====
       function isContract(address account) internal view returns (bool) {
          // This method relies in extcodesize, which returns 0 for contracts in
          // construction, since the code is only stored at the end of the
```

```
// constructor execution.
           uint256 size:
           // solhint-disable-next-line no-inline-assembly
           assembly { size := extcodesize(account) }
           return size > 0;
        * @dev Replacement for Solidity's `transfer`: sends `amount` wei to
         '`recipient`, forwarding all available gas and reverting on errors.
        * https://eips.ethereum.org/EIPS/eip-1884[EIP1884] increases the gas cost
        * of certain opcodes, possibly making contracts go over the 2300 gas limit
        * imposed by `transfer`, making them unable to receive funds via

* `transfer`. {sendValue} removes this limitation.
        * https://diligence.consensys.net/posts/2019/09/stop-using-soliditys-transfer-
now/[Learn more].
        * IMPORTANT: because control is transferred to `recipient`, care must be
        * taken to not create reentrancy vulnerabilities. Consider using
         * {ReentrancvGuard} or the
        * https://solidity.readthedocs.io/en/v0.5.11/security-considerations.html#use-
the-checks-effects-interactions-pattern[checks-effects-interactions pattern].
       function sendValue(address payable recipient, uint256 amount) internal {
    require(address(this).balance >= amount, "Address: insufficient balance");
           // solhint-disable-next-line avoid-low-level-calls, avoid-call-value
           (bool success, ) = recipient.call{ value: amount }(""); require(success, "Address: unable to send value, recipient may have
reverted");
        * Odev Performs a Solidity function call using a low level `call`. A
        ^{\star} plain`call` is an unsafe replacement for a function call: use this
        * function instead.
        * If `target` reverts with a revert reason, it is bubbled up by this * function (like regular Solidity function calls).
        * Returns the raw returned data. To convert to the expected return value,
        * use https://solidity.readthedocs.io/en/latest/units-and-global-
variables.html?highlight=abi.decode#abi-encoding-and-decoding-functions[`abi.decode`].
       * Requirements:
          - `target` must be a contract.
- calling `target` with `data` must not revert.
           Available since v3.1._
       function functionCall(address target, bytes memory data) internal returns
         return functionCall(target, data, "Address: low-level call failed");
        * @dev Same as {xref-Address-functionCall-address-bytes-}[`functionCall`], but
with
        * `errorMessage` as a fallback revert reason when `target` reverts.
           Available since v3.1.
       function functionCall(address target, bytes memory data, string memory
errorMessage) internal returns (bytes memory) {
          return _functionCallWithValue(target, data, 0, errorMessage);
       /**
        * @dev Same as {xref-Address-functionCall-address-bytes-}[`functionCall`],
        * but also transferring `value` wei to `target`.
        * Requirements:
```

```
* - the calling contract must have an ETH balance of at least `value`.
        * - the called Solidity function must be `payable`.
          Available since v3.1.
       function functionCallWithValue(address target, bytes memory data, uint256
value) internal returns (bytes memory) {
          return functionCallWithValue(target, data, value, "Address: low-level call
with value failed");
        * @dev Same as {xref-Address-functionCallWithValue-address-bytes-
uint256-}[`functionCallWithValue`], but
        * with `errorMessage` as a fallback revert reason when `target` reverts.
          _Available since v3.1._
       function functionCallWithValue(address target, bytes memory data, uint256
value, string memory errorMessage) internal returns (bytes memory) {
          require(address(this).balance >= value, "Address: insufficient balance for
          return functionCallWithValue(target, data, value, errorMessage);
       function functionCallWithValue(address target, bytes memory data, uint256
weiValue, string memory errorMessage) private returns (bytes memory) {
    require(isContract(target), "Address: call to non-contract");
           // solhint-disable-next-line avoid-low-level-calls
           (bool success, bytes memory returndata) = target.call{ value:
weiValue } (data);
          if (success) {
              return returndata;
           } else {
              // Look for revert reason and bubble it up if present if (returndata.length > 0) ( \,
                  // The easiest way to bubble the revert reason is using memory via
assembly
                  // solhint-disable-next-line no-inline-assembly
                  assembly {
                     let returndata_size := mload(returndata)
                     revert (add (32, returndata), returndata size)
              } else
                  revert (errorMessage);
    ^{\star} @dev Interface of the ERC20 standard as defined in the EIP.
    interface IERC20 {
        ^{\star} Qdev Returns the amount of tokens in existence.
       function totalSupply() external view returns (uint256);
        * \ensuremath{\text{Qdev}} Returns the amount of tokens owned by `account`.
       function balanceOf(address account) external view returns (uint256);
        * @dev Moves `amount` tokens from the caller's account to `recipient`.
        * Returns a boolean value indicating whether the operation succeeded.
        * Emits a {Transfer} event.
       function transfer(address recipient, uint256 amount) external returns (bool);
       /**
```

```
* @dev Returns the remaining number of tokens that `spender` will be
        * allowed to spend on behalf of `owner` through {transferFrom}. This is
        * zero by default.
        * This value changes when {approve} or {transferFrom} are called.
       function allowance (address owner, address spender) external view returns
(uint256);
       * @dev Sets `amount` as the allowance of `spender` over the caller's tokens.
        * Returns a boolean value indicating whether the operation succeeded.
        * IMPORTANT: Beware that changing an allowance with this method brings the
risk
        ^{\star} that someone may use both the old and the new allowance by unfortunate
        * transaction ordering. One possible solution to mitigate this race
        * condition is to first reduce the spender's allowance to 0 and set the
        * desired value afterwards:
        * https://github.com/ethereum/EIPs/issues/20#issuecomment-263524729
        * Emits an {Approval} event.
       function approve (address spender, uint256 amount) external returns (bool);
       * @dev Moves `amount` tokens from `sender` to `recipient` using the
        ^{\star} allowance mechanism. `amount` is then deducted from the caller's
        * allowance.
        * Returns a boolean value indicating whether the operation succeeded.
        * Emits a {Transfer} event.
       function transferFrom(address sender,
                                              address recipient, uint256 amount)
external returns (bool);
        * \mbox{\it Cdev Emitted when `value` tokens are moved from one account (`from`) to}
        * another (`to`).
        * Note that `value` may be zero.
       event Transfer (address indexed from, address indexed to, uint256 value);
        * @dev Emitted when the allowance of a `spender` for an `owner` is set by
         a call to {approve}. `value` is the new allowance.
       event Approval (address indexed owner, address indexed spender, uint256 value);
    * @dev Implementation of the {IERC20} interface.
    * This implementation is agnostic to the way tokens are created. This means
    ^{\star} that a supply mechanism has to be added in a derived contract using {_mint}.
    * For a generic mechanism see {ERC20PresetMinterPauser}.
    * TIP: For a detailed writeup see our guide
    ^*\ https://forum.zeppelin.solutions/t/how-to-implement-erc20-supply-
mechanisms/226[How
    * to implement supply mechanisms].
    ^{\star} We have followed general OpenZeppelin guidelines: functions revert instead
    * of returning `false` on failure. This behavior is nonetheless conventional
    ^{\star} and does not conflict with the expectations of ERC20 applications.
    * Additionally, an {Approval} event is emitted on calls to {transferFrom}.
    * This allows applications to reconstruct the allowance for all accounts just
    * by listening to said events. Other implementations of the EIP may not emit
    * these events, as it isn't required by the specification.
    * Finally, the non-standard {decreaseAllowance} and {increaseAllowance}
    * functions have been added to mitigate the well-known issues around setting
```

```
* allowances. See {IERC20-approve}.
   contract ERC20 is Context, IERC20 {
       using SafeMath for uint256;
       using Address for address;
       mapping (address => uint256) public balances;
       mapping (address => mapping (address => uint256)) internal allowances;
       uint256 public _totalSupply;
       string internal _name;
string internal _symbol;
uint8 internal _decimals;
        * @dev Sets the values for {name} and {symbol}, initializes {decimals} with
        * a default value of 18.
        * To select a different value for {decimals}, use { setupDecimals}.
        * All three of these values are immutable: they can only be set once during
        * construction.
       constructor (string memory name, string memory symbol) public
           _name = name;
           \_symbol = symbol;
           _decimals = 18;
        * @dev Returns the name of the token.
       function name() public view returns (string memory)
           return _name;
        ^{\star} Odev Returns the symbol of the token, usually a shorter version of the
        * name.
        function symbol() public view returns (string memory) {
           return _symbol;
        * @dev Returns the number of decimals used to get its user representation.
* For example, if `decimals` equals `2`, a balance of `505` tokens should
* be displayed to a user as `5,05` (`505 / 10 ** 2`).
        * Tokens usually opt for a value of 18, imitating the relationship between * Ether and Wei. This is the value {ERC20} uses, unless {_setupDecimals} is
         * called.
        * NOTE: This information is only used for _display_ purposes: it in * no way affects any of the arithmetic of the contract, including
          {IERC20-balanceOf} and {IERC20-transfer}.
       function decimals() public view returns (uint8) {
           return decimals;
        /**
        * @dev See {IERC20-totalSupply}.
       function totalSupply() public view virtual override returns (uint256) {
           return _totalSupply;
        * @dev See {IERC20-balanceOf}.
       function balanceOf(address account) public view virtual override returns
(uint256) {
           return _balances[account];
```

```
* @dev See {IERC20-transfer}.
        * Requirements:
        \star - `recipient` cannot be the zero address.
        * - the caller must have a balance of at least `amount`.
       function transfer(address recipient, uint256 amount) public virtual override
returns (bool) {
           transfer( msgSender(), recipient, amount);
           return true;
        * @dev See {IERC20-allowance}.
       function allowance (address owner, address spender) public view virtual override
returns (uint256) {
          return _allowances[owner][spender];
        * @dev See {IERC20-approve}.
        * Requirements:
        * - `spender` cannot be the zero address.
       function approve(address spender, uint256 amount) public virtual override
returns (bool) {
           _approve(_msgSender(), spender, amount);
           return true;
        * @dev See {IERC20-transferFrom}.
        * Emits an {Approval} event indicating the updated allowance. This is not * required by the EIP. See the note at the beginning of {ERC20};
        * Requirements:
        * - `sender` and `recipient` cannot be the zero address.
* - `sender` must have a balance of at least `amount`.
        * - the caller must have allowance for ``sender``'s tokens of at least
          `amount`
       function transferFrom(address sender, address recipient, uint256 amount) public
virtual override returns (bool) {
           _transfer(sender, recipient, amount);
            approve(sender, _msgSender(), _allowances[sender][_msgSender()].sub(amount,
"ERC20: transfer amount exceeds allowance"));
          return true;
        * Odev Atomically increases the allowance granted to `spender` by the caller.
        * This is an alternative to {approve} that can be used as a mitigation for
        * problems described in {IERC20-approve}.
        ^{\star} Emits an {Approval} event indicating the updated allowance.
        * Requirements:
        * - `spender` cannot be the zero address.
       function increaseAllowance(address spender, uint256 addedValue) public virtual
returns (bool) {
           _approve(_msgSender(), spender,
_allowances[_msgSender()][spender].add(addedValue));
          return true;
        * Odev Atomically decreases the allowance granted to `spender` by the caller.
```

```
^{\star} This is an alternative to {approve} that can be used as a mitigation for
        * problems described in {IERC20-approve}.
        * Emits an {Approval} event indicating the updated allowance.
        * Requirements:
        * - `spender` cannot be the zero address.
        * - `spender` must have allowance for the caller of at least
        * `subtractedValue`.
       function decreaseAllowance(address spender, uint256 subtractedValue) public
virtual returns (bool) {
           _approve(_msgSender(), spender,
allowances[_msgSender()][spender].sub(subtractedValue, "ERC20: decreased allowance
below zero"));
          return true;
        * @dev Moves tokens `amount` from `sender` to `recipient`.
        * This is internal function is equivalent to {transfer}, and can be used to
        * e.g. implement automatic token fees, slashing mechanisms, etc.
        * Emits a {Transfer} event.
        * Requirements:
        * - `sender` cannot be the zero address.
        * - `recipient` cannot be the zero address.
        * - `sender` must have a balance of at least `amount`.
       function transfer(address sender, address recipient, uint256 amount) internal
virtual {
          require(sender != address(0), "ERC20: transfer from the zero address");
          require(recipient != address(0), "ERC20: transfer to the zero address");
          beforeTokenTransfer(sender, recipient, amount);
           balances[sender] = _balances[sender].sub(amount, "ERC20: transfer amount
exceeds balance");
          balances[recipient] = balances[recipient].add(amount);
          emit Transfer(sender, recipient, amount);
                         `amount` tokens and assigns them to `account`, increasing
        ** @dev Creates
          the total supply.
         Emits a {Transfer} event with `from` set to the zero address.
          Requirements
           `to` cannot be the zero address.
       function mint(address account, uint256 amount) internal virtual {
          require (account != address(0), "ERC20: mint to the zero address");
          beforeTokenTransfer(address(0), account, amount);
          _totalSupply = _totalSupply.add(amount);
_balances[account] = _balances[account].add(amount);
          emit Transfer(address(0), account, amount);
        * @dev Destroys `amount` tokens from `account`, reducing the
        * total supply.
        * Emits a {Transfer} event with `to` set to the zero address.
        * Requirements
        * - `account` cannot be the zero address.
* - `account` must have at least `amount` tokens.
```

```
function burn(address account, uint256 amount) internal virtual {
           require (account != address(0), "ERC20: burn from the zero address");
           beforeTokenTransfer(account, address(0), amount);
            balances[account] = balances[account].sub(amount, "ERC20: burn amount
exceeds balance");
           totalSupply = totalSupply.sub(amount);
           emit Transfer(account, address(0), amount);
        * @dev Sets `amount` as the allowance of `spender` over the `owner`s tokens.
        ^{\star} This is internal function is equivalent to 'approve', and can be used to
        * e.g. set automatic allowances for certain subsystems, etc.
        * Emits an {Approval} event.
        * Requirements:
        * - `owner` cannot be the zero address.
        * - `spender` cannot be the zero address.
       function approve(address owner, address spender, uint256 amount) internal
virtual {
           require(owner != address(0), "ERC20: approve from the zero address");
          require(spender != address(0), "ERC20: approve to the zero address");
            allowances[owner][spender] = amount;
           emit Approval(owner, spender, amount);
        * @dev Sets {decimals} to a value other than the default one of 18.
        ^{\star} WARNING: This function should only be called from the constructor. Most
        ^{\star} applications that interact with token contracts will not expect
        ^{\star} {decimals} to ever change, and may work incorrectly if it does.
       function _setupDecimals(uint8 decimals_)
                                                   internal {
          _decimals = decimals_;
        * @dev Hook that is called before any transfer of tokens. This includes
          minting and burning.
          Calling conditions:
          - when `from` and `to` are both non-zero, `amount` of ``from``'s tokens will be to transferred to `to`.
           when `from` is zero, `amount` tokens will be minted for `to`.

when `to` is zero, `amount` of ``from``'s tokens will be burned.

`from` and `to` are never both zero.
        * To learn more about hooks, head to xref:ROOT:extending-contracts.adoc#using-
hooks[Using Hooks].
       function beforeTokenTransfer(address from, address to, uint256 amount)
internal virtual { }
   contract SfgToken is ERC20 {
    constructor(address SfgFarm) ERC20("Stable Finance Governance Token", "SFG")
public {
         uint8 decimals = 18;
         _setupDecimals(decimals);
          mint(SfgFarm, 21000000 * 10 ** uint256(decimals));
                                                                      // 100%, 21000000
    contract SfyToken is ERC20 {
```

```
constructor(address SfyFarm) ERC20("Stable Finance Yield Token", "SFY") public {
        uint8 decimals = 18;
         setupDecimals(decimals);
         mint(SfyFarm, 21000000 * 10 ** uint256(decimals)); // 100%, 21000000
   pragma solidity ^0.6.0;
   // helper methods for interacting with ERC20 tokens and sending ETH that do not
consistently\ return\ true/false
   library TransferHelper {
       function safeApprove(address token, address to, uint value) internal {
          // bytes4(keccak256(bytes('approve(address,uint256)')));
          (bool success, bytes memory data) =
token.call(abi.encodeWithSelector(0x095ea7b3, to, value));
          require(success && (data.length == 0 || abi.decode(data, (bool))),
'TransferHelper: APPROVE FAILED');
       function safeTransfer(address token, address to, uint value) internal {
          // bytes4(keccak256(bytes('transfer(address,uint256)')));
          (bool success, bytes memory data) =
token.call(abi.encodeWithSelector(0xa9059cbb, to, value));
          require(success && (data.length == 0 || abi.decode(data,
                                                                      (bool))),
'TransferHelper: TRANSFER FAILED');
       function safeTransferFrom(address token, address from, address to, uint value)
internal {
          // bytes4(keccak256(bytes('transferFrom(address,address,uint256)')));
          (bool success, bytes memory data)
token.call(abi.encodeWithSelector(0x23b872dd, from, to, value));
          require(success && (data.length == 0 || abi.decode(data, (bool))),
'TransferHelper: TRANSFER_FROM_FAILED');
       function safeTransferETH(address to, uint value) internal {
   (bool success,) = to.call{value:value} (new bytes(0));
          require(success, 'TransferHelper: ETH_TRANSFER_FAILED');
```

# 5. Appendix B: vulnerability risk rating criteria

Smart contract	vulnerability rating standard	
Vulnerability	Vulnerability rating description	
rating		
High risk	The loophole which can directly cause the contract or the user's	
vulnerability	fund loss, such as the value overflow loophole which can cause	
	the value of the substitute currency to zero, the false recharge	
	loophole that can cause the exchange to lose the substitute coin,	
	can cause the contract account to lose the ETH or the reentry	
	loophole of the substitute currency, and so on; It can cause the	
	loss of ownership rights of token contract, such as: the key	
	function access control defect or call injection leads to the key	
	function access control bypassing, and the loophole that the token	
	contract can not work properly. Such as: a denial-of-service	
	vulnerability due to sending ETHs to a malicious address, and a	
	denial-of-service vulnerability due to gas depletion.	
Middle risk	High risk vulnerabilities that need specific addresses to trigger,	
vulnerability	such as numerical overflow vulnerabilities that can be triggered	
	by the owner of a token contract, access control defects of non-	
	critical functions, and logical design defects that do not result in	
	direct capital losses, etc.	
Low risk	A vulnerability that is difficult to trigger, or that will harm a	
vulnerability	limited number after triggering, such as a numerical overflow that	
	requires a large number of ETH or tokens to trigger, and a	
	vulnerability that the attacker cannot directly profit from after	
	triggering a numerical overflow. Rely on risks by specifying the	
	order of transactions triggered by a high gas.	

# 6. Appendix C: Introduction of test tool

## 6.1. Manticore

Manticore is a symbolic execution tool for analysis of binaries and smart contracts. It discovers inputs that crash programs via memory safety violations. Manticore records an instruction-level

trace of execution for each generated input and exposes programmatic access to its analysis engine via a Python API.

### 6.2. Oyente

Oyente is a smart contract analysis tool that Oyente can use to detect common bugs in smart contracts, such as reentrancy, transaction ordering dependencies, and more. More conveniently, Oyente's design is modular, so this allows advanced users to implement and insert their own detection logic to check for custom attributes in their contracts.

## 6.3. securify.sh

Securify can verify common security issues with Ethereum smart contracts, such as transactional out-of-order and lack of input validation. It analyzes all possible execution paths of the program while fully automated. In addition, Securify has a specific language for specifying vulnerabilities. Securify can keep an eye on current security and other reliability issues.

#### 6.4. Echidna

Echidna is a Haskell library designed for fuzzing EVM code.

#### **6.5. MAIAN**

MAIAN is an automated tool for finding Ethereum smart contract vulnerabilities. Maian deals with the contract's bytecode and tries to establish a series of transactions to find and confirm errors.

# 6.6. ethersplay

Ethersplay is an EVM disassembler that contains related analysis tools.

#### 6.7. ida-evm

Ida-evm is an IDA processor module for the Ethereum Virtual Machine (EVM).

#### 6.8. Remix-ide

Remix is a browser-based compiler and IDE that allows users to build Ethereum contracts and debug transactions using the Solidity language.

# 6.9. Knownsec Penetration Tester Special Toolkit

Knownsec penetration tester special tool kit, developed and collected by Knownsec penetration testing engineers, includes batch automatic testing tools dedicated to testers, self-developed tools, scripts, or utility tools.