<u>UNIT IV</u> TRANSPORT LAYER

Transport Layer: Transport service, Elements of transport protocols, User Datagram Protocol, Transmission Control Protocol, Quality of service, Leaky Bucket and Token Bucket algorithm

Introduction:

The network layer provides end-to-end packet delivery using data-grams or virtual circuits. The transport layer builds on the network layer to provide data transport from a process on a source machine to a process on a destination machine with a desired level of reliability that is independent of the physical networks currently in use. It provides the abstractions that applications need to use the network.


Transport Entity: The hardware and/or software which make use of services provided by the network layer, (within the transport layer) is called transport entity.

Transport Service Provider: Layers 1 to 4 are called Transport Service Provider.

Transport Service User: The upper layers i.e., layers 5 to 7 are called Transport Service User.

Transport Service Primitives: Which allow transport users (application programs) to access the transport service.

TPDU (**Transport Protocol Data Unit**): Transmissions of message between 2 transport entities are carried out by TPDU. The transport entity carries out the transport service primitives by blocking the caller and sending a packet the service. Encapsulated in the payload of this packet is a transport layer message for the server's transport entity. The task of the transport layer is to provide reliable, cost-effective data transport from the source machine to the destination machine, independent of physical network or networks currently in use.



TRANSPORT SERVICE

1. Services Provided to the Upper Lavers

The ultimate goal of the transport layer is to provide efficient, **reliable**, **and cost-effective data transmission** service to its users, normally processes in the application layer. To achieve this, the transport layer makes use of the **services pro-vided by the network layer**. The software and/or hardware within the transport layer that does the work is called the **transport entity**. The transport entity can be located in the operating system kernel, in a library package bound into network applications, in a separate user process, or even on the network interface card.




Fig 4.1: The network, Application and transport layer

There are two types of network service

- Connection-oriented
- Connectionless

Similarly, there are also two types of transport service. The connection-oriented transport service is similar to the connection-oriented network service in many ways.

In both cases, connections have three phases:

- o Establishment
- Data transfer
- o Release.
- Addressing and flow control are also similar in both layers. Furthermore, the connectionless transport service is also very similar to the connectionless network service.
- The bottom four layers can be seen as the transport service provider, whereas the upper layer(s) are the transport service user.

2. Transport Service Primitives

- > To allow users to access the transport service, the transport layer must provide some operations to application programs, that is, a transport service interface. Each transport service has its own interface.
- The transport service is similar to the network service, but there are also some important differences.
- ➤ The **main difference** is that the network service is intended to model the service offered by real networks. Real networks can lose packets, so the network service is generally **unreliable.**
- ➤ The (connection-oriented) transport service, in contrast, is **reliable**

As an example, consider two processes connected by pipes in UNIX. They assume the connection between them is perfect. They do not want to know about acknowledgements, lost packets, congestion, or anything like that. What they want is a 100 percent reliable connection. Process A puts data into one end of the pipe, and process B takes it out of the other.

A **second difference** between the network service and transport service is **whom the services are intended for**. The network service is used only by the transport entities. Consequently, the transport service must be convenient and easy to use.

Primitive	Packet sent	Meaning
LISTEN	(none)	Block until some process tries to connect
CONNECT	CONNECTION REQ.	Actively attempt to establish a connection
SEND	DATA	Send information
RECEIVE	(none)	Block until a DATA packet arrives
DISCONNECT	DISCONNECTION REQ.	This side wants to release the connection

Table: 4.1 - The primitives for a simple transport service.

Eg: Consider an application with a server and a number of remote clients.

- 1. The server executes a "LISTEN" primitive by calling a library procedure that makes a System call to block the server until a client turns up.
- 2. When a client wants to talk to the server, it executes a "CONNECT" primitive, with "CONNECTION REQUEST" TPDU sent to the server.
- 3. When it arrives, the TE unblocks the server and sends a "CONNECTION ACCEPTED" TPDU back to the client.
- 4. When it arrives, the client is unblocked and the connection is established. Data can now be exchanged using "SEND" and "RECEIVE" primitives.
- 5. When a connection is no longer needed, it must be released to free up table space within the 2 transport entries, which is done with "DISCONNECT" primitive by sending "DISCONNECTION REQUEST"

TPDU. This disconnection can b done either by asymmetric variant (connection is released, depending on other one) or by symmetric variant (connection is released, independent of other one).




Figure 4.2 - Nesting of TPDUs, packets, and frames

- The term segment for messages sent from transport entity to transport entity.
- TCP, UDP and other Internet protocols use this term. Segments (exchanged by the transport layer) are contained in packets (exchanged by the network layer).
- These packets are contained in frames(exchanged by the data link layer). When a frame arrives, the data link layer processes the frame header and, if the destination address matches for local delivery, passes the contents of the frame payload field up to the network entity.
- The network entity similarly processes the packet header and then passes the contents of the packet payload up to the transport entity. This nesting is illustrated in <u>Fig. 4.2</u>.




Figure 4.3 - A state diagram for a simple connection management scheme. Transitions labelled in italics are caused by packet arrivals. The solid lines show the client's state sequence. The dashed lines show the server's state sequence.

In fig. 4.3 each transition is triggered by some event, either a primitive executed by the local transport user or an incoming packet. For simplicity, we assume here that each TPDU is separately acknowledged. We also assume that a symmetric disconnection model is used, with the client going first. Please note that this model is quite unsophisticated. We will look at more realistic models later on.

BERKLEY SOCKETS

These primitives are socket primitives used in Berkley UNIX for TCP.

The socket primitives are mainly used for TCP. These sockets were first released as part of the Berkeley UNIX 4.2BSD software distribution in 1983. They quickly became popular. The primitives are now widely used for Internet programming on many operating systems, especially UNIX -based systems, and there is a socket-style API for Windows called "winsock."

Primitive	Meaning
SOCKET	Create a new communication end point
BIND	Attach a local address to a socket
LISTEN	Announce willingness to accept connections; give queue size
ACCEPT	Block the caller until a connection attempt arrives
CONNECT	Actively attempt to establish a connection
SEND	Send some data over the connection
RECEIVE	Receive some data from the connection
CLOSE	Release the connection

Figure 4.4 - The socket primitives for TCP.

The first four primitives in the list are executed in that order by servers.

The **SOCKET** primitive creates a new endpoint and allocates table space for it within the transport entity. The parameter includes the addressing format to be used, the type of service desired and the protocol. Newly created sockets do not have network addresses.

- ➤ The **BIND** primitive is used to connect the newly created sockets to an address. Once a server has bound an address to a socket, remote clients can connect to it.
- ➤ The **LISTEN** call, which allocates space to queue incoming calls for the case that several clients try to connect at the same time.
- ➤ The server executes an **ACCEPT** primitive to block waiting for an incoming connection.

Some of the client side primitives are. Here, too, a socket must first be created

- ➤ The **CONNECT** primitive blocks the caller and actively starts the connection process. When it completes, the client process is unblocked and the connection is established.
- ➤ Both sides can now use **SEND** and **RECEIVE** to transmit and receive data over the full-duplex connection.
- ➤ Connection release with sockets is symmetric. When both sides have executed a **CLOSE** primitive, the connection is released.

ELEMENTS OF TRANSPORT PROTOCOLS

The transport service is implemented by a transport protocol used between the two transport entities. The transport protocols resemble the data link protocols. Both have to deal with error control, sequencing, and flow control, among other issues. The difference transport protocol and data link protocol depends upon the environment in which they are operated.

These differences are due to major dissimilarities between the environments in which the two protocols operate, as shown in Fig.

At the data link layer, two routers communicate directly via a physical channel, whether wired or wireless, whereas at the transport layer, this physical channel is replaced by the entire network. This difference has many important implications for the protocols.





Figure (a) Environment of the data link layer. (b) Environment of the transport layer.

In the data link layer, it is not necessary for a router to specify which router it wants to talk to. In the transport layer, explicit addressing of destinations is required.

In the transport layer, initial connection establishment is more complicated, as we will see. Difference between the data link layer and the transport layer is the potential existence of storage capacity in the subnet

Buffering and flow control are needed in both layers, but the presence of a large and dynamically varying number of connections in the transport layer may require a different approach than we used in the data link layer.

The transport service is implemented by a transport protocol between the 2 transport entities.



<u>Figure 4.5</u> illustrates the relationship between the NSAP, TSAP and transport connection. Application processes, both clients and servers, can attach themselves to a TSAP to establish a connection to a remote TSAP.

These connections run through NSAPs on each host, as shown. The purpose of having TSAPs is that in some networks, each computer has a single NSAP, so some way is needed to distinguish multiple transport end points that share that NSAP.

The elements of transport protocols are:

- 1. ADDRESSING
- 2. Connection Establishment.
- 3. Connection Release.
- 4. Error control and flow control
- 5. Multiplexing.

1. ADDRESSING

When an application (e.g., a user) process wishes to set up a connection to a remote application process, it must specify which one to connect to. The method normally used is to define transport addresses to which processes can listen for connection requests. In the Internet, these endpoints are called **ports**.

There are two types of access points.

TSAP (**Transport Service Access Point**) to mean a specific endpoint in the transport layer.

The analogous endpoints in the network layer (i.e., network layer addresses) are not surprisingly called

NSAPs (**Network Service Access Points**). IP addresses are examples of NSAPs.




Fig 4.5: TSAP and NSAP network connections

Application processes, both clients and servers, can attach themselves to a local TSAP to establish a connection to a remote TSAP. These connections run through NSAPs on each host. The purpose of having TSAPs is that in some networks, each computer has a single NSAP, so some way is needed to distinguish multiple transport endpoints that share that NSAP.

A possible scenario for a transport connection is as follows:

- 1. A mail server process attaches itself to TSAP 1522 on host 2 to wait for an incoming call. How a process attaches itself to a TSAP is outside the networking model and depends entirely on the local operating system. A call such as our LISTEN might be used, for example.
- 2. An application process on host 1 wants to send an email message, so it attaches itself to TSAP 1208 and issues a CONNECT request. The request specifies TSAP 1208 on host 1 as the source and TSAP 1522 on host 2 as the destination. This action ultimately results in a transport connection being established between the application process and the server.
- 3. The application process sends over the mail message.
- 4. The mail server responds to say that it will deliver the message.
- 5. The transport connection is released.

2. CONNECTION ESTABLISHMENT:

With packet lifetimes bounded, it is possible to devise a fool proof way to establish connections safely. Packet lifetime can be bounded to a known maximum using one of the following techniques:

- Restricted subnet design
- Putting a hop counter in each packet
- Time stamping in each packet

Using a 3-way hand shake, a connection can be established. This establishment protocol doesn't require both sides to begin sending with the same sequence number.




Fig 4.6: Three protocol scenarios for establishing a connection using a three-way handshake. CR denotes CONNEC TION REQUEST (a) Normal operation. (b) Old duplicate CONNECTION REQUEST appearing out of nowhere. (c) Duplicate CONNECTION REQUEST and duplicate ACK.

- The **first technique** includes any method that prevents packets from looping, combined with some way of bounding delay including congestion over the longest possible path. It is difficult, given that internets may range from a single city to international in scope.
- ➤ The **second method** consists of having the hop count initialized to some appropriate value and decremented each time the packet is forwarded. The network protocol simply discards any packet whose hop counter becomes zero.
- > The **third method** requires each packet to bear the time it was created, with the routers agreeing to discard any packet older than some agreed-upon time.

In **fig** (A) Tomlinson (1975) introduced the **three-way handshake**.

- This establishment protocol involves one peer checking with the other that the connection request is indeed current. Host 1 chooses a sequence number, x, and sends a CONNECTION REQUEST segment containing it to host 2. Host 2replies with an ACK segment acknowledging x and announcing its own initial sequence number, y.
- Finally, host 1 acknowledges host 2's choice of an initial sequence number in the first data segment that it sends

In **fig** (**B**) the first segment is a delayed duplicate CONNECTION REQUEST from an old connection.

- ➤ This segment arrives at host 2 without host 1's knowledge. Host 2 reacts to this segment by sending host1an ACK segment, in effect asking for verification that host 1 was indeed trying to set up a new connection.
- ➤ When host 1 rejects host 2's attempt to establish a connection, host 2 realizes that it was tricked by a delayed duplicate and abandons the connection. In this way, a delayed duplicate does no damage.
- ➤ The worst case is when both a delayed CONNECTION REQUEST and an ACK are floating around in the subnet.

In fig (C) previous example, host 2 gets a delayed CONNECTION REQUEST and replies to it.

- At this point, it is crucial to realize that host 2 has proposed using y as the initial sequence number for host 2 to host 1 traffic, knowing full well that no segments containing sequence number y or acknowledgements to y are still in existence.
- ➤ When the second delayed segment arrives at host 2, the fact that z has been acknowledged rather than y tells host 2 that this, too, is an old duplicate.

The important thing to realize here is that there is no combination of old segments that can cause the protocol to fail and have a connection set up by accident when no one wants it.

3.CONNECTION RELEASE:


A connection is released using either asymmetric or symmetric variant. But, the improved protocol for releasing a connection is a 3-way handshake protocol.

There are two styles of terminating a connection:

- 1) Asymmetric release and
- 2) Symmetric release.

Asymmetric release is the way the telephone system works: when one party hangs up, the connection is broken. **Symmetric release** treats the connection as two separate unidirectional connections and requires each one to be released separately.

Fig-(a)	Fig-(b)	Fig-(c)	Fig-(d)
One of the user sends a DISCONNECTION REQUEST TPDU in order to initiate connection release. When it arrives, the recipient sends back a DR-TPDU, too, and starts a timer. When this DR arrives, the original sender sends back an ACK- TPDU and releases the connection. Finally, when the ACK-TPDU arrives, the receiver also releases the connection.	Initial process is done in the same way as in fig-(a). If the final ACK-TPDU is lost, the situation is saved by the timer. When the timer is expired, the connection is released.	If the second DR is lost, the user initiating the disconnection will not receive the expected response, and will timeout and starts all over again.	Same as in fig-(c) except that all repeated attempts to retransmit the DR is assumed to be failed due to lost TPDUs. After 'N' entries, the sender just gives up and releases the connection.



4.FLOW CONTROL AND BUFFERING:

Flow control is done by having a sliding window on each connection to keep a fast transmitter from over running a slow receiver. Buffering must be done by the sender, if the network service is unreliable. The sender buffers all the TPDUs sent to the receiver. The buffer size varies for different TPDUs.

They are:

- a) Chained Fixed-size Buffers
- b) Chained Variable-size Buffers
- c) One large Circular Buffer per Connection

(a). Chained Fixed-size Buffers:

If most TPDUs are nearly the same size, the buffers are organized as a pool of identical size buffers, with one TPDU per buffer.

(b). Chained Variable-size Buffers:

This is an approach to the buffer-size problem. i.e., if there is wide variation in TPDU size, from a few characters typed at a terminal to thousands of characters from file transfers, some problems may occur:

- If the buffer size is chosen equal to the largest possible TPDU, space will be wasted whenever a short TPDU arrives.
- If the buffer size is chosen less than the maximum TPDU size, multiple buffers will be needed for long TPDUs.

To overcome these problems, we employ variable-size buffers.

(c). One large Circular Buffer per Connection:

A single large circular buffer per connection is dedicated when all connections are heavily loaded.

- 1. Source Buffering is used for low band width bursty traffic
- 2. Destination Buffering is used for high band width smooth traffic.
- 3. Dynamic Buffering is used if the traffic pattern changes randomly.




Figure 4.7. (a) Chained fixed-size buffers. (b) Chained variable-sized buffers. (c) One large circular buffer per connection.

5.MULTIPLEXING:

In networks that use virtual circuits within the subnet, each open connection consumes some table space in the routers for the entire duration of the connection. If buffers are dedicated to the virtual circuit in each router as well, a user who left a terminal logged into a remote machine, there is need for multiplexing. There are 2 kinds of multiplexing:




Figure 4.8. (a) Upward multiplexing. (b) Downward multiplexing

(a). UP-WARD MULTIPLEXING:

In the below figure, all the 4 distinct transport connections use the same network connection to the remote host. When connect time forms the major component of the carrier's bill, it is up to the transport layer to group port connections according to their destination and map each group onto the minimum number of port connections.

(b). **DOWN-WARD MULTIPLEXING:**

- If too many transport connections are mapped onto the one network connection, the performance will be poor.
- If too few transport connections are mapped onto one network connection, the service will be expensive.

The possible solution is to have the transport layer open multiple connections and distribute the traffic among them on round-robin basis, as indicated in the below figure:

With 'k' network connections open, the effective band width is increased by a factor of 'k'.

TRANSPORT PROTOCOLS - UDP

The Internet has two main protocols in the transport layer, **a connectionless protocol** and a **connection-oriented** one. The protocols complement each other. The connectionless protocol is **UDP**. It does almost nothing beyond sending packets between applications, letting applications build their own protocols on top as needed.

The connection-oriented protocol is **TCP.** It does almost everything. It makes connections and adds reliability with retransmissions, along with flow control and congestion control, all on behalf of the

applications that use it. Since UDP is a transport layer protocol that typically runs in the operating system and protocols that use UDP typically run in user s pace, these uses might be considered applications.

INTROUCTION TO UDP

- ➤ The Internet protocol suite supports a connectionless transport protocol called UDP (User Datagram Protocol). UDP provides a way for applications to send encapsulated IP datagrams without having to establish a connection.
- ➤ UDP transmits segments consisting of an 8-byte header followed by the pay-load. The two ports serve to identify the end-points within the source and destination machines.
- ➤ When a UDP packet arrives, its payload is handed to the process attached to the destination port. This attachment occurs when the BIND primitive. Without the port fields, the transport layer would not know what to do with each incoming packet. With them, it delivers the embedded segment to the correct application.




Fig 4.9: The UDP header

Source port, destination port: Identifies the end points within the source and destination machines.

UDP length: Includes 8-byte header and the data

UDP checksum: Includes the UDP header, the UDP data padded out to an even number of bytes if need be. It is an optional field.

Well-Known Ports for UDP

Table 23.1 shows some well-known port numbers used by UDP. Some port numbers can be used by both UDP and TCP. Table 23.1 *Well-known ports used with UDP*

Table 23.1 Well-known ports used with UDP


Port	Protocol	Description
7	7 Echo Echoes a received datagram back to the se	
9	Discard Discards any datagram that is received	
11	Users	Active users

Table 23.1 Well-known ports used with UDP (continued)

Port	Protocol	Description
13	Daytime	Returns the date and the time
17	Quote	Returns a quote of the day
19	Chargen	Returns a string of characters
53	Nameserver	Domain Name Service
67	BOOTPs	Server port to download bootstrap information
68	BOOTPc	Client port to download bootstrap information
69	TFTP	Trivial File Transfer Protocol
III	RPC	Remote Procedure Call
123	NTP	Network Time Protocol
161	SNMP	Simple Network Management Protocol
162	SNMP	Simple Network Management Protocol (trap)

User Datagram

UDP packets, called user datagrams, have a fixed-size header of 8 bytes. Figure shows the format of a user datagram. The fields are as follows:



- **Source port number**. This is the port number used by the process running on the source host. It is 16 bits long, which means that the port number can range from 0 to 65,535. If the source host is the client (a client sending a request), the port number, in most cases, is an ephemeral port number requested by the process and chosen by the UDP software running on the source host. If the source host is the server (a server sending a response), the port number, in most cases, is a well-known port number.
- **Destination port number**. This is the port number used by the process running on the destination host. It is also 16 bits long. If the destination host is the server (a client sending a request), the port number, in most cases, is a well-known port number. If the destination host is the client (a server sending a response), the port number, in most cases, is an ephemeral port number. In this case, the server copies the ephemeral port number it has received in the request packet.
- **Length**. This is a 16-bit field that defines the total length of the user datagram, header plus data. The 16 bits can define a total length of 0 to 65,535 bytes. However, the total length needs to be much less because a UDP user datagram is stored in an IP datagram with a total length of 65,535 bytes.

UDP length = IP length - IP header's length

• **Checksum**. This field is used to detect errors over the entire user datagram (header plus data). The checksum is discussed next.

Checksum.

The UDP checksum calculation is different from the one for IP and ICMP. Here the checksum includes three sections: a pseudo header, the UDP header, and the data coming from the application layer. The pseudo header is the part of the header of the IP packet in which the user datagram is to be encapsulated with some fields filled with Os (see Figure).

Pseudoheader for checksum calculation

der	32-bit source IP address 32-bit destination IP address		
Pseudoheader			
Pg	AliOs 8-bit protocol (17)	16-bit UDP total length	
	Source port address 16 bits	Destination port address 16 bits	
	UDP total length 16 bits	Checksum 16 bits	

(Padding

If the checksum does not include the pseudo header, a user datagram may arrive safe and sound. However, if the IP header is corrupted, it may be delivered to the wrong host. The protocol field is added to ensure that the packet belongs to UDP, and not to other transport-layer protocols. We will see later that if a process can use either UDP or TCP, the destination port number can be the same. The value of the protocol field for UDP is 17. If this value is changed during transmission, the checksum calculation at the receiver will detect it and UDP drops the packet. It is not delivered to the wrong protocol. Note the similarities between the pseudo header fields and the last 12 bytes of the IP header.

UDP Operation

UDP uses concepts common to the transport layer. These concepts will be discussed here briefly.

Connectionless Services

As mentioned previously, UDP provides a connectionless service. This means that each user datagram sent by UDP is an independent datagram. There is no relationship between the different user datagrams even if they are coming from the same source process and going to the same destination program. The user datagrams are not numbered. Also, there is no connection establishment and no connection termination, as is the case for TCP. This means that each user datagram can travel on a different path. One of the ramifications of being connectionless is that the process that uses UDP cannot send a stream of data to UDP and expect UDP to chop them into different related user datagrams. Instead each request must be small enough to fit into one user Datagram. Only those processes sending short messages should use UDP.

Flow and Error Control

UDP is a very simple, unreliable transport protocol. There is no flow control and hence no window mechanism. The receiver may overflow with incoming messages. There is no error control mechanism in UDP except for the checksum. This means that the sender does not know if a message has been lost or duplicated. When the receiver detects an error through the checksum, the user datagram is silently discarded. The lack of flow control and error control means that the process using UDP should provide these mechanisms.

Encapsulation and Decapsulation

To send a message from one process to another, the UDP protocol encapsulates and encapsulates messages in an IP datagram.

Queuing

We have talked about ports without discussing the actual implementation of them. In UDP, queues are associated with ports .

UDP WORKING

At the client site, when a process starts, it requests a port number from the operating system. Some implementations create both an incoming and an outgoing queue associated with each process. Other implementations create only an incoming queue associated with each process. Note that even if a process wants to communicate with multiple processes, it obtains only one port number and eventually one outgoing and one incoming queue.

The queues opened by the client are, in most cases, identified by ephemeral port numbers. The queues function as long as the process is running. When the process terminates, the queues are destroyed. The client process can send messages to the outgoing queue by using the source port number specified in the request. UDP removes the messages one by one and, after adding the UDP header, delivers them to IP. An outgoing queue can overflow

If this happens, the operating system can ask the client process to wait before sending any more messages. When a message arrives for a client, UDP checks to see if an incoming queue has been created for the port number specified in the destination port number field of the user datagram. If there is such a queue, UDP sends the received user datagram to the end of the queue. If there is no such queue, UDP discards the user datagram and asks the ICMP protocol to send a *port unreachable* message to the server. All the incoming messages for one particular client program, whether coming from the same or a different server, are sent to the same queue. An incoming queue can overflow. If this happens, UDP drops the user datagram and asks for a port unreachable message to be sent to the server.

At the server site, the mechanism of creating queues is different. In its simplest form, a server asks for incoming and outgoing queues, using its well-known port, when it starts running. The queues remain open as long as the server is running. When a message arrives for a server, UDP checks to see if an incoming queue has been created for the port number specified in the destination port number field of the user datagram. If there is such a queue, UDP sends the received user datagram to the end of the queue. If there is no such queue, UDP discards the user datagram and asks the ICMP protocol to send a port unreachable message to the client. All the incoming messages for one particular server, whether coming from the same or a different client, are sent to the same queue. An incoming queue can overflow. If this happens, UDP drops the user datagram and asks for a port unreachable message to be sent to the client.

Use of UDP

The following lists some uses of the UDP protocol:

- UDP is suitable for a process that requires simple request-response communication with little concern for flow and error control. It is not usually used for a process such as FrP that needs to send bulk data
- UDP is suitable for a process with internal flow and error control mechanisms. For example, the Trivial File Transfer Protocol (TFTP) process includes flow and error control. It can easily use UDP.
- UDP is a suitable transport protocol for multicasting. Multicasting capability is embedded in the UDP software but not in the TCP software.
- UDP is used for management processes such as SNMP.
- UDP is used for some route updating protocols such as Routing Information Protocol(RIP)

TCP (TRANSMISSION CONTROL PROTOCOL)

It was specifically designed to provide a reliable end-to end byte stream over an unreliable network. It was designed to adapt dynamically to properties of the inter network and to be robust in the face of many kinds of failures.

Each machine supporting TCP has a TCP transport entity, which accepts user data streams from local processes, breaks them up into pieces not exceeding 64kbytes and sends each piece as a separate IP datagram. When these datagram's arrive at a machine, they are given to TCP entity, which reconstructs the original byte streams. It is up to TCP to time out and retransmits them as needed, also to reassemble datagram's into messages in proper sequence.


The different issues to be considered are:

- 1. The TCP Service Model
- 2. The TCP Protocol
- 3. The TCP Segment Header
- 4. The Connection Management
- 5. TCP Transmission Policy
- 6. TCP Congestion Control
- 7. TCP Timer Management.

The TCP Service Model

- TCP service is obtained by having both the sender and receiver create end points called **SOCKETS**
- Each socket has a socket number(address)consisting of the IP address of the host, called a "**PORT**" (= TSAP)
- To obtain TCP service a connection must be explicitly established between a socket on the sending machine and a socket on the receiving machine
- All TCP connections are full duplex and point to point i.e., multicasting or broadcasting is not supported.
- A TCP connection is a byte stream, not a message stream i.e., the data is delivered as chunks

E.g.: 4 * 512 bytes of data is to be transmitted.



Sockets:

A socket may be used for multiple connections at the same time. In other words, 2 or more connections may terminate at same socket. Connections are identified by socket identifiers at same socket. Connections are identified by socket identifiers at both ends. Some of the sockets are listed below:

Primitive	Meaning
SOCKET	Create a new communication end point
BIND	Attach a local address to a socket
LISTEN	Announce willingness to accept connections; give queue size
ACCEPT	Block the caller until a connection attempt arrives
CONNECT	Actively attempt to establish a connection
SEND	Send some data over the connection
RECEIVE	Receive some data from the connection
CLOSE	Release the connection

Ports: Port numbers below 256 are called Well- known ports and are reserved for standard services. *Eg*:

PORT-21	To establish a connection to a host to transfer a file using FTP
PORT-23	To establish a remote login session using TELNET

The TCP Protocol

- A key feature of TCP, and one which dominates the protocol design, is that every byte on a TCP connection has its own 32-bit sequence number.
- ➤ When the Internet began, the lines between routers were mostly 56-kbps leased lines, so a host blasting away at full speed took over 1 week to cycle through the sequence numbers.
- The basic protocol used by TCP entities is the **sliding window protocol**.
- When a sender transmits a segment, it also starts a timer.
- ➤ When the segment arrives at the destination, the receiving TCP entity sends back a segment (with data if any exist, otherwise without data) bearing an acknowledgement number equal to the next sequence number it expects to receive.
- ➤ If the sender's timer goes off before the acknowledgement is received, the sender transmits the segment again.

The TCP Segment Header

Every segment begins with a fixed-format, 20-byte header. The fixed header may be followed by header options. After the options, if any, up to 65,535 - 20 - 20 = 65,495 data bytes may follow, where the first 20 refer to the IP header and the second to the TCP header. Segments without any data are legal and are commonly used for acknowledgements and control messages.




Fig 4.11: The TCP Header

Source Port, Destination Port: Identify local end points of the connections

Sequence number: Specifies the sequence number of the segment

Acknowledgement Number: Specifies the next byte expected.

TCP header length: Tells how many 32-bit words are contained in TCP header

URG: It is set to 1 if URGENT pointer is in use, which indicates start of urgent data.

ACK: It is set to 1 to indicate that the acknowledgement number is valid.

PSH: Indicates pushed data

RST: It is used to reset a connection that has become confused due to reject an invalid segment or refuse an attempt to open a connection.

FIN: Used to release a connection.

SYN: Used to establish connections.

Features OF TCP

- TCP is reliable protocol. That is, the receiver always sends either positive or negative acknowledgement about the data packet to the sender, so that the sender always has bright clue about whether the data packet is reached the destination or it needs to resend it.
- TCP ensures that the data reaches intended destination in the same order it was sent.
- TCP is connection oriented. TCP requires that connection between two remote points be established before sending actual data.
- TCP provides error-checking and recovery mechanism.
- TCP provides end-to-end communication.
- TCP provides flow control and quality of service.
- TCP operates in Client/Server point-to-point mode.
- TCP provides full duplex server, i.e. it can perform roles of both receiver and sender.

TCP Connection Establishment

To establish a connection, one side, say, the server, passively waits for an incoming connection by executing the LISTEN and ACCEPT primitives, either specifying a specific source or nobody in particular.

The other side, say, the client, executes a CONNECT primitive, specifying the IP address and port to which it wants to connect, the maximum TCP segment size it is willing to accept, and optionally some user data (e.g., a password).

The CONNECT primitive sends a TCP segment with the SYN bit on and ACK bit off and waits for a response.




Fig 4.12: a) TCP Connection establishment in the normal case b) Call Collision

TCP Connection Release

- Although TCP connections are full duplex, to understand how connections are released it is best to think of them as a pair of simplex connections.
- Each simplex connection is released independently of its sibling. To release a connection, either party can send a TCP segment with the *FIN* bit set, which means that it has no more data to transmit.
- ➤ When the *FIN* is acknowledged, that direction is shut down for new data. Data may continue to flow indefinitely in the other direction, however.
- When both directions have been shut down, the connection is released.
- Normally, four TCP segments are needed to release a connection, one *FIN* and one *ACK* for each direction. However, it is possible for the first *ACK* and the second *FIN* to be contained in the same segment, reducing the total count to three.

TCP Connection Management Modeling

The steps required establishing and release connections can be represented in a finite state machine with the 11 states listed in <u>Fig. 4.13</u>. In each state, certain events are legal. When a legal event happens, some action may be taken. If some other event happens, an error is reported.

State	Description
CLOSED	No connection is active or pending
LISTEN	The server is waiting for an incoming call
SYN RCVD	A connection request has arrived; wait for ACK
SYN SENT	The application has started to open a connection
ESTABLISHED	The normal data transfer state
FIN WAIT 1	The application has said it is finished
FIN WAIT 2	The other side has agreed to release
TIMED WAIT	Wait for all packets to die off
CLOSING	Both sides have tried to close simultaneously
CLOSE WAIT	The other side has initiated a release
LAST ACK	Wait for all packets to die off

Figure 4.13. The states used in the TCP connection management finite state machine.




Figure 4.14 - TCP connection management finite state machine.

TCP Connection management from server's point of view:

- 1. The server does a **LISTEN** and settles down to see who turns up.
- 2. When a SYN comes in, the server acknowledges it and goes to the SYNRCVD state
- 3. When the servers **SYN** is itself acknowledged the 3-way handshake is complete and server goes to the **ESTABLISHED** state. Data transfer can now occur.
- 4. When the client has had enough, it does a close, which causes a **FIN** to arrive at the server [dashed box marked passive close].
- 5. The server is then signaled.
- 6. When it too, does a **CLOSE**, a **FIN** is sent to the client.
- 7. When the client's acknowledgement shows up, the server releases the connection and deletes the connection record.

TCP Transmission Policy





Figure 4.15 - Window management in TCP.

- 1. In the above example, the receiver has 4096-byte buffer.
- 2. If the sender transmits a 2048-byte segment that is correctly received, the receiver will acknowledge the segment.
- 3. Now the receiver will advertise a window of 2048 as it has only 2048 of buffer space, now.
- 4. Now the sender transmits another 2048 bytes which are acknowledged, but the advertised window is '0'.
- 5. The sender must stop until the application process on the receiving host has removed some data from the buffer, at which time TCP can advertise a layer window.

SILLY WINDOW SYNDROME:

This is one of the problems that ruin the TCP performance, which occurs when data are passed to the sending TCP entity in large blocks, but an interactive application on the receiving side reads 1 byte at a time.



- Initially the TCP buffer on the receiving side is full and the sender knows this(win=0)
- Then the interactive application reads 1 character from tcp stream.
- Now, the receiving TCP sends a window update to the sender saying that it is all right to send 1 byte.
- The sender obligates and sends 1 byte.
- The buffer is now full, and so the receiver acknowledges the 1 byte segment but sets window to zero. This behavior can go on forever.

TCP CONGESTION CONTROL:

TCP does to try to prevent the congestion from occurring in the first place in the following way:

When a connection is established, a suitable window size is chosen and the receiver specifies a window based on its buffer size. If the sender sticks to this window size, problems will not occur due to buffer overflow at the receiving end. But they may still occur due to internal congestion within the network. Let's see this problem occurs.




Figure 4.16. (a) A fast network feeding a low-capacity receiver. (b) A slow network feeding a high-capacity receiver.

In fig (a): We see a thick pipe leading to a small- capacity receiver. As long as the sender does not send more water than the bucket can contain, no water will be lost.

In fig (b): The limiting factor is not the bucket capacity, but the internal carrying capacity of the n/w. if too much water comes in too fast, it will backup and some will be lost.

- ➤ When a connection is established, the sender initializes the congestion window to the size of the max segment in use our connection.
- ➤ It then sends one max segment if this max segment is acknowledged before the timer goes off, it adds one segment s worth of bytes to the congestion window to make it two maximum size segments and sends 2 segments.
- As each of these segments is acknowledged, the congestion window is increased by one max segment size.
- ➤ When the congestion window is 'n' segments, if all 'n' are acknowledged on time, the congestion window is increased by the byte count corresponding to 'n' segments.
- > The congestion window keeps growing exponentially until either a time out occurs or the receiver's window is reached.
- ➤ The internet congestion control algorithm uses a third parameter, the "threshold" in addition to receiver and congestion windows.

Different congestion control algorithms used by TCP are:

- RTT variance Estimation.
- Exponential RTO back-off Re-transmission Timer Management
- Karn's Algorithm
- Slow Start
- Dynamic window sizing on congestion
- Fast Retransmit
 Window Management
- Fast Recovery

TCP TIMER MANAGEMENT:

TCP uses 3 kinds of timers:

- 1. Retransmission timer
- 2. Persistence timer
- 3. Keep-Alive timer.

1. Retransmission timer: When a segment is sent, a timer is started. If the segment is acknowledged before the timer expires, the timer is stopped. If on the other hand, the timer goes off before the acknowledgement comes in, the segment is retransmitted and the timer is started again. The algorithm that constantly adjusts the time-out interval, based on continuous measurements of n/w performance was proposed by JACOBSON and works as follows:

- for each connection, TCP maintains a variable RTT, that is the best current estimate of the round trip time to the destination inn question.
- When a segment is sent, a timer is started, both to see how long the acknowledgement takes and to trigger a retransmission if it takes too long.
- If the acknowledgement gets back before the timer expires, TCP measures how long the measurements took say M
- It then updates RTT according to the formula

RTT =
$$\alpha$$
RTT + (1- α) **M**

Where $\alpha = a$ smoothing factor that determines how much weight is given to the old value. Typically, $\alpha = 7/8$ Retransmission timeout is calculated as

$$\mathbf{D} = \alpha \mathbf{D} + (\mathbf{1} - \alpha) | \mathbf{RTT} - \mathbf{M} |$$

Where D = another smoothed variable, Mean RTT = expected acknowledgement value M = observed acknowledgement value

$$Timeout = RTT + (4*D)$$

2. Persistence timer:


It is designed to prevent the following deadlock:

- The receiver sends an acknowledgement with a window size of '0' telling the sender to wait later, the receiver updates the window, but the packet with the update is lost now both the sender and receiver are waiting for each other to do something
- when the persistence timer goes off, the sender transmits a probe to the receiver the response to the probe gives the window size
- if it is still zero, the persistence timer is set again and the cycle repeats
- if it is non zero, data can now be sent
- **3. Keep-Alive timer:** When a connection has been idle for a long time, this timer may go off to cause one side to check if other side is still there. If it fails to respond, the connection is terminated.

Flow Control

TCP uses a sliding window, as discussed in UNIT-2, to handle flow control. The sliding window protocol used by TCP, however, is something between the *Go-Back-N* and Selective Repeat sliding window. The sliding window protocol in TCP looks like the Go-Back-N protocol because it does not use NAKs; it looks like Selective Repeat because the receiver holds the out-of-order segments until the missing ones arrive. There are two big differences between this sliding window and the one we used at the data link layer. First, the sliding window of TCP is byte-oriented; the one we discussed in the data link layer is frame-oriented. Second, the TCP's sliding window is of variable size; the one we discussed in the data link layer was of fixed size.

Figure 23.21 Half-close



Error control in TCP

TCP protocol has methods for finding out corrupted segments, missing segments, out-of-order segments and duplicated segments. **Error control** in TCP is mainly done through use of **three simple techniques**:

- **Checksum** Every segment contains a checksum field which is used to find corrupted segment. If the segment is corrupted, then that segment is discarded by the destination TCP and is considered as lost.
- **Acknowledgement** TCP has another mechanism called acknowledgement to affirm that the data segments have been delivered. Control segments that contain no data but has sequence number will be acknowledged as well but ACK segments are not acknowledged.
- **Retransmission** When a segment is missing, delayed to deliver to receiver, corrupted when it is checked by receiver then that segment is retransmitted again. Segments are retransmitted only during two events: when the sender receives three duplicate acknowledgements (ACK) or when a retransmission timer expires.
- **Retransmission after RTO:** TCP always preserve one retransmission time-out (RTO) timer for all sent but not acknowledged segments. When the timer runs out of time, the earliest segment is retransmitted. Here no timer is set for acknowledgement. In TCP, RTO value is dynamic in nature and it is updated using round trip time (RTT) of segments. RTT is the time duration needed for a segment to reach receiver and an acknowledgement to be received to the sender.


Traffic Shaping

Traffic shaping is a mechanism to control the amount and the rate of the traffic sent to the network. Two techniques can shape traffic: leaky bucket and token bucket.


Leaky Bucket

If a bucket has a small hole at the bottom, the water leaks from the bucket at a constant rate as long as there is water in the bucket. The rate at which the water leaks does not depend on the rate at which the water is input to the bucket unless the bucket is empty. The input rate can vary, but the output rate remains constant. Similarly, in networking, a technique called leaky bucket can smooth out bursty traffic. Bursty chunks are stored in the bucket and sent out at an average rate. Figure 24.19 shows a leaky bucket and its effects.

Figure 24.18 Weighted fair queuing



Leaky bucket



In the figure, we assume that the network has committed a bandwidth of 3 Mbps for a host. The use of the leaky bucket shapes the input traffic to make it conform to this commitment. In Figure 24.19 the host sends a burst of data at a rate of 12 Mbps for 2 s, for a total of 24 Mbits of data. The host is silent for 5 s and then sends data at a rate of 2 Mbps for 3 s, for a total of 6 Mbits of data. In all, the host has sent 30 Mbits of data in lOs. The leaky bucket smoothes the traffic by sending out data at a rate of 3 Mbps during the same 10 s. Without the leaky bucket, the beginning burst may have hurt the network by consuming more bandwidth than is set aside for this host. We can also see that the leaky bucket may prevent congestion.

As an analogy, consider the freeway during rush hour (bursty traffic). If, instead, commuters could stagger their working hours, congestion on our freeways could be avoided. A simple leaky bucket implementation is shown in Figure 24.20. A FIFO queue holds the packets. If the traffic consists of fixed-size packets . the process removes a fixed number of packets from the queue at each tick of the clock. If the traffic consists of variable-length packets, the fixed output rate must be based on the number of bytes or bits.

The following is an algorithm for variable-length packets:

- 1. Initialize a counter to *n* at the tick of the clock.
- 2. If n is greater than the size of the packet, send the packet and decrement the counter by the packet size. Repeat this step until n is smaller than the packet size.


3. Reset the counter and go to step 1.

Token Bucket

The leaky bucket is very restrictive. It does not credit an idle host. For example, if a host is not sending for a while, its bucket becomes empty. Now if the host has bursty data, the leaky bucket allows only an average rate. The time when the host was idle is not taken into account. On the other hand, the token bucket algorithm allows idle hosts to accumulate credit for the future in the form of tokens. For each tick of the clock, the system sends n tokens to the bucket. The system removes one token for every cell (or byte) of data sent. For example, if n is 100 and the host is idle for 100 ticks, the bucket collects 10,000 tokens.

Now the host can consume all these tokens in one tick with 10,000 cells, or the host takes 1000 ticks with 10 cells per tick. In other words, the host can send bursty data as long as the bucket is not empty. Figure 24.21 shows the idea. The token bucket can easily be implemented with a counter. The token is initialized to zero. Each time a token is added, the counter is incremented by 1. Each time a unit of data is sent, the counter is decremented by 1. When the counter is zero, the host cannot send data.

Figure 24.21 Token bucket



Combining Token Bucket and Leaky Bucket

The two techniques can be combined to credit an idle host and at the same time regulate the traffic. The leaky bucket is applied after the token bucket; the rate of the leaky bucket needs to be higher than the rate of tokens dropped in the bucket.

Quality of Service (QoS) in Computer Network

QoS is an overall performance measure of the computer network.

Important flow characteristics of the QoS are given below:

1. Reliability

If a packet gets lost or acknowledgement is not received (at sender), the re-transmission of data will be needed. This decreases the reliability.

The importance of the reliability can differ according to the application.

For example:

E- mail and file transfer need to have a reliable transmission as compared to that of an audio conferencing.

2. Delay

Delay of a message from source to destination is a very important characteristic. However, delay can be tolerated differently by the different applications.

For example:

The time delay cannot be tolerated in audio conferencing (needs a minimum time delay), while the time delay in the e-mail or file transfer has less importance.

3. Jitter

The jitter is the variation in the packet delay.

If the difference between delays is large, then it is called as **high jitter.** On the contrary, if the difference between delays is small, it is known as **low jitter.**

Example:

Case1: If 3 packets are sent at times 0, 1, 2 and received at 10, 11, 12. Here, the delay is same for all packets and it is acceptable for the telephonic conversation.

Case2: If 3 packets 0, 1, 2 are sent and received at 31, 34, 39, so the delay is different for all packets. In this case, the time delay is not acceptable for the telephonic conversation.

4. Bandwidth

Different applications need the different bandwidth.

For example:

Video conferencing needs more bandwidth in comparison to that of sending an e-mail.

Integrated Services and Differentiated Service

These two models are designed to provide Quality of Service (QoS) in the network.

1. Integrated Services (IntServ)

Integrated service is flow-based QoS model and designed for **IP**.

In integrated services, user needs to create a flow in the network, from source to destination and needs to inform

all routers (every router in the system implements IntServ) of the resource requirement.

Following are the steps to understand how integrated services works.

I) Resource Reservation Protocol (RSVP)

An IP is connectionless, datagram, packet-switching protocol. To implement a flow-based model, a signaling protocol is used to run over **IP**, which provides the signaling mechanism to make reservation (every applications need assurance to make reservation), this protocol is called as **RSVP**.

ii) Flow Specification

While making reservation, resource needs to define the flow specification. The flow specification has two parts:

a) Resource specification

It defines the resources that the flow needs to reserve. For example: Buffer, bandwidth, etc.

b) Traffic specification

It defines the traffic categorization of the flow.

iii) Admit or deny

After receiving the flow specification from an application, the **router decides to admit or deny the service** and the decision can be taken based on the previous commitments of the router and current availability of the resource.

Classification of services

The two classes of services to define Integrated Services are:

a) Guaranteed Service Class

This service guarantees that the packets arrive within a specific delivery time and not discarded, if the traffic flow maintains the traffic specification boundary.

This type of service is designed for real time traffic, which needs a guaranty of minimum end to end delay.

For example: Audio conferencing.

b) Controlled Load Service Class

This type of service is designed for the applications, which can accept some delays, but are sensitive to overload network and to the possibility to lose packets.

For example: E-mail or file transfer.

Problems with Integrated Services.

The two problems with the Integrated services are:

i) Scalability

In Integrated Services, it is necessary for each router to keep information of each flow. But, this is not always possible due to growing network.

ii) Service- Type Limitation

The integrated services model provides only two types of services, guaranteed and control-load.

- 2. Differentiated Services (DS or Diffserv):
- DS is a computer networking model, which is designed to achieve the scalability by managing the network traffic.
- DS is a class based QoS model specially designed for IP.
- DS was designed by IETF (Internet Engineering Task Force) to handle the problems of Integrated Services. The solutions to handle the problems of Integrated Services are explained below:

1. Scalability

The main processing unit can be moved from central place to the edge of the network to achieve the scalability. The router does not need to store the information about the flows and the applications (or the hosts) define the type of services they want every time while sending the packets.

2. Service Type Limitation

The routers, route the packets on the basis of class of services define in the packet and not by the flow. This method is applied by defining the classes based on the requirement of the applications.