Error Propagation Formula

Consider the variance of the energy, E(p, x), which is a function of the momentum, p, and the coordinate, x:

$$\left\langle \left(\Delta E\right)^{2}\right\rangle = \left\langle \left(\frac{\partial E}{\partial p}\Delta p + \frac{\partial E}{\partial x}\Delta x\right)\left(\frac{\partial E}{\partial p}\Delta p + \frac{\partial E}{\partial x}\Delta x\right)\right\rangle$$

$$= \left\langle \left|\frac{\partial E}{\partial p}\right|^{2}(\Delta p)^{2} + 2\frac{\partial E}{\partial p}\frac{\partial E}{\partial x}\Delta p\Delta x + \left|\frac{\partial E}{\partial x}\right|^{2}(\Delta x)^{2}\right\rangle ,$$

$$= \left|\frac{\partial E}{\partial p}\right|^{2}\left\langle \left(\Delta p\right)^{2}\right\rangle + 2\frac{\partial E}{\partial p}\frac{\partial E}{\partial x}\left\langle \Delta p\Delta x\right\rangle + \left|\frac{\partial E}{\partial x}\right|^{2}\left\langle \left(\Delta x\right)^{2}\right\rangle ,$$

where $\Delta E = E - \langle E \rangle$, etc., and the a bracket denotes an expectation value.

If the momentum and coordinate are statistically independent,

$$\langle \Delta p \Delta x \rangle = \langle \Delta p \rangle \langle \Delta x \rangle = 0$$

and hence

$$\langle (\Delta E)^2 \rangle = \left| \frac{\partial E}{\partial p} \right|^2 \langle (\Delta p)^2 \rangle + \left| \frac{\partial E}{\partial x} \right|^2 \langle (\Delta x)^2 \rangle.$$