

Extracts whitespaces.

bool.

operations

boolalpha/noboolalpha

skipws/noskipws

dec/hex/oct

Activates/deactivates the extraction of alphanumerical representations of values of type

Activates/deactivates whether leading whitespaces are discarded before formatted input

Sets that base used to interpret integral numerical values.

The following extended manipulators can also be applied to istream objects (these take additional arguments and require the explicit inclusion of the <iomanip> header):

manipulator	Effect
setbase	Sets the numerical base used to interpret integral numerical values.
setiosflags/resetiosflags	Set/reset format flags.

🤁 Return Value

The istream object (*this).

The extracted value or sequence is not returned, but directly stored in the variable passed as argument.

Errors are signaled by modifying the *internal state flags*, except for (3), that never sets any flags (but the particular manipulator applied may):

mampalator applica may).		
flag	error	
eofbit	The input sequence has no more characters available (end-of-file reached).	
failbit	Either no characters were extracted, or the characters extracted could not be interpreted as a valid value of the appropriate type. For (2), it is set when no characters are inserted in the object pointed by sb, or when sb is a null pointer.	
badbit	Error on stream (such as when this function catches an exception thrown by an internal operation). When set, the integrity of the stream may have been affected.	

Multiple flags may be set by a single operation.

If the operation sets an *internal state flag* that was registered with member exceptions, the function throws an exception of member type failure.

Example

```
1 // example on extraction
                        // std::cin, std::cout, std::hex
  #include <iostream>
4 int main () {
    int n;
    std::cout << "Enter a number: ";</pre>
    std::cin >> n;
std::cout << "You have entered: " << n << '\n';
10
11
    std::cout << "Enter a hexadecimal number: ";</pre>
    12
13
14
15
    return 0:
16 }
```

This example demonstrates the use of some of the overloaded operator>> functions shown above using the standard istream object cin.

Data races

Modifies val or the object pointed by sb.

Modifies the stream object.

Concurrent access to the same stream object may cause data races, except for the standard stream object cin when this is *synchronized with stdio* (in this case, no data races are initiated, although no guarantees are given on the order in which extracted characters are attributed to threads).

Exception safety

Basic guarantee: if an exception is thrown, the object is in a valid state.

It throws an exception of member type failure if the resulting *error state flag* is not goodbit and member exceptions was set to throw for that state.

Any exception thrown by an internal operation is caught and handled by the function, setting badbit. If badbit was set on the last call to exceptions, the function rethrows the caught exception.

istream::get	Get characters (public member function)
istream::getline	Get line (public member function)
ostream::operator<<	Insert formatted output (public member function)
istream::sentry	Prepare stream for input (public member class)

Home page | Privacy policy © cplusplus.com, 2000-2015 - All rights reserved - v3.1 Spotted an error? contact us