# 10878 Physik der Kondensierten Materie Summary

Reto Flütsch

HS 2020

## Introduction

#### On this document

This document are my personal notes on the lecture 10878 Physik der Kondensierten Materie at Uni Basel in the Fall semester 2020. I type this document during the lectures (while the Professors speak) with minimal editing between lectures - there are A LOT of spelling mistakes, typos and errors of various severity.

#### Information about this Course

all lectures online, exercises online Tue 8:15 to 10:00 in two groups nanophononics.physik.unibas.ch/pages/teaching.htm and adam will hold the presentations Exercises 30 points per sheet 60% of points required, hand in on thursday till 12am before lectures. Released on Friday. Links for exercise class will be sent by assistants.

Written exam on 20.01.2021 10:00 - 12:00, 5 pages double a4 handwritten notes and non-programmable calculator. Exam is based on exercise sheets.

Course mostly based on The Oxford Solid State Basics, Steven H. Simon. Some parts based on other books.

# Contents

1	Hea	at in Solids	3	
	1.1	Introduction	3	
	1.2	Heat Capacity - Definitions		
	1.3	Dulong-Petit		
	1.4	Einstein Model		
	1.5	Debye Model of Solids		
2	Dru	ide Theory	8	
	2.1	Relaxation Time Approximation	8	
	2.2	$e^-$ in electric fields - Drude conductivity	9	
	2.3	$e^-$ in $ec{E}$ and $ec{B}$ - Hall effect in the Drude model		
	2.4	Heat Capacity due to $e^-$		
	2.5	Thermoelectric Properties - how the Drude model fails		
	2.6	Success and Failures of the Drude model		
		2.6.1 Mean free path of $e^-$ - $\lambda$		
		2.6.2 Measured Values		
3	Sommerfeld Theory for free electrons in metals			
	3.1	Fermi-Dirac Statistics	2	
	3.2	Quantum States of $e^-$ in solids		
	3.3	Density of States - $q_{ij}$		

## Chapter 1

## Heat in Solids

#### 1.1 Introduction

What is condensed Matter physics and why is it important?

We deal in solids and liquids Condensed: interactions between atoms win over entropy. Key question is how to reproduce the properties of matter which is a many body problem. Currently the largest subfield of Physics.

Intro question: Which keeps coffee warmest?

- Steel Cup
- Ceramic Cup
- Glass Cup

The Steel cup looses, electrical conducters are also good thermal conductors. Glass acctually has the lowest thermal conductivity, yet the ceramic cup still wins. Why?

It's not only the thermal conductivity that matters, it's also the heat capacity that matters, and in this regard ceramics are almost unbeatable.

### 1.2 Heat Capacity - Definitions

Heat Capacity is how much heat can you store in a material per change in temperature.

$$C = \frac{\partial U}{\partial T}.$$

Specific heat  $c_v$  is the heat capacity per unit volume.  $C_{N_a}$  is the heat capacity per mole, as it's otherwise per atom. We will only deal with the Heat Capacity at constant presure and volume.

$$C_P \approx C_V = C$$
.

We will now derive the Heat Capacity in a solid from the Heat Capacity in a Gas

$$\frac{C_V}{N} = \frac{3}{2}K_B$$
 for a momo-atomic gas.

Multiplying by  $N_A$  yields:  $C_V = \frac{3}{2}R$ .

#### 1.3 Dulong-Petit

Purely observational law for many solids:

$$C = 3K_B$$
 per atom  $C = 3R$ .

Works pretty well for many materials at room temperature (notable exception is Diamond).

Where did the law for Gas come from? Equipartition system, each degree of freedom gets equal amount of the internal energy  $\frac{1}{2}K_BT$ . In a Gas there are 3 degrees of Freedom (three elements of momentum).

For solids there are an additional 3 degrees of freedom from the potential energy (positional degrees of freedom)

3 degrees of freedom from kinetic energy + 3 degrees of freedom from potential energy = 6 degrees of freedom.

$$U = \frac{3+3}{2}K_BT.$$
 
$$C = \frac{\partial U}{\partial T} = 3K_B \text{ per atom.}$$
 
$$\implies C = 3R \text{ per mole.}$$

This 'law' fails for very low temperatures for all materials, and for some (notably diamond) it even fails completely.

#### 1.4 Einstein Model

Assumes the particles are oscilating around their positional groundstate, and uses the expectation value of the potential energy instead of its' groundstate energy.

We assume the atoms are in a harmonic potential well and behave like harmonic oscilators with energy eigenstaten  $E_m = \hbar\omega \left(n + \frac{1}{2}\right)$ . (Einstein did not include the factor  $+\frac{1}{2}$  as QM was not yet dicovered).

We introduce the  $Partition\ Function\ Z$ , which describes the distribution among all possible microstates of a system. This function is extremly important in statistical mechanics and can be used to derive most macroscopic properties. It is given by:

$$Z = \sum_{n=0}^{\infty} \exp\left(-\beta E_n\right).$$

With  $\beta = \frac{1}{K_B T}$ .

We can use the partition function for example to calculate the probability to find a system in a certain microstate as  $P(E_n) = \frac{\exp(-\beta E_n)}{Z}$ . We can thus write the expectation value of the energy as

$$\langle E \rangle = \sum_{n=0}^{\infty} P(E_n) E_n = \frac{1}{Z} \sum_{n=0}^{\infty} E_n \exp(-\beta E_n).$$

Looking at this result we realize that

$$\frac{\partial Z}{\partial \beta} = \sum_{n=0}^{\infty} -E_n \exp(-\beta E_n)$$

$$\implies \langle E \rangle = -\frac{1}{Z} \frac{\partial Z}{\partial \beta}.$$

This is the more general form of the energy expectation in terms of the partition function. For the harmonic oscilator where  $E_n = \hbar\omega \left(n + \frac{1}{2}\right)$  we therefore get:

$$Z = \sum_{n=0}^{\infty} \exp\left(-\beta\hbar\omega\left(n + \frac{1}{2}\right)\right)$$
$$= \exp\left(-\frac{\beta\hbar\omega}{2}\right) * \sum_{n=0}^{\infty} \exp\left(-\beta\hbar\omega n\right) = \exp\left(\frac{-\beta\hbar\omega}{2}\right) * \sum_{n=0}^{\infty} \exp\left(-\beta\hbar\omega\right)^{n}$$

we recognize a geometric series and rewrite

$$Z = \exp\left(-\frac{\beta\hbar\omega}{2}\right) * \frac{1}{1 - \exp\left(-\beta\hbar\omega\right)} = \frac{1}{\exp\left(\frac{\beta\hbar\omega}{2}\right) + \exp\left(-\frac{\beta\hbar\omega}{2}\right)} = \frac{1}{2\sinh\left(\frac{\beta\hbar\omega}{2}\right)}.$$

For the energy expectatation value we thus get

$$\langle E \rangle = -\frac{1}{Z} \frac{\partial Z}{\partial \beta} = -\frac{\hbar \omega}{2} \coth\left(-\frac{\beta \hbar \omega}{2}\right).$$

Introducing the Bose occupation factor  $n_B(x) = \frac{1}{\exp(x)-1}$  we get

$$\langle E \rangle = \hbar\omega \left( n_B \left( \beta \hbar \omega \right) + \frac{1}{2} \right).$$

In this calculation we have only considered a one-dimensional harmonic oscilator, in reality we have to consider the three-dimensional case. In three dimensions the expectation value for the energy is three times higher

$$< E_{3d}> = 3 < E_{1d}> = 3\hbar\omega\left(n_B\left(\beta\hbar\omega\right) + \frac{1}{2}\right).$$

According to definition the Heat capacity is given by

$$c = \frac{\partial \langle E \rangle}{\partial T} = K_B (\beta \hbar \omega)^2 \frac{\exp(\beta \hbar \omega)}{[\exp(\beta \hbar \omega) - 1]^2}.$$

We will now investigate this new expression in the limit for very big and very small temperatures:

 $\lim_{T\to\infty}c=\lim_{\beta\to 0}c=3K_B$  for big temperatures we recover the Dulong-Petit Law as expected

 $\lim_{T\to 0} c = \lim_{\beta\to\infty} c = 0$  for very small Temperatures the model predicts an exponential decay.

This approximation models all materials at high and low temperatures, but still fails at very low temperatures, where it predicts a exponential decay, where in experimets a decay  $\propto T^3$  is measured.

## 1.5 Debye Model of Solids

Assumes that atoms at the bottom of their potential well oscillate not independently from each other, but are coppeled in a collective motion. Simmilar to sound waves.

QM was not yot discovered, but the quantisation of light was known, Debye thus applied that same line of thinking to sound waves. It's important to note, that soundwaves, contrary to lightwaves can also have a longitudional part. We will treat waves in a finite solid with periodic boundary conditions. We define a periodic space on which there is a periodicity such that all waves are same at x = 0 and x = L. Thus only wavelength of the foarm

$$\lambda_m = \frac{2L}{m}$$
 are allowed.

The Wavelengths of the 'allowed' waves are given by

$$K = \frac{2\pi m}{L}.$$

Whenever we want to treat the sum over 'all possible' values of k we can replace the sum over all k with an integral (provwided that L is big)

$$\sum_{k} \to \frac{L}{2\pi} \int_{-\infty}^{\infty} dk.$$

In three dimensions this integral is over the three dimensional k-space

$$\sum_{k} \to \left(\frac{L}{2\pi}^{3}\right) \int d^{3}k.$$

Debye assumed that the oscillation modes in a solid behave like sound waves, and therefor have a linear dispersion relation

$$\omega(k) = v|k|.$$

The only adaptation to Einstein we have to do, is to integrate over all possible k.

$$\langle E \rangle = 3 \sum_{k} \hbar \omega(\vec{k}) \left( n_{B} (\beta \hbar \omega(\vec{k})) + \frac{1}{2} \right).$$

$$\implies \langle E \rangle = 3 \frac{L^{3}}{(2\pi)^{3}} \int \hbar \omega(\vec{k}) \left( n_{B} (\beta \hbar \omega(\vec{k})) + \frac{1}{2} \right) d\vec{k}.$$

By switching to spherical coordinates we get  $\int d\vec{k} \to 4\pi \int_0^\infty k^2 dk$ 

$$\Longrightarrow \langle E \rangle = \frac{3(4\pi)L^3}{(2\pi)^3} \int_0^\infty k^2 \hbar \omega \left( n_B(\beta \hbar \omega) + \frac{1}{2} \right).$$

We now use the dispersion relation and insert  $\omega = vk$ 

$$\implies vdk = d\omega \text{ and } k^2 = \frac{\omega^2}{v^2}.$$

$$\Longrightarrow < E > = 3 \frac{4\pi L^3}{(2\pi)^3} \int_0^\infty \omega^2 \frac{1}{v^3} \hbar \omega \left( n_B(\beta \hbar \omega) + \frac{1}{2} \right) d\omega.$$

If a solid has n-atoms per unit volume then a cube of side L has a total of N atoms.  $\rightarrow N = nL^3 \implies L^3 = \frac{N}{n}$ .

$$\implies < E > = \int_0^\infty \left( \frac{12\pi\omega^2 N}{(2\pi)^3 n} \right) \frac{1}{v^3} \hbar\omega \left( n_B(\beta\hbar\omega) + \frac{1}{2} \right) d\omega.$$

If we define the density of States as

$$g(\omega) = N\left(\frac{12\pi\omega^2}{\left(2\pi\right)^3 nv^3}\right).$$

We can rewrite the energy expectation as

$$\langle E \rangle = \int_{0}^{\infty} g(\omega) \hbar \omega \left( n_B(\beta \hbar \omega) + \frac{1}{2} \right).$$

The density of states  $g(\omega)$  is a factor weighing ow many states that there are at a given frequency. The Integral is thus just equal to the density of the states times the energy of the states at a given frequencyp.

If we further define a Debye frequency  $\omega_D=6\pi^2nv^3$  we can further simplify the density  $g(\omega)=N\frac{9\omega^2}{\omega_D^3}$ .

The final result for the energy expectation is thus:

$$_{tot} = \frac{9N\hbar}{\omega_D^3} \int_0^\infty \frac{\omega^3}{\exp\left(\beta\hbar\omega\right) - 1} d\omega.$$

Note: we have left out the factor of  $\frac{1}{2}$ , because we will differentiate later and it'd fall out anyway (also leaving it in creates unnecessary mathematical difficulties).

To solve the integral we make a change of variables

$$x = \beta \hbar \omega \to \frac{dx}{\beta \hbar} = d\omega.$$

The solution is still very tedious, the final result is given by

$$< E > = 9N \frac{(K_B T)^4}{(\hbar \omega_D)^3} \left(\frac{\pi^4}{15}\right).$$

We therefore get

$$C = \frac{\partial \langle E \rangle}{\partial T} = \dots \propto T^3.$$

Debye thus correctly models the low temperature regime ( $T^3$  dependence) but fails for high temperatures, and does not converge to the Dulang-Petit.

The problem of the Debye model is that we were integrating over an infinite number of modes, but in reality there can never be an infinite amount of modes.

No. of modes 
$$=\int_0^\infty g(\omega) \to \infty$$
.

Debye thus introduced a 'cutoff frequency' such that the total number of modes are equal to the total number of degrees of freedom

$$3N = \int_0^{\omega_{cutoff}} g(\omega) d\omega.$$

With this correction we get

$$\langle E \rangle = \int_{0}^{\omega_{c}} g(\omega) \hbar \omega n_{B}(\beta \hbar \omega) d\omega.$$

At high temperatures we thus get:

$$T \to \infty \implies n_B(\beta\hbar\omega) \to K_B \frac{T}{\hbar\omega}.$$
 
$$\Longrightarrow \langle E \rangle = K_B T \int_0^{\omega_c} g(\omega) d\omega = 2K_B T N.$$
 
$$\Longrightarrow C = 3NK_B = 3R \text{ (Dulang-Petit!)}.$$

It's a bi tad-hoc, but it works.

We acctually find that the cutoff frequency is equal to the Debye frequency

$$\omega_{cutoff} = \omega_D$$
.

The final result of Debye is thus:

$$< E>_{tot} = \int_0^{\omega_c} g(\omega) \left( n_B(\beta\hbar\omega) + \frac{1}{2} \right).$$

The Debye model is the first model that does not feature a fitting parameter. Unfortunatelly there are still some problems:

- $\omega_{cutoff}$  is an unexplained ad hoc correction
- The dispersion relation used  $\omega = vk$  does not hold at high temperature
- There are still some exotic material that are not modelled cerrectly
- For metals the heat capacity c at low temperatures is different:  $c \propto \alpha T^3 + \gamma T$ . Only the  $T^3$  dependence is moddled correctly by the Debye model.

## Chapter 2

## Drude Theory

Developed three years after the discovery of electrons. To accurately describe metals we have to take the electron  $e^-$  into account.

Drude applies the kinetic theory of Bolzman to electrons, a few assumptions are necessary:

- There are collisions among electrons with a scattering time  $\tau$ . The probability of scattering is given by  $\frac{dt}{\tau}$
- After scattering the momentum  $\vec{p}_{final} = 0$ . This obviously only holds on average across many collisions
- If there are electric and magnetic fields  $\vec{E}$   $\vec{M}$  the electrons will interact with them

While assumptions 1 and 3 are also valid in gasses, the third assumption obviously only holds for electrons.

#### 2.1 Relaxation Time Approximation

We consider a electron traveling through a cristal with momentum  $\vec{p}$ . After some time a scattering event occures, after this event it has a new momentum  $\vec{p}(t+\delta t)$ . We first consider all the electrons that collide in the time  $\delta t$ . The probability is given as  $\frac{\delta t}{\tau}$ , according to the second assumption, those electrons will end up with  $\vec{p}=0$ . Electrons that don't collide. The probability of no collision is given as  $1-\frac{\delta t}{\tau}$ . When an electron does not collide, it will accelerate due to the force acting on it  $\vec{F}=m_e a=\frac{d\vec{p}}{dt}$ . The force can naturally vary with time  $\rightarrow \vec{F}+O(t)$ .

$$\implies \delta \vec{p} = \vec{F} \delta t + O\left(\delta t^2\right).$$

What we search is  $\vec{p}(t + \delta t)$ .

$$\vec{p}(t+\delta t) = \frac{\delta t}{\tau} \vec{p}_{final} + \left(1 - \frac{\delta t}{\tau}\right) \left[\vec{p}(t) + \vec{F}(t)\delta t + O\left(\delta t^2\right)\right].$$

The first term is 0 because of assumption 2

$$\implies \vec{p}(t+\delta t) = \left(1 - \frac{\delta t}{\tau}\right) \left[\vec{p}(t) + \vec{F}(t)\delta t\right) = \vec{p}(t) + \vec{F}(t)\delta t - \frac{\delta t}{\tau}\vec{p}(t).$$

$$\implies \frac{d\vec{p}(t)}{dt} = \vec{F} - \frac{\vec{p}(t)}{\tau}.$$

This result is called the relaxation time equation of the drude model. We know that

$$\vec{F} = -e\left(\vec{E} + \vec{v} \times \vec{B}\right).$$

The other term  $\vec{p}/\tau$  can be understood as a kind of drag on the electrons. As an example we consider  $\vec{F} = 0$  and get

$$\frac{d\vec{p}(t)}{dt} = -\frac{\vec{p}(t)}{\tau} \implies \vec{p}(t) = \vec{p_0} \exp\left(-\frac{t}{\tau}\right).$$

On average the momentum  $\vec{p}$  tends to zero (due to scattering) in absence of no external force  $\vec{F}$ .

#### 2.2 $e^-$ in electric fields - Drude conductivity

We recall ohm's law  $\vec{j} = \sigma \vec{E}$ . We assume that we have  $\vec{E} \neq 0$  but  $\vec{B} = 0 \implies \vec{F} = -e\vec{E}$ . We thus get

$$\frac{d\vec{p}}{dt} = -e\vec{E} - \frac{\vec{p}}{\tau}.$$

We are interested in a steady state  $\frac{d\vec{p}}{dt} = 0$ 

$$\implies \vec{p} = -e\tau \vec{E} = m\vec{v}.$$

$$\implies \vec{v} = -\frac{e\tau}{m_c} \vec{E}.$$

We now use ohm's law with current density  $\vec{J} = -ne\vec{v}$ , with the electron density n.

$$\vec{J} = -ne\vec{v} = -ne\left(-\frac{e\tau}{m_e}\vec{E}\right) = \frac{ne^2\tau}{m_e}\vec{E} = \sigma\vec{E}.$$

$$\implies \sigma_{drude} = \frac{ne^2\tau}{m_e}.$$

The conclusion of this part, is that if you can measure  $\sigma_{drude}$  you can use it to measure the electron density in a material.

### 2.3 $e^-$ in $\vec{E}$ and $\vec{B}$ - Hall effect in the Drude model

$$\vec{F} = -e \left( \vec{E} + \vec{v} \times \vec{B} \right).$$

$$\implies \frac{d\vec{p}}{dt} = -e \left( \vec{E} + \vec{v} \times \vec{B} \right) - \frac{\vec{p}}{\tau}.$$

Again we are interested in the steady state.

$$-e\vec{E} - e\vec{v} \times \vec{B} - \frac{\vec{p}}{\tau} = 0.$$

$$\implies -e\vec{E} + \frac{\vec{J} \times \vec{B}}{n} + \frac{m_e}{ne\tau} \vec{J} = 0.$$

We assume that  $\vec{B} = -B_z \vec{e_z}$ . We then take a piece of metal with dimensions  $L_x$ ,  $L_y$ , and  $L_z$ , and run a current trough the metal along the X-axis a  $\implies \vec{J} = J_x \vec{e_x}$ , thus we also know that  $\vec{E} = E_x \vec{e_x} + E_y \vec{e_y}$  will only have components in the X/Y-Plane.

X component: 
$$eE_x = 0 + \frac{m_e}{ne\tau}J_x \implies E_x = \frac{m_e}{ne^2\tau}J_x$$
  
y component:  $eE_y = \frac{J_xB_z}{n} + 0 \implies E_y = \frac{B_zJ_x}{ne}$ .  
z component:  $0 = 0 + 0$ .

We know that  $\vec{J} = \sigma \vec{E} = \frac{1}{\rho} \vec{E}$  but we now see that the restance  $\rho$  depends on the direction (aka. is a matrix).

$$\rho_{xx} = \frac{E_x}{J_x} = \frac{ne^2\tau}{m_e}$$

$$\rho_{xy} = \frac{E_y}{J_x} = -\frac{B}{ne}$$

The really important coefficient is  $\rho_{xy}$  (the longitudinal resistivity  $\rho_{xx}$  is expected). We call  $\rho_{xy}$  the Hall resistivity, which means that there is a voltage along Y that we call Hall voltage.

The Hall effect thus is the effect, that when applying a magnetic field pependicular to a current density we suddenly measure a voltage perpendicular to both. This effect is used for a variety of measurements. We define the Hall coefficient:

$$R_H = \frac{\rho_{xy}}{|B|} = -\frac{1}{ne}.$$

How can the Hall effect can acctually be used?

- Hall sensors to measure magnetic fields  $\vec{B}$ . If n, e and  $\vec{J}$  are known we can use the Hall effect to measure a magnetic field. Note: High Hall voltages are easier to measure, for such sensors we want to choose materials with a big Hall coefficient  $R_H = -\frac{1}{ne}$ , aka. with small n (semiconductors).
- If we know  $\vec{B}$  and  $\vec{J}$  we can measure the electron density.

#### 2.4 Heat Capacity due to $e^-$

We study a cylinder that we are heating on one end. There will be a heat flow  $\vec{Q}$  and a heat flux, or heat current density,  $\vec{J}_Q = \frac{\text{energy}}{\text{time*area}}$ .

$$J_O = -\kappa \nabla T$$
.

Druede assuemes that the heat in metals is only transported by the electorns, and he describes electrons with the kinetic theory of gasses.

$$\kappa = \frac{1}{3}nC < v > \lambda = \frac{1}{2}nc < v >^{2} \tau.$$

With  $\lambda = \langle v \rangle \tau$  the distance an electron will travel before scattering. From the last Lecture we know that  $\frac{C}{N} = \frac{3}{2}K_B$ . We also know an expression for the velocity  $\langle v^2 \rangle = \frac{3K_BT}{m_c}$ 

$$\implies \kappa = n \frac{3}{2} \frac{K_B^2 T}{m_e} \tau.$$

Note: we assumed  $\langle v^2 \rangle = \langle v \rangle^2$  which does not hold generally and will lead to problems later on. The question now is: how do we find  $\tau$ ?

From earlier we know  $\sigma_{Drude} = \frac{ne^2\tau}{me}$  we thus consider

Lorenz number: 
$$L_{Drude} = \frac{\kappa}{\sigma T} = \frac{3}{2} \left(\frac{K_B}{e}\right)^2 \frac{1}{T}$$
.

We call the ratio between  $\kappa$  and  $\sigma$  the Wiedeman-Franz ratio

$$\frac{\kappa}{\sigma} = \frac{3}{2} \left( \frac{K_B}{e} \right)^2.$$

The Wiedeman-Franz law states that

$$LT = \frac{\kappa}{\sigma}.$$

Thus we know that in metals thermal conductivity  $\kappa$  and electrical conductivity  $\sigma$  are proportional to each other. The interisting thing is that the Lorenz number has another definition

$$L = \frac{\pi^2 K_B^2}{3e^2} \approx 2 * L_{Drude}.$$

Even with the factor of 2 the Drude model is still a success because previously it was unexplained why the Wiedeman-Franz law even holds (previously it was only known experimentaly). The exact value of the Lorenz number given above comes from modern quantum mechanical calculations.

### 2.5 Thermoelectric Properties - how the Drude model fails

Conversion of Heat into electricity. Electrical currents always carry heat. But an electrical current is always heating the conducter via Joule heating  $I^2R$ , for use in thermoelectric devices one wants to minimize R.

 $\Delta V = S\Delta T$  with S the Seekech coefficient.

 $Q = \Pi I$  with  $\Pi$  the Peltier coefficient.

We get the relationship

$$\vec{J}_q = \Pi \vec{J}.$$

With  $\vec{J_q}$  the heat current density and  $\vec{J}$  the electrical current density. We already know:

$$\begin{split} \vec{J} &= -en\vec{v} \\ \Longrightarrow & \Pi = \frac{J_q}{J} = -\frac{1}{3}\frac{C_vT}{e} = -\frac{C_vT}{3e} = -\frac{K_BT}{2e}. \end{split}$$

There is also an expression for S the Seebeck coefficient

$$S = \frac{\Pi}{T} = -\frac{K_B}{2e} = -4.3 * 10^{-4} \frac{\text{V}}{\text{K}}.$$

But the real values of S are on the order of  $\propto 10^{-6} \frac{\rm V}{\rm K}$ . We now found a significant failure of the Drude system. But why did it work so well for the heat capacity but fails so badly for thermoelectrical effects? Drude committed two errors, that cancelled each other out in the case of the heat capacity.

- He assumed  $\langle v \rangle^2 = 3 \frac{K_B T}{m_e} \gg \text{ acctual } \langle v \rangle^2$
- He assumed  $\frac{C_v}{N} = \frac{3}{2}K_B \gg$  the acctual heat capacity

#### Success and Failures of the Drude model 2.6

#### Mean free path of $e^-$ - $\lambda$ 2.6.1

$$\lambda = < v > *\tau.$$
 
$$\sigma = \frac{ne^2\tau}{m_e} \ , \ \rho = \frac{1}{\sigma}.$$

 $\rho$  can be measured in materials and can thus be used to measure  $\tau$ .

$$\implies \tau = \frac{m_e}{ne^2 \rho} \approx 1 - 10 \text{fs}$$

$$< v > \approx \sqrt{\frac{2K_B T}{m_e}}$$

$$\implies \lambda = < v > \tau \approx 0.1 - 1 \text{nm}.$$

Close to the lattice constants in materials  $\rightarrow$  success of Drude.

#### 2.6.2Measured Values

With the Hall effect we can measure the electron density

$$n = -\frac{1}{eR_H}.$$

We can now compare the values measured electron density to the theoretical values for the electron density. We call the density of atoms in a solid  $n_a$ . For monovalent atoms (with only one atom in the valence shell) we find

$$n_a = n$$

We can infere a general quantity  $\alpha = \frac{n}{n_a}$ . For Valence  $= 1 \implies \alpha = 1$ , for valence  $V \implies \alpha = V$ . When we compare the known valence of various Metals to the theoretically measured  $\alpha$  's we find a good match for Li or Ne (with a valence of V=1), but fails for elements with V>1.

The Drude model works pretty well for monovalent atoms, but fails for higher valence atoms (sometimes even getting the sign of  $\alpha$  wrong).

Other successes:

•  $\delta T$  respects the Wiedemann-Franz law (with only an error factor of 2)

Other failures:

• Seebeck coefficient is too big (by two orders of magnitude).

## Chapter 3

# Sommerfeld Theory for free electrons in metals

The mistake of Drude, was that he applied the kinetic theory of gasses (based on Bose-Einstein statistics) to electrons. He thus implicitly assumed electrons to be bosons, but hey are fermions.

#### 3.1 Fermi-Dirac Statistics

Historical context

- 1925: Pauli exclusion principle (two  $e^-$  cannot be in the exact same state)
- 1926: Schroedinger Equation and Fermi-Dirac statistics
- 1927: Sommerfeld applies FD statistics to metals

We have to define a Fermi occupation function  $n_F(\beta(\epsilon - \mu)) = \frac{1}{\exp(\beta(\epsilon - \mu)) + 1}$ . It's the probability that the fermion occupies a state with energy  $\epsilon$ .  $\mu$  is the chemical potential, is defined by the Fermi occupation function. We use this Fermi occupation function  $n_F$  instead of the Bose-Einstein occupation function  $n_B$ .

$$n_B = \frac{g_i}{\exp\left(\frac{(\epsilon_i - \mu)}{K_B T}\right) - 1}$$
 with  $g_i$  the states degeneracy.

$$n_F = \frac{1}{\exp\left(\frac{\epsilon_i - \mu}{K_B T}\right) + 1}.$$

Fermi Statistics cannot allow for degeneracy, since fermions can *never* be in the exact same state. We have to differentiate Bosons (indistinguishable quantum particles) and Fermions (distinguishable quantum particles). Sommerfeld used FD and quantum mechanics to desciribe the electrons in a metal as a "Fermi-Gas". He does two upgrades to the Drude Model:

- calculates the energy quantum mechanically
- usese FD statistics

### 3.2 Quantum States of $e^-$ in solids

We consider a solid with regularly spaced atoms and look at the potential. The real potential is complicated so Sommerfeld made some approximations

- He neglected core electrons and considered only valence electrons.
- He replaced the true coulomb-potential with a constant, average, potential  $V_0$ .

- He ignored interactions between electrons.
- He assumes that the surface of the solid act like a barrier of height  $\infty$ .

With these approximations we can write the Schroedinger Equation in 1d:

$$\frac{\hbar^2}{2m_e} \frac{\partial^2}{\partial x^2} \psi(x) = V \psi(x)$$

Because of the assumption that the surface of the solid has a potential of  $V_{boundary} = \infty$  we get the boundary conditions

$$\psi(0) = \psi(L) = 0$$

$$\implies \psi(x) = A \sin(k_x x).$$

We get standing waves with  $k_x = \frac{2\pi}{L} n_x$  with  $n_x \in \mathbb{Z}$ . We get the Energy of a state as

$$E_n = \frac{\hbar^2 k_{x,n}^2}{2m_e} = \frac{\hbar^2 4\pi^2 n_x^2}{2m_e L}.$$

We have a discrete, quadratic potential. The energy entierly determined by the quantum number  $n_x$ . According to the Pauli exclusion principle each electron has to have unique quantum numbers. There are multiple quantum numbers, they are

- $n_x$ ,  $n_y$ , and  $n_z$
- spin number  $n_s = \pm \frac{1}{2}$

We know that if two electrons have the same energy state (given by  $\vec{n}$ ) must have opposite spin. Every value of the three energy state numbers  $(\vec{n})$  can hold two electrons (one with spin 'up' and one with spin 'down').

#### 3.3 Density of States - $q_{\omega}$

We now consider the K-space, in which only discrete values are allowed. We know that the spacing between the allowed values in the *i*-axis is given by  $\frac{2\pi}{L_i}$ , with  $L_i$  the length of the solid in the *i*-axis. The area of a discrete value in a two dimensional K-space is given by

$$A = \frac{2\pi}{L_x} \frac{2\pi}{L_y} = \frac{(2\pi)}{L_x L_y}$$

In 3d we get a volume

$$V = \frac{\left(2\pi\right)^3}{L_x L_y L_z}.$$

We consider a two dimensional system and lable the K-states

$$E = \frac{\hbar \vec{K}^2}{2m_e} = \frac{\hbar^2}{2m_e} \left( K_x^2 + K_y^2 \right) = \frac{\hbar^2 \left( 2\pi \right)^2}{2m_e} \left( \frac{n_x^2}{L_x^2} + \frac{n_y^2}{L_y^2} \right).$$

We thus have to fill the K-space from the center outwards, up to a certain maximum  $\vec{K_F}$ , that we call Fermi K-Vector. We have to choose  $\vec{K_F}$  such that we can fill the sphere in the K-space with radius  $|\vec{K_F}|$  with all of our electrons.

$$E = \frac{\hbar^2 K^2}{2m_e} \implies E_F = \frac{\hbar^2 \vec{K_F}^2}{2m_e}$$
 Fermi energy.

We thus get a sphere containing allowed energy states, we call this sphere Fermi Sphere, the maximum allowed energy in this Fermi Sphere is the Fermi Energy  $E_F = \frac{\hbar^2 \vec{K_F}^2}{2m_e}$ . No matter what dimensionality our problem has, we can define the Fermi Sphere and get the occupation probability

$$n_F = \frac{1}{\exp\left(\frac{E - E_F}{K_B T}\right) + 1}.$$

At T=0 this probability is a step-function with  $n_F=1 \forall E < E_F$  and  $n_F=0 \forall E > E_F$ . For any other temperatures the step function is 'smoothed' out and we get  $n_F=\frac{1}{2}$  at  $E=E_F$ .