
Chapter 9: Virtual Memory





Chapter 9: Virtual Memory

- Background
- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing
- Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples





Background

- Code needs to be in memory to execute, but entire program rarely used
 - Error code, unusual routines, large data structures
- Entire program code not needed at same time
- Consider ability to execute partially-loaded program
 - Program no longer constrained by limits of physical memory
 - Each program takes less memory while running -> more programs run at the same time
 - Increased CPU utilization and throughput with no increase in response time or turnaround time





Background (Cont.)

- Virtual memory separation of user logical memory from physical memory
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
 - More programs running concurrently
 - Less I/O needed to load or swap processes






Background (Cont.)

- Virtual address space logical view of how process is stored in memory
 - Usually starts at address 0, contiguous addresses until end of space
 - Meanwhile, physical memory organized in page frames
 - MMU must map logical to physical
- □ Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation





Virtual Memory That is Larger Than Physical Memory








Virtual-address Space


- Usually design logical address space for stack to start at Max logical address and grow "down" while heap grows "up"
 - Maximizes address space use
 - Unused address space between the two is hole
- Enables sparse address spaces with holes left for growth, dynamically linked libraries, etc
- System libraries shared via mapping into virtual address space
- Shared memory by mapping pages readwrite into virtual address space
- Pages can be shared during fork(), speeding process creation







Shared Library Using Virtual Memory








Demand Paging

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
 - Less I/O needed, no unnecessary I/O
 - Less memory needed
 - Faster response
 - More users
- Similar to paging system with swapping (diagram on right)
- □ Page is needed ⇒ reference to it
 - invalid reference ⇒ abort
 - □ not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
 - Swapper that deals with pages is a pager







Basic Concepts

- With swapping, pager guesses which pages will be used before swapping out again
- Instead, pager brings in only those pages into memory
- How to determine that set of pages?
 - Need new MMU functionality to implement demand paging
- □ If pages needed are already memory resident
 - No difference from non demand-paging
- If page needed and not memory resident
 - Need to detect and load the page into memory from storage
 - Without changing program behavior
 - Without programmer needing to change code





Valid-Invalid Bit

- With each page table entry a valid—invalid bit is associated $(\mathbf{v} \Rightarrow \text{in-memory} - \text{memory} \text{resident}, \mathbf{i} \Rightarrow \text{not-in-memory})$
- Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:


Frame #	valid-	<u>i</u> nvalid bit
]
	V	
	V	
	V	
	i	


	i	
	i]
page tab	le	_

During MMU address translation, if valid—invalid bit in page table entry is $i \Rightarrow$ page fault




Page Table When Some Pages Are Not in Main Memory









Page Fault

If there is a reference to a page, first reference to that page will trap to operating system:


page fault

- 1. Operating system looks at another table to decide:
 - □ Invalid reference ⇒ abort
 - Just not in memory
- 2. Find free frame
- 3. Swap page into frame via scheduled disk operation
- Reset tables to indicate page now in memory Set validation bit = v
- 5. Restart the instruction that caused the page fault





Steps in Handling a Page Fault







Aspects of Demand Paging

- Extreme case start process with no pages in memory
 - OS sets instruction pointer to first instruction of process, nonmemory-resident -> page fault
 - And for every other process pages on first access
 - Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
 - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
 - Pain decreased because of locality of reference
- Hardware support needed for demand paging
 - Page table with valid / invalid bit
 - Secondary memory (swap device with swap space)
 - Instruction restart





Performance of Demand Paging

- Stages in Demand Paging (worse case)
- 1. Trap to the operating system
- 2. Save registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
 - 1. Wait in a queue for this device until the read request is serviced
 - Wait for the device seek and/or latency time
 - 3. Begin the transfer of the page to a free frame
- 6. CPU is allocated to some other process
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other process
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show that page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- Restore registers, process state, and new page table, and then resume the interrupted instruction



Performance of Demand Paging (Cont.)

- Three major activities
 - Service the interrupt careful coding means just several hundred instructions needed
 - □ Read the page lots of time
 - Restart the process again just a small amount of time
- □ Page Fault Rate $0 \le p \le 1$

 - \square if p = 1, every reference is a fault
- □ Effective Access Time (EAT)

EAT =
$$(1 - p)$$
 x memory access
+ p (page fault overhead
+ swap page out
+ swap page in)





Demand Paging Example

- ☐ Memory access time = 200 nanoseconds
- □ Average page-fault service time = 8 milliseconds

□ EAT =
$$(1 - p) \times 200 + p$$
 (8 milliseconds)
= $(1 - p \times 200 + p \times 8,000,000$
= $200 + p \times 7,999,800$

☐ If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!

- ☐ If want performance degradation < 10 percent
 - 220 > 200 + 7,999,800 x p20 > 7,999,800 x p
 - □ p < .0000025
 - < one page fault in every 400,000 memory accesses</p>





What Happens if There is no Free Frame?

- Used up by process pages
- □ Also in demand from the kernel, I/O buffers, etc
- How much to allocate to each?
- Page replacement find some page in memory, but not really in use, page it out
 - Algorithm terminate? swap out? replace the page?
 - Performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times






Page Replacement


- Prevent over-allocation of memory by modifying pagefault service routine to include page replacement
- ☐ Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory







Need For Page Replacement













Basic Page Replacement

- 1. Find the location of the desired page on disk
- 2. Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a victim frame
 - Write victim frame to disk if dirty
- Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Continue the process by restarting the instruction that caused the trap

Note now potentially 2 page transfers for page fault – increasing EAT






Page and Frame Replacement Algorithms


- □ Frame-allocation algorithm determines
 - How many frames to give each process
 - Which frames to replace
- □ Page-replacement algorithm
 - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
 - String is just page numbers, not full addresses
 - Repeated access to the same page does not cause a page fault
 - Results depend on number of frames available
- In all our examples, the reference string of referenced page numbers is

7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1






Graph of Page Faults Versus The Number of Frames







First-In-First-Out (FIFO) Algorithm

- Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- □ 3 frames (3 pages can be in memory at a time per process)


15 page faults





Least Recently Used (LRU) Algorithm

- Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Associate time of last use with each page



□ 12 faults – better than FIFO Generally good algorithm and frequently used



Allocation of Frames

- Each process needs *minimum* number of frames
- Maximum of course is total frames in the system
- Two major allocation schemes
 - fixed allocation
 - priority allocation
- Many variations





Fixed Allocation

- Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process
 20 frames
 - Keep some as free frame buffer pool
- □ Proportional allocation Allocate according to the size of process
 - Dynamic as degree of multiprogramming, process sizes change m = 64

$$-s_i = \text{size of process } p_i$$

$$-S = \sum s_i$$

$$-m = total number of frames$$

$$-a_i = \text{allocation for } p_i = \frac{s_i}{s} \times m$$

$$m = 64$$

$$s_1 = 10$$

$$s_2 = 127$$

$$a_1 = \frac{10}{137} \cdot 62 \gg 4$$

$$a_2 = \frac{127}{137} \cdot 62 \gg 57$$



Priority Allocation

- Use a proportional allocation scheme using priorities rather than size
- □ If process P_i generates a page fault,
 - select for replacement one of its frames
 - select for replacement a frame from a process with lower priority number





Global vs. Local Allocation

- ☐ Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
 - But then process execution time can vary greatly
 - But greater throughput so more common
- Local replacement each process selects from only its own set of allocated frames
 - More consistent per-process performance
 - But possibly underutilized memory






Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high
 - Page fault to get page
 - Replace existing frame
 - But quickly need replaced frame back
 - This leads to:
 - Low CPU utilization
 - Operating system thinking that it needs to increase the degree of multiprogramming
 - Another process added to the system
- □ Thrashing = a process is busy swapping pages in and out





Thrashing (Cont.)








Demand Paging and Thrashing

- Why does demand paging work?
 Locality model
 - Process migrates from one locality to another
 - Localities may overlap
- Why does thrashing occur?Σ size of locality > total memory size
 - Limit effects by using local or priority page replacement





Locality In A Memory-Reference Pattern









Working-Set Model

- Δ = working-set window = a fixed number of page references Example: 10,000 instructions
- □ WSS_i (working set of Process P_i) = total number of pages referenced in the most recent Δ (varies in time)
 - \square if \triangle too small will not encompass entire locality
 - \square if \triangle too large will encompass several localities
 - if $\Delta = \infty \Rightarrow$ will encompass entire program
- $D = \Sigma WSS_i \equiv \text{total demand frames}$
 - Approximation of locality
- □ if $D > m \Rightarrow$ Thrashing
- Policy if D > m, then suspend or swap out one of the processes page reference table

... 2615777751623412344434344413234443444...









Allocating Kernel Memory

- Treated differently from user memory
- Often allocated from a free-memory pool
 - Kernel requests memory for structures of varying sizes
 - Some kernel memory needs to be contiguous
 - ▶ I.e. for device I/O






Buddy System

- Allocates memory from fixed-size segment consisting of physicallycontiguous pages
- Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - Request rounded up to next highest power of 2
 - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - Continue until appropriate sized chunk available
- For example, assume 256KB chunk available, kernel requests 21KB
 - □ Split into A_{L and} A_R of 128KB each
 - One further divided into B_L and B_R of 64KB
 - One further into C_L and C_R of 32KB each one used to satisfy request
- □ Advantage quickly **coalesce** unused chunks into larger chunk
- □ Disadvantage fragmentation



Buddy System Allocator

physically contiguous pages








Slab Allocator

- Alternate strategy
- Slab is one or more physically contiguous pages
- Cache consists of one or more slabs
- Single cache for each unique kernel data structure
 - Each cache filled with objects instantiations of the data structure
- When cache created, filled with objects marked as free
- When structures stored, objects marked as used
- If slab is full of used objects, next object allocated from empty slab
 - If no empty slabs, new slab allocated
- Benefits include no fragmentation, fast memory request satisfaction






Slab Allocation







Slab Allocator in Linux

- For example process descriptor is of type struct task_struct
- □ Approx 1.7KB of memory
- New task -> allocate new struct from cache
 - Will use existing free struct task_struct
- Slab can be in three possible states
 - 1. Full all used
 - 2. Empty all free
 - 3. Partial mix of free and used
- Upon request, slab allocator
 - 1. Uses free struct in partial slab
 - 2. If none, takes one from empty slab
 - 3. If no empty slab, create new empty





Slab Allocator in Linux (Cont.)

- Slab started in Solaris, now wide-spread for both kernel mode and user memory in various OSes
- ☐ Linux 2.2 had SLAB, now has both SLOB and SLUB allocators
 - SLOB for systems with limited memory
 - Simple List of Blocks maintains 3 list objects for small, medium, large objects
 - SLUB is performance-optimized SLAB removes per-CPU queues, metadata stored in page structure



End of Chapter 9

