Sage Reference Manual: Probability Release 6.6

The Sage Development Team

CONTENTS

1	Probability Distributions	1
2	Random variables and probability spaces	11
3	Indices and Tables	15

PROBABILITY DISTRIBUTIONS

This module provides three types of probability distributions:

- RealDistribution: various real-valued probability distributions.
- SphericalDistribution: uniformly distributed points on the surface of an n-1 sphere in n dimensional euclidean space.
- GeneralDiscreteDistribution: user-defined discrete distributions.

AUTHORS:

- Josh Kantor (2007-02): first version
- William Stein (2007-02): rewrite of docs, conventions, etc.
- Carlo Hamalainen (2008-08): full doctest coverage, more documentation, GeneralDiscreteDistribution, misc fixes.
- Kwankyu Lee (2010-05-29): F-distribution support.

REFERENCES:

GNU gsl library, General discrete distributions http://www.gnu.org/software/gsl/manual/html_node/General-Discrete-Distributions.html

GNU gsl library, Random number distributions http://www.gnu.org/software/gsl/manual/html_node/Random-Number-Distributions.html

class sage.gsl.probability_distribution.GeneralDiscreteDistribution
 Bases: sage.gsl.probability_distribution.ProbabilityDistribution

Create a discrete probability distribution.

INPUT:

- •P list of probabilities. The list will automatically be normalised if sum (P) is not equal to 1.
- •rng (optional) random number generator to use. May be one of 'default', 'luxury', or 'taus'.
- •seed (optional) seed to use with the random number generator.

OUTPUT:

•a probability distribution where the probability of selecting x is P[x].

EXAMPLES:

Constructs a General Discrete Distribution with the probability distribution

```
where
                                       P(0) = 0.3
                                        P(1) = 0.4
                                        P(2) = 0.3
sage: P = [0.3, 0.4, 0.3]
sage: X = GeneralDiscreteDistribution(P)
sage: X.get_random_element()
Checking the distribution of samples:
sage: P = [0.3, 0.4, 0.3]
sage: counts = [0] * len(P)
sage: X = GeneralDiscreteDistribution(P)
sage: nr_samples = 10000
sage: for _ in range(nr_samples):
         counts[X.get_random_element()] += 1
sage: [1.0*x/nr_samples for x in counts]
[0.30420000000000, 0.3973000000000, 0.29850000000000]
The distribution probabilities will automatically be normalised:
sage: P = [0.1, 0.3]
sage: X = GeneralDiscreteDistribution(P, seed = 0)
sage: counts = [0, 0]
sage: for _ in range(10000):
         counts[X.get_random_element()] += 1
sage: float(counts[1]/counts[0])
3.042037186742118
TESTS:
Make sure that repeated initializations are randomly seeded (trac ticket #9770):
sage: P = [0.001] * 1000
sage: Xs = [GeneralDiscreteDistribution(P).get_random_element() for _ in range(1000)]
sage: len(set(Xs)) > 2^{32}
True
The distribution probabilities must be non-negative:
sage: GeneralDiscreteDistribution([0.1, -0.1])
Traceback (most recent call last):
ValueError: The distribution probabilities must be non-negative
get_random_element()
    Get a random sample from the probability distribution.
    EXAMPLE:
    sage: P = [0.3, 0.4, 0.3]
    sage: X = GeneralDiscreteDistribution(P)
    sage: [X.get_random_element() for _ in range(10)]
    [1, 0, 1, 1, 0, 1, 1, 1, 1, 1]
```

```
sage: isinstance(X.get_random_element(), sage.rings.integer.Integer)
         True
     reset_distribution()
         This method resets the distribution.
         EXAMPLE:
         sage: T = GeneralDiscreteDistribution([0.1, 0.3, 0.6])
         sage: T.set_seed(0)
         sage: [T.get_random_element() for _ in range(10)]
         [2, 2, 2, 2, 1, 2, 2, 1, 2]
         sage: T.reset_distribution()
         sage: [T.get_random_element() for _ in range(10)]
         [2, 2, 2, 2, 2, 1, 2, 2, 1, 2]
     set_random_number_generator(rng='default')
         Set the random number generator to be used by gsl.
         EXAMPLE:
         sage: X = GeneralDiscreteDistribution([0.3, 0.4, 0.3])
         sage: X.set_random_number_generator('taus')
     set seed (seed)
         Set the seed to be used by the random number generator.
         EXAMPLE:
         sage: X = GeneralDiscreteDistribution([0.3, 0.4, 0.3])
         sage: X.set_seed(1)
         sage: X.get_random_element()
class sage.gsl.probability_distribution.ProbabilityDistribution
     Bases: object
     Concrete probability distributions should be derived from this abstract class.
     generate histogram data(num samples=1000, bins=50)
         Compute a histogram of the probability distribution.
         INPUT:
            •num_samples - (optional) number of times to sample from the probability distribution
            •bins - (optional) number of bins to divide the samples into.
         OUTPUT:
            •a tuple. The first element of the tuple is a list of length bins, consisting of the normalised histogram
             of the random samples. The second list is the bins.
         EXAMPLE:
         sage: from sage.gsl.probability_distribution import GeneralDiscreteDistribution
         sage: P = [0.3, 0.4, 0.3]
         sage: X = GeneralDiscreteDistribution(P)
         sage: h, b = X.generate_histogram_data(bins = 10)
         sage: h
         [1.6299999999999999999999]
          0.0,
          0.0,
```

```
0.0,
0.0,
1.9049999999999985,
0.0,
0.0,
0.0,
1.46500000000000031
sage: b
Save the histogram from generate_histogram_data() to a file.
```

generate_histogram_plot (name, num_samples=1000, bins=50)

INPUT:

- •name file to save the histogram plot (as a PNG).
- •num_samples (optional) number of times to sample from the probability distribution
- •bins (optional) number of bins to divide the samples into.

EXAMPLE:

This saves the histogram plot to my_general_distribution_plot.png in the temporary directory SAGE_TMP:

```
sage: from sage.gsl.probability_distribution import GeneralDiscreteDistribution
sage: import os
sage: P = [0.3, 0.4, 0.3]
sage: X = GeneralDiscreteDistribution(P)
sage: file = os.path.join(SAGE_TMP, "my_general_distribution_plot")
sage: X.generate_histogram_plot(file)
```

get random element()

To be implemented by a derived class:

```
sage: P = sage.gsl.probability_distribution.ProbabilityDistribution()
sage: P.get_random_element()
Traceback (most recent call last):
NotImplementedError: implement in derived class
```

class sage.gsl.probability_distribution.RealDistribution

```
Bases: sage.gsl.probability_distribution.ProbabilityDistribution
```

The RealDistribution class provides a number of routines for sampling from and analyzing and visualizing probability distributions. For precise definitions of the distributions and their parameters see the gsl reference manuals chapter on random number generators and probability distributions.

EXAMPLES:

Uniform distribution on the interval [a, b]:

```
sage: a = 0
sage: b = 2
sage: T = RealDistribution('uniform', [a, b])
sage: T.get_random_element()
0.8175557665526867
sage: T.distribution function(0)
sage: T.cum_distribution_function(1)
0.5
```

```
sage: T.cum_distribution_function_inv(.5)
1.0
The gaussian distribution takes 1 parameter sigma. The standard gaussian distribution has sigma = 1:
sage: sigma = 1
sage: T = RealDistribution('gaussian', sigma)
sage: T.get_random_element()
-0.5860943109756299
sage: T.distribution_function(0)
0.3989422804014327
sage: T.cum_distribution_function(1)
0.8413447460685429
sage: T.cum_distribution_function_inv(.5)
0.0
The rayleigh distribution has 1 parameter sigma:
sage: sigma = 3
sage: T = RealDistribution('rayleigh', sigma)
sage: T.get_random_element()
5.748307572643492
sage: T.distribution_function(0)
0.0
sage: T.cum_distribution_function(1)
0.054040531093234534
sage: T.cum_distribution_function_inv(.5)
3.532230067546424
The lognormal distribution has two parameters sigma and zeta:
sage: zeta = 0
sage: sigma = 1
sage: T = RealDistribution('lognormal', [zeta, sigma])
sage: T.get_random_element()
0.3876433713532701
sage: T.distribution_function(0)
sage: T.cum_distribution_function(1)
sage: T.cum_distribution_function_inv(.5)
1.0
The pareto distribution has two parameters a, and b:
sage: a = 1
sage: b = 1
sage: T = RealDistribution('pareto', [a, b])
sage: T.get_random_element()
10.418714048916407
sage: T.distribution_function(0)
0.0
sage: T.cum_distribution_function(1)
0.0
sage: T.cum_distribution_function_inv(.5)
2.0
```

The t-distribution has one parameter nu:

```
sage: nu = 1
sage: T = RealDistribution('t', nu)
sage: T.get_random_element() # rel tol 1e-15
-8.404911172800615
sage: T.distribution_function(0)
                                      # rel tol 1e-15
0.3183098861837906
sage: T.cum_distribution_function(1) # rel tol 1e-15
0.75
sage: T.cum_distribution_function_inv(.5)
0.0
The F-distribution has two parameters nu1 and nu2:
sage: nu1 = 9; nu2 = 17
sage: F = RealDistribution('F', [nu1, nu2])
sage: F.get_random_element() # rel tol 1e-14
1.239233786115256
sage: F.distribution_function(1) # rel tol 1e-14
0.6695025505192798
sage: F.cum_distribution_function(3.68) # rel tol 1e-14
0.9899717772300652
sage: F.cum_distribution_function_inv(0.99) # rel tol 1e-14
3.682241524045864
The chi-squared distribution has one parameter nu:
sage: nu = 1
sage: T = RealDistribution('chisquared', nu)
sage: T.get_random_element()
0.4603367753992381
sage: T.distribution_function(0)
+infinity
sage: T.cum_distribution_function(1) # rel tol 1e-14
0.6826894921370856
sage: T.cum_distribution_function_inv(.5) # rel tol 1e-14
0.45493642311957305
The exponential power distribution has two parameters a and b:
sage: a = 1
sage: b = 2.5
sage: T = RealDistribution('exppow', [a, b])
sage: T.get_random_element()
0.16442075306686463
sage: T.distribution_function(0) # rel tol 1e-14
0.5635302489930136
sage: T.cum_distribution_function(1) # rel tol 1e-14
0.940263052542855
The beta distribution has two parameters a and b:
sage: a = 2
sage: b = 2
sage: T = RealDistribution('beta', [a, b])
sage: T.get_random_element() # rel tol 1e-14
0.7110581877139808
sage: T.distribution_function(0)
0.0
sage: T.cum_distribution_function(1)
1.0
```

The weibull distribution has two parameters a and b:

```
sage: a = 1
sage: b = 1
sage: T = RealDistribution('weibull', [a, b])
sage: T.get_random_element()
1.1867854542468694
sage: T.distribution_function(0)
1.0
sage: T.cum_distribution_function(1)
0.6321205588285577
sage: T.cum_distribution_function_inv(.5)
0.6931471805599453
```

It is possible to select which random number generator drives the sampling as well as the seed. The default is the Mersenne twister. Also available are the RANDLXS algorithm and the Tausworthe generator (see the gsl reference manual for more details). These are all supposed to be simulation quality generators. For RANDLXS

```
use rng = 'luxury' and for tausworth use rng = 'taus':
sage: T = RealDistribution('gaussian', 1, rng = 'luxury', seed = 10)
```

To change the seed at a later time use set_seed:

```
sage: T.set_seed(100)
```

TESTS:

Make sure that repeated initializations are randomly seeded (trac ticket #9770):

```
sage: Xs = [RealDistribution('gaussian', 1).get_random_element() for _ in range(1000)]
sage: len(set(Xs)) > 2^32
True
```

cum_distribution_function(x)

Evaluate the cumulative distribution function of the probability distribution at x.

EXAMPLE:

```
sage: T = RealDistribution('uniform', [0, 2])
sage: T.cum_distribution_function(1)
0.5
```

cum_distribution_function_inv(x)

Evaluate the inverse of the cumulative distribution distribution function of the probability distribution at x.

EXAMPLE:

```
sage: T = RealDistribution('uniform', [0, 2])
sage: T.cum_distribution_function_inv(.5)
1.0
```

distribution_function(x)

Evaluate the distribution function of the probability distribution at x.

EXAMPLES:

```
sage: T = RealDistribution('uniform', [0, 2])
sage: T.distribution_function(0)
0.5
sage: T.distribution_function(1)
0.5
```

```
sage: T.distribution_function(1.5)
    0.5
    sage: T.distribution_function(2)
    0.0
get_random_element()
    Get a random sample from the probability distribution.
    EXAMPLE:
    sage: T = RealDistribution('gaussian', 1, seed = 0)
    sage: T.get_random_element() # rel tol 4e-16
    0.13391860811867587
plot (*args, **kwds)
    Plot the distribution function
                                 for the probability
                                                      distribution.
                                                                       Parameters
                                                                                 to
    sage.plot.plot.plot.plot can be passed through *args and **kwds.
    EXAMPLE:
    sage: T = RealDistribution('uniform', [0, 2])
    sage: P = T.plot()
reset distribution()
    This method resets the distribution.
    EXAMPLE:
    sage: T = RealDistribution('gaussian', 1, seed = 10)
    sage: [T.get_random_element() for _ in range(10)] # rel tol 4e-16
    [-0.7460999595745819, -0.004644606626413462, -0.8720538317207641, 0.6916259921666037, 2.676693166099959574581]
    sage: T.reset_distribution()
    sage: [T.get_random_element() for _ in range(10)] # rel tol 4e-16
    set_distribution (name='uniform', parameters=| |)
    This method can be called to change the current probability distribution.
    EXAMPLES:
    sage: T = RealDistribution('gaussian', 1)
    sage: T.set_distribution('gaussian', 1)
    sage: T.set_distribution('pareto', [0, 1])
set_random_number_generator(rng='default')
    Set the gsl random number generator to be one of default, luxury, or taus.
    EXAMPLE:
    sage: T = SphericalDistribution()
    sage: T.set_random_number_generator('default')
    sage: T.set_seed(0)
    sage: T.get_random_element() # rel tol 4e-16
    (0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
    sage: T.set_random_number_generator('luxury')
    sage: T.set_seed(0)
    sage: T.get_random_element() # rel tol 4e-16
    (0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
```

 $set_seed(seed)$

Set the seed for the underlying random number generator.

EXAMPLE:

```
sage: T = RealDistribution('gaussian', 1, rng = 'luxury', seed = 10)
sage: T.set_seed(100)
```

class sage.gsl.probability_distribution.SphericalDistribution

```
Bases: sage.gsl.probability_distribution.ProbabilityDistribution
```

This class is capable of producing random points uniformly distributed on the surface of an n-1 sphere in n dimensional euclidean space. The dimension, n is selected via the keyword dimension. The random number generator which drives it can be selected using the keyword rng. Valid choices are default which uses the Mersenne-Twister, luxury which uses RANDLXS, and taus which uses the tausworth generator. The default dimension is 3.

EXAMPLES:

```
sage: T = SphericalDistribution()
sage: T.get_random_element() # rel tol 1e-14
(-0.2922296724828204, -0.9563459345927822, 0.0020668595602153454)
sage: T = SphericalDistribution(dimension = 4, rng = 'luxury')
sage: T.get_random_element() # rel tol 1e-14
(-0.0363300434761631, 0.6459885817544098, 0.24825817345598158, 0.7209346430129753)
```

TESTS:

Make sure that repeated initializations are randomly seeded (trac ticket #9770):

```
sage: Xs = [tuple(SphericalDistribution(2).get_random_element()) for _ in range(1000)]
sage: len(set(Xs)) > 2^{32}
True
```

get_random_element()

Get a random sample from the probability distribution.

EXAMPLE:

```
sage: T = SphericalDistribution(seed = 0)
sage: T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
```

reset_distribution()

This method resets the distribution.

EXAMPLE

```
sage: T = SphericalDistribution(seed = 0)
sage: [T.get_random_element() for _ in range(4)] # rel tol 4e-16
[(0.07961564104639995, -0.05237671627581255, 0.9954486572862178), (0.4123599490593727, 0.560
sage: T.reset_distribution()
sage: [T.get_random_element() for _ in range(4)] # rel tol 4e-16
[(0.07961564104639995, -0.05237671627581255, 0.9954486572862178), (0.4123599490593727, 0.560)
```

set_random_number_generator(rng='default')

Set the gsl random number generator to be one of default, luxury, or taus.

EXAMPLE:

```
sage: T = SphericalDistribution()
sage: T.set_random_number_generator('default')
sage: T.set_seed(0)
sage: T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
sage: T.set_random_number_generator('luxury')
```

```
sage: T.set_seed(0)
sage: T.get_random_element() # rel tol 4e-16
(0.07961564104639995, -0.05237671627581255, 0.9954486572862178)
```

set_seed(seed)

Set the seed for the underlying random number generator.

EXAMPLE:

```
sage: T = SphericalDistribution(seed = 0)
sage: T.set_seed(100)
```

RANDOM VARIABLES AND PROBABILITY SPACES

This introduces a class of random variables, with the focus on discrete random variables (i.e. on a discrete probability space). This avoids the problem of defining a measure space and measurable functions.

coaomain=None check=False)

Bases: sage.probability.random_variable.ProbabilitySpace_generic, sage.probability.random_variable.DiscreteRandomVariable

The discrete probability space

entropy()

The entropy of the probability space.

set()

The set of values of the probability space taking possibly nonzero probability (a subset of the domain).

 ${\bf class} \ {\tt sage.probability.random_variable.DiscreteRandomVariable} \ (X, \\ f,$

codomain=None,

check=False)
Bases: sage.probability.random variable.RandomVariable generic

A random variable on a discrete probability space.

correlation(other)

The correlation of the probability space X = self with Y = other.

covariance (other)

The covariance of the discrete random variable X = self with Y = other.

Let S be the probability space of X = self, with probability function p, and E(X) be the expectation of X. Then the variance of X is:

$$\mathrm{cov}(X,Y) = E((X - E(X) * (Y - E(Y)) = \sum_{x \in S} p(x)(X(x) - E(X))(Y(x) - E(Y))$$

expectation()

The expectation of the discrete random variable, namely $\sum_{x \in S} p(x)X[x]$, where X = self and S is the probability space of X.

function()

The function defining the random variable.

standard_deviation()

The standard deviation of the discrete random variable.

Let S be the probability space of X = self, with probability function p, and E(X) be the expectation of X. Then the standard deviation of X is defined to be

$$\sigma(X) = \sqrt{\sum_{x \in S} p(x)(X(x) - E(x)) **2}$$

translation correlation (other, map)

The correlation of the probability space X = self with image of Y = other under map.

translation_covariance(other, map)

The covariance of the probability space X = self with image of Y = other under the given map of the probability space.

Let S be the probability space of X = self, with probability function p, and E(X) be the expectation of X. Then the variance of X is:

$$\mathrm{cov}(X,Y) = E((X - E(X) * (Y - E(Y)) = \sum_{x \in S} p(x)(X(x) - E(X))(Y(x) - E(Y))$$

translation_expectation(map)

The expectation of the discrete random variable, namely $\sum_{x \in S} p(x) X[e(x)]$, where X = self, S is the probability space of X, and e = map.

translation_standard_deviation(map)

The standard deviation of the translated discrete random variable $X \circ e$, where X = self and e = map.

Let S be the probability space of X = self, with probability function p, and E(X) be the expectation of X. Then the standard deviation of X is defined to be

$$\sigma(X) = \sqrt{\sum_{x \in S} p(x)(X(x) - E(x)) **2}$$

translation_variance (map)

The variance of the discrete random variable $X \circ e$, where X = self, and e = map.

Let S be the probability space of X = self, with probability function p, and E(X) be the expectation of X. Then the variance of X is:

$$var(X) = E((X - E(x))^{2}) = \sum_{x \in S} p(x)(X(x) - E(x))^{2}$$

variance()

The variance of the discrete random variable.

Let S be the probability space of X = self, with probability function p, and E(X) be the expectation of X. Then the variance of X is:

$$var(X) = E((X - E(x))^{2}) = \sum_{x \in S} p(x)(X(x) - E(x))^{2}$$

class sage.probability.random_variable.ProbabilitySpace_generic (domain, RR)

Bases: sage.probability.random_variable.RandomVariable_generic

A probability space.

domain()

x.__init__(...) initializes x; see help(type(x)) for signature

```
class sage.probability.random_variable.RandomVariable_generic(X, RR)
     Bases: sage.structure.parent_base.ParentWithBase
     A random variable.
     codomain()
          x.__init__(...) initializes x; see help(type(x)) for signature
     domain()
          x.__init__(...) initializes x; see help(type(x)) for signature
     field()
          x.__init__(...) initializes x; see help(type(x)) for signature
     probability_space()
          x__init__(...) initializes x; see help(type(x)) for signature
sage.probability.random\_variable.is\_DiscreteProbabilitySpace(S)
     x.__init__(...) initializes x; see help(type(x)) for signature
sage.probability.random_variable.is_DiscreteRandomVariable(X)
     x.__init__(...) initializes x; see help(type(x)) for signature
sage.probability.random_variable.is_ProbabilitySpace(S)
     x.__init__(...) initializes x; see help(type(x)) for signature
sage.probability.random_variable.is_RandomVariable(X)
     x. init (...) initializes x; see help(type(x)) for signature
```

Sage Reference Manual: Probability, Release 6.6								

CHAPTER

THREE

INDICES AND TABLES

- Index
- Module Index
- Search Page

PYTHON MODULE INDEX

```
g
sage.gsl.probability_distribution, 1
p
sage.probability.random_variable, 11
```

18 Python Module Index

C codomain() (sage.probability.random variable.RandomVariable generic method), 13 correlation() (sage.probability.random_variable.DiscreteRandomVariable method), 11 covariance() (sage.probability.random_variable.DiscreteRandomVariable method), 11 cum distribution function() (sage.gsl.probability distribution.RealDistribution method), 7 cum_distribution_function_inv() (sage.gsl.probability_distribution.RealDistribution method), 7 D DiscreteProbabilitySpace (class in sage.probability.random_variable), 11 DiscreteRandomVariable (class in sage.probability.random_variable), 11 distribution_function() (sage.gsl.probability_distribution.RealDistribution method), 7 domain() (sage.probability.random_variable.ProbabilitySpace_generic method), 12 domain() (sage.probability.random variable.RandomVariable generic method), 13 Ε entropy() (sage.probability.random_variable.DiscreteProbabilitySpace method), 11 expectation() (sage.probability.random_variable.DiscreteRandomVariable method), 11 F field() (sage.probability.random_variable.RandomVariable_generic method), 13 function() (sage.probability.random_variable.DiscreteRandomVariable method), 11 G GeneralDiscreteDistribution (class in sage.gsl.probability_distribution), 1 generate_histogram_data() (sage.gsl.probability_distribution.ProbabilityDistribution method), 3 generate_histogram_plot() (sage.gsl.probability_distribution.ProbabilityDistribution method), 4 get_random_element() (sage.gsl.probability_distribution.GeneralDiscreteDistribution method), 2 get_random_element() (sage.gsl.probability_distribution.ProbabilityDistribution method), 4 get_random_element() (sage.gsl.probability_distribution.RealDistribution method), 8 get random element() (sage.gsl.probability distribution.SphericalDistribution method), 9 is_DiscreteProbabilitySpace() (in module sage.probability.random_variable), 13 is_DiscreteRandomVariable() (in module sage.probability.random_variable), 13 is ProbabilitySpace() (in module sage.probability.random variable), 13 is RandomVariable() (in module sage.probability.random variable), 13

plot() (sage.gsl.probability_distribution.RealDistribution method), 8 probability_space() (sage.probability.random_variable.RandomVariable_generic method), 13 ProbabilityDistribution (class in sage.gsl.probability_distribution), 3 ProbabilitySpace_generic (class in sage.probability.random_variable), 12 R RandomVariable_generic (class in sage.probability_random_variable), 12 RealDistribution (class in sage.gsl.probability_distribution), 4 reset_distribution() (sage.gsl.probability_distribution.GeneralDiscreteDistribution method), 3 reset_distribution() (sage.gsl.probability_distribution.RealDistribution method), 8 reset_distribution() (sage.gsl.probability_distribution.SphericalDistribution method), 9 S sage.gsl.probability_distribution (module), 1 sage.probability_distribution_variable (module), 11 set() (sage.probability.random_variable.DiscreteProbabilitySpace method), 11

sage.probability.random_variable (module), 11
set() (sage.probability.random_variable.DiscreteProbabilitySpace method), 11
set_distribution() (sage.gsl.probability_distribution.RealDistribution method), 8
set_random_number_generator() (sage.gsl.probability_distribution.RealDistribution method), 3
set_random_number_generator() (sage.gsl.probability_distribution.RealDistribution method), 8
set_random_number_generator() (sage.gsl.probability_distribution.SphericalDistribution method), 9
set_seed() (sage.gsl.probability_distribution.GeneralDiscreteDistribution method), 3
set_seed() (sage.gsl.probability_distribution.RealDistribution method), 8
set_seed() (sage.gsl.probability_distribution.SphericalDistribution method), 10
SphericalDistribution (class in sage.gsl.probability_distribution), 9
standard_deviation() (sage.probability.random_variable.DiscreteRandomVariable method), 11

Т

translation_correlation() (sage.probability.random_variable.DiscreteRandomVariable method), 12 translation_covariance() (sage.probability.random_variable.DiscreteRandomVariable method), 12 translation_expectation() (sage.probability.random_variable.DiscreteRandomVariable method), 12 translation_standard_deviation() (sage.probability.random_variable.DiscreteRandomVariable method), 12 translation_variance() (sage.probability.random_variable.DiscreteRandomVariable method), 12

V

variance() (sage.probability.random_variable.DiscreteRandomVariable method), 12

20 Index