Lecture 7 Paging

Prof. Yinqian Zhang

Spring 2023

Outline

- Introduction to paging
- Multi-level page tables
- Other page table structures
- Real-world paging schemes
- Translation lookaside buffer


Introduction to Paging

Recall: Problems with Segmentation

- OS context switch must also save and restore all pairs of segment registers
- A segment may grow, which may or may not be possible
- Management of free spaces of physical memory with variablesized segments
- External fragmentation: gaps between allocated segments
 - Segmentation may also have internal fragmentation if more space allocated than needed.


Solutions for Segmentation

- OS context switch must also save and restore all pairs of segment registers
 - Table of base/bounds stored in memory rather than registers
 - Pointer to the table stored in a register
 - Cons: one more memory read per address translation




Solutions for Segmentation (Cont'd)

 A segment may grow, which may or may not be possible




Solutions for Segmentation (Cont'd)

- A segment may grow, which may or may not be possible
 - Virtually continuous memory can be physically discontinuous



Solutions for Segmentation (Cont'd)

- Management of free spaces of physical memory with variable-sized segments
 - Fixed-sized segments
 - Physical memory curved into fixed sized chunks, index by an integer
 - Can use simple vector of bits to handle allocation (1-allocated, 0-free) 110110101101010110
- External fragmentation
 - Fixed-sized segments
 - Each request is of the same fixed size always fit, no external fragmentation



Paging: Put All These Ideas Together


- Physical memory conceptually divided into fixed size
 - Each is called a page frame
 - Typical size 1KB to 16KB, most ISA uses 4KB
- Virtual address space conceptually divided into the same size
 - Each is called a page
- Page mapped to page frame
 One to one mapping
 Many to one mapping -> memory sharing
- One page table per processResides in physical memory

 - One entry for one virtual->physical translation


How big is one page (frame)?

- Too big -> internal fragmentation
- Too small -> page table too big


Paging Illustrated




Virtual Address = Virtual Page Number || Offset




Physical Address = Physical Page Number || Offset




Paging Illustrated (Cont'd)





Paging Illustrated (Cont'd)




Memory Sharing with Paging









Virtual Address and Paging

- Length of virtual address determines size of address space
- Length of offset determines size of a page/page frame
- In case of m-bit virtual address and k-bit offset
 - Size of address space: 2^m
 - Size of a page: 2^k
 - e.g., 32-bit virtual address, 4KB page: m = 32, k = 12

	m	k+1	k		
	VPN			Offset	
Virtual	Address				


Page #	Page Frame #				
0	PFN				
1	PFN				
2	PFN				
•••	••••				
2^{m-k} -1	PFN				

Page Table Entry

- An entry in the page table is called a page table entry (PTE).
- Besides PFN, PTE also contains a valid bit
 - Virtual pages with no valid mapping: valid bit = 0
 - Important for sparse address space (e.g., 2⁶⁴ bytes)
- PTE also contains protection bits
 - Permission to read from or write, or execute code on this page
- PTE also contains an access bit, a dirty bit, a present bit
 - Present bit: whether this page is in physical memory or on disk
 - Dirty bit: whether the page has been modified since it was brought into memory
 - · Access bit: whether a page has been accessed

How Big are Page Tables


- Assume 32-bit machine and 4KB pages, and each PTE takes 4 bytes (PFN plus status bits)
 - Number of PTEs: $2^{32-12} = 2^{20}$
 - Size of page table: 4MB
 - What if 100 processes running? 400MB
- Page tables are stored in memory and context switch only changes the pointer to page table (e.g., CR3 register)



Multi-level Page Tables


Two-level Page Tables

· Use two levels of page tables to save space




A Tree of Page Tables


- A page table also occupies a page frame
 - e.g., 4KB page and 4-byte PTE:
 1024 entries per table
- Two-level page table forms a tree of page tables
 - In theory 1024 level-2 page tables, but only a subset are valid
 - A subset of valid page tables are stored in memory (others on disk)




A Tree of Page Tables (Cont'd)

Swapped-out pages on disk








Other Page Table Structures

Page Table Structures

- Hierarchical page tables
 - 2-level page tables
 - 3-level page tables
 - 4-level page tables
- Hashed Page Tables
- Inverted Page Tables


Hashed Page Tables

- Hash function
 - input: VPN
 - output: index in the hashed page table
- Collision handling
 - · A linked list
 - Each element consists of three fields: (1) VPN, (2) PFN, and (3) pointer to the next element



Inverted Page Tables


- One page table for the whole system
 - Used in 64-bit UltraSPARC and PowerPC
- Each entry corresponds to one physical page frame
 - Process ID and VPN
- Page table lookup requires linear search of the entire table
- Memory sharing is hard




Real-world Paging Schemes

Virtual Memory on RISC-V

- RISC-V supports multiple MMU
 - For RV32: SV32
 - For RV64: SV39 and SV48
- Here we introduce SV39
 - Page size: 4KB
 - · Virtual address: 39 bits
 - remaining bits of total 64 bits reserved
 - Physical address: 56 bits



SV39: Three Levels of Page Tables




SV39: Page Table Entries

- A PTE in SV39 takes 8 bytes (64 bits)
 - Bit 8-0 status bits
 - Bit 53-10 is PFN (or physical page number, PPN)
 - Bits 63-54 reserved
- The 9 status bits
 - D (dirty), A (accessed), V (valid)
 - G (Global): G=1 the page is mapped in all address spaces
 - U (User): U-mode code may access this page
 - RSW: reserved for s-mode

63	54 53	28	3 27	19 18	10	9	8 7	6	5	4	3	2	1	0
Reser	ved 1	PPN[2]	PPN[1]	P	PN[0]	RSW	D	A	G	U	X	W	R	V
10	10.00	26	9		9	2	1	1	1	1	1	1	1	1


Virtual Memory on IA-32


- Intel's 32-bit CPU (IA-32) uses two stage address translation: segmentation + paging
- A virtual address contains a 16-bit segment selector and 32bit offset



Virtual Memory on IA-32

- Two descriptor tables: GDT & LDT
- Six segment register to cache segment base addresses






Translation Lookaside Buffer

Issues of Paging

- Time complexity
 - Extra memory references during address translation
 - Three-level page tables requires 3 additional memory reads
 - If every memory reference needs 4 memory reads

Question:


 How to speed up address translation and avoid extra memory reads?




Translation Lookaside Buffer

- A translation lookaside buffer (TLB) is a hardware cache that is part of the MMU
 - A cache for the PTEs: holding a translation likely to be re-used
 - Replacement policy: LRU, FIFO, random
 - Each entry holds mapping of a virtual address to a physical address
- Before a virtual-to-physical address translation is to be performed, TLB is looked up using VPN
 - TLB hit: VPN is found, and the PFN of the same entry used
 - TLB miss: VPN not found, page table walk


Translation Lookaside Buffer (Cont'd)



Translation Lookaside Buffer (Cont'd)




Translation Lookaside Buffer (Cont'd)



Why Does TLB Work?

- Ideally one page table walk for the entire page
 - TLB is smaller than page table, but
- Spatial locality
 - Sequentially executed instructions, local variables (on stack), arrays (on heap) likely on the same page
 - E.g., accessing a[0] to a[9]
 - m,h,h,m,h,h,m,h,h -> 70% hit rate
 - Large page size increases hit rate
- Temporal locality
 - Accesses to the same page tend to be close in time



Issues with Context Switch

 Two process may use the same virtual address

• P1: 100 -> 110

• P2: 100 -> 170

Solutions

- Flush TLB upon context switch
 - Invalidate all entries: V->I
- Extending TLB with address space ID
 - No need to flush tlb

VPN	PFN	valid	
-	-		
100	110	٧	
-	-	1	
100	170	V	

VPN	PFN	valid	ASID
-	-		-
100	110	V	1
-	-	-	-
100	170	V	2

Thank you!

