# Advanced Robot Programming Labs C++ Programming

Labs 3-4: Using classes

### 1 Content of this lab

The goal of this lab is to read, use and build C++ classes in order to develop an elementary simulator for a ground robot.

#### 1.1 The simulator

The simulator is defined by several headers and source files, as defined in Figure 1.




Figure 1: Files used by the simulator

The main file is main.cpp and is compiled to an eecutable.

The files robot.h and robot.cpp define a Robot class and will be modified in the first lab to implement new methods that allow using the simulator.

The file envir.h defines the Environment structure that describes the environment in which the robot is moving. It uses another structure, a point with attributes x and y. An environment is then defined by a std::vector of points, defining a polygon which is considered as walls.

The defaults.h file defines a default environment consisting of a  $20 \times 20m$  square, as shown in Figure 2 .

### 1.2 Expected work

During the lab the files will be modified and others will be created. At the end of the lab, please send by email a zip file allowing to compile and test the program.

You may answer the questions by inserting comments in the code at the corresponding lines.






Figure 2: Robot in its environment

# 2 Building the Robot class

- Q1 Compile and execute the program. According to the main.cpp file, the robot is following some velocity setpoints defined in the  $(x, y, \theta)$  space. In which files are the following elements defined:
  - 1. DefaultEnvironment
  - 2. DefaultCartesianSetpoint
  - 3. Environment
- Q2 Explain the signature of DefaultCartesianSetpoint, especially the way to pass arguments. From the main() function, can i be modified in DefaultCartesianSetpoint? What about vx?
- Q3 In practice it is often impossible to control a ground robot by sending  $(x, y, \theta)$  velocities. A classical way to control such a robot is to send a setpoint with a linear velocity v and an angular velocity  $\omega$ , expressed in the robot frame as shown in Figure 3.




Figure 3: Differential drive model

The corresponding model is quite simple:

$$\begin{cases} \dot{x} = v \cos \theta \\ \dot{y} = v \sin \theta \\ \dot{\theta} = \omega \end{cases} \tag{1}$$



Implement such a function in Robot::MoveVW. This method should compute the  $(x, y, \theta)$  velocities from  $(v, \omega)$  and then call the Robot::MoveXYT method.

- Q4 Now that a realistic way to control the robot is possible, should the Robot::MoveXYT method stay available for external use? What can we do in the robot.h file to make it impossible to use it from outside the Robot class?
- $\underline{\mathbf{Q5}}$  When a robot is equipped with two actuated wheels, a simple model is the differential drive model, as shown in Figure 3. Assuming the two wheels have a radius r and are separated with a distance b, then the kinematic model yields:

$$\begin{cases} v = r \frac{\omega_l + \omega_r}{2} \\ \omega = r \frac{\omega_l - \omega_r}{2b} \end{cases}$$
 (2)

As in question 3, implement such a function in the Robot::RotateWheels method, so that it can be possible to control the robot by sending wheel velocities. You may want to define new attributes in the Robot class in order to initialize the radius and base distance through the Robot::InitWheel method. We use the following values:

$$\begin{cases}
 r = 0.05m \\
 b = 0.3m
\end{cases}$$
(3)

The method should rely on Robot::MoveXYT after having computed the  $(x, y, \theta)$  velocities from  $(\omega_l, \omega_r)$ .

**Q6** By using the wheels\_init\_ attribute, make sure that it is impossible to do anything in Robot::RotateWheels if the radius and base have not been initialized.

## 3 Velocity limits

With the current simulation, we can control the robot:

- by sending linear and angular velocity setpoint with Robot::MoveVW
- or by sending wheel velocities with Robot::RotateWheels

These two methods call Robot::MoveXYT<sup>1</sup> and the robot can reach any velocity. In practice, the wheels have a limited velocity at  $\pm 100$  round per minute (rpm).

Q1 Modify the Robot::InitWheels method in order to pass a new argument that defines the wheel angular velocity limit. You may need to define a new attribute of the Robot class to store this limit. Update the main.cpp file with the value in radian per second corresponding to 80 rpm.



<sup>&</sup>lt;sup>1</sup>which should not be calable anymore from outside the Robot class

- Q2 Modify the Robot::RotateWheels method in order to ensure that the applied velocities  $(\omega_l, \omega_r)$  are within the bounds. The method should also print a message if the velocity setpoint is too high. Note that if you just saturate the velocities, the robot motion will be different. A scaling is a better strategy.
- Q3 Although the robot actually moves by having its wheels rotate, it would be easier to be able to send linear and angular velocity setpoints. Modify the Robot::MoveVW method so that a  $(v, \omega)$  setpoint is changed to a  $(\omega_l, \omega_r)$  setpoint that will then be called through Robot::RotateWheels. Apply the default  $(v, \omega)$  trajectory in the simulator. The inverse of model (2) yields:

$$\begin{cases}
\omega_l = \frac{v + b\omega}{r} \\
\omega_r = \frac{v - b\omega}{r}
\end{cases}$$
(4)

## 4 Range sensors

The sensor.h files defines a Sensor class that has four methods:

- void Init: initializes the relative pose between the sensor and the robot
- virtual void Update: updates the measurement from the robot current position
- void Print: prints the current measurement
- void Plot: plots the measurement history

The Update method is defined as a pure virtual function, which makes the Sensor class a abstract class. It is thus impossible to declare a variable to be of Sensor type, as this class is only designed to build daughter-classes depending on the sensor type.

The Robot class already has a attribute called sensors\_ which is a vector of Sensor\*. As the Sensor class is abtract it is forbidden to use it by itself, but pointers are still possible.

- Q1 Create a sensor\_range.h file that defines a SensorRange class that is derived from Sensor. The Update method has to be defined so that the code compiles. For now, just make the method print something to the screen.
- $\underline{\mathbf{Q2}}$  Include this file in main.cpp and declare a SensorRange variable. We will use a front range sensor placed at (0.1,0,0) in the robot frame. Call the Update method at the beginning of the for loop. Run the program and ensure that the sensor is updated.
- Q3 In this question we will build the Update function. This sensor should return the distance to the first wall in its x-axis. The sensor can thus be simulated in two steps:



1. Compute the absolute position and orientation of the sensor. As the robot is passed to the Update method, we can use its own  $(x_r, y_r, \theta_r)$  position and the relative position  $(x_s, y_s, \theta_s)$  of the sensor to get the absolute sensor position:

$$\begin{cases} x = x_r + x_s \cos \theta_r - y_s \sin \theta_r \\ y = y_r + x_s \sin \theta_r + y_s \cos \theta_r \\ \theta = \theta_r + \theta_s \end{cases}$$
 (5)

2. Compute the distance to the nearest wall. In the environment variable, the walls are defined by a list of points available in envir.walls. Figure 4 shows a configuration where the sensor is at  $(x, y, \theta)$  and is facing a wall defined by  $(x_1, y_1)$  and  $(x_2, y_2)$ . In this case, the distance to the wall is:




Figure 4: Distance to a segment defined by two points.

$$d = \frac{x_1 y_2 - x_1 y - x_2 y_1 + x_2 y + x y_1 - x y_2}{x_1 \sin \theta - x_2 \sin \theta - y_1 \cos \theta + y_2 \cos \theta}$$
(6)

The computed distance is positive if the wall is in front of the sensor, and negative if it is behind (in this case this wall is actually not measured). Also, the denominator may be null if the wall is parallel to the sensor orientation.

Define the Update function so that it updates the attribute s of the sensor with the distance to the nearest wall.

 $\underline{\mathbf{Q4}}$  At the end of the Update method, add the command to append the measurement history:  $s_{\text{history}}$ .push\_back( $s_{\text{-}}$ );

At the end of the program call the Plot method of the range sensor in order to display the measurements.

