Redfield equation with multi-axis noise

Huo Chen

November 19, 2020

0.1 Redfield equation with multi-axis couplings

In this example, we show how to solve the Redfield equation with the following Hamiltonian

$$H(s) = -\sigma_z + \sigma_x \otimes B_1 + \sigma_z \otimes B_2 + H_B$$

where B_1 and B_2 are independent Ohmic bath with different cutoff frequencies.

0.1.1 Define annealing

First, we need to combine AbstractCouplings with AbstractBath into an Interaction object. Then we combine different interactions into an InteractionSet:

```
using OrdinaryDiffEq, OpenQuantumTools, Plots
```

```
coupling_1 = ConstantCouplings(["X"])
bath_1 = Ohmic(1e-4, 4, 16)
interaction_1 = Interaction(coupling_1, bath_1)

coupling_2 = ConstantCouplings(["Z"])
bath_2 = Ohmic(1e-4, 0.1, 16)
interaction_2 = Interaction(coupling_2, bath_2)

interaction_set = InteractionSet(interaction_1, interaction_2);
```


Finally, we can create an Annealing object with Interaction Set instead of coupling and bath:

```
 H = Dense Hamiltonian([(s) \rightarrow 1.0], -[\sigma z], unit = :\hbar) \\ u0 = Pauli Vec[1][1] \\ annealing_1 = Annealing(H, u0, coupling=coupling_1, bath = bath_1) \\ annealing_2 = Annealing(H, u0, coupling=coupling_2, bath = bath_2) \\ annealing = Annealing(H, u0, interactions=interaction_set) \\ Annealing with hType QTBase.Dense Hamiltonian Complex Float 64} and uType Array Complex Float 64}, 1} \\ u0 with size: (2,)
```

0.1.2 Solve Redfield equation

We solve the Redfield equation with X, Z, and X plus Z couplings:


```
tf = 10
# Generate the unitary first
U = solve_unitary(annealing, tf, alg=Tsit5(), reltol=1e-6)
# tag the unitary so the solver know it has implace update method
# this will speed up the calculation of integral
U = InplaceUnitary(U)
# Solve the Redfield equation
sol_1 = solve_redfield(annealing_1, tf, U, alg = Tsit5(), abstol = 1e-6, reltol = 1e-6)
sol_2 = solve_redfield(annealing_2, tf, U, alg = Tsit5(), abstol = 1e-6, reltol = 1e-6)
sol = solve_redfield(annealing, tf, U, alg = Tsit5(), abstol = 1e-6, reltol = 1e-6)
We plot \langle X \rangle for the above three cases:
t_list = range(0,tf,length=200)
x_nopulse = []
z_nopulse = []
xz nopulse = []
for s in t_list
    push!(x_nopulse, real(tr(\sigma x*sol_1(s))))
    push!(z_nopulse, real(tr(\sigma x*sol_2(s))))
    push!(xz_nopulse, real(tr(σx*sol(s))))
plot(t_list, x_nopulse, linewidth=2, label="X coupling")
plot!(t_list, z_nopulse, linewidth=2, label="Z coupling")
plot!(t_list, xz_nopulse, linewidth=2, label="X+Z coupling")
xlabel!("s")
ylabel!("<X>")
      1.0
```



0.1.3 Instantaneous pulses

In the last section, we run the same simulation with a single X pulse in the middle of the evolution (spin echo). The can be done by creating a Callback object and feed it to the solver. For ideal pulses, we can use the built-in function InstPulseCallback. This has similar effects as the dynamical decoupling (except the pulse does not commute with the system Hamiltonian).

```
# in this example, we apply an Z pulse in the middle of the annealing
# for the InstPulseCallback constructor
# the first argument is a list of times where the pulses are applied
# the second argument is a function to update the state update!(c, pulse_index
# the function will update the state c with give pulse_index
cbu = InstPulseCallback([0.5 * tf], (c, x) \rightarrow c .= \sigmax * c)
cb = InstPulseCallback([0.5 * tf], (c, x) \rightarrow c .= \sigmax * c * \sigmax)
annealing_1 = Annealing(H, u0, coupling = coupling_1, bath = bath_1)
annealing_2 = Annealing(H, u0, coupling=coupling_2, bath = bath_2)
annealing = Annealing(H, u0, interactions=interaction_set)
U = solve_unitary(annealing, tf, alg=Tsit5(), reltol=1e-6, callback = cbu);
U = InplaceUnitary(U)
sol_1 = solve_redfield(annealing_1, tf, U, alg = Tsit5(), reltol = 1e-6, callback=cb)
sol 2 = solve redfield(annealing 2, tf, U, alg = Tsit5(), reltol = 1e-6, callback=cb)
sol = solve_redfield(annealing, tf, U, alg = Tsit5(), reltol = 1e-6, callback=cb);
t_list = range(0,tf,length=200)
x pulse = []
z_pulse = []
xz_pulse = []
for s in t_list
    push!(x_pulse, real(tr(σx*sol_1(s))))
    push!(z_pulse, real(tr(\sigma x*sol_2(s))))
    push!(xz_pulse, real(tr(\sigma x*sol(s))))
plot(t_list, x_pulse, linewidth=2, label="X coupling", legend=:topleft, color=1)
plot!(t_list, z_pulse, linewidth=2, label="Z coupling", color=2)
plot!(t_list, xz_pulse, linewidth=2, label="X+Z coupling", color=3)
plot!(t_list, x_nopulse, linewidth=2, linestyle=:dash, label="X coupling with no pulse",
color=1)
plot!(t_list, z_nopulse, linewidth=2, linestyle=:dash, label="Z coupling with no pulse",
color=2)
plot!(t_list, xz_nopulse, linewidth=2, linestyle=:dash, label="X+Z coupling with no
pulse", color=3)
xlabel!("s")
ylabel!("<X>")
```



We can see that the echo pulse slightly reduced the envelope's decay rate for the case where Z coupling is present.