ESS 411/511 Geophysical Continuum Mechanics Class #5

Highlights from Class #4 — Madeleine Lucas Today's highlights on Monday — Barrett Johnson

Remember we are looking for just 2 or 3 *highlights*, not a summary of the entire class. (What did you think was most important?)

Warm-up question (break-out) –

- Ground displacements (and initial wave amplitudes at an epicenter) can be a meter or more
- Why are amplitudes only cm or mm (or less) when the waves arrive at Seattle?

Class-prep answers (break-out)

- In a visco-elastic material, why is attenuation low at "high" and "low" frequencies, but higher at mid-range ($\omega \tau \sim 1$)
- What is τ ?

ESS 411/511 Geophysical Continuum Mechanics

For Monday class

Please read Mase, Smelser, and Mase, CH 2 through Section 2.3

Your short CR/NC Pre-class prep writing assignment (1 point) in Canvas

- It will be due in Canvas at the start of class.
- I will send another message when it is posted in Canvas.

ESS 411/511 Geophysical Continuum Mechanics

Broad Outline for the Quarter

- Continuum mechanics in 1-D
- 1-D models with springs, dashpots, sliding blocks
- Attenuation
- Mathematical tools vectors, tensors, coordinate changes
- Stress principal values, Mohr's circles for 3-D stress
- Coulomb failure, pore pressure, crustal strength
- Measuring stress in the Earth
- Strain Finite strain; infinitesimal strains
- Moments lithosphere bending; Earthquake moment magnitude
- Conservation laws
- Constitutive relations for elastic and viscous materials
- Elastic waves; kinematic waves

Problem Set #1

- How did it go yesterday?
- Suggestions to make the sessions better?
- Questions about the actual problems?

Energy and Work

Total energy input between from time 0 to t

$$\Delta E(t) = \int_0^t \sigma(t')\dot{e}(t')dt'$$

For elastic material, substitute: $\sigma(t) = \mu e(t)$

$$\Delta E(t) = \int_0^t \mu e(t')\dot{e}(t') dt' = \frac{1}{2}\mu e^2(t) = \frac{\sigma^2(t)}{2\mu}$$

 $\Delta E(t)$ returns to zero whenever σ returns to zero.

All energy is recovered

Energy and Work

Total energy input between from time 0 to t

$$\Delta E(t) = \int_0^t \sigma(t')\dot{e}(t')dt'$$

For viscous material:

$$\sigma(t) = \eta \dot{e}(t)$$

$$\Delta E(t) = \int_0^t \eta \dot{e}(t)^2 dt'$$

The integrand is always positive


- $\Delta E(t)$ can never return to zero if strain rate is ever nonzero
- energy is always lost if any strain has occurred.

Harmonic stress loading

Stress:
$$\sigma(t) = \sigma_0 e^{i\omega t}$$
 (σ_0 is real)

Response is also harmonic (but δ is a phase lag)*

$$e(t) = e_0 e^{i\omega t} = (|e_0|e^{i\delta})e^{i\omega t}$$



*Notation challenge – be aware that *e* can be either strain or natural base

Energy in harmonically driven material

$$E(t) = E_0 + \Delta E(t)$$

Energy input from time 0 to t

$$\Delta E(t) = \int_0^t \sigma(t')\dot{e}(t')dt'$$

After breaking exponentials into cos and sin


$$\exp(-iy) = \cos(y) - i\sin(y)$$

$$E(t) = -\frac{w\sigma_o^2}{|m|} \int_0^t \frac{\cos wt' \sin (wt' - \delta)dt' + E_o}{\sigma}$$

$$= \frac{\sigma_0^2}{4|m|} \frac{(\cos 2 wt - 1) \cos \delta + \frac{w\sigma_o^2}{|m|} \int_0^t \cos^2 wt'dt' \sin \delta + E_o}{\text{Monotonic, dissipation}}$$

Debye Dispersion in Harmonic loading


- Elastic wave speed is proportional to elastic modulus |m|
- When different frequencies in a wave packet travel at different speeds, the packet breaks up or disperses



Attenuation in real rocks

There is a broad plateau of low Q over several decades of frequency ω

- Probably a sum of various dissipative processes centered on different frequencies.
 - Dislocations inside crystals
 - Interactions among adjacent crystals
 - Pore fluids



Earthquake waves

Peak-to-peak amplitude and energy density decrease with distance from source, due to 2 processes.

- (1) Geometrical spreading with distance *r* from source
 - In body waves (p & s) energy is spread over expanding spherical wave front, so wave-front area increases as r^2 for
 - Energy decreases as $1/r^2$
 - In surface waves (Love, Rayleigh, etc) energy is spread over expanding cylindrical wave front, so wave-front area increases as *r* .
 - Energy decreases as 1/r

Earthquake waves

Peak-to-peak amplitude and energy density decrease with distance from source, due to 2 processes.

(2) Intrinsic attenuation quantified by Quality factor Q

$$Q^{-1} = \frac{\Delta E}{2\pi E}$$

- $Q^{-1} = \frac{\Delta E}{2\pi E}$ Q^{-1} is fractional energy lost per cycle of the wave. For most rocks, Q >> 1 (~30 80 is typical)

Amplitude A(r) of a seismic wave:

$$A(r) = A_0 \exp\left(-\frac{\omega r}{2cQ}\right)$$

- $A(r) = A_0 \exp\left(-\frac{\omega r}{2cO}\right)$ c is wave speed (e.g. 8 km/s for mantle p-waves) ω is angular frequency ($\omega = 2\pi f$)

 - Let's use Q=75, r=100 km, and f=1 & 10 Hz

Results:

$$f = 1 \text{ Hz}: A = 0.59 A_0$$

$$f = 10 \text{ Hz}$$
: A = 0.0053 A_0

f = 1 Hz: A = 0.59 A_0 So a 1 Hz wave loses 40% of its amplitude for every 100 km it travels, while a 10 Hz wave f = 10 Hz: A = 0.0053 A_0 loses 99.5% of its amplitude every 100 km

> We don't see much energy at 10 Hz from teleseisms!