Lesson 6

Yul continued

Accessing Variables

For local storage variables or state variables, a single Yul identifier is not sufficient, since they do not necessarily occupy a single full storage slot. Therefore, their "address" is composed of a slot and a byte-offset inside that slot. To retrieve the slot pointed to by the variable x, you use x.slot, and to retrieve the byte-offset you use x.offset. Using x itself will result in an error. You can also assign to the .slot part of a local storage variable pointer. For these (structs, arrays or mappings), the .offset part is always zero.

It is not possible to assign to the slot or offset part of a state variable, though.

For example

}

We can access addresses and function selectors associated with a function with

fun.selector and fun.address for function fun For example

```
let ptr := memoryguard(size)
```

(where size has to be a literal number) promises that they only use memory in either the range [0, size) or the unbounded range starting at ptr.

Since the presence of a memoryguard call indicates that all memory access adheres to this restriction, it allows the optimizer to perform additional optimization steps

Verbatim keyword

The set of verbatim... builtin functions lets you create bytecode for opcodes that are not known to the Yul compiler. It also allows you to create bytecode sequences that will not be modified by the optimizer.

The functions are verbatim_<n>i_<m>o("<data>", ...), where

- n is a decimal between 0 and 99 that specifies the number of input stack slots / variables
- m is a decimal between 0 and 99 that specifies the number of output stack slots / variables
- data is a string literal that contains the sequence of bytes

If you for example want to define a function that multiplies the input by two, without the optimiser touching the constant two, you can use

```
let x := calldataload(0)
let double := verbatim_1i_1o(hex"600202", x)
```

Error handling

Error handling in Yul is limited, we need to detect the error conditions ourselves.

We can react to errors with the revert function

There are more details of using custom errors in this blog

post

which has this example

What is missing in Yul?

Yul tries to hide some of the complexity, therefore the following opcodes are not provided

SWAP, DUP, JUMPDEST, JUMP and JUMPI, PUSH

The POP instruction just discards the value See the table in

https://docs.soliditylang.org/en/v0.8.15/yul.html#evm-dialect

Yul can be used in stand alone mode

As an example

```
// A contract consists of a single object with sub-
objects representing
// the code to be deployed or other contracts it can
create.
// The single "code" node is the executable code of
the object.
// Every (other) named object or data section is
serialized and
// made accessible to the special built-in functions
datacopy / dataoffset / datasize
// The current object, sub-objects and data items
inside the current object
// are in scope.
object "Contract1" {
    // This is the constructor code of the contract.
    code {
        function allocate(size) -> ptr {
            ptr := mload(0x40)
            if iszero(ptr) { ptr := 0x60 }
            mstore(0x40, add(ptr, size))
        }
        // first create "Contract2"
        let size := datasize("Contract2")
        let offset := allocate(size)
        // This will turn into codecopy for EVM
        datacopy(offset, dataoffset("Contract2"),
size)
        // constructor parameter is a single number
0x1234
```

```
mstore(add(offset, size), 0x1234)
        pop(create(offset, add(size, 32), 0))
        // now return the runtime object (the
currently
        // executing code is the constructor code)
        size := datasize("Contract1_deployed")
        offset := allocate(size)
        // This will turn into a memory->memory copy
for Ewasm and
        // a codecopy for EVM
        datacopy(offset,
dataoffset("Contract1_deployed"), size)
        return(offset, size)
    }
    data "Table2" hex"4123"
    object "Contract1_deployed" {
        code {
            function allocate(size) -> ptr {
                ptr := mload(0x40)
                if iszero(ptr) { ptr := 0x60 }
                mstore(0x40, add(ptr, size))
            }
            // runtime code
            mstore(0, "Hello, World!")
            return(0, 0x20)
        }
    }
    // Embedded object. Use case is that the outside
```

is a factory contract,

```
// and Contract2 is the code to be created by the
factory
  object "Contract2" {
      code {
          // code here ...
      }
      object "Contract2_deployed" {
          code {
               // code here ...
          }
      data "Table1" hex"4123"
    }
}
```

Yul ERC20 Example

See <u>Documentation</u>

See introduction from Fuel labs.

Yul+ adds

- Memory structures (mstruct)
- Enums (enum)
- Constants (const)
- Ethereum standard ABI signature/topic generation (sig"function ...", topic"event ...)
- Booleans (true, false)
- Safe math (over/under flow protection for addition, subtraction, multiplication)
- Injected methods (mslice and require)

IDE Support

Yul in Remix

Yul is supported (but currently not Yul+)

Yul+ support in Foundry

Yul template

From Matt Solomon

- 1. Build with forge build —extra—output ir OR add extra—output = ["ir"] to your config
- 2. Run cat ./out/<file>.sol/<contract>.json | jq -r
 .ir | perl -pe 's/\\n/\n/g' > ir.sol (file is .sol for
 syntax highlighting)

Viewing Yul output from the solidity compiler

Use the --ir flag with the solidity compiler to get a Yul version, it can be useful to clarify what is happening in your solidity code.