

```
[0x00000818c 255 alxchk_ls]> pd $r @ loc.000008189+3 # 0x818c
(fcn) fcn.000081a9 283
 0x00000818c 488b1c24    mov rbx, [rsp]
 0x000008190 488b6c2408  mov rbp, [rsp+0x8]
 0x000008195 4c8b642410  mov r12, [rsp+0x10]
 0x00000819a 4c8b6c2418  mov r13, [rsp+0x18]
 0x00000819f 4c8b742420  mov r14, [rsp+0x20]
 0x0000081a4 4883c428    add rsp, 0x28
 0x0000081a8  c3          ret
 0x0000081a9 0f1f800000. nop [rax]
 0x0000081b0 498b30      mov rsi, [r8]
 0x0000081b3 4839ee      cmp rsi, rbp
 0x0000081b6 7427        jz 0x81df [1]
 0x0000081b8 4889ef      mov rdi, rbp
; CODE (CALL) XREF from 0x000081f8 (fcn.000081f8)
 0x0000081bb 41ff542438  call qword [r12+0x38] ; (fcn.000081f8) [2]
  fcn.000081f8()
 0x0000081c0 84c0        test al, al
 0x0000081c2 7514        jnz 0x81d8 [3]
 0x0000081c4 488b5b08    mov rbx, [rbx+0x8]
 0x0000081c8 4c8b4308    mov r8, [rbx+0x8]
 0x0000081cc 4d85c0      test r8, r8
 0x0000081cf 75df        jnz 0x81b0 [4]
 0x0000081d1 31f6        xor esi, esi
; CODE (CALL) XREF from 0x00008189 (fcn.0000805c)
 0x0000081d3 ebb4        jmp loc.00008189 [5]
 0x0000081d5 0f1f00      nop [rax]
 0x0000081d8 4c8b4308    mov r8, [rbx+0x8]
 0x0000081dc 498b30      mov rsi, [r8]
 0x0000081df 4584ed      test r13b, r13b
 0x0000081e2 74a5        jz loc.00008189 [6]
 0x0000081e4 498b4008    mov rax, [r8+0x8]
 0x0000081e8 49c7000000. mov qword [r8], 0x0
 0x0000081ef 48894308    mov [rbx+0x8], rax
 0x0000081f3 498b442448  mov rax, [r12+0x48]
; CODE (CALL) XREF from 0x000081bb (fcn.0000805c)
(fcn) fcn.000081f8 175
 0x0000081f8 49894008    mov [r8+0x8], rax
 0x0000081fc 4d89442448  mov [r12+0x48], r8
 0x000008201 eb86        jmp loc.00008189 [7]
 0x000008203 0f1f440000  nop [rax+rax]
 0x000008208 48c7030000. mov qword [rbx], 0x0
 0x00000820f e975fffff   jmp loc.00008189 [8]
; CODE (CALL) XREF from 0x00008214 (fcn.00008214)
(fcn) fcn.00008214 147
 0x000008214 6666662e0f1. o16 nop [cs:rax+rax]
; CODE (CALL) XREF from 0x00005762 (fcn.000041b0)
; CODE (CALL) XREF from 0x00006251 (fcn.000041b0)
; CODE (CALL) XREF from 0x000063d2 (fcn.000041b0)
(fcn) fcn.00008220 135
 0x000008220 488b07      mov rax, [rdi]
```

# Table of Contents

introduction	1.1
Introduction	1.2
History	1.2.1
Overview	1.2.2
Getting radare2	1.2.3
Compilation and Portability	1.2.4
Compilation on Windows	1.2.5
Command-line Flags	1.2.6
Basic Usage	1.2.7
Command Format	1.2.8
Expressions	1.2.9
Rax2	1.2.10
Basic Debugger Session	1.2.11
Contributing to radare2	1.2.12
Configuration	1.3
Colors	1.3.1
Common Configuration Variables	1.3.2
Basic Commands	1.4
Seeking	1.4.1
Block Size	1.4.2
Sections	1.4.3
Mapping Files	1.4.4
Print Modes	1.4.5
Flags	1.4.6
Write	1.4.7
Zoom	1.4.8
Yank/Paste	1.4.9
Comparing Bytes	1.4.10
Visual mode	1.5
Visual Disassembly	1.5.1

---

Searching bytes	1.6
Basic Searches	1.6.1
Configuring the Search	1.6.2
Pattern Search	1.6.3
Automatization	1.6.4
Backward Search	1.6.5
Search in Assembly	1.6.6
Searching for AES Keys	1.6.7
Disassembling	1.7
Adding Metadata	1.7.1
ESIL	1.7.2
Scripting	1.8
Loops	1.8.1
Macroses	1.8.2
R2pipe	1.8.3
Rabin2	1.9
File Identification	1.9.1
Entrypoint	1.9.2
Imports	1.9.3
Symbols (exports)	1.9.4
Libraries	1.9.5
Strings	1.9.6
Program Sections	1.9.7
Radiff2	1.10
Binary Differencing	1.10.1
Rasm2	1.11
Assemble	1.11.1
Disassemble	1.11.2
Analysis	1.12
Code Analysis	1.12.1
Rahash2	1.13
Rahash Tool	1.13.1
Debugger	1.14
Getting Started	1.14.1

---

---

Registers	1.14.2
Remote Access Capabilities	1.15
Remoting Capabilities	1.15.1
Plugins	1.16
Plugins	1.16.1
Crackmes	1.17
IOLI	1.17.1
IOLI 0x00	1.17.1.1
IOLI 0x01	1.17.1.2
Avatao	1.17.2
R3v3rs3 4	1.17.2.1
.intro	1.17.2.1.1
.radare2	1.17.2.1.2
.first_steps	1.17.2.1.3
.main	1.17.2.1.4
.vmloop	1.17.2.1.5
.instructionset	1.17.2.1.6
.bytecode	1.17.2.1.7
.outro	1.17.2.1.8
Reference Card	1.18

---

## R2 "Book"

# Welcome to the Radare2 Book

- Webpage: <https://www.gitbook.com/book/radare/radare2book/details>
- Online: <http://radare.gitbooks.io/radare2book/content/>
- PDF: <https://www.gitbook.com/download/pdf/book/radare/radare2book>
- Epub: <https://www.gitbook.com/download/epub/book/radare/radare2book>
- Mobi: <https://www.gitbook.com/download/mobi/book/radare/radare2book>

## Authors & Contributors

### The radare2 book

Rework by maijin on the original radare book

Contributors:

- Anton Kochkov
- aoighost
- Austin Hartzheim
- David Tomaschik
- DZ\_ruyk
- Grigory Rechistov
- hdznrrd
- Jeffrey Crowell
- John
- Judge Dredd
- jvoisin
- Kevin Grandemange
- muzlightbeer
- Peter C
- sghctoma
- SkUaTeR
- TDKPS
- Thanat0s

## The original radare book

Original author and greetings from [The radare book](#) : pancake

- God. aka Flying Spaghetti Monster
- Nibble (ELF32/64 and PE parser+lot of bugfixes and core work)
- ora8 (w32 port debugger, syscallproxying, hw breakpoints..)
- nopcode guys (for the cons and
- Sexy Pandas (let's pwn the plugs!)
- 48bits (keep up the good work)
- Gerardo (ideas and tips for the book)
- pof (for the crackme tutorial and usability tips)
- Esteve (search engine+some code graph stuff)
- revenge (OSX debugger+mach0 work)
- Lia (4teh luf :)

# Introduction

This book aims to cover most usage aspects of radare2. A framework for reverse engineering and analyzing binaries.

--pancake

# History

The radare project began in February of 2006 to provide a free and simple command-line hexadecimal editor with support for 64-bit offsets. The intention was to use the tool to perform searches and help recover data from hard-disks.

Since then, the project has evolved to provide a complete framework for analyzing binaries while making use of basic \*NIX concepts. Those concepts include the famous "everything is a file," "small programs that interact using stdin/stdout," and "keep it simple" paradigms.

It is mostly a single-person project. However, ideas and source code contributions are greatly appreciated.

The central focus of this project is the hexadecimal editor. Additionally, this project contains an assembler/disassembler, code/data analysis and graphing tools, scripting features, easy Unix integration, and more.

# Overview

The Radare2 project is a set of small command-line utilities that can be used together or independently.

## radare2

The core of the hexadecimal editor and debugger. radare2 allows you to open a number of input/output sources as if they were simple, plain files, including disks, network connections, kernel drivers, processes under debugging, and so on.

It implements an advanced command line interface for moving around a file, analyzing data, disassembling, binary patching, data comparison, searching, replacing, visualizing. It can be scripted with a variety of languages, including Ruby, Python, Lua, and Perl.

## rabin2

A program to extract information from executable binaries, such as ELF, PE, Java CLASS, and Mach-O. rabin2 is used by the core to get exported symbols, imports, file information, cross references (xrefs), library dependencies, sections, etc.

## rasm2

A command line assembler and disassembler for multiple architectures (including Intel x86 and x86-64, MIPS, ARM, PowerPC, Java, and MSIL).

## Examples

```
$ rasm2 -a java 'nop'
00

$ rasm2 -a x86 -d '90'
nop

$ rasm2 -a x86 -b 32 'mov eax, 33'
b821000000

$ echo 'push eax;nop;nop' | rasm2 -f -
509090
```

## rahash2

An implementation of a block-based hash tool. From small text strings to large disks, rahash2 supports multiple algorithms, including MD4, MD5, CRC16, CRC32, SHA1, SHA256, SHA384, SHA512, par, xor, xorpair, mod255, hamdist, or entropy. rahash2 can be used to check the integrity of, or track changes to, big files, memory dumps, and disks.

## Examples

```
$ rahash2 file
file: 0x00000000-0x00000007 sha256: 887cfbd0d44aaff69f7bdbebedb282ec96191cce9d7fa73362
98a18efc3c7a5a

$ rahash2 file -a md5
file: 0x00000000-0x00000007 md5: d1833805515fc34b46c2b9de553f599d
```

## radiff2

A binary diffing utility that implements multiple algorithms. It supports byte-level or delta diffing for binary files, and code-analysis diffing to find changes in basic code blocks obtained from the radare code analysis, or from the IDA analysis using the rsc idc2rdb script.

## rafind2

A program to find byte patterns in files.

## ragg2

A frontend for r\_egg. ragg2 compiles programs written in a simple high-level language into tiny binaries for x86, x86-64, and ARM.

## Examples

```
$ cat hi.r
/* hello world in r_egg */
write@syscall(4); //x64 write@syscall(1);
exit@syscall(1); //x64 exit@syscall(60);

main@global(128) {
    .var0 = "hi!\n";
    write(1, .var0, 4);
    exit(0);
}
$ ragg2 -O -F hi.r
$ ./hi
hi!

$ cat hi.c
main@global(0,6) {
    write(1, "Hello0", 6);
    exit(0);
}
$ ragg2 hi.c
$ ./hi.c.bin
Hello
```

## rarun2

A launcher for running programs within different environments, with different arguments, permissions, directories, and overridden default file descriptors. rarun2 is useful for:

- Crackmes
- Fuzzing
- Test suites

## Sample rarun2 script

```
$ cat foo.rr2
#!/usr/bin/rarun2
program=./pp400
arg0=10
stdin=foo.txt
chdir=/tmp
#chroot=.
./foo.rr2
```

## Connecting a Program to a Socket

```
$ nc -l 9999
$ rarun2 program=/bin/ls connect=localhost:9999
```

## Debugging a Program by Redirecting IO to Another Terminal

1 - open a new terminal and type 'tty' to get a terminal name:

```
$ tty ; clear ; sleep 999999
/dev/ttys010
```

2 - Create a new file containing the following rarun2 profile named foo.r2:

```
#!/usr/bin/rarun2
program=/bin/ls
stdio=/dev/ttys010
```

3 - Launch the following radare2 command: r2 -R foo.rr2 -d ls

## rax2

A minimalistic mathematical expression evaluator for the shell that is useful for making base conversions between floating point values, hexadecimal representations, hexpair strings to ASCII, octal to integer, etc. It also supports endianness settings and can be used as an interactive shell if no arguments are given.

## Examples

```
$ rax2 1337
0x539

$ rax2 0x400000
4194304

$ rax2 -b 01111001
y

$ rax2 -S radare2
72616461726532

$ rax2 -s 617765736f6d65
awesome
```



# Getting radare2

You can get radare from the website, <http://radare.org/>, or the GitHub repository, <https://github.com/radare/radare2>.

Binary packages are available for a number of operating systems (Ubuntu, Maemo, Gentoo, Windows, iPhone, and so on). Yet, you are highly encouraged to get the source and compile it yourself to better understand the dependencies, to make examples more accessible and of course to have the most recent version.

A new stable release is typically published every month. Nightly tarballs are sometimes available at <http://bin.rada.re/>.

The radare development repository is often more stable than the 'stable' releases. To obtain the latest version:

```
$ git clone https://github.com/radare/radare2.git
```

This will probably take a while, so take a coffee break and continue reading this book.

To update your local copy of the repository, use `git pull` anywhere in the radare2 source code tree:

```
$ git pull
```

If you have local modifications of the source, you can revert them (and loose them!) with:

```
$ git reset --hard HEAD
```

Or send me a patch:

```
$ git diff > radare-foo.patch
```

The most common way to get r2 updated and installed system wide is by using:

```
$ sys/install.sh
```

## Helper Scripts

Take a look at the sys/\* scripts, those are used to automatize stuff related to syncing, building and installing r2 and its bindings.

The most important one is sys/install.sh. It will pull, clean, build and symstall r2 system wide.

Symstalling is the process of installing all the programs, libraries, documentation and data files using symlinks instead of copying the files.

By default it will be installed in /usr, but you can define a new prefix as argument.

This is useful for developers, because it permits them to just run 'make' and try changes without having to run make install again.

## Cleaning Up

Cleaning up the source tree is important to avoid problems like linking to old objects files or not updating objects after an ABI change.

The following commands may help you to get your git clone up to date:

```
$ git clean -xdf  
$ git reset --hard @~10  
$ git pull
```

If you want to remove previous installations from your system, you must run the following commands:

```
$ ./configure --prefix=/usr/local  
$ make purge
```

# Compilation and Portability

Currently the core of radare2 can be compiled on many systems and architectures, but the main development is done on GNU/Linux with GCC, and on MacOS X with clang. Radare is also known to compile on many different systems and architectures (including TCC and SunStudio).

People often want to use radare as a debugger for reverse engineering. Currently, the debugger layer can be used on Windows, GNU/Linux (Intel x86 and x86\_64, MIPS, and ARM), FreeBSD, NetBSD, and OpenBSD (Intel x86 and x86\_64). There are plans to support Solaris and MacOS X.

Compared to core, the debugger feature is more restrictive portability-wise. If the debugger has not been ported to your favorite platform, you can disable the debugger layer with the `--without-debugger` `configure` script option when compiling radare2.

Note that there are I/O plugins that use GDB, GDB Remote, or Wine as back-ends, and therefore rely on presence of corresponding third-party tools.

To build on a system using ACR/GMAKE (e.g. on \*BSD systems):

```
$ ./configure --prefix=/usr  
$ gmake  
$ sudo gmake install
```

There is also a simple script to do this automatically:

```
$ sys/install.sh
```

## Static Build

You can build statically radare2 and all the tools with the command:

```
$ sys/static.sh
```

## Docker

Radare2 repository ships a [Dockerfile](#) that you can use with Docker.

This dockerfile is also used by Remnux distribution from SANS, and is available on the docker [registryhub](#).

## Cleaning Up Old Radare2 Installations

```
./configure --prefix=/old/r2/prefix/installation  
make purge
```

# Compilation on Windows

## Mingw32

The easy way to compile things for Windows is using Mingw32. The w32 builds distributed from the radare homepage are generated from a GNU/Linux box using Mingw32 and they are tested with Wine. Also keep in mind, that Mingw-w64 isn't tested, so no guarantees here.

Be sure to setup your Mingw32 to compile with **thread model: win32**, not **posix**, and target should be **mingw32**. Before the starting of compilation you need to setup git first, for a proper automatic fetching of capstone:

```
git config --global core.autocrlf true
git config --global core.filemode false
```

The following is an example of compiling with MinGW32 (you need to have installed **zip** for Windows):

```
CC=i486-mingw32-gcc ./configure
make
make w32dist
zip -r w32-build.zip w32-build
```

This generates a native, 32-bit console application for Windows. The 'i486-mingw32-gcc' compiler is the one I have in my box, you will probably need to change this.

To simplify the building under Windows/Mingw32 there is a script in radare2 sources:

`sys/mingw32.bat` . Simply run it from the cmd.exe (or ConEmu/cmd.exe). It assumes that you have Mingw32 installed in `C:\Mingw` and Git in `C:\Program Files (x86)\Git` . If you want to use another installations, just set `MINGW_PATH` and `GIT_PATH` variables correspondingly:

```
set MINGW_PATH=D:\Mingw32
set "GIT_PATH=E:\Program and Stuff\Git"
sys\mingw32.bat
```

Please, note, that this script should be run from radare2 directory.

## Cygwin

Cygwin is another possibility; however, issues related to Cygwin libraries can make debugging difficult. But using binary compiled for Cygwin will allow you to use Unicode in the Windows console, and to have 256 colors.

Note, Cygwin build require exactly the opposite git configuration, so setup git first, for a proper automatic fetching of capstone:

```
git config --global core.autocrlf false
```

Please, be sure to build radare2 from the same environment you're going to use r2 in. If you are going to use r2 in MinGW32 shell or cmd.exe — you should build r2 in the MinGW32 environment. And if you are going to use r2 in Cygwin — you have to build r2 from the Cygwin shell. Since Cygwin is more UNIX-compatible than MinGW, the radare2 supports more colors and Unicode symbols if build using the former one.

There is a script that automates process of detecting the crosscompiler toolchain configuration, and builds a zip file containing r2 programs and libraries that can be deployed on Windows or Wine:

```
sys/mingw32.sh
```

## Mingw-W64

- Download the MSYS2 distribution from the official site: <http://msys2.github.io/>
- Setup the proxy (if needed):

```
export http_proxy=<myusername>:<mypassword>@zz-wwwproxy-90-v:8080
export https_proxy=$http_proxy
export ftp_proxy=$http_proxy
export rsync_proxy=$http_proxy
export rsync_proxy=$http_proxy
export no_proxy="localhost,127.0.0.1,localaddress,.localdomain.com"
```

- Update packages:

```
pacman --needed -Sy bash pacman pacman-mirrors msys2-runtime mingw-w64-x86_64-toolchain
```

- Close MSYS2, run it again from Start menu and update the rest with

```
pacman -Su
```

- Install the building essentials:

```
pacman -S git make zip gcc patch
```

- Compile the radare2:

```
./configure --with-ostype=windows ; make ; make w32dist
```

## Bindings

To build radare2 bindings, you will need to install [Vala \(valac\)](#) for Windows

Then download [valabind](#) and build it:

```
git clone https://github.com/radare/valabind.git valabind
cd valabind
make
make install
```

After you installed valabind, you can build radare2-bindings, for example for Python and Perl:

```
git clone https://github.com/radare/radare2-bindings.git radare2-bindings
cd radare2-bindings
./configure --enable=python,perl
make
make install
```

# Command-line Options

The radare core accepts many flags from command line.

An excerpt from usage help message:

```
$ radare2 -h
Usage: r2 [-dDwntLqv] [-P patch] [-p prj] [-a arch] [-b bits] [-i file] [-s addr] [-B
blocksize] [-c cmd] [-e k=v] file|-

-a [arch]      set asm.arch
-A             run 'aa' command to analyze all referenced code
-b [bits]       set asm.bits
-B [baddr]     set base address for PIE binaries
-c 'cmd..'    execute radare command
-C             file is host:port (alias for -c+=http://%s/cmd/)
-d             use 'file' as a program for debug
-D [backend]   enable debug mode (e cfg.debug=true)
-e k=v         evaluate config var
-f             block size = file size
-h, -hh        show help message, -hh for long
-i [file]      run script file
-k [kernel]    set asm.os variable for asm and anal
-l [lib]        load plugin file
-L             list supported IO plugins
-m [addr]      map file at given address
-n             disable analysis
-N             disable user settings
-q             quiet mode (no prompt) and quit after -i
-p [prj]        set project file
-P [file]      apply rapatch file and quit
-s [addr]      initial seek
-S             start r2 in sandbox mode
-t             load rabin2 info in thread
-v, -V         show radare2 version (-V show lib versions)
-w             open file in write mode
```

Common usage patterns of command-line options.

- Open a file in write mode without parsing the file format headers.

```
$ r2 -nw file
```

- Quickly get into an r2 shell without opening any file.

```
$ r2 -
```

Specify which sub-binary you want to select when opening a fatbin file:

## Command-line Flags

---

```
$ r2 -a ppc -b 32 ls.fat
```

Run a script before showing interactive command-line prompt:

```
$ r2 -i patch.r2 target.bin
```

Execute a command and quit without entering the interactive mode:

```
$ r2 -qc ij hi.bin > imports.json
```

Configure an eval variable:

```
$ r2 -e scr.color=false blah.bin
```

Debug a program:

```
$ r2 -d ls
```

Use an existing project file:

```
$ r2 -p test
```

# Basic Radare Usage

The learning curve for radare is usually somewhat steep at the beginning. Although after an hour of using it you should easily understand how most things work, and how to combine various tools radare offers, you are encouraged to read the rest of this book to understand how some non-trivial things work, and to ultimately improve your skills with radare.

Navigation, inspection and modification of a loaded binary file is performed using three simple actions: seek (to position), print (buffer), and alternate (write, append).

The 'seek' command is abbreviated as `s` and accepts an expression as its argument. The expression can be something like `10`, `+0x25`, or `[0x100+ptr_table]`. If you are working with block-based files, you may prefer to set the block size to a required value with `b` command, and seek forward or backwards with positions aligned to it. Use `>` and `<` commands to navigate this way.

If r2 opens an executable file, by default it will open the file in VA mode and the sections will be mapped to their virtual addresses. In VA mode, seeking is based on the virtual address and the starting position is set to the entry point of the executable. Using `-n` option you can suppress this default behavior and ask r2 to open the file in non-VA mode for you. In non-VA mode, seeking is based on the offset from the beginning of the file.

The 'print' command is abbreviated as `p` and has a number of submodes — the second letter specifying a desired print mode. Frequent variants include `px` to print in hexadecimal, and `pd` for disassembling.

To be allowed to write files, specify the `-w` option to radare when opening a file. The `w` command can be used to write strings, hexpairs (`x` subcommand), or even assembly opcodes (`a` subcommand). Examples:

```
> w hello world          ; string
> wx 90 90 90 90         ; hexpairs
> wa jmp 0x8048140        ; assemble
> wf inline.bin           ; write contents of file
```

Appending a `?` to a command will show its help message, for example, `p?`.

To enter visual mode, press `v<enter>`. Use `q` to quit visual mode and return to the prompt. In visual mode you can use HJKL keys to navigate (left, down, up, and right, respectively). You can use these keys in cursor mode toggled by `c` key. To select a byte range in cursor mode, hold down `SHIFT` key, and press navigation keys HJKL to mark your selection. While

in visual mode, you can also overwrite bytes by pressing `i`. You can press `TAB` to switch between the hex (middle) and string (right) columns. Pressing `q` inside the hex panel returns you to visual mode.

# Command Format

A general format for radare commands is as follows:

```
[ .][times][cmd][~grep][@[@iter]addr!size][|>pipe] ;
```

Commands are identified by a single case-sensitive character [a-zA-Z]. To repeatedly execute a command, prefix the command with a number:

```
px      # run px  
3px    # run px 3 times
```

The `!` prefix is used to execute a command in shell context. If a single exclamation mark is used, commands will be sent to the `system()` hook defined in currently loaded I/O plugin. This is used, for example, by the `ptrace` I/O plugin, which accepts debugger commands from radare interface.

A few examples:

```
ds          ; call the debugger's 'step' command  
px 200 @ esp        ; show 200 hex bytes at esp  
pc > file.c        ; dump buffer as a C byte array to file.c  
wx 90 @@ sym.*      ; write a nop on every symbol  
pd 2000 | grep eax ; grep opcodes that use the 'eax' register  
px 20 ; pd 3 ; px 40 ; multiple commands in a single line
```

The `@` character is used to specify a temporary offset at which the command to its left will be executed. The original seek position in a file is then restored. For example, `pd 5 @ 0x100000fce` to disassemble 5 instructions at address `0x100000fce`.

The `~` character enables internal grep-like function used to filter output of any command. For example:

```
pd 20~call           ; disassemble 20 instructions and grep output for 'call'
```

Additionally, you can either grep for columns or rows:

```
pd 20~call:0         ; get first row  
pd 20~call:1         ; get second row  
pd 20~call[0]        ; get first column  
pd 20~call[1]        ; get second column
```

Or even combine them:

```
pd 20~call:0[0]      ; grep the first column of the first row matching 'call'
```

This internal grep function is a key feature for scripting radare, because it can be used to iterate over a list of offsets or data generated by disassembler, ranges, or any other command. Refer to the macros section (iterators) for more information.

# Expressions

Expressions are mathematical representations of 64-bit numerical values. They can be displayed in different formats, be compared or used with all commands accepting numeric arguments. Expressions can use traditional arithmetic operations, as well as binary and boolean ones. To evaluate mathematical expressions prepend them with command `? .` For example:

```
[0xB7F9D810]> ? 0x8048000
134512640 0x8048000 01001100000 128.0M 804000:0000 134512640 00000000 134512640.0 0.00
0000
[0xB7F9D810]> ? 0x8048000+34
134512674 0x8048022 01001100042 128.0M 804000:0022 134512674 00100010 134512674.0 0.00
0000
[0xB7F9D810]> ? 0x8048000+0x34
134512692 0x8048034 01001100064 128.0M 804000:0034 134512692 00110100 134512692.0 0.00
0000
[0xB7F9D810]> ? 1+2+3-4*3
-6 0xfffffffffffffff 017777777777777777777772 17179869183.0G ffffff000:0ffa -6
```

Supported arithmetic operations are:

- `+` : addition
- `-` : subtraction
- `*` : multiplication
- `/` : division
- `%` : modulus
- `>` : shift right
- `<` : shift left

Binary operations should be escaped:

- `|` : logical OR // ("? 0001010b | 0101001b ")
- `&` : logical AND
- `^` : logical XOR

Values are numbers can be displayed in several formats:

```
0x033  : hexadecimal can be displayed
3334   : decimal
sym.fo : resolve flag offset
10K    : KBytes 10*1024
10M    : MBytes 10*1024*1024
```

You can also use variables and seek positions to build complex expressions. Available values include:

```
?@?    or type @@?      ; misc help for '@' (seek), '~' (grep) (see ~??)
?$?    ; show available '$' variables
$$?    ; here (the current virtual seek)
$1     ; opcode length
$s     ; file size
$j     ; jump address (e.g. jmp 0x10, jz 0x10 => 0x10)
$f     ; jump fail address (e.g. jz 0x10 => next instruction)
$m     ; opcode memory reference (e.g. mov eax,[0x10] => 0x10)
```

Some more examples:

```
[0x4A13B8C0]> :? $m + $1
140293837812900 0x7f98b45df4a4 03771426427372244 130658.0G 8b45d000:04a4 1402938378129
00 10100100 140293837812900.0 -0.000000

[0x4A13B8C0]> :pd 1 @ +$1
0x4A13B8C2  call 0x4a13c000
```

# Rax2

The `rax2` utility comes with the radare framework and aims to be a minimalistic expression evaluator for the shell. It is useful for making base conversions between floating point values, hexadecimal representations, hexpair strings to ascii, octal to integer. It supports endianness and can be used as a shell if no arguments are given.

```
$ rax2 -h

Usage: rax2 [options] [expr ...]
int  -> hex          ; rax2 10
hex  -> int          ; rax2 0xa
-int -> hex          ; rax2 -77
-hex -> int          ; rax2 0xfffffffffb3
int  -> bin          ; rax2 b30
bin  -> int          ; rax2 1010d
float -> hex         ; rax2 3.33f
hex   -> float        ; rax2 Fx40551ed8
oct   -> hex         ; rax2 350
hex   -> oct          ; rax2 0x12 (0 is a letter)
bin   -> hex          ; rax2 1100011b
hex   -> bin          ; rax2 Bx63
raw   -> hex          ; rax2 -S < /binfile
hex   -> raw          ; rax2 -s 414141
-b   binstr -> bin    ; rax2 -b 01000101 01110110
-B   keep base        ; rax2 -B 33+3 -> 36
-d   force integer     ; rax2 -d 3 -> 3 instead of 0x3
-e   swap endianness  ; rax2 -e 0x33
-f   floating point    ; rax2 -f 6.3+2.1
-h   help              ; rax2 -h
-k   randomart         ; rax2 -k 0x34 1020304050
-n   binary number     ; rax2 -e 0x1234 # 34120000
-s   hexstr -> raw    ; rax2 -s 43 4a 50
-S   raw -> hexstr    ; rax2 -S < /bin/ls > ls.hex
-t   tstamp -> str    ; rax2 -t 1234567890
-x   hash string       ; rax2 -x linux osx
-u   units              ; rax2 -u 389289238 # 317.0M
-v   version            ; rax2 -V
```

Some examples:

```
$ rax2 3+0x80
0x83

$ rax2 0x80+3
131

$ echo 0x80+3 | rax2
131

$ rax2 -s 4142
AB

$ rax2 -S AB
4142

$ rax2 -S < bin.foo
...

$ rax2 -e 33
0x21000000

$ rax2 -e 0x21000000
33

$ rax2 -k 90203010
+-[0x10302090]---+
|Eo. .
| . . .
|   o
|   .
|   s
|
|
|
+-----+
```

# Basic Debugger Session

To debug a program, start radare with `-d` option. You can attach to a running process by specifying its PID, or you can start a new program by specifying its name and parameters: \$ pidof mc 32220 \$ r2 -d 32220

```
$ r2 -d /bin/ls
```

In the second case, the debugger will fork and load the debugger `ls` program in memory. It will pause its execution early in `ld.so` dynamic linker. Therefore, do not expect to see an entrypoint or shared libraries at this point. You can override this behavior by setting another name for and entry breakpoint. To do this, add a radare command `e dbg.bep=entry` or `e dbg.bep=main` to your startup script, usually it is `~/.radare2rc`. Be warned though that certain malware or other tricky programs can actually execute code before `main()` and thus you'll be unable to control them.

Below is a list of most common commands used with debugger:

```
> d?          ; get help on debugger commands
> ds 3        ; step 3 times
> db 0x8048920 ; setup a breakpoint
> db -0x8048920 ; remove a breakpoint
> dc          ; continue process execution
> dcs         ; continue until syscall
> dd          ; manipulate file descriptors
> dm          ; show process maps
> dmp A S rwx ; change page at A with size S protection permissions
> dr eax=33   ; set register value. eax = 33
```

Maybe a simpler method to use debugger in radare is to switch it to visual mode. That way you will not have to remember many commands nor to keep program state in your mind. To enter visual mode use `v`:

```
[0xB7F0C8C0]> v
```

The initial view after entering visual mode is a hexdump view of current target program counter (e.g., EIP for x86). Pressing `p` will allow you to cycle through the rest of visual mode views. You can press `p` and `P` to rotate through the most commonly used print modes. Use `F7` or `s` to step into and `F8` or `s` to step over current instruction. With the `c` key you can toggle the cursor mode to mark a byte range selection (for example, to later overwrite them with `nop`). You can set breakpoints with `F2` key.

In visual mode you can enter regular radare commands by prepending them with `:`. For example, to dump a one block of memory contents at ESI: `x @ esi`

To get help on visual mode, press `?`. To scroll help screen, use arrows. To exit help view, press `q`.

A frequently used command is `dr`, to read or write values of target's general purpose registers. You can also manipulate the hardware and extended/floating point registers.

# Contributing

## Radare2 Book

If you want to contribute to the Radare2 book, you can do it at the [Github repository](#).

Suggested contributions include:

- Crackme writeups
- CTF writeups
- Documentation on how to use Radare2
- Documentation on developing for Radare2
- Conference presentations/workshops using Radare2
- Missing content from the Radare1 book updated to Radare2

Please get permission to port any content you do not own/did not create before you put it in the Radare2 book.

# Configuration

The core reads `~/.radare2rc` while starting. You can add `e` commands to this file to tune radare configuration to your taste.

To prevent radare from parsing this file at start, pass it `-n` option. To have a less verbose output for batch mode runs, it is also better to decrease verbosity level with `-v` command-line option.

All the configuration of radare is done with the `eval` commands. A typical startup configuration file looks like this:

```
$ cat ~/.radare2rc
e scr.color = true
e dbg.bep   = loader
```

Configuration can also be changed with `-e` command-line option. This way you can adjust configuration from the command line, keeping the `.radare2rc` file intact. For example, to start with empty configuration and then adjust `scr.color` and `asm.syntax` the following line may be used:

```
$ radare2 -n -e scr.color=true -e asm.syntax=intel -d /bin/ls
```

Internally, the configuration is stored in a hash table. The variables are grouped in namespaces: `cfg.`, `file.`, `dbg.`, `scr.` and so on.

To get a list of all configuration variables just type `e` in the command line prompt. To limit output to a selected namespace, pass it with an ending dot to `e.`. For example, `e file.` will display all variables defined inside "file" namespace.

To get help about `e` command type `e?`:

```
Usage: e[?] [var[=value]]
e?                      show this help
e?asm.bytes      show description
e??                     list config vars with description
e                      list config vars
e-                     reset config vars
e*                     dump config vars in r commands
e!a                    invert the boolean value of 'a' var
er [key]                set config key as readonly. no way back
ec [k] [color]          set color for given key (prompt, offset, ...)
e a                    get value of var 'a'
e a=b                  set var 'a' the 'b' value
env [k[=v]]             get/set environment variable
```

A simpler alternative to `e` command is accessible from the visual mode. Type `ve` to enter it, use arrows (up, down, left, right) to navigate the configuration, and `q` to exit it. The start screen for the visual configuration edit looks like this:

```
Eval spaces:
```

```
> anal
asm
scr
asm
bin
cfg
diff
dir
dbg
cmd
fs
hex
http
graph
hud
scr
search
io
```

# Colors

Console access is wrapped in API that permits to show output of any command as ANSI, w32 console or HTML formats (more to come: ncurses, Pango etc.) This allows radare's core to run inside environments with limited displaying capabilities, like kernels or embedded devices. It is still possible to receive data from it in your favorite format. To enable colors support by default, add a corresponding configuration option to the .radare2 configuration file:

```
$ echo 'e scr.color=true' >> ~/.radare2rc
```

It is possible to configure color of almost any element of disassembly output. For \*NIX terminals, r2 accepts color specification in RGB format. To change the console color palette use `ec` command. Type `ec` to get a list of all currently used colors. Type `ecs` to show a color palette to pick colors from:

[0x00000000] > ecs					
black	red	white	green	magenta	yellow
cyan	blue	gray			
<b>Greyscale:</b>					
rgb:000	rgb:111	rgb:222	rgb:333	rgb:444	rgb:555
rgb:666	rgb:777	rgb:888	rgb:999	rgb:aaa	rgb:bbb
rgb:ccc	rgb:ddd	rgb:eee	rgb:fff		
<b>RGB:</b>					
rgb:000	rgb:030	rgb:060	rgb:090	rgb:0c0	rgb:0f0
rgb:003	rgb:033	rgb:063	rgb:093	rgb:0c3	rgb:0f3
rgb:006	rgb:036	rgb:066	rgb:096	rgb:0c6	rgb:0f6
rgb:009	rgb:039	rgb:069	rgb:099	rgb:0c9	rgb:0f9
rgb:00c	rgb:03c	rgb:06c	rgb:09c	rgb:0cc	rgb:0fc
rgb:00f	rgb:03f	rgb:06f	rgb:09f	rgb:0cf	rgb:0ff
rgb:300	rgb:330	rgb:360	rgb:390	rgb:3c0	rgb:3f0
rgb:303	rgb:333	rgb:363	rgb:393	rgb:3c3	rgb:3f3
rgb:306	rgb:336	rgb:366	rgb:396	rgb:3c6	rgb:3f6
rgb:309	rgb:339	rgb:369	rgb:399	rgb:3c9	rgb:3f9
rgb:30c	rgb:33c	rgb:36c	rgb:39c	rgb:3cc	rgb:3fc
rgb:30f	rgb:33f	rgb:36f	rgb:39f	rgb:3cf	rgb:3ff
rgb:600	rgb:630	rgb:660	rgb:690	rgb:6c0	rgb:6f0
rgb:603	rgb:633	rgb:663	rgb:693	rgb:6c3	rgb:6f3
rgb:606	rgb:636	rgb:666	rgb:696	rgb:6c6	rgb:6f6
rgb:609	rgb:639	rgb:669	rgb:699	rgb:6c9	rgb:6f9
rgb:60c	rgb:63c	rgb:66c	rgb:69c	rgb:6cc	rgb:6fc
rgb:60f	rgb:63f	rgb:66f	rgb:69f	rgb:6cf	rgb:6ff
rgb:900	rgb:930	rgb:960	rgb:990	rgb:9c0	rgb:9f0
rgb:903	rgb:933	rgb:963	rgb:993	rgb:9c3	rgb:9f3
rgb:906	rgb:936	rgb:966	rgb:996	rgb:9c6	rgb:9f6
rgb:909	rgb:939	rgb:969	rgb:999	rgb:9c9	rgb:9f9
rgb:90c	rgb:93c	rgb:96c	rgb:99c	rgb:9cc	rgb:9fc
rgb:90f	rgb:93f	rgb:96f	rgb:99f	rgb:9cf	rgb:9ff
rgb:c00	rgb:c30	rgb:c60	rgb:c90	rgb:cc0	rgb:cf0
rgb:c03	rgb:c33	rgb:c63	rgb:c93	rgb:cc3	rgb:cf3
rgb:c06	rgb:c36	rgb:c66	rgb:c96	rgb:cc6	rgb:cf6
rgb:c09	rgb:c39	rgb:c69	rgb:c99	rgb:cc9	rgb:cf9
rgb:c0c	rgb:c3c	rgb:c6c	rgb:c9c	rgb:ccc	rgb:cf0
rgb:c0f	rgb:c3f	rgb:c6f	rgb:c9f	rgb:ccf	rgb:cff
rgb:f00	rgb:f30	rgb:f60	rgb:f90	rgb:fc0	rgb:ff0
rgb:f03	rgb:f33	rgb:f63	rgb:f93	rgb:fc3	rgb:ff3
rgb:f06	rgb:f36	rgb:f66	rgb:f96	rgb:fc6	rgb:ff6
rgb:f09	rgb:f39	rgb:f69	rgb:f99	rgb:fc9	rgb:ff9
rgb:f0c	rgb:f3c	rgb:f6c	rgb:f9c	rgb:fcc	rgb:ffc
rgb:f0f	rgb:f3f	rgb:f6f	rgb:f9f	rgb:fcf	rgb:fff

## xvilka theme

```

ec fname rgb:0cf
ec label rgb:0f3
ec math rgb:660
ec bin rgb:f90
ec call rgb:f00
ec jmp rgb:03f
ec cjmp rgb:33c
ec offset rgb:366
ec comment rgb:0cf
ec push rgb:0c0
ec pop rgb:0c0
ec cmp rgb:060
ec nop rgb:000
ec b0x00 rgb:444
ec b0x7f rgb:555
ec b0xff rgb:666
ec btext rgb:777
ec other rgb:bbb
ec num rgb:f03
ec reg rgb:6f0
ec fline rgb:fc0
ec flow rgb:0f0

```

```

+ con vi "www_im_doc_re_mus_fil/etc xvilkas@XLaptop:~/r2-test
[ENCL] | 1 | 2 | 3 | 4 | 5 | 6 | 7 | 8 | 9 | 10 | 11 | 12 | 13 | 14 | 15 | 16 | 17 | 18 | 19 |
[0x000f574d 255 asrock_p4165g.bin]> pd $r @ section.bootblk+22349 # 0xf574d
;
; value = 0x03; reg = 0x4; // XMIT_SLVA - Transmit Slave Address
/ function: SMB_Req_Write_BYTE_SL (57)
| f000:574d bbd04        mov ax, 0x4d3
| f000:5750 bf5557       mov di, 0x5755
;--> f000:5753 e031       jmp SMBus_ICH5_Reg_Write_BYTE_SL [1]
| f000:5755 66c1c008     rol eax, 0x8
| f000:5759 0c80          or al, 0x80
;--> f000:5759 reg = 0x3; // HST_CMD - Host Command
| f000:5760 b408          mov ah, 0xd
| f000:5762 bf0c57       mov di, 0x5762
;--> f000:5769 ab21       jmp SMBus_ICH5_Reg_Write_BYTE_SL [2]
; value = 0x48; reg = 0x2; // HST_CNT - Host Control, value [6] - Start transmission, [3] - Byte Data mode
|| ;--> f000:576d b5402        mov ax, 0x248
|| f000:5765 bf6e57       mov di, 0x576a
;--> f000:5768 eb1c       jmp SMBus_ICH5_Reg_Write_BYTE_SL [3]
|| f000:576a b93075       mov cx, 0x7530
;--> f000:576d e6ed        out 0xed, al
;--> f000:576f e2fc        loop 0xf57bd ; (SMB_Wait) ; (SMB_Req_Write_BYTE_SL) [4]
|| f000:5771 b5f700       mov ax, 0xf
|| f000:5774 bf7857       mov di, 0x5779
;--> f000:5777 ab04       jmp SMBus_ICH5_Reg_Write_BYTE_SL [5]
;--> f000:5779 b405        mov ah, 0x5
;--> f000:577b bf8057       mov di, 0x5780
;--> f000:577e eb0e       jmp SMBus_ICH5_Reg_Read_BYTE_SL [6]
|| f000:5780 660fcf       bsuap edi
|| f000:5783 fb             clc
|| f000:5784 ffe7          jp di
; void SMBus_ICH5_Reg_Write_BYTE_SL(uint8_t reg<ah>, uint8_t value<al>);
/ function: SMBus_ICH5_Reg_Write_BYTE_SL (8)
;--> f000:5786 ba104        mov dx, 0x400
f000:5789 8ad4          mov dl, ah
f000:5790 ee              out dx, al
f000:5791 ffe7          jp di
;
; void SMBus_ICH5_Reg_Read_BYTE_SL<dl>(uint8_t reg<ah>);
/ function: SMBus_ICH5_Reg_Read_BYTE_SL (8)
;--> f000:5786 ba104        mov dx, 0x400
f000:5791 8ad4          mov dl, ah
f000:5793 ec              in al, dx
f000:5794 ffe7          jmp di
;--> f000:5796 7426          jz 0xf57be [7]
f000:5798 bbf000          mov ax, 0x70
f000:579b 90              nop
f000:579c bca257          mov sp, 0x5782
f000:579f e9b9f2          jmp 0xf4a5b [8]
f000:57a2 a4              movsb
f000:57a3 57              push di

```

# Common Configuration Variables

Below is a list of the most frequently used configuration variables. You can get a complete list by issuing `e` command without arguments. For example, to see all variables defined in the "cfg" namespace, issue `e cfg.` (mind the ending dot). You can get help on any eval configuration variable by using `??e cfg.`

```
asm.arch
```

Defines target CPU architecture used for disassembling (`pd`, `pD` commands) and code analysis (`a` command). You can find the list of possible value by looking at the result of `e asm.arch=?` or `rasm2 -L`. It is quite simple to add new architectures for disassembling and analyzing code. There is an interface for that. For x86, it is used to attach a number of third-party disassembler engines, including GNU binutils, Udis86 and a few of handmade ones.

```
asm.bits
```

Determines width in bits of registers for current architecture. Supported values: 8, 16, 32, 64. Note that not all target architectures support all combinations for `asm.bits`.

```
asm.syntax
```

Changes syntax flavor for disassembler between Intel and AT&T. At the moment, this setting affects Udis86 disassembler for Intel 32/Intel 64 targets only. Supported values are `intel` and `att`.

```
asm.pseudo
```

A boolean value to choose a string disassembly engine. "False" indicates a native one, defined by current architecture, "true" activates a pseudocode strings format; for example, it will show `eax=ebx` instead of a `mov eax, ebx`.

```
asm.os
```

Selects a target operating system of currently loaded binary. Usually OS is automatically detected by `rabin -rI`. Yet, `asm.os` can be used to switch to a different syscall table employed by another OS.

```
asm.flags
```

If defined to "true", disassembler view will have flags column.

```
asm.linescall
```

If set to "true", draw lines at the left of disassemble output (`pd`, `pD` commands) to graphically represent control flow changes (jumps and calls) that are targeted inside current block. Also, see `asm.linesout`.

```
asm.linesout
```

When defined as "true", the disassembly view will also draw control flow lines that go outside of the block.

```
asm.linestyle
```

A boolean value which changes the direction of control flow analysis. If set to "false", it is done from top to bottom of a block; otherwise, it goes from bottom to top. The "false" setting seems to be a better choice for improved readability, and is the default one.

```
asm.offset
```

Boolean value which controls visibility of offsets for individual disassembled instructions.

```
asm.trace
```

A boolean value that controls displaying of tracing information (sequence number and counter) at the left of each opcode. It is used to assist programs trace analysis.

```
asm.bytes
```

A boolean value used to show or hide displaying of raw bytes of instructions.

```
cfg.bigendian
```

Change endianness. "true" means big-endian, "false" is for little-endian. "file.id" and "file.flag" both to be true.

```
scr.color
```

This boolean variable enables or disables colorized screen output.

```
scr.seek
```

This variable accepts an expression, a pointer (eg. eip), etc. If set, radare will set seek position to its value on startup.

```
cfg.fortunes
```

Enables or disables "fortune" messages displayed at each radare start.

# Basic Commands

Most command names in radare are derived from action names. They should be easy to remember, as they are short. Actually, all commands are single letters. Subcommands or related commands are specified using the second character of command name. For example, `/ foo` is a command to search plain string, while `/x 90 90` is used to look for hexadecimal pairs.

The general format for a valid command (as explained in the 'Command Format' chapter) looks like this:

```
[ [.][times][cmd][~grep][@[@iter]addr!size][|>pipe] ; ...
```

For example,

```
> 3s +1024 ; seeks three times 1024 from the current seek
```

If a command starts with `!`, the rest of the string is passed to currently loaded IO plugin (a debugger, for example). If no plugin can handle the command, `posix_system()` is called to pass the command to your shell. To make sure your command is directly passed to the shell, prefix it with two exclamation signs `!!`.

```
> !help ; handled by the debugger or shell  
> !!ls ; run `ls` in the shell
```

The meaning of arguments (iter, addr, size) depends on the specific command. As a rule of thumb, most commands take a number as an argument to specify number of bytes to work with, instead of currently defined block size. Some commands accept math expressions, or strings.

```
> px 0x17 ; show 0x17 bytes in hexa at current seek  
> s base+0x33 ; seeks to flag 'base' plus 0x33  
> / lib ; search for 'lib' string.
```

The `@` sign is used to specify a temporary offset location or seek position at which the command is executed, instead of current seek position. This is quite useful as you don't have to seek around all the time.

```
> p8 10 @ 0x4010 ; show 10 bytes at offset 0x4010  
> f patata @ 0x10 ; set 'patata' flag at offset 0x10
```

Using `@@` you can execute a single command on a list of flags matching the glob. You can think of this as a foreach operation:

```
> s 0  
> / lib ; search 'lib' string  
> p8 20 @@ hit0_* ; show 20 hexpairs at each search hit
```

The `>` operation is used to redirect output of a command into a file (overwriting it if it already exists).

```
> pr > dump.bin ; dump 'raw' bytes of current block to file named 'dump.bin'  
> f > flags.txt ; dump flag list to 'flags.txt'
```

The `|` operation (pipe) is similar to what you are used to expect from it in a \*NIX shell: us output of one command as input to another.

```
[0x4A13B8C0]> f | grep section | grep text  
0x0805f3b0 512 section._text  
0x080d24b0 512 section._text_end
```

You can pass several commands in a single line by separating them with semicolon `;`:

```
> px ; dr
```

# Seeking

Current seek position is changed with `s` command. It accepts a math expression as argument. The expression can be composed of shift operations, basic math operations, or memory access operations.

```
[0x00000000]> s?
Usage: s[+-] [addr]
s                      print current address
s 0x320                seek to this address
s-                     undo seek
s+                     redo seek
s*                     list undo seek history
s++                    seek blocksize bytes forward
s--                    seek blocksize bytes backward
s+ 512                 seek 512 bytes forward
s- 512                 seek 512 bytes backward
sg/sG                  seek begin (sg) or end (sG) of section or file
s.hexoff               Seek honoring a base from core->offset
sa [[+-]a] [asz]        seek asz (or bsize) aligned to addr
sn/sp                  seek next/prev scr.nkey
s/ DATA                 search for next occurrence of 'DATA'
s/x 9091                search for next occurrence of \x90\x91
sb                     seek aligned to bb start
so [num]                seek to N next opcode(s)
sf                     seek to next function (f->addr+f->size)
sc str                 seek to comment matching given string
sr pc                  seek to register

> 3s++      ; 3 times block-seeking
> s 10+0x80  ; seek at 0x80+10
```

If you want to inspect the result of a math expression, you can evaluate it using the `?` command. Simply pass the expression as an argument. The result can be displayed in hexadecimal, decimal, octal or binary formats.

```
> ? 0x100+200
0x1C8 ; 456d ; 710o ; 1100 1000
```

In the visual mode you can press `u` (undo) or `u` (redo) inside the seek history to return back to previous or forward to the next location.

# Open file

As test file lets use some simple hello\_world.c compiled in Linux ELF format. After we compiled it lets open it with radare2

```
r2 hello_world
```

Now we have command prompt

```
[0x00400410]>
```

Now we are ready to go deeper.

## Seeking at any position

All seeking commands that have address in command parameters can use any base such as hex/octal/binary or decimal.

Seek to address 0x0, alternative command is just `0x0`

```
[0x00400410]> s 0x0
[0x00000000]>
```

Print current address

```
[0x00000000]> s
0x0
[0x00000000]>
```

there is alternate way how to print current position `?v $$`

Seek N positions forward, space is optional

```
[0x00000000]> s+ 128
[0x00000080]>
```

Lets undo last two seeks to beginning

```
[0x00000080]> s-
[0x00000000]> s-
[0x00400410]>
```

Now we are at same position as at beginning `0x00400410`.

Lets search in hello\_world ELF file 'Hello'. After search our position will set to searched string position. But we always can go back with `s-`.

```
[0x00400410]> s/ Hello
Searching 5 bytes from 0x00400411 to 0x00600928: 48 65 6c 6c 6f
Searching 5 bytes in [0x400411-0x600928]
hits: 1 hit0_0 .. hit0_0
0x004005b4 hit0_0 "Hello"
[0x004005b4]>s-
[0x00400410]>
```

There is history command to see all our changes

```
[0x00400410]> s*
f undo_3 @ 0x400410
f undo_2 @ 0x40041a
f undo_1 @ 0x400410
f undo_0 @ 0x400411
# Current undo/redo position.
f redo_0 @ 0x4005b4
```

# Block Size

The block size determines how many bytes Radare commands will process. All commands will work with this constraint. You can temporally change the block size by specifying a numeric argument to the print commands. For example `px 20`.

```
[0xB7F9D810]> b?
Usage: b[f] [arg]
b          display current block size
b+3       increase blocksize by 3
b-16      decrement blocksize by 16
b 33      set block size to 33
b eip+4   numeric argument can be an expression
bf foo    set block size to flag size
bm 1M     set max block size
```

The `b` command is used to change the block size:

```
[0x0000000000]> b 0x100 ; block size = 0x100
[0x0000000000]> b +16    ; ... = 0x110
[0x0000000000]> b -32    ; ... = 0xf0
```

The `bf` command is used to change the block size to value specified by a flag. For example, in symbols, the block size of the flag represents the size of the function.

```
[0x0000000000]> bf sym.main ; block size = sizeof(sym.main)
[0x0000000000]> pd @ sym.main ; disassemble sym.main
...
```

You can combine two operations in a single one (`pdf`):

```
[0x0000000000]> pdf @ sym.main
```

# Sections

Firmware images, bootloaders and binary files usually place various sections of a binary at different addresses in memory. To represent this behavior, radare offers the `s` command.

Here's the help message:

```
[0xB7EE8810]> S?
Usage: S[?--*=adlr] [...]
S           ; list sections
S.          ; show current section name
S?          ; show this help message
S*          ; list sections (in radare commands)
S=          ; list sections (in nice ascii-art bars)
Sa[-] [arch] [bits] [[off]] ; Specify arch and bits for given section
Sd [file]    ; dump current section to a file (see dmd)
Sl [file]    ; load contents of file into current section (see dml)
Sr [name]   ; rename section on current seek
S [off] [vaddr] [sz] [vsz] [name] [rwx] ; add new section
S-[id|0xoff|*] ; remove this section definition
```

You can specify a section in a single line:

```
# Add new section
S [off] [vaddr] [sz] [vsz] [name] [rwx]
```

For example:

```
[0x000404888]> S 0x00000100 0x00400000 0x0001ae08 0001ae08 test rwx
```

Displaying information about sections:

```
# List sections
[0x00404888]> S

[00] . 0x00000238 r-- va=0x00400238 sz=0x0000001c vsz=0000001c .interp
[01] . 0x00000254 r-- va=0x00400254 sz=0x00000020 vsz=00000020 .note.ABI_tag
[02] . 0x00000274 r-- va=0x00400274 sz=0x00000024 vsz=00000024 .note.gnu.build_id
[03] . 0x00000298 r-- va=0x00400298 sz=0x00000068 vsz=00000068 .gnu.hash
[04] . 0x00000300 r-- va=0x00400300 sz=0x00000c18 vsz=00000c18 .dynsym

# List sections (in nice ascii-art bars)
[0xB7EEA810]> S=

...
25 0x0001a600 |-----#| 0x0001a608 --- .gnu_debuglink
26 0x0001a608 |-----#| 0x0001a706 --- .shstrtab
27* 0x00000000 |#####| 0x0001ae08 rwx ehdr
=> 0x00004888 |-----^-----| 0x00004988
```

The first three lines are sections and the last one (prefixed by `=>`) is the current seek location.

To remove a section definition, simply prefix the name of the section with `-` :

```
[0xB7EE8810]> S - .dynsym
```

# Mapping Files

Radare IO system allows to map contents of files into the same IO space used to contain loaded binary. New contents can be placed at random offsets. This is useful to open multiple files in a single view or to 'emulate' a static environment similar to what you would have using a debugger where the program and all its libraries are loaded in memory and can be accessed.

Using the `s` (sections) command you can define base address for each library to be loaded.

Mapping files is done using the `o` (open) command. Let's read the help:

```
[0x0000000000]> o?
Usage: o[com- ] [file] ([offset])
o                         list opened files
oc [file]                 open core file, like relaunching r2
oo                        reopen current file (kill+fork in debugger)
oo+                       reopen current file in read-write
o 4                      prioritize io on fd 4 (bring to front)
o-1                      close file index 1
o /bin/ls                 open /bin/ls file in read-only
o+/bin/ls                open /bin/ls file in read-write mode
o /bin/ls 0x4000          map file at 0x4000
on /bin/ls 0x4000         map raw file at 0x4000 (no r_bin involved)
om[?]                    create, list, remove IO maps
```

To prepare a simple layout:

```
$ rabin2 -l /bin/ls
[Linked libraries]
libselinux.so.1
librt.so.1
libacl.so.1
libc.so.6

4 libraries
```

To map a file:

```
[0x000001190]> o /bin/zsh 0x499999
```

To list mapped files:

```
[0x00000000]> o
- 6 /bin/ls @ 0x0 ; r
- 10 /lib/ld-linux.so.2 @ 0x100000000 ; r
- 14 /bin/zsh @ 0x499999 ; r
```

To print hexadecimal values from /bin/zsh:

```
[0x00000000]> px @ 0x499999
```

To unmap files use `o-` command. Pass required file descriptor to it as an argument:

```
[0x00000000]> o-14
```

# Print Modes

One of the key features of radare is displaying information in many formats. The goal is to offer a selection of displaying choices to best interpret binary data.

Binary data can be represented as integers, shorts, longs, floats, timestamps, hexpair strings, or more complex formats like C structures, disassembly listings, decompilations, be a result of an external processing...

Below is a list of available print modes listed by `p?`:

```
[0x08049AD0]> p?
Usage: p[=68abcdFfiImrstuxz] [arg|len]
p=[bep?] [blk] show entropy/printable chars/chars bars
p2 [len] 8x8 2bpp-tiles
p6[de] [len] base64 decode/encode
p8 [len] 8bit hexpair list of bytes
pa[ed] [hex asm] assemble (pa) or disasm (pad) or esil (pae) from hexpairs
p[bB] [len] bitstream of N bytes
pc[p] [len] output C (or python) format
p[dD][lf] [l] disassemble N opcodes/bytes (see pd?)
pf[?|.nam] [fmt] print formatted data (pf.name, pf.name $<expr>)
p[iI][df] [len] print N instructions/bytes (f=func) (see pi? and pdi)
pm [magic] print libmagic data (pm? for more information)
pr [len] print N raw bytes
p[kK] [len] print key in randomart (K is for mosaic)
ps[pwz] [len] print pascal/wide/zero-terminated strings
pt[dn?] [len] print different timestamps
pu[w] [len] print N url encoded bytes (w=wide)
pv[jh] [mode] bar|json|histogram blocks (mode: e?search.in)
p[xX][owq] [len] hexdump of N bytes (o=octal, w=32bit, q=64bit)
pz [len] print zoom view (see pz? for help)
pwd display current working directory
```

## Hexadecimal View

`px` gives a user-friendly output showing 16 pairs of numbers per row with offsets and raw representations:

```
[0x00404888]> px
- offset - 0 1 2 3 4 5 6 7 8 9 A B C D E F 0123456789ABCDEF
0x00404888 31ed 4989 d15e 4889 e248 83e4 f050 5449 1.I..^H..H...PTI
0x00404898 c7c0 4024 4100 48c7 c1b0 2341 0048 c7c7 ..@$A.H...#A.H..
0x004048a8 d028 4000 e83f dcff fff4 6690 662e 0f1f .(@..?....f.f...
```

## Show Hexadecimal Words Dump (32 bits)

```
[0x00404888]> pxw
0x00404888 0x8949ed31 0x89485ed1 0xe48348e2 0x495450f0 1.I..^H..H...PTI
0x00404898 0x2440c0c7 0xc7480041 0x4123b0c1 0xc7c74800 ...@$A.H...#A.H..
0x004048a8 0x004028d0 0xffdc3fe8 0x9066f4ff 0x1f0f2e66 .(@..?....f.f...

[0x00404888]> e cfg.bigEndian
false

[0x00404888]> e cfg.bigEndian = true

[0x00404888]> pxw
0x00404888 0x31ed4989 0xd15e4889 0xe24883e4 0xf0505449 1.I..^H..H...PTI
0x00404898 0xc7c04024 0x410048c7 0xc1b02341 0x0048c7c7 ...@$A.H...#A.H..
0x004048a8 0xd0284000 0xe83fdcff 0xffff46690 0x662e0f1f .(@..?....f.f...
```

## 8 bits Hexpair List of Bytes

```
[0x00404888]> p8 16
31ed4989d15e4889e24883e4f0505449
```

## Show Hexadecimal Quad-words Dump (64 bits)

```
[0x08049A80]> pxq
0x00001390 0x65625f6b63617473 0x646e6962006e6967 stack_begin.bind
0x000013a0 0x616d6f6474786574 0x7469727766006e69 textdomain.fwrit
0x000013b0 0x6b636f6c6e755f65 0x6d63727473006465 e_unlocked.strcm
...
```

## Date/Time Formats

Currently supported timestamp output modes are:

```
[0x00404888]> pt?
|Usage: pt[dn?]
| pt      print unix time (32 bit cfg.big_endian)
| ptd     print dos time (32 bit cfg.big_endian)
| ptn     print ntfs time (64 bit !cfg.big_endian)
| pt?    show help message
```

For example, you can 'view' the current buffer as timestamps in the ntfs time:

```
[0x08048000]> eval cfg.bigendian = false
[0x08048000]> pt 4
29:04:32948 23:12:36 +0000
[0x08048000]> eval cfg.bigendian = true
[0x08048000]> pt 4
20:05:13001 09:29:21 +0000
```

As you can see, the endianness affects the result. Once you have printed a timestamp, you can grep output, for example, by year value:

```
[0x08048000]> pt | grep 1974 | wc -l
15
[0x08048000]> pt | grep 2022
27:04:2022 16:15:43 +0000
```

The default date format can be configured using the `cfg.datefmt` variable. Formatting rules for it follow the well known `strftime(3)` format. An excerpt from the `strftime(3)` manpage:

```
%a The abbreviated name of the day of the week according to the current locale.
%A The full name of the day of the week according to the current locale.
%b The abbreviated month name according to the current locale.
%B The full month name according to the current locale.
%c The preferred date and time representation for the current locale.
%C The century number (year/100) as a 2-digit integer. (SU)
%d The day of the month as a decimal number (range 01 to 31).
%D Equivalent to %m/%d/%y. (Yecch—for Americans only. Americans should note that in other countries %d/%m/%y is rather common. This means that in international context this format is ambiguous and should not be used.) (SU)
%e Like %d, the day of the month as a decimal number, but a leading zero is replaced by a space. (SU)
%E Modifier: use alternative format, see below. (SU)
%F Equivalent to %Y-%m-%d (the ISO 8601 date format). (C99)
%G The ISO 8601 week-based year (see NOTES) with century as a decimal number. The 4-digit year corresponding to the ISO week number (see %V). This has the same format and value as %Y, except that if the ISO week number belongs to the previous or next year, that year is used instead. (TZ)
%g Like %G, but without century, that is, with a 2-digit year (00-99). (TZ)
%h Equivalent to %b. (SU)
%H The hour as a decimal number using a 24-hour clock (range 00 to 23).
%I The hour as a decimal number using a 12-hour clock (range 01 to 12).
%j The day of the year as a decimal number (range 001 to 366).
%k The hour (24-hour clock) as a decimal number (range 0 to 23); single digits are preceded by a blank. (See also %H.) (TZ)
%l The hour (12-hour clock) as a decimal number (range 1 to 12); single digits are preceded by a blank. (See also %I.) (TZ)
%m The month as a decimal number (range 01 to 12).
%M The minute as a decimal number (range 00 to 59).
%n A newline character. (SU)
%O Modifier: use alternative format, see below. (SU)
```

```
%p Either "AM" or "PM" according to the given time value, or the corresponding string
s for the current locale. Noon is treated as "PM" and midnight as "AM".
%P Like %p but in lowercase: "am" or "pm" or a corresponding string for the current l
ocale. (GNU)
%r The time in a.m. or p.m. notation. In the POSIX locale this is equivalent to %I:%
M:%S %p. (SU)
%R The time in 24-hour notation (%H:%M). (SU) For a version including the seconds, s
ee %T below.
%s The number of seconds since the Epoch, 1970-01-01 00:00:00 +0000 (UTC). (TZ)
%S The second as a decimal number (range 00 to 60). (The range is up to 60 to allow
for occasional leap seconds.)
%t A tab character. (SU)
%T The time in 24-hour notation (%H:%M:%S). (SU)
%u The day of the week as a decimal, range 1 to 7, Monday being 1. See also %w. (SU
)
%U The week number of the current year as a decimal number, range 00 to 53, starting
with the first Sunday as the first day of week 01. See also %V and %W.
%V The ISO 8601 week number (see NOTES) of the current year as a decimal number, rang
e 01 to 53, where week 1 is the first week that has at least 4 days in the new year.
See also %U and %W.(U)
%w The day of the week as a decimal, range 0 to 6, Sunday being 0. See also %u.
%W The week number of the current year as a decimal number, range 00 to 53, starting
with the first Monday as the first day of week 01.
%x The preferred date representation for the current locale without the time.
%X The preferred time representation for the current locale without the date.
%y The year as a decimal number without a century (range 00 to 99).
%Y The year as a decimal number including the century.
%z The +hhmm or -hhmm numeric timezone (that is, the hour and minute offset from UTC)
. (SU)
%Z The timezone name or abbreviation.
%+ The date and time in date(1) format. (TZ) (Not supported in glibc2.)
%% A literal '%' character.
```

## Basic Types

There are print modes available for all basic types. If you are interested in a more complex structure, just type : `pf?`. The list of the print modes for basic types ( `pf?` ):

```
Usage: pf[.key[.field[=value]]|[ val]][[times][format] [arg0 arg1 ...]
Examples:
  pf 10xiz pointer length string
  pf {array_size}b @ array_base
  pf.          # list all formats
  pf.obj xxdz prev next size name
  pf.obj      # run stored format
  pf.obj.name # show string inside object
  pf.obj.size=33 # set new size
Format chars:
  e - temporally swap endian
  f - float value (4 bytes)
  c - char (signed byte)
  b - byte (unsigned)
  B - show 10 first bytes of buffer
  i - %i integer value (4 bytes)
  w - word (2 bytes unsigned short in hex)
  q - quadword (8 bytes)
  p - pointer reference (2, 4 or 8 bytes)
  d - 0x%08x hexadecimal value (4 bytes)
  D - disassemble one opcode
  x - 0x%08x hexadecimal value and flag (fd @ addr)
  z - \0 terminated string
  Z - \0 terminated wide string
  s - 32bit pointer to string (4 bytes)
  S - 64bit pointer to string (8 bytes)
  * - next char is pointer (honors asm.bits)
  + - toggle show flags for each offset
  : - skip 4 bytes
  . - skip 1 byte
```

Some examples are below:

```
[0x4A13B8C0]> pf i
0x00404888 = 837634441

[0x4A13B8C0]> pf
0x00404888 = 837634432.000000
```

## High-level Languages Views

Valid print code formats for human-readable languages are:

```

pc      C
pcs    string
pcj    json
pcJ    javascript
pcp    python
pcw    words (4 byte)
pcd    dwords (8 byte)

[0xB7F8E810]> pc 32
#define _BUFFER_SIZE 32
unsigned char buffer[_BUFFER_SIZE] = {
0x89, 0xe0, 0xe8, 0x49, 0x02, 0x00, 0x89, 0xc7, 0xe8, 0xe2, 0xff, 0xff, 0xff, 0x
81, 0xc3, 0xd6, 0xa7, 0x01, 0x00, 0x8b, 0x83, 0x00, 0xff, 0xff, 0xff, 0x5a, 0x8d, 0x24
, 0x84, 0x29, 0xc2 };

[0x7fc6a891630]> pcs
"\x48\x89\xe7\xe8\x68\x39\x00\x00\x49\x89\xc4\x8b\x05\xef\x16\x22\x00\x5a\x48\x8d\x24\
\xc4\x29\xc2\x52\x48\x89\xd6\x49\x89\xe5\x48\x83\xe4\xf0\x48\x8b\x3d\x06\x1a"

```

## Strings

Strings are probably one of the most important entrypoints when starting to reverse engineer a program, because they usually reference information about functions' actions (asserts, debug or info messages...) Therefore radare supports various string formats:

```

[0x00000000]> ps?
|Usage: ps[zpw] [N]Print String
| ps   print string
| psi  print string inside curseek
| psb  print strings in current block
| psx  show string with escaped chars
| psz  print zero terminated string
| psp  print pascal string
| psu  print utf16 unicode (json)
| psw  print wide string
| psj  print string in JSON format

```

Most strings are zero-terminated. Here is an example by using the debugger to continue the execution of a program until it executes the 'open' syscall. When we recover the control over the process, we get the arguments passed to the syscall, pointed by %ebx. In the case of the 'open' call, it is a zero terminated string which we can inspect using `psz`.

```
[0x4A13B8C0]> dcs open
0x4a14fc24 syscall(5) open ( 0x4a151c91 0x00000000 0x00000000 ) = 0xffffffffda
[0x4A13B8C0]> dr
  eax 0xffffffffda    esi 0xffffffff    eip 0x4a14fc24
  ebx 0x4a151c91    edi 0x4a151be1    oeax 0x00000005
  ecx 0x00000000    esp 0xbfbbedb1c    eflags 0x200246
  edx 0x00000000    ebp 0xbfbbedbb0    cPaZstIdor0 (PZI)
[0x4A13B8C0]>
[0x4A13B8C0]> psz @ 0x4a151c91
/etc/ld.so.cache
```

## Print Memory Contents

It is also possible to print various packed data types using the `pf` command:

```
[0xB7F08810]> pf xxS @ rsp
0x7fff0d29da30 = 0x00000001
0x7fff0d29da34 = 0x00000000
0x7fff0d29da38 = 0x7fff0d29da38 -> 0xd29f7ee /bin/ls
```

This can be used to look at the arguments passed to a function. To achieve this, simply pass a 'format memory string' as an argument to `pf`, and temporally change current seek position / offset using `@`. It is also possible to define arrays of structures with `pf`. To do this, prefix the format string with a numeric value. You can also define a name for each field of the structure by appending them as a space-separated arguments list.

```
[0x4A13B8C0]> pf 2*xw pointer type @ esp
0x00404888 [0] {
  pointer :
  (*0xffffffff8949ed31)      type : 0x00404888 = 0x8949ed31
  0x00404890 = 0x48e2
}
0x00404892 [1] {
  (*0x50f0e483)      pointer : 0x00404892 = 0x50f0e483
  type : 0x0040489a = 0x2440
}
```

A practical example for using `pf` on a binary of a GStreamer plugin:

```
$ radare ~/.gstreamer-0.10/plugins/libgstflumms.so
[0x000028A0]> seek sym.gst_plugin_desc
[0x000185E0]> pf iissxsssss major minor name desc _init version \
    license source package origin
    major : 0x000185e0 = 0
    minor : 0x000185e4 = 10
    name : 0x000185e8 = 0x000185e8 flumms
    desc : 0x000185ec = 0x000185ec Fluendo MMS source
    _init : 0x000185f0 = 0x00002940
    version : 0x000185f4 = 0x000185f4 0.10.15.1
    license : 0x000185f8 = 0x000185f8 unknown
    source : 0x000185fc = 0x000185fc gst-fluendo-mms
    package : 0x00018600 = 0x00018600 Fluendo MMS source
    origin : 0x00018604 = 0x00018604 http://www.fluendo.com
```

## Disassembly

The `pd` command is used to disassemble code. It accepts a numeric value to specify how many instructions should be disassembled. The `pD` command is similar but instead of a number of instructions, it decompiles a given number of bytes.

```
d : disassembly N opcodes      count of opcodes
D : asm.arch disassembler     bsize bytes

[0x00404888]> pd 1
    ;-- entry0:
    0x00404888 31ed          xor ebp, ebp
```

## Selecting Target Architecture

The architecture flavor for disassembler is defined by the `asm.arch` eval variable. You can use `e asm.arch = ?` to list all available architectures.

```
[0xB7F08810]> e asm.arch = ?

_d 16          8051      PD      8051 Intel CPU
_d 16 32       arc       GPL3    Argonaut RISC Core
ad 16 32 64    arm       GPL3    Acorn RISC Machine CPU
_d 16 32 64    arm.cs    BSD     Capstone ARM disassembler
_d 16 32       arm.winedbg LGPL2   WineDBG's ARM disassembler
_d 16 32       avr       GPL     AVR Atmel
ad 32          bf        LGPL3   Brainfuck
_d 16          cr16      LGPL3   cr16 disassembly plugin
_d 16          csr       PD      Cambridge Silicon Radio (CSR)
ad 32 64       dalvik    LGPL3   AndroidVM Dalvik
ad 16          dcpu16    PD      Mojang's DCPU-16
_d 32 64       ebc       LGPL3   EFI Bytecode
_d 8           gb        LGPL3   GameBoy(TM) (z80-like)
_d 16          h8300     LGPL3   H8/300 disassembly plugin
_d 8           i8080     BSD     Intel 8080 CPU
ad 32          java      Apache  Java bytecode
_d 16 32       m68k      BSD     Motorola 68000
_d 32          malbolge  LGPL3   Malbolge Ternary VM
ad 32 64       mips      GPL3   MIPS CPU
_d 16 32 64    mips.cs   BSD     Capstone MIPS disassembler
_d 16 32 64    msil      PD      .NET Microsoft Intermediate Language
_d 32          nios2     GPL3   NIOS II Embedded Processor
_d 32 64       ppc       GPL3   PowerPC
_d 32 64       ppc.cs    BSD     Capstone PowerPC disassembler
ad             rar       LGPL3   RAR VM
_d 32          sh        GPL3   SuperH-4 CPU
_d 32 64       sparc     GPL3   Scalable Processor Architecture
_d 32          tms320    LGPLv3  TMS320 DSP family
_d 32          ws        LGPL3   Whitespace esoteric VM
_d 16 32 64    x86      BSD     udis86 x86-16,32,64
_d 16 32 64    x86.cs   BSD     Capstone X86 disassembler
a_ 32 64       x86.nz   LGPL3   x86 handmade assembler
ad 32          x86.olly  GPL2   OllyDBG X86 disassembler
ad 8           z80       NC-GPL2 Zilog Z80
```

## Configuring the Disassembler

There are multiple options which can be used to configure the output of disassembler. All these options are described in `e? asm.`

```

        asm.os: Select operating system (kernel) (linux, darwin, w32,...)
        asm.bytes: Display the bytes of each instruction
        asm.cmtflrefs: Show comment flags associated to branch referece
        asm.cmtright: Show comments at right of disassembly if they fit in screen
        asm.comments: Show comments in disassembly view
        asm.decode: Use code analysis as a disassembler
        asm.dwarf: Show dwarf comment at disassembly
        asm.esil: Show ESIL instead of mnemonic
        asm.filter: Replace numbers in disassembly using flags containing a dot in t
he name in disassembly
        asm.flags: Show flags
        asm.lbytes: Align disasm bytes to left
        asm.lines: If enabled show ascii-art lines at disassembly
        asm.linecall: Enable call lines
        asm.linesout: If enabled show out of block lines
        asm.linesright: If enabled show lines before opcode instead of offset
        asm.linesstyle: If enabled iterate the jump list backwards
        asm.linewidth: If enabled put an space between lines
        asm.middle: Allow disassembling jumps in the middle of an instruction
        asm.offset: Show offsets at disassembly
        asm.pseudo: Enable pseudo syntax
        asm.size: Show size of opcodes in disassembly (pd)
        asm.stackptr: Show stack pointer at disassembly
        asm.cycles: Show cpu-cycles taken by instruction at disassembly
        asm.tabs: Use tabs in disassembly
        asm.trace: Show execution traces for each opcode
        asm.ucase: Use uppercase syntax at disassembly
        asm.varsub: Substitute variables in disassembly
        asm.arch: Set the arch to be used by asm
        asm.parser: Set the asm parser to use
        asm.segoff: Show segmented address in prompt (x86-16)
        asm.cpu: Set the kind of asm.arch cpu
        asm.profile: configure disassembler (default, simple, gas, smart, debug, full
)
        asm.xrefs: Show xrefs in disassembly
        asm.functions: Show functions in disassembly
        asm.syntax: Select assembly syntax
        asm.nbytes: Number of bytes for each opcode at disassembly
        asm.bytespace: Separate hex bytes with a whitespace
        asm.bits: Word size in bits at assembler
        asm.linewidth: Number of columns for program flow arrows
    
```

## Disassembly Syntax

The `asm.syntax` variable is used to change flavor of assembly syntax used by a disassembler engine. To switch between Intel and AT&T representations:

```

e asm.syntax = intel
e asm.syntax = att
    
```

You can also check `asm.pseudo`, which is an experimental pseudocode view, and `asm.esil` which outputs ESIL ('Evaluable Strings Intermediate Language'). ESIL's goal is to have a human-readable representation of every opcode semantics. Such representations can be evaluated (interpreted) to emulate effects of individual instructions.

# Flags

Flags are similar to bookmarks. They represent a certain offset in a file. Flags can be grouped in 'flag spaces'. A flag space is something like a namespace for flags. They are used to group flags of similar characteristic or type. Examples for flag spaces: sections, registers, symbols.

To create a flag type:

```
[0x4A13B8C0]> f flag_name @ offset
```

You can remove a flag by appending the `-` character to command. Most of commands accept `-` as argument-prefix as an indication to delete something.

```
[0x4A13B8C0]> f- flag_name
```

To switch between or create new flagspaces use the `fs` command:

```
# List flag spaces
[0x4A13B8C0]> fs

00  symbols
01  imports
02  sections
03  strings
04  regs
05  maps

[0x4A13B8C0]> fs symbols ; select only flags in symbols flagspace
[0x4A13B8C0]> f           ; list only flags in symbols flagspace
[0x4A13B8C0]> fs *        ; select all flagspaces
[0x4A13B8C0]> f myflag   ; create a new flag called 'myflag'
[0x4A13B8C0]> f- myflag  ; delete the flag called 'myflag'
```

You can rename flags with `fr`.

# Writing Data

Radare can manipulate with a loaded binary file in many ways. You can resize the file, move and copy/paste bytes, insert new bytes (shifting data to the end of the block or file), or simply overwrite bytes. New data may come from another file contents, be a widestring, or even be represented as inline assembler statement.

To resize, use the `r` command. It accepts a numeric argument. A positive value sets new size to a file. A negative one will strip N bytes from the current seek, making the file smaller.

```
r 1024      ; resize the file to 1024 bytes
r -10 @ 33  ; strip 10 bytes at offset 33
```

To write bytes, use `w` command. It accepts multiple input formats, like inline assembly, endian-friendly dwords, files, hexpair files, wide strings:

```
[0x00404888]> w?
|Usage: w[x] [str] [<file> [<<EOF>] [@addr]
| w foobar      write string 'foobar'
| wh r2         whereis/which shell command
| wr 10         write 10 random bytes
| ww foobar     write wide string 'f\x00o\x00o\x00b\x00a\x00r\x00'
| wa push ebp   write opcode, separated by ';' (use ''' around the command)
| waf file     assemble file and write bytes
| wA r 0        alter/modify opcode at current seek (see wA?)
| wb 010203    fill current block with cyclic hexpairs
| wc[ir*?]     write cache undo/commit/reset/list (io.cache)
| wx 9090       write two intel nops
| wv eip+34    write 32-64 bit value
| wo? hex      write in block with operation. 'wo?' fmi
| wm f0ff      set binary mask hexpair to be used as cyclic write mask
| ws pstring   write 1 byte for length and then the string
| wf -|file    write contents of file at current offset
| wF -|file    write contents of hexpairs file here
| wp -|file    apply radare patch file. See wp? fmi
| wt file [sz]  write to file (from current seek, blocksize or sz bytes)
```

Some examples:

```
[0x0000000000]> wx 123456 @ 0x8048300
[0x0000000000]> wv 0x8048123 @ 0x8049100
[0x0000000000]> wa jmp 0x8048320
```

## Write Over

The `wo` command (write over) has many subcommands. It is applied to the current block. Supported operations: XOR, ADD, SUB...

```
[0x4A13B8C0]> wo?
|Usage: wo[asmdxoAr124] [hexpairs] @ addr[:bsize]
|Example:
| wox 0x90    ; xor cur block with 0x90
| wox 90      ; xor cur block with 0x90
| wox 0x0203 ; xor cur block with 0203
| woa 02 03   ; add [0203][0203][...] to curblk
| woe 02 03
|Supported operations:
| wow == write looped value (alias for 'wb')
| woa += addition
| wos -= subtraction
| wom *= multiply
| wod /= divide
| wox ^= xor
| woo |= or
| woA &= and
| woR random bytes (alias for 'wr $b')
| wor >>= shift right
| wol <<= shift left
| wo2 2= 2 byte endian swap
| wo4 4= 4 byte endian swap
```

It is possible to implement cipher-algorithms using radare core primitives and `wo`. A sample session performing `xor(90) + add(01, 02)`:

```
[0x7fcd6a891630]> px
- offset -      0 1 2 3 4 5 6 7 8 9  A B  C D  E F  0123456789ABCDEF
0x7fcd6a891630 4889 e7e8 6839 0000 4989 c48b 05ef 1622 H...h9..I....."
0x7fcd6a891640 005a 488d 24c4 29c2 5248 89d6 4989 e548 .ZH.$.).RH..I..H
0x7fcd6a891650 83e4 f048 8b3d 061a 2200 498d 4cd5 1049 ...H.=.."I.L..I
0x7fcd6a891660 8d55 0831 ede8 06e2 0000 488d 15cf e600 .U.1.....H.....

[0x7fcd6a891630]> wox 90
[0x7fcd6a891630]> px
- offset -      0 1 2 3 4 5 6 7 8 9  A B  C D  E F  0123456789ABCDEF
0x7fcd6a891630 d819 7778 d919 541b 90ca d81d c2d8 1946 ..wx..T.....F
0x7fcd6a891640 1374 60d8 b290 d91d 1dc5 98a1 9090 d81d .t`.....
0x7fcd6a891650 90dc 197c 9f8f 1490 d81d 95d9 9f8f 1490 ...|.....
0x7fcd6a891660 13d7 9491 9f8f 1490 13ff 9491 9f8f 1490 ..... .

[0x7fcd6a891630]> woa 01 02
[0x7fcd6a891630]> px
- offset -      0 1 2 3 4 5 6 7 8 9  A B  C D  E F  0123456789ABCDEF
0x7fcd6a891630 d91b 787a 91cc d91f 1476 61da 1ec7 99a3 ..xz.....va.....
0x7fcd6a891640 91de 1a7e d91f 96db 14d9 9593 1401 9593 ...~.....
0x7fcd6a891650 c4da 1a6d e89a d959 9192 9159 1cb1 d959 ...m...Y...Y...Y
0x7fcd6a891660 9192 79cb 81da 1652 81da 1456 a252 7c77 ..y....R...V.R|w
```

# Zoom

The zoom is a print mode that allows you to get a global view of the whole file or a memory map on a single screen. In this mode, each byte represents `file_size/block_size` bytes of the file. Use the `p0` (zoom out print mode) to enter this mode, or just toggle `z` in the visual mode to zoom-out/zoom-in.

The cursor can be used to scroll faster through the zoom out view. Pressing `z` again will zoom-in where at new cursor position.

```
[0x004048c5]> pz?
|Usage: pz [len] print zoomed blocks (filesize/N)
| e zoom.maxsz  max size of block
| e zoom.from   start address
| e zoom.to     end address
| e zoom.byte   specify how to calculate each byte
| pzp          number of printable chars
| pzf          count of flags in block
| pzs          strings in range
| pz0          number of bytes with value '0'
| pzF          number of bytes with value 0xFF
| pze          calculate entropy and expand to 0-255 range
| pzh          head (first byte value); This is the default mode
```

Let's see some examples:

```
[0x08049790]> pz // or default pzh

0x0000000000 7f00 0000 e200 0000 146e 6f74 0300 0000 .....not....
0x0000000010 0000 0000 0068 2102 00ff 2024 e8f0 007a .....h!...$...z
0x0000000020 8c00 18c2 ffff 0080 4421 41c4 1500 5dff .....D!A...].
0x0000000030 ff10 0018 0fc8 031a 000c 8484 e970 8648 .....p.H
0x0000000040 d68b 3148 348b 03a0 8b0f c200 5d25 7074 ..1H4.....]%pt
0x0000000050 7500 00e1 ffe8 58fe 4dc4 00e0 dbc8 b885 u.....X.M.....
```

```
[0x08049790]> e zoom.byte=p
[0x08049790]> p0 // or pzp

0x0000000000 2f47 0609 070a 0917 1e9e a4bd 2a1b 2c27 /G.....*.,'
0x0000000010 322d 5671 8788 8182 5679 7568 82a2 7d89 2-Vq....Vyu..}.
0x0000000020 8173 7f7b 727a 9588 a07b 5c7d 8daf 836d .s.{rz...{\}...m
0x0000000030 b167 6192 a67d 8aa2 6246 856e 8c9b 999f .ga..}..bF.n....
0x0000000040 a774 96c3 b1a4 6c8e a07c 6a8f 8983 6a62 .t....l..|j...jb
0x0000000050 7d66 625f 7ea4 7ea6 b4b6 8b57 a19f 71a2 }fb_~.~....W..q.
```

```
[0x08049790]> eval zoom.byte = flags
[0x08049790]> p0 // or pzf

0x00406e65 48d0 80f9 360f 8745 ffff ffef ae66 0f1f H...6..E....f..
0x00406e75 4400 0083 f801 0f85 3fff ffff 410f b600 D.....?....A...
0x00406e85 3c78 0f87 6301 0000 0fb6 c8ff 24cd 0026 <x..c.....$..&
0x00406e95 4100 660f 1f84 0000 0000 0084 c074 043c A.f.....t.<
0x00406ea5 3a75 18b8 0500 0000 83f8 060f 95c0 e9cd :u.....
0x00406eb5 feff ff0f 1f84 0000 0000 0041 8801 4983 .....A..I.
0x00406ec5 c001 4983 c201 4983 c101 e9ec feff ff0f ..I....I.....
```

```
[0x08049790]> e zoom.byte=F
[0x08049790]> p0 // or pzF

0x0000000000 0000 0000 0000 0000 0000 0000 0000 0000 .....
0x0000000010 0000 2b5c 5757 3a14 331f 1b23 0315 1d18 ..+\WW:.3..#....
0x0000000020 222a 2330 2b31 2e2a 1714 200d 1512 383d "*/#0+1.*...8=
0x0000000030 1e1a 181b 0a10 1a21 2a36 281e 1d1c 0e11 .....!*6(....
0x0000000040 1b2a 2f22 2229 181e 231e 181c 1913 262b .*"/")..#....&+
0x0000000050 2b30 4741 422f 382a 1e22 0f17 0f10 3913 +0GAB/8*. ....9.
```

You can limit zooming to a range of bytes instead of the whole bytespace. Change `zoom.from` and `zoom.to` eval variables:

```
[0x465D8810]> e zoom.
zoom.byte = f
zoom.from = 0
zoom.maxsz = 512
zoom.to = 118368???
```



# Yank/Paste

You can yank/paste bytes in visual mode using the `y` and `Y` key bindings which are aliases for `y` and `yy` commands of command-line interface. These commands operate on an internal buffer which stores copies of bytes taken starting from the current seek position. You can write this buffer back to different seek position using `yy` command:

```
[0x00000000]> y?
|Usage: y[ptxy] [len] [[@]addr]
| y           show yank buffer information (srcoff len bytes)
| y 16        copy 16 bytes into clipboard
| y 16 0x200  copy 16 bytes into clipboard from 0x200
| y 16 @ 0x200 copy 16 bytes into clipboard from 0x200
| yp          print contents of clipboard
| yx          print contents of clipboard in hexadecimal
| yt 64 0x200 copy 64 bytes from current seek to 0x200
| yf 64 0x200 file copy 64 bytes from 0x200 from file (opens w/ io), use -1 for all bytes
| yfa file copy copy all bytes from from file (opens w/ io)
| yy 0x3344   paste clipboard
```

Sample session:

```
[0x00000000]> s 0x100      ; seek at 0x100
[0x00000100]> y 100        ; yanks 100 bytes from here
[0x00000200]> s 0x200      ; seek 0x200
[0x00000200]> yy          ; pastes 100 bytes
```

You can perform a yank and paste in a single line by just using the `yt` command (yank-to). The syntax is as follows:

```
[0x4A13B8C0]> x
    offset  0 1 2 3 4 5 6 7 8 9  A B  0123456789AB
0x4A13B8C0, 89e0 e839 0700 0089 c7e8 e2ff ...9.....
0x4A13B8CC, ffff 81c3 eea6 0100 8b83 08ff .....
0x4A13B8D8, ffff 5a8d 2484 29c2      ..Z.$.)..

[0x4A13B8C0]> yt 8 0x4A13B8CC @ 0x4A13B8C0

[0x4A13B8C0]> x
    offset  0 1 2 3 4 5 6 7 8 9  A B  0123456789AB
0x4A13B8C0, 89e0 e839 0700 0089 c7e8 e2ff ...9.....
0x4A13B8CC, 89e0 e839 0700 0089 8b83 08ff ...9.....
0x4A13B8D8, ffff 5a8d 2484 29c2      ..Z.$.)..
```



# Comparing Bytes

`c` (short for "compare") allows you to compare arrays of bytes from different sources. The command accepts input in a number of formats, and then compares it against values found at current seek position.

```
[0x00404888]> c?
|Usage: c[?dfx] [argument]
| c [string]      Compares a plain with escaped chars string
| cc [at] [(at)]  Compares in two hexdump columns of block size
| c4 [value]       Compare a doubleword from a math expression
| c8 [value]       Compare a quadword from a math expression
| cx [hexpair]    Compare hexpair string
| cx [addr]        Like 'cc' but using hexdiff output
| cf [file]        Compare contents of file at current seek
| cg[o] [file]     Graphdiff current file and [file]
| cu [addr] @at   Compare memory hexdumps of $$ and dst in unified diff
| cw[us?] [...]   Compare memory watchers
| cat [file]       Show contents of file (see pwd, ls)
| cl|cls|clear    Clear screen, (clear0 to goto 0, 0 only)
```

To compare memory contents at current seek position against given string of values, use

`cx` :

```
[0x08048000]> p8 4
7f 45 4c 46

[0x08048000]> cx 7f 45 90 46
Compare 3/4 equal bytes
0x00000002 (byte=03) 90 ' ' -> 4c 'L'
[0x08048000]>
```

Another subcommand of `c` command is `cc` which stands for "compare code". To compare a byte sequence with a sequence in memory:

```
[0x4A13B8C0]> cc 0x39e8e089 @ 0x4A13B8C0
```

To compare contents of two functions specified by their names:

```
[0x08049A80]> cc sym.main2 @ sym.main
```

c8 compares a quadword from the current seek (in the example below, 0x00000000) against a math expression:

```
[0x00000000]> c8 4

Compare 1/8 equal bytes (0%)
0x00000000 (byte=01) 7f ' ' -> 04 ' '
0x00000001 (byte=02) 45 'E' -> 00 ' '
0x00000002 (byte=03) 4c 'L' -> 00 ' '
```

The number parameter can of course also be a math expressions which uses flag names etc:

```
[0x00000000]> cx 7f469046

Compare 2/4 equal bytes
0x00000001 (byte=02) 45 'E' -> 46 'F'
0x00000002 (byte=03) 4c 'L' -> 90 ' '
```

You can use compare command to find differences between a current block and a file previously dumped to a disk:

```
r2 /bin/true
[0x08049A80]> s 0
[0x08048000]> cf /bin/true
Compare 512/512 equal bytes
```

# Visual Mode

The visual mode is a more user-friendly interface alternative to radare2's command-line prompt. It uses HJKL or arrow keys to move around data and code, has a cursor mode for selecting bytes, and offers numerous key bindings to simplify debugger use. To enter visual mode, use `v` command. To exit from it back to command line, press `q`.

```
[0x00404890 16% 120 /bin/ls]> pd $r @ entry0
/fcn) entry0 42
;-- entry0:
0x00404890 31ed xor ebp, ebp
0x00404892 4989d1 mov r9, rdx
0x00404895 5e pop rsi
0x00404896 4889e2 mov rdx, rsp
0x00404899 4883c4f0 and rsp, 0xffffffffffff
0x0040489d 50 push rax
0x0040489e 54 push rsp
0x0040489f 49c7c0d01e41. mov r8, 0x411ed0
0x004048a0 48c7c1601e41. mov rcx, 0x411e60
0x004048a4 48c7c7c02840. mov rdi, main ; "AWAVAUATUH..S..H..
0x004048b4 e837dc ffff call sym.imp._libc_start_main ;[1]
sym.imp._libc_start_main(unk, unk, unk)
0x004048b9 f4 ht
0x004048ba 660f1f440000 nop word [rax + rax]
/fcn) fcn.004048c0 41
; CALL XREF from 0x0040493d (fcn.00404930)
0x004048c0 b8f5a61000 mov eax, 0x61a5ff ; "hstrtab" @ 0x6
0x004048c5 55 push rbp
0x004048c6 482df8a56100 sub rax, 0x61a5f8
0x004048cc 4883f80e cmp rax, 0xe
0x004048d0 4889e5 mov rbp, rsp

[0x00404890 16% 120 /bin/ls]> pc @ entry0
#define _BUFFER_SIZE 120
unsigned char buffer[120] =
0x31, 0xed, 0x49, 0x89, 0xd1, 0x5e, 0x48, 0x89, 0xe2, 0x48, 0x83,
0x44, 0xf0, 0x50, 0x54, 0x49, 0xc7, 0xc0, 0xd0, 0x1e, 0x41, 0x00,
0x48, 0xc7, 0xc1, 0x60, 0x1e, 0x41, 0x00, 0x48, 0xc7, 0xc0,
0x28, 0x40, 0x00, 0x8, 0x37, 0xdc, 0xff, 0xf4, 0x66, 0x0f,
0x1f, 0x44, 0x00, 0x00, 0xb8, 0xff, 0xa5, 0x61, 0x00, 0x55, 0x48,
0x2d, 0xf8, 0xa5, 0x61, 0x00, 0x48, 0x83, 0xf8, 0x0e, 0x48, 0x89,
0x5, 0x77, 0x02, 0x5d, 0xc3, 0xb8, 0x00, 0x00, 0x00, 0x48,
0x85, 0xc0, 0x74, 0xf4, 0x5d, 0xbff, 0x8f, 0xa5, 0x61, 0x00, 0xff,
0xe0, 0x1f, 0x80, 0x00, 0x00, 0x00, 0x00, 0xb8, 0xf8, 0xa5,
0x61, 0x00, 0x55, 0x48, 0x2d, 0xf8, 0xa5, 0x61, 0x00, 0x48, 0xc1,
0xf8, 0x03, 0x48, 0x89, 0xe5, 0x48, 0x89, 0x2c, 0x48, 0xc1];

[0x00404890 16% 368 /bin/ls]> x @ entry0
offset - 0 1 2 3 4 5 6 7 8 9 A B C D E F 0123456789ABCDEF
0x00404890 31ed 4989 d15e 4889 e248 83e4 f050 5449 1.I..^H...PTI
0x004048a0 c7c0 d01e 4100 48c7 c160 1e41 0048 c7c7 ....A.H..`A.H..
0x004048b0 c028 4000 e837 dcff fff4 660f 1f44 0000 .@(.7...f.D..
0x004048b4 b8f5 a561 0055 482d f8a5 6100 4883 f80e ...a.UH..a.H..
0x004048d0 4889 e577 025d c3b5 0000 0000 4885 c074 H.w....H.t
0x004048e0 f45d bff8 a561 00ff e0ff f1f80 0000 0000 .]...a.....
0x004048f0 b8f8 a561 0055 482d f8a5 6100 48c1 f803 ...a.UH..a.H..
0x00404900 4889 e548 89c2 48c1 ea3f 4801 d048 d1f8 H..H..?H..H..
0x00404910 7502 5dc3 ba00 0000 0048 85d2 74f4 5d48 u.]....H.t.]H
0x00404920 89c6 bfff a561 00ff e20f f1f80 0000 0000 .....a.....
0x00404930 803d 215d 2100 0075 1155 4889 e5e8 7eff .!=!]..u.UH...~.
0x00404940 ffff 5dc6 0500 5d21 0001 f3c3 0f1f 4000 .]...!]!..u.UH...~.
0x00404950 4883 d3a8 5421 0000 741e b800 0000 0048 H.=T!.t..H
0x00404960 85c0 7414 55bf 009e 6100 4889 e5ff d0ff .t.U..a.H..]
0x00404970 e97b ffff ff0f 1f80 e973 ffff ff0f 1f80 .{.....s....}
0x00404980 488b 0731 d248 f7f6 4889 d0c3 0f1f 4000 H..I..H..H..@.
0x00404990 31c0 488b 1648 3917 7406 f3c3 0f1f 4000 I..H..H.t..@.
0x004049a0 488b 4608 4839 4708 0f94 c0c3 0f1f 4000 H.F..H9G....@.
0x004049b0 8b05 8266 2100 85c0 7506 893d 7866 2100 ...f!...u..=xf!.
0x004049c0 f3c3 6666 6666 662e 0f1f 8400 0000 0000 .....ffff.....
0x004049d0 e91b d8f5 ff66 662e 0f1f 8400 0000 0000 .....ff.....
/fcn) entry0 42
;-- entry0:
0x00404890 31ed xor ebp, ebp
0x00404892 4989d1 mov r9, rdx
0x00404895 5e pop rsi
0x00404896 4889e2 mov rdx, rsp
0x00404899 4883c4f0 and rsp, 0xffffffffffff
0x0040489d 50 push rax
0x0040489e 54 push rsp
0x0040489f 49c7c0d01e41. mov r8, 0x411ed0
```

## print modes aka Panels

The Visual mode uses "print modes" which are basically different panel that you can rotate. By default those are:

⌚ Hexdump panel → Disassembly panel → Debugger panel → Hexadecimal words dump panel → Output C format panel → Op analysis color map panel → Annotated hexdump panel ⌚.

Notice that the top of the panel contains the commands which is used, for example for the disassembly panel:

```
[0x00404890 16% 120 /bin/ls]> pd $r @ entry0
```

## Getting Help

To see help on all key bindings defined for visual mode, press `? :`

```

Visual mode help:
?          show this help or manpage in cursor mode
&          rotate asm.bits between supported 8, 16, 32, 64
%          in cursor mode finds matching pair, otherwise toggle autoblocksz
@          set cmd.vprompt to run commands before the visual prompt
!          enter into the visual panels mode
-          enter the hud
=          set cmd.vprompt (top row)
|          set cmd.cprompt (right column)
.          seek to program counter
/          in cursor mode search in current block
:cmd       run radare command
;[-]cmt   add/remove comment
/*+-[]    change block size, [] = resize hex.cols
>||<     seek aligned to block size
a/A       (a)ssemble code, visual (A)ssembler
b          toggle breakpoint
c/C       toggle (c)ursor and (C)oolors
d[f?]    define function, data, code, ..
D          enter visual diff mode (set diff.from/to)
e          edit eval configuration variables
f/F       set/unset or browse flags. f- to unset, F to browse, ..
gG       go seek to begin and end of file (0-$s)
hjkl     move around (or HJKL) (left-down-up-right)
i          insert hex or string (in hexdump) use tab to toggle
mK/'K    mark/go to Key (any key)
M          walk the mounted filesystems
n/N       seek next/prev function/flag/hit (scr.nkey)
o          go/seek to given offset
O          toggle asm.esil
p/P       rotate print modes (hex, disasm, debug, words, buf)
q          back to radare shell
r          browse anal info and comments
R          randomize color palette (ecr)
ss        step / step over
T          enter textlog chat console (TT)
uu        undo/redo seek
v          visual code analysis menu
V          (V)iew graph using cmd.graph (agv?)
ww        seek cursor to next/prev word
xx        show xrefs/refs of current function from/to data/code
yy        copy and paste selection
z          toggle zoom mode
Enter     follow address of jump/call
Function Keys: (See 'e key.'), defaults to:
F2        toggle breakpoint
F7        single step
F8        step over
F9        continue

```



# Visual Disassembly

## Navigation

Move within the Disassembly using `arrows` or `hjk1`. Use `o` to seek directly to a flag or an offset, type it when requested by the prompt: `[offset]>`. Follow a jump or a call using the number of your keyboard `[0-9]` and the number on the right in disassembly to follow a call or a jump. In this example typing `1` on the keyboard would follow the call to `sym.imp.__libc_start_main` and therefore, seek at the offset of this symbol.

```
0x00404894      e857dcffff      call sym.imp.__libc_start_main ;[1]
```

Seek back to the previous location using `u`, `u` will allow you to redo the seek.

## d as define

`d` can be used to change the type of data of the current block, several basic types/structures are available as well as more advanced one using `pf` template:

```
d → ...
0x004048f7      48c1e83f      shr rax, 0x3f

d → b
0x004048f7 .byte 0x48
d → B
0x004048f7 .word 0xc148

d → d
0x004048f7 hex length=165 delta=0

0x004048f7 48c1 e83f 4801 c648 d1fe 7415 b800 0000 H..?H..H..t.....
...
...
```

To improve code readability change how radare2 presents numerical values in disassembly, by default most of disassembly display numerical value as hexadecimal. Sometimes you would like to view it as a decimal, binary or even custom defined constant. To change value format you can use `d` following by `i` then choose what base to work in, this is the equivalent to `ahi`:

```

d → i → ...
0x004048f7    48c1e83f    shr rax, 0x3f

d → i → 10
0x004048f7    48c1e83f    shr rax, 63

d → i → 2
0x004048f7    48c1e83f    shr rax, '?'

```

## Usage of the Cursor for Inserting/Patching...

Remember that, to be able to actually edit files loaded in radare2, you have to start it with `-w` option. Otherwise a file is opened in read-only mode.

Pressing lowercase `c` toggles the cursor mode. When this mode is active, currently selected byte (or byte range) is highlighted by having a highlighted background.

```
[0x00404890 16% 330 (0x6:-1=1)]> pd $r @ entry0+6 # 0x404896
/ (fcn) entry0 42
    ;-- entry0:
    0x00404890 31ed      xor ebp, ebp
    0x00404892 4989d1    mov r9, rdx
    0x00404895 5e        pop rst
    0x00404896 * 4889e2    mov rdx, rsp
    0x00404899 4883e4f0    and rsp, 0xfffffffffffffff0
    0x0040489d 50        push rax
    0x0040489e 54        push rsp
    0x0040489f 49c7c0d01e41. mov r8, 0x411ed0
    0x004048a6 48c7c1601e41. mov rcx, 0x411e60
    0x004048ad 48c7c7c02840. mov rdi, main           ; "AWAVAUATUH..S..H...." @ 0x4028c0
    0x004048b4 e837dcffff    call sym.imp.__libc_start_main ;[1]
    sym.imp.__libc_start_main(unk, unk)
    0x004048b9 f4        hlt
    0x004048ba 660f1f440000    nop word [rax + rax]
```

The cursor is used to select a range of bytes or simply to point to a byte. You can use the latter to create a named flag. Seek to required position, then press `f` and enter a name for a flag. If you select a range of bytes (with HJKL and SHIFT key pressed), and file write mode has been enabled with `-w` radare2 option, you can press `i` and then enter a byte array to overwrite selected range with new values, used as circular buffer. For example:

```
<select 10 bytes in visual mode using SHIFT+HJKL>
<press 'i' and then enter '12 34'>
```

10 bytes you have selected will be changed to "12 34" repeated in a circular manner: 12 34 12 34 12 34 12 34 12 34.

The Visual Assembler using `A`, this will give you a live-preview of the change you want to do in the disassembly.

## XREF

When radare2 has discovered a XREF during the analysis, it will show you the information in the Visual Disassembly using `XREF` tag:

```
; DATA XREF from 0x00402e0e (unk)
str.David_MacKenzie:
```

To see where this string is called press on `x`, if you want to jump to the location where the data is used then press the corresponding number [0-9] on your keyboard. (This functionality is similar to `axt`)

`x` corresponds to the reverse operation aka `axf`.

## Add a comment

To add a comment just press `;`.

## Type other commands

Quickly type commands using `:`.

## Search

`/`: allows highlighting in the current display. `:cmd` allows you to type r2 command which can give you more search possibility.

## The HUDS

### The "UserFriendly HUD"

Using `??` the "UserFriendly HUD" is displayed. It can be seen as an interactive Cheat sheet that one can complete with its own set of command. This HUD is convenient for newcomers. For experienced user, a HUD per type of activity could also be interesting when dealing with a lot of command within radare2.

### The "flag/comment/functions/.. HUD"

This HUD can be displayed using `_`, it basically shows a list of all the flags and will allow you to jump to it. Using the keyboard you can quickly filter flag that contain a specific pattern.

# Tweaking the Disassembly

You can change the disassembly look and feel by using the Visual Configuration Editor.

## Visual Configuration Editor

`ve` or `e` in visual mode allows you to edit radare2 configuration visually. For example, if you want to change the assembly display just select `asm` in the list and choose your assembly display flavor.

```
[EvalSpace]
anal
> asm
bin
cfg
cmd
dbg
diff
dir
esil
file
fs
graph
hex
http
hud
io
key
magic
pdb
rap
rop
scr
search
stack
time
zoom

Sel:asm.arch

/ (fcn) entry0 42
  ;-- entry0:
  0x00404890  31ed      xor ebp, ebp
  0x00404892  4989d1    mov r9, rdx
  0x00404895  5e         pop rsi
  0x00404896  4889e2    mov rdx, rsp
  0x00404899  4883e4f0  and rsp, 0xfffffffffffffff0
```

Example switch to pseudo disassembly:

```
[EvalSpace < Variables: asm.arch]

asm.functions = true
asm.indent = false
asm.lbytes = true
asm.lines = true
asm.linescall = false
asm.linesout = true
asm.linesright = false
asm.linesstyle = false
asm.lineswide = false
asm.linewidth = 7
asm.maxrefs = 5
asm.middle = false
asm.nbytes = 6
asm.offset = true
asm.os = linux
asm.parser = x86.pseudo
> asm.pseudo = false
asm.reloff = false
asm.section = false
asm.segoff = false
asm.size = false
asm.stackptr = false
asm.syntax = intel
asm.tabs = 0
asm.trace = false
asm.tracespace = false
asm.ucase = false
asm.vars = true
asm.varsub = true
asm.varxs = false
asm.xrefs = true

Selected: asm.pseudo (Enable pseudo syntax)

/ (fcn) entry0 42
| -- entry0:
|   0x00404890  31ed          xor    ebp, ebp
|   0x00404892  4989d1        mov    r9, rdx
|   0x00404895  5e             pop    rsi
|   0x00404896  4889e2        mov    rdx, rsp
|   0x00404899  4883e4f0      and    rsp, 0xfffffffffffffff0
```

```
[EvalSpace < Variables: asm.arch]

asm.functions = true
asm.indent = false
asm.lbytes = true
asm.lines = true
asm.linescall = false
asm.linesout = true
asm.linesright = false
asm.linesstyle = false
asm.lineswide = false
asm.linewidth = 7
asm.maxrefs = 5
asm.middle = false
asm.nbytes = 6
asm.offset = true
asm.os = linux
asm.parser = x86.pseudo
> asm.pseudo = true
asm.reloff = false
asm.section = false
asm.segoff = false
asm.size = false
asm.stackptr = false
asm.syntax = intel
asm.tabs = 0
asm.trace = false
asm.tracespace = false
asm.ucase = false
asm.vars = true
asm.varsub = true
asm.varxs = false
asm.xrefs = true

Selected: asm.pseudo (Enable pseudo syntax)

/ (fcn) entry0 42
  ;-- entry0:
  0x00404890  31ed          ebp = 0
  0x00404892  4989d1        r9 = rdx
  0x00404895  5e             pop rsi
  0x00404896  4889e2        rdx = rsp
  0x00404899  4883e4f0      rsp &= 0xfffffffffffffff0
```

Following are some example of eval variable related to disassembly.

## Examples

### **asm.arch: Change Architecture && asm.bits: Word size in bits at assembler**

You can view the list of all arch using `e asm.arch=?`

```
e asm.arch = dalvik
    0x00404870    31ed4989    cmp-long v237, v73, v137
    0x00404874    d15e4889    rsub-int v14, v5, 0x8948
    0x00404878    e24883e4    ushr-int/lit8 v72, v131, 0xe4
    0x0040487c    f0505449c7c0  +invoke-object-init-range {}, method+18772
; [0]
    0x00404882    90244100    add-int v36, v65, v0
```

```
e asm.bits = 16
    0000:4870    31ed        xor bp, bp
    0000:4872    49          dec cx
    0000:4873    89d1        mov cx, dx
    0000:4875    5e          pop si
    0000:4876    48          dec ax
    0000:4877    89e2        mov dx, sp
```

This latest operation can also be done using `&` in Visual mode.

## asm.pseudo: Enable pseudo syntax

```
e asm.pseudo = true
    0x00404870    31ed        ebp = 0
    0x00404872    4989d1    r9 = rdx
    0x00404875    5e          pop rsi
    0x00404876    4889e2    rdx = rsp
    0x00404879    4883e4f0  rsp &= 0xfffffffffffff0
```

## asm.syntax: Select assembly syntax (intel, att, masm...)

```
e asm.syntax = att
    0x00404870    31ed        xor %ebp, %ebp
    0x00404872    4989d1    mov %rdx, %r9
    0x00404875    5e          pop %rsi
    0x00404876    4889e2    mov %rsp, %rdx
    0x00404879    4883e4f0  and $0xfffffffffffff0, %rsp
```

## asm.describe: Show opcode description

```
e asm.describe = true
    0x00404870      31ed        xor ebp, ebp           ; logical exclusive or
    0x00404872      4989d1        mov r9, rdx          ; moves data from src to dst
    0x00404875      5e          pop rsi             ; pops last element of stack and stores the result in argument
    0x00404876      4889e2        mov rdx, rsp          ; moves data from src to dst
    0x00404879      4883e4f0        and rsp, 0xfffffffffffffff0 ; binary and operation between src and dst, stores result on dst
```

# Searching for Bytes

The radare2 search engine is based on work done by esteve, plus multiple features implemented on top of it. It supports multiple keyword searches, binary masks, hexadecimal. It automatically flags search hit entries to ease future referencing. Search is initiated by `/` command.

```
[0x0000000000]> /?
Usage: /[amx/] [arg]
/f foo\x00      search for string `foo\0`
/w foo          search for wide string `f\00\00\0` 
/wi foo         search for wide string ignoring case `f\00\00\0` 
/! ff           search for first occurrence not matching 
/i foo          search for string `foo` ignoring case 
/e /E.F/i       match regular expression 
/x ff0033       search for hex string 
/x ff..33       search for hex string ignoring some nibbles 
/x ff43 ffd0    search for hexpair with mask 
/d 101112       search for a deltified sequence of bytes 
/!x 00          inverse hexa search (find first byte != 0x00) 
/c jmp [esp]    search for asm code (see search.asmstr) 
/a jmp eax      assemble opcode and search its bytes 
/A              search for AES expanded keys 
/r sym.printf  analyze opcode reference an offset 
/R              search for ROP gadgets 
/P              show offset of previous instruction 
/m magicfile   search for matching magic file (use blocksize) 
/p patternsize  search for pattern of given size 
/z min max     search for strings of given size 
/v[?248] num   look for a asm.bigendian 32bit value 
//              repeat last search 
/b              search backwards
```

Because everything is treated as a file in radare2, it does not matter whether you search in a socket, a remote device, in process memory, or a file.

# Basic Search

A basic search for a plain text string in a file would be something like:

```
$ r2 -q -c "/ lib" /bin/ls
Searching 3 bytes from 0x00400000 to 0x0041ae08: 6c 69 62
hits: 9
0x00400239 hit0_0 "lib64/ld-linux-x86-64.so.2"
0x00400f19 hit0_1 "libselinux.so.1"
0x00400fae hit0_2 "librt.so.1"
0x00400fc7 hit0_3 "libacl.so.1"
0x00401004 hit0_4 "libc.so.6"
0x004013ce hit0_5 "libc_start_main"
0x00416542 hit0_6 "libs/"
0x00417160 hit0_7 "lib/xstrtol.c"
0x00417578 hit0_8 "lib"
```

As it can been seen from the output above, radare2 generates a "hit" flag for every entry found. Then you can use `ps` command to see strings at offsets stored in this group of flags:

```
[0x00404888]> / ls
...
[0x00404888]> ps @ hit0_0
lseek
```

You can also search for wide-char strings (e.g., ones containing zeros between letters) using the `/w` in this way:

```
[0x0000000000]> /w Hello
0 results found.
```

To perform a case-insensitive search for strings use `/i`:

```
[0x0040488f]> /i Stallman
Searching 8 bytes from 0x00400238 to 0x0040488f: 53 74 61 6c 6c 6d 61 6e
[# ]hits: 004138 < 0x0040488f hits = 0
```

It is possible to specify hexadecimal escape sequences in the search string by prepending them with "\x":

```
[0x0000000000]> / \xFELF
```

But, if you look for a string of hexadecimal values, you would most likely prefer to pass it as hexpairs. Use `/x` command:

```
[0x00000000]> /x 7F454C46
```

Once the search is done, results are stored in the `search` flag space.

```
[0x00000000]> f
0x000000135 512 hit0_0
0x000000b71 512 hit0_1
0x000000bad 512 hit0_2
0x000000bdd 512 hit0_3
0x000000bfb 512 hit0_4
0x000000f2a 512 hit0_5
```

To remove "hit" flags after you do not need them anymore, use the `f@-hit*` command.

Often, during long search sessions, you will need to launch the latest search more than once. Rather than type the same string over and over again, you will probably prefer to use the `//` command.

```
[0x000000f2a]> //      ; repeat last search
```

# Configuring Search Options

The radare2 search engine can be configured through several configuration variables, modifiable with `e` command.

```
e cmd.hit = x      ; radare2 command to execute on every search hit
e search.distance = 0 ; search string distance
e search.in = [foo]   ; search scope limit. Supported values: raw, block, file, section
e search.align = 4    ; only show search results aligned by specified boundary.
e search.from = 0     ; start address
e search.to = 0       ; end address
e search.asmstr = 0    ; search for string instead of assembly
e search.flags = true ; if enabled, create flags on hits
```

The `search.align` variable is used to limit valid search hits to certain alignment. For example, with `e search.align=4` you will see only hits found at 4-bytes aligned offsets.

The `search.flags` boolean variable instructs the search engine to flag hits so that they can be referenced later. If a currently running search is interrupted with `ctrl-c` keyboard sequence, current search position is flagged with "search\_stop".

## Pattern Matching Search

The `/p` command allows you to apply repeated pattern searches on IO backend storage. It is possible to identify repeated byte sequences without explicitly specifying them. The only command's parameter sets minimum detectable pattern length. Here is an example:

```
[0x0000000000]> /p 10
```

This command output will show different patterns found and how many times each of them is encountered.

# Search Automatization

The `cmd.hit eval` variable is used to define a radare2 command to be executed when a matching entry is found by the search engine. If you want to run several commands, separate them with `; .`. Alternatively, you can arrange them in a separate script, and then invoke it as a whole with `. script-file-name` command. For example:

```
[0x00404888]> e cmd.hit = p8 8
[0x00404888]> / lib
Searching 3 bytes from 0x00400000 to 0x0041ae08: 6c 69 62
hits: 9
0x00400239 hit4_0 "lib64/ld-linux-x86-64.so.2"
31ed4989d15e4889
0x00400f19 hit4_1 "libselinux.so.1"
31ed4989d15e4889
0x00400fae hit4_2 "librt.so.1"
31ed4989d15e4889
0x00400fc7 hit4_3 "libacl.so.1"
31ed4989d15e4889
0x00401004 hit4_4 "libc.so.6"
31ed4989d15e4889
0x004013ce hit4_5 "libc_start_main"
31ed4989d15e4889
0x00416542 hit4_6 "libs/"
31ed4989d15e4889
0x00417160 hit4_7 "lib/xstrtol.c"
31ed4989d15e4889
0x00417578 hit4_8 "lib"
31ed4989d15e4889
```

# Searching Backwards

To search backwards, just use `/b` command.

## Assembler Search

If you want to search for a certain assembler opcodes, you can either use `/c` or `/a` commands.

- `/c jmp [esp]` - search for specified asm mnemonics

```
[0x00404888]> /c jmp qword [rdx] f hit_0 @ 0x0040e50d # 2: jmp qword [rdx] f hit_1 @  
0x00418dbb # 2: jmp qword [rdx] f hit_2 @ 0x00418fcb # 3: jmp qword [rdx] f hit_3 @  
0x004196ab # 6: jmp qword [rdx] f hit_4 @ 0x00419bf3 # 3: jmp qword [rdx] f hit_5 @  
0x00419c1b # 3: jmp qword [rdx] f hit_6 @ 0x00419c43 # 3: jmp qword [rdx]
```

- `/a jmp eax` - assemble string to machine code, and then search for resulting bytes.

```
[0x00404888]> /a jmp eax hits: 1 0x004048e7 hit3_0 ffe00f1f8000000000b8
```

## Searching for AES Keys

Thanks to Victor Muñoz, radare2 now has support of the algorithm he developed, capable of finding expanded AES keys with `/ca` command. It searches from current seek position up to the `search.distance` limit, or until end of file is reached. You can interrupt current search by pressing `ctrl-c`. For example, to look for AES keys in physical memory of your system:

```
$ sudo r2 /dev/mem  
[0x00000000]> /Ca  
0 AES keys found
```

# Disassembling

Disassembling in radare is just a way to represent an array of bytes. It is handled as a special print mode within `p` command.

In the old times, when the radare core was smaller, the disassembler was handled by an external rsc file. That is, radare first dumped current block into a file, and then simply called `objdump` configured to disassemble for Intel, ARM etc... It was a working solution, but it was inefficient as it repeated the same actions over and over, because there were no caches. As a result, scrolling was terribly slow. Nowadays, the disassembler support is one of the basic features of radare. It now allows many options, including target architecture flavor, disassembler variants, among other things.

To see disassembly, use the `pd` command. It accepts a numeric argument to specify how many opcodes of current block you want to see. Most of commands in radare consider current block size as a default limit for data input. If you want to disassemble more bytes, you should use the `b` command to set new block size.

```
[0x0000000000]> b 100      ; set block size to 100
[0x0000000000]> pd        ; disassemble 100 bytes
[0x0000000000]> pd 3      ; disassemble 3 opcodes
[0x0000000000]> pd 30     ; disassemble 30 bytes
```

The `pd` command works like `pd` but accepts number of input bytes, instead of number of opcodes, as its parameter.

The "pseudo" syntax may be somewhat easier for a human to understand than default assembler notations. But it can become annoying if you read lots of code. To play with it:

```
[0x00405e1c]> e asm.pseudo = true
[0x00405e1c]> pd 3
; JMP XREF from 0x00405dfa (fcn.00404531)
0x00405e1c 488b9424a80. rdx = [rsp+0x2a8]
0x00405e24 64483314252. rdx ^= [fs:0x28]
0x00405e2d 4889d8          rax = rbx

[0x00405e1c]> e asm.syntax = intel
[0x00405e1c]> pd 3
; JMP XREF from 0x00405dfa (fcn.00404531)
0x00405e1c 488b9424a80. mov rdx, [rsp+0x2a8]
0x00405e24 64483314252. xor rdx, [fs:0x28]
0x00405e2d 4889d8          mov rax, rbx

[0x00405e1c]> e asm.syntax=att
[0x00405e1c]> pd 3
; JMP XREF from 0x00405dfa (fcn.00404531)
0x00405e1c 488b9424a80. mov 0x2a8(%rsp), %rdx
0x00405e24 64483314252. xor %fs:0x28, %rdx
0x00405e2d 4889d8          mov %rbx, %rax
```

# Adding Metadata to Disassembly

Typical work of reversing binary files makes the task of taking notes and adding annotations on top of disassembly, data views etc. very important. Radare offers multiple ways to store and retrieve such metadata information.

By following common basic \*NIX principles it is easy to write a small utility in a scripting language which uses `objdump`, `otool`, etc. to obtain information from a binary and to import it into radare. For an example, take a look at one of many scripts that are distributed with radare, e.g., `idc2r.py`. To use it, invoke it as `idc2r.py file.idc > file.r2`. It reads an IDC file exported from an IDA Pro database and produces an r2 script containing the same comments, names of functions etc. You can import resulting 'file.r2' by using the dot `.` command of radare:

```
[0x00000000]> . file.r2
```

The `.` command is used to interpret Radare commands from external sources, including files and program output. For example, to omit generation of an intermediate file and import the script directly you can use this combination:

```
[0x00000000]> .!idc2r.py < file.idc
```

The `c` command is used to manage comments and data conversions. You can define a range of program's bytes to be interpreted either as code, binary data or string. It is possible to define flags and execute external code in certain seek position to fetch a comment from an external file or database.

Here's the help:

```
[0x00404cc0]> C?
|Usage: C[-LCvsdfm?] [...]
| C*                                List meta info in r2 commands
| C- [len] [@][ addr]                 delete metadata at given address range
| CL[-] [addr|file:line [addr] ]      show 'code line' information (bininfo)
| C1 file:line [addr]                add comment with line information
| CC[-] [comment-text]              add/remove comment. Use CC! to edit with $EDITOR
| CCa[-at][at] [text]               add/remove comment at given address
| Cv[-] offset reg name           add var substitution
| Cs[-] [size] [[addr]]            add string
| Ch[-] [size] [@addr]             hide data
| Cd[-] [size]                   hexdump data
| Cf[-] [sz] [fmt..]              format memory (see pf?)
| Cm[-] [sz] [fmt..]              magic parse (see pm?)

[0x00404cc0]>
```

```
[0x0000000000]> CCA 0x00000002 this guy seems legit
```

```
[0x0000000000]> pd 2
    0x0000000000    0000      add [rax], al
;     this guy seems legit
    0x0000000002    0000      add [rax], al
```

The `c` command allows to change type for a byte range. Three basic types are: code (disassembly is done using `asm.arch`), data (a byte array) or string.

It is easier to manage data types conversion in the visual mode, because the action is bound to "d" key, short for "data type change". Use the cursor to select a range of bytes (press `c` key to toggle cursor mode and use HJKL keys to expand selection) and then press 'ds' to convert it to a string. Alternatively, you can use the `cs` command from the shell:

```
[0x0000000000]> f string_foo @ 0x800
[0x0000000000]> Cs 10 @ string_foo
```

The folding/unfolding support is quite premature, but the idea comes from "folder" concept found in Vim editor. You can select a range of bytes in the disassembly view and press '<' to fold them in a single line, or '>' to unfold them. This is used to improve readability by hiding unimportant portions of code/data.

The `cm` command is used to define a memory format string (the same used by the `pf` command). Here's a example:

```
[0x7fd9f13ae630]> Cf 16 2xi foo bar
[0x7fd9f13ae630]> pd
    ;-- rip:
    0x7fd9f13ae630 format 2xi foo bar {
0x7fd9f13ae630 [0] {
    foo : 0x7fd9f13ae630 = 0xe8e78948
    bar : 0x7fd9f13ae634 = 14696
}
0x7fd9f13ae638 [1] {
    foo : 0x7fd9f13ae638 = 0x8bc48949
    bar : 0x7fd9f13ae63c = 571928325
}
} 16
0x7fd9f13ae633      e868390000  call 0x7fd9f13b1fa0
    0x7fd9f13b1fa0() ; rip
0x7fd9f13ae638      4989c4      mov r12, rax
```

It is possible to define structures with simple oneliners. See 'print memory' for more information.

All these "C\*" commands can also be accessed from the visual mode by pressing 'd' (data conversion) key.

# ESIL

ESIL stands for 'Evaluable Strings Intermediate Language'. It aims to describe a [Forth](#)-like representation for every target CPU opcode semantics. ESIL representations can be evaluated (interpreted) in order to emulate individual instructions. Each command of an ESIL expression is separated by a comma. Its virtual machine can be described as this:

```
while ((word=haveCommand())) {
    if (word.isOperator()) {
        esilOperators[word](esil);
    } else {
        esil.push (word);
    }
    nextCommand();
}
```

As we can see ESIL uses a stack-based interpreter similar to what is commonly used for calculators. You have two categories of inputs: values and operators. A value simply gets pushed on the stack, an operator then pops values (its arguments if you will) off the stack, performs its operation and pushes its results (if any) back on. We can think of ESIL as a post-fix notation of the operations we want to do.

So let's see an example:

```
4, esp, -=, ebp, esp, =[4]
```

Can you guess what this is? If we take this post-fix notation and transform it back to in-fix we get

```
esp -= 4
4bytes(dword) [esp] = ebp
```

We can see that this corresponds to the x86 instruction `push ebp` ! Isn't that cool? The aim is to be able to express most of the common operations performed by CPUs, like binary arithmetic operations, memory loads and stores, processing syscalls etc. This way if we can transform the instructions to ESIL we can see what a program does while it is running even for the most cryptic architectures you definitely don't have a device to debug on for.

## Use ESIL

Using visual mode is great to inspect the esil evaluations.

There are 2 environment variables that are important for watching what a program does:

```
[0x0000000000]> e asm.emu = true
[0x0000000000]> e asm.emustr = true
```

"asm.emu" tells r2 if you want ESIL information to be displayed. If it is set to true you will see comments appear to the right of your disassembly that tell you how the contents of registers and memory addresses are changed by the current instruction. For example if you have an instruction that subtracts a value from a register it tells you what the value was before and what it becomes after. This is super useful so you don't have to sit there yourself and track which value goes where.

One problem with this is that it is a lot of information to take in at once and sometimes you simply don't need it. r2 has a nice compromise for this. That is what the "asm.emustr" variable is for. Instead of this super verbose output with every register value, this only adds really useful information to the output, e.g., strings that are found at addresses a program uses or whether a jump is likely to be taken or not.

The third important variable is "asm.esil". This switches your disassembly to no longer show you the actual disassembled instructions, but instead now shows you corresponding ESIL expressions that describe what the instruction does. So if you want to take a look at how instructions are expressed in ESIL simply set "asm.esil" to true.

```
[0x0000000000]> e asm.esil = true
```

In visual mode you can also toggle this by simply typing `o`.

## ESIL Commands

- "ae" : Evaluate ESIL expression.

```
[0x0000000000]> "ae 1,1,+"  
0x2  
[0x0000000000]>
```

- "aes" : ESIL Step.

```
[0x0000000000]> aes  
[0x0000000000]>10aes
```

- "aes0" : ESIL Step Over.

```
[0x00000000]> aes0
[0x00000000]>1aes0
```

- "aesu" : ESIL Step Until.

```
[0x00001000]> aesu 0x1035
ADDR BREAK
[0x00001019]>
```

- "ar" : Show/modify ESIL registry

```
[0x00001ec7]> ar r_00 = 0x1035
[0x00001ec7]> ar r_00
0x00001035
[0x00001019]>
```

## ESIL Instruction Set

Here is the complete instruction set used by the ESIL VM:

ESIL Opcode	Operands	Name	Operation	example
TRAP	src	Trap	Trap signal	
\$	src	Syscall	syscall	
\$\$	src	Instruction address	Get address of current instruction stack=instruction address	
==	src,dst	Compare	stack = (dst == src) ; update_eflags(dst - src)	
<	src,dst	Smaller (signed comparison)	stack = (dst < src) ; update_eflags(dst - src)	[0x00000000]> "ae 1,5,<" 0x0 [0x00000000]> "ae 5,5" 0x0"
<=	src,dst	Smaller or Equal	stack = (dst <= src) ;	[0x00000000]> "ae 1,5,<" 0x0

<code>&lt;=</code>	src,dst	(signed comparison)	update_eflags(dst - src)	[0x00000000]> "ae 5,5" 0x1"
<code>&gt;</code>	src,dst	Bigger (signed comparison)	stack = (dst > src) ; update_eflags(dst - src)	[0x00000000]> "ae 1,5,>" 0x1 [0x00000000]> "ae 5,5,>" 0x0
<code>&gt;=</code>	src,dst	Bigger or Equal (signed comparison)	stack = (dst >= src) ; update_eflags(dst - src)	[0x00000000]> "ae 1,5,>=" 0x1 [0x00000000]> "ae 5,5,>=" 0x1
<code>&lt;&lt;</code>	src,dst	Shift Left	stack = dst << src	[0x00000000]> "ae 1,1,<<" 0x2 [0x00000000]> "ae 2,1,<<" 0x4
<code>&gt;&gt;</code>	src,dst	Shift Right	stack = dst >> src	[0x00000000]> "ae 1,4,>>" 0x2 [0x00000000]> "ae 2,4,>>" 0x1
<code>&lt;&lt;&lt;</code>	src,dst	Rotate Left	stack=dst ROL src	[0x00000000]> "ae 31,1,<<<" 0x80000000 [0x00000000]> "ae 32,1,<<<" 0x1
<code>&gt;&gt;&gt;</code>	src,dst	Rotate Right	stack=dst ROR src	[0x00000000]> "ae 1,1,>>>" 0x80000000 [0x00000000]> "ae 32,1,>>>" 0x1
<code>&amp;</code>	src,dst	AND	stack = dst & src	[0x00000000]> "ae 1,1,&" 0x1 [0x00000000]> "ae 1,0,&" 0x0 [0x00000000]> "ae 0,1,&"

				[0x00000000]> "ae 0,0,&" 0x0
**`	`**	src,dst	OR	stack = dst `
^	src,dst	XOR	stack = dst ^src	[0x00000000]> "ae 1,1," 0x0 [0x00000000]> "ae 1,0," 0x1 [0x00000000]> "ae 0,1," 0x1 [0x00000000]> "ae 0,0," 0x0
+	src,dst	ADD	stack = dst + src	[0x00000000]> "ae 3,4,+" 0x7 [0x00000000]> "ae 5,5,+" 0xa
-	src,dst	SUB	stack = dst - src	[0x00000000]> "ae 3,4,-" 0x1 [0x00000000]> "ae 5,5,-" 0x0 [0x00000000]> "ae 4,3,-" 0xffffffffffffffffffff
*	src,dst	MUL	stack = dst * src	[0x00000000]> "ae 3,4, * " 0xc [0x00000000]> "ae 5,5, * " 0x19
/	src,dst	DIV	stack = dst / src	[0x00000000]> "ae 2,4,/" 0x2 [0x00000000]> "ae 5,5,/" 0x1 [0x00000000]> "ae 5,9,/" 0x1
				[0x00000000]> "ae

%	src,dst	MOD	stack = dst % src	[0x00000000]> "ae 2,4,"% 0x0 [0x00000000]> "ae 5,5,"% 0x0 [0x00000000]> "ae 5,9,"% 0x4
!	src	NEG	stack = !!!src	[0x00000000]> "ae 1,!" 0x0 [0x00000000]> "ae 4,!" 0x0 [0x00000000]> "ae 0,!" 0x1
++	src	INC	stack = src++	[0x00000000]> ar r_00=0;ar r_00 0x00000000 [0x00000000]> "ae r_00,++" 0x1 [0x00000000]> ar r_00 0x00000000 [0x00000000]> "ae 1,++" 0x2
--	src	DEC	stack = src--	[0x00000000]> ar r_00=5;ar r_00 0x00000005 [0x00000000]> "ae r_00,--" 0x4 [0x00000000]> ar r_00 0x00000005 [0x00000000]> "ae 5,--" 0x4
+=	src,reg	ADD eq	reg = reg + src	[0x00000000]> ar r_01=5;ar r_00=0;ar r_00 0x00000000 [0x00000000]> "ae r_01,r_00,+=" [0x00000000]> ar r_00 0x00000005 [0x00000000]> "ae 5,r_00,+=" [0x00000000]> ar r_00 0x0000000a
				[0x00000000]> "ae

<code>-=</code>	src,reg	SUB eq	reg = reg - src	<pre>r_01,r_00,-= [0x00000000]&gt; ar r_00 0x00000004 [0x00000000]&gt; "ae 3,r_00,-= [0x00000000]&gt; ar r_00 0x00000001</pre>
<code>*=</code>	src,reg	MUL eq	reg = reg * src	<pre>[0x00000000]&gt; ar r_01=3;ar r_00=5;ar r_00 0x00000005 [0x00000000]&gt; "ae r_01,r_00,* = [0x00000000]&gt; ar r_00 0x0000000f [0x00000000]&gt; "ae 2,r_00,* = [0x00000000]&gt; ar r_00 0x0000001e</pre>
<code>/=</code>	src,reg	DIV eq	reg = reg / src	<pre>[0x00000000]&gt; ar r_01=3;ar r_00=6;ar r_00 0x00000006 [0x00000000]&gt; "ae r_01,r_00,/=* [0x00000000]&gt; ar r_00 0x00000002 [0x00000000]&gt; "ae 1,r_00,/=* [0x00000000]&gt; ar r_00 0x00000002</pre>
<code>%=</code>	src,reg	MOD eq	reg = reg % src	<pre>[0x00000000]&gt; ar r_01=3;ar r_00=7;ar r_00 0x00000007 [0x00000000]&gt; "ae r_01,r_00,%= [0x00000000]&gt; ar r_00 0x00000001 [0x00000000]&gt; ar r_00=9;ar r_00 0x00000009 [0x00000000]&gt; "ae 5,r_00,%= [0x00000000]&gt; ar r_00 0x00000004</pre>
				<pre>[0x00000000]&gt; ar r_00=1;ar r_01=1;ar r_01 0x00000001</pre>

<<=	src,reg	Shift Left eq	reg = reg << src	0x00000001 [0x00000000]> "ae r_00,r_01,<==" [0x00000000]> ar r_01 0x00000002 [0x00000000]> "ae 2,r_01,<==" [0x00000000]> ar r_01 0x00000008
>>=	src,reg	Shift Right eq	reg = reg << src	[0x00000000]> ar r_00=1;ar r_01=8;ar r_01 0x00000008 [0x00000000]> "ae r_00,r_01,>>==" [0x00000000]> ar r_01 0x00000004 [0x00000000]> "ae 2,r_01,>>==" [0x00000000]> ar r_01 0x00000001
&=	src,reg	AND eq	reg = reg & src	[0x00000000]> ar r_00=2;ar r_01=6;ar r_01 0x00000006 [0x00000000]> "ae r_00,r_01,&==" [0x00000000]> ar r_01 0x00000002 [0x00000000]> "ae 2,r_01,&==" [0x00000000]> ar r_01 0x00000002 [0x00000000]> "ae 1,r_01,&==" [0x00000000]> ar r_01 0x00000000
**	=**	src,reg	OR eq	reg = reg `
^=	src,reg	XOR eq	reg = reg ^ src	[0x00000000]> ar r_00=2;ar r_01=0xab;ar r_01 0x000000ab [0x00000000]> "ae r_00,r_01,^==" [0x00000000]> ar r_01

				[0x00000000]> "ae 2,r_01,^="
<b>++=</b>	reg	INC eq	reg = reg + 1	[0x00000000]> ar r_00=4;ar r_00 0x00000004 [0x00000000]> "ae r_00,++="
<b>--=</b>	reg	DEC eq	reg = reg - 1	[0x00000000]> ar r_00=4;ar r_00 0x00000004 [0x00000000]> "ae r_00,--="
<b>!=</b>	reg	NOT eq	reg = !reg	[0x00000000]> ar r_00=4;ar r_00 0x00000004 [0x00000000]> "ae r_00,!="
---	---	---	---	----- -----
<b>=[]</b> <b>=[*]</b> <b>=[1]</b> <b>=[2]</b> <b>=[4]</b> <b>=[8]</b>	src,dst	poke	*dst=src	[0x00010000]> "ae 0xdeadbeef,0x10000,=[4]," [0x00010000]> pxw 4@0x10000 0x00010000 0xdeadbeef .... [0x00010000]> "ae 0x0,0x10000,=[4]," [0x00010000]> pxw 4@0x10000 0x00010000 0x00000000
<b>[]</b> <b>[*]</b> <b>[1]</b>				[0x00010000]> w test@0x10000 [0x00010000]> "ae 0x10000,[4]," 0x74736574

[1] [2] [4] [8]	src	peek	stack=*src	0x74736574 [0x00010000]> ar r_00=0x10000 [0x00010000]> "ae r_00,[4]," 0x74736574
'	=[] 	=[1] 	=[2] 	=[4] 
SWAP		Swap	Swap two top elements	SWAP
PICK	n	Pick	Pick nth element from the top of the stack	2,PICK
RPICK	m	Reverse Pick	Pick nth element from the base of the stack	0,RPICK
DUP		Duplicate	Duplicate top element in stack	DUP
NUM		Numeric	If top element is a reference (register name, label, etc), dereference it and push its real value	NUM
CLEAR		Clear	Clear stack	CLEAR
BREAK		Break	Stops ESIL emulation	BREAK
GOTO	n	Goto	Jumps to Nth ESIL word	GOTO 5
TODO		To Do	Stops execution (reason: ESIL expression not completed)	TODO

## ESIL Flags

ESIL VM has an internal state flags that are read only and can be used to export those values to the underlying target CPU flags. It is because the ESIL VM always calculates all flag changes, while target CPUs only update flags under certain conditions or at specific instructions.

Internal flags are prefixed with `$` character.

```

z      - zero flag, only set if the result of an operation is 0
b      - borrow, this requires to specify from which bit (example: $b4 - checks if bor-
row from bit 4)
c      - carry, same like above (example: $c7 - checks if carry from bit 7)
p      - parity
r      - regsize (asm.bits/8)
[0-9]* - Used to set flags and registers without having any side effects,
          i.e. setting esil_cur, esil_old and esil_lastsz.
          (example: "$0,of,=" to reset the overflow flag)

```

## Syntax and Commands

A target opcode is translated into a comma separated list of ESIL expressions.

```
xor eax, eax    -> 0, eax, =, 1, zf, =
```

Memory access is defined by brackets operation:

```
mov eax, [0x80480]    -> 0x80480, [], eax, =
```

Default operand size is determined by size of operation destination.

```
movb $0, 0x80480    -> 0, 0x80480, =[1]
```

The `?{}` operator uses the value of its argument to decide whether to evaluate the expression in curly braces.

1. Is the value zero? -> Skip it.
2. Is the value non-zero? -> Evaluate it.

```

cmp eax, 123  -> 123, eax, ==, $z, zf, =
jz eax        -> zf, ?{}, eax, eip, =, }
```

If you want to run several expressions under a conditional, put them in curly braces:

```
zf, ?{}, eip, esp, =[], eax, eip, =, $r, esp, -=, }
```

Whitespaces, newlines and other chars are ignored. So the first thing when processing a ESIL program is to remove spaces:

```
esil = r_str_replace (esil, " ", "", R_TRUE);
```

Syscalls need special treatment. They are indicated by '\$' at the beginning of an expression. You can pass an optional numeric value to specify a number of syscall. An ESIL emulator must handle syscalls. See (`r_esil_syscall`).

## Arguments Order for Non-associative Operations

As discussed on IRC, current implementation works like this:

```
a, b, -      b - a  
a, b, /=     b /= a
```

This approach is more readable, but it is less stack-friendly.

## Special Instructions

NOPs are represented as empty strings. As it was said previously, syscalls are marked by '\$' command. For example, '0x80,\$'. It delegates emulation from the ESIL machine to a callback which implements syscalls for a specific OS/kernel.

Traps are implemented with the `<code>, TRAP` command. They are used to throw exceptions for invalid instructions, division by zero, memory read error, etc.

## Quick Analysis

Here is a list of some quick checks to retrieve information from an ESIL string. Relevant information will be probably found in the first expression of the list.

indexOf('[')	->	have memory references
indexOf("=[")	->	write in memory
indexOf("pc,=")	->	modifies program counter (branch, jump, call)
indexOf("sp,=")	->	modifies the stack (what if we found sp+= or sp-=?)
indexOf("=")	->	retrieve src and dst
indexOf(":")	->	unknown esil, raw opcode ahead
indexOf("\$")	->	accesses internal esil vm flags ex: \$z
indexOf("\$")	->	syscall ex: 1,\$
indexOf("TRAP")	->	can trap
indexOf('++')	->	has iterator
indexOf('--')	->	count to zero
indexOf("{?}")	->	conditional
equalsTo("")	->	empty string, means: nop (wrong, if we append pc+=x)

Common operations:

- Check dstreg
- Check srcreg
- Get destination
- Is jump
- Is conditional
- Evaluate
- Is syscall

## CPU Flags

CPU flags are usually defined as single bit registers in the RReg profile. They are sometimes found under the 'flg' register type.

## Variables

Properties of the VM variables:

1. They have no predefined bit width. This way it should be easy to extend them to 128, 256 and 512 bits later, e.g. for MMX, SSE, AVX, Neon SIMD.
2. There can be unbound number of variables. It is done for SSA-form compatibility.
3. Register names have no specific syntax. They are just strings.
4. Numbers can be specified in any base supported by RNum (dec, hex, oct, binary ...)
5. Each ESIL backend should have an associated RReg profile to describe the ESIL register specs.

## Bit Arrays

What to do with them? What about bit arithmetics if use variables instead of registers?

## Arithmetics

1. ADD ("+"
2. MUL ("\*")
3. SUB ("-")
4. DIV ("/")
5. MOD ("%")

## Bit Arithmetics

1. AND "&"
2. OR "|"
3. XOR "^"
4. SHL "<<"
5. SHR ">>"
6. ROL "<<<"
7. ROR ">>>"
8. NEG "!"

## Floating Point Support

*TODO*

## Handling x86 REP Prefix in ESIL

ESIL specifies that the parsing control-flow commands must be uppercase. Bear in mind that some architectures have uppercase register names. The corresponding register profile should take care not to reuse any of the following:

```
3,SKIP - skip N instructions. used to make relative forward GOTOs
3,GOTO - goto instruction 3
LOOP - alias for 0,GOTO
BREAK - stop evaluating the expression
STACK - dump stack contents to screen
CLEAR - clear stack
```

## Usage example:

## rep cmpsb

`cx,!,{BREAK},esi,[1],edi,[1]==,{BREAK},esi,++ edi,++ cx,-- 0, GOTO`

## Unimplemented/unhandled Instructions

Those are expressed with the 'TODO' command. which acts as a 'BREAK', but displays a warning message describing that an instruction is not implemented and will not be emulated.  
For example:

```
fmulp ST(1), ST(0)      =>      TODO, fmulp ST(1), ST(0)
```

## ESIL Disassembly Example:

```
[0x1000010f8]> e asm.esil=true
[0x1000010f8]> pd $r @ entry0
;      [0] va=0x1000010f8 pa=0x000010f8 sz=13299 vsz=13299 rwx=-r-x 0.__text
;-- section.0.__text:
0x1000010f8    55          8, rsp, -=, rbp, rsp, =[8]
0x1000010f9    4889e5      rsp, rbp, =
0x1000010fc    4883c768    104, rdi, +=
0x100001100    4883c668    104, rsi, +=
0x100001104    5d          rsp, [8], rbp, =, 8, rsp, +=
   |< 0x100001105    e950350000  0x465a, rip, = ;[1]
| 0x10000110a    55          8, rsp, -=, rbp, rsp, =[8]
| 0x10000110b    4889e5      rsp, rbp, =
|   | 0x10000110e    488d4668    rsi, 104, +, rax, =
| 0x100001112    488d7768    rdi, 104, +, rsi, =
| 0x100001116    4889c7      rax, rdi, =
| 0x100001119    5d          rsp, [8], rbp, =, 8, rsp, +=
   |< 0x10000111a    e93b350000  0x465a, rip, = ;[1]
|| 0x10000111f    55          8, rsp, -=, rbp, rsp, =[8]
|| 0x100001120    4889e5      rsp, rbp, =
|| 0x100001123    488b4f60    rdi, 96, +, [8], rcx, =
|| 0x100001127    4c8b4130    rcx, 48, +, [8], r8, =
| 0x10000112b    488b5660    rsi, 96, +, [8], rdx, =
|| 0x10000112f    b801000000  1, eax, = ; 0x00000001
|| 0x100001134    4c394230    rdx, 48, +, [8], r8, ==, cz, ?=
   |< 0x100001138    7f1a        sf, of, !, ^, zf, !, &, ?{, 0x1154, rip, =, } ;[2]
   |< 0x10000113a    7d07        of, !, sf, ^, ?{, 0x1143, rip, } ;[3]
||| 0x10000113c    b8ffffffff  0xffffffff, eax, = ; 0xffffffff
   |< 0x100001141    eb11        0x1154, rip, = ;[2]
|> 0x100001143    488b4938    rcx, 56, +, [8], rcx, =
||| 0x100001147    48394a38    rdx, 56, +, [8], rcx, ==, cz, ?=
```

## Introspection

To ease ESIL parsing we should have a way to express introspection expressions to extract data we want. For example, we may want to get the target address of a jump. The parser for ESIL expressions should offer API to make it possible to extract information by analyzing the expressions easily.

```
> ao~esil,opcode  
opcode: jmp 0x10000465a  
esil: 0x10000465a,rip,=
```

We need a way to retrieve the numeric value of 'rip'. This is a very simple example, but there are more complex, like conditional ones. We need expressions to be able to get:

- opcode type
- destination of jump
- condition depends on
- all regs modified (write)
- all regs accessed (read)

## API HOOKS

It is important for emulation to be able to setup hooks in parser, so we can extend it to implement analysis without having to change parser again and again. That is, every time an operation is about to be executed, a user hook is called. It can be used to determine if rip is going to change, or if the instruction updates stack, etc. Later, we can split that callback into several ones to have an event-based analysis API that may be extended in js like this:  
esil.on('regset', function(){.. esil.on('syscall', function(){esil.regset('rip'

For the API, see functions `hook_flag_read()`, `hook_execute()`, `hook_mem_read()`. A callback should return true if you want to override the action taken for a callback. For example, to deny memory reads in a region, or voiding memory writes, effectively making it read-only. Return false or 0 if you want to trace ESIL expression parsing.

Other operations that require bindings to external functionalities to work. In this case, `r_ref` and `r_io`. This must be defined when initializing the esil vm.

- Io Get/Set Out ax, 44 44,ax,:ou
- Selectors (cs,ds,gs...) Mov eax, ds:[ebp+8] Ebp,8,+,:ds,eax,=

Radare2 provides a wide set of features to automate boring work. It ranges from the simple sequencing of the commands to the calling scripts/another programs via IPC (Inter-Process Communication), called r2pipe.

As mentioned a few times before there is an ability to sequence commands using ; semicolon operator.

```
[0x00404800]> pd 1 ; ao 1
    0x00404800      b827e66100      mov eax, 0x61e627      ; "tab"
address: 0x404800
opcode: mov eax, 0x61e627
prefix: 0
bytes: b827e66100
ptr: 0x0061e627
refptr: 0
size: 5
type: mov
esil: 6415911,rax,=
stack: null
family: cpu
[0x00404800]>
```

It simply runs second command after finishing the first one, like in shell.

The second important way to sequence the commands is simple pipe |

```
ao|grep address
```

Note, the | pipe only can pipe output of r2 commands to external (shell) commands, like system programs or builtin shell commands. And for providing the similar way to sequence r2 commands, there is backtick operator `` as well, working exactly the same way it works in shell.

For example we want to see a few bytes of the memory at the address, referred by 'mov eax, addr' instruction for further call. We can do that without jumping to it, we just need to sequence a couple of commands:

```
[0x00404800]> pd 1
    0x00404800      b827e66100      mov eax, 0x61e627      ; "tab"
[0x00404800]> ao
address: 0x404800
opcode: mov eax, 0x61e627
prefix: 0
bytes: b827e66100
ptr: 0x0061e627
refptr: 0
size: 5
type: mov
esil: 6415911,rax,=
stack: null
family: cpu
[0x00404800]> ao~ptr[1]
0x0061e627
0
[0x00404800]> px 10 @ `ao~ptr[1]`
- offset - 0 1 2 3 4 5 6 7 8 9 A B C D E F 0123456789ABCDEF
0x0061e627 7461 6200 2e69 6e74 6572                      tab..inter
[0x00404800]>
```

And of course it's possible to redirect the output of r2 command into file, using `>` and `>>` commands

```
[0x00404800]> px 10 @ `ao~ptr[1]` > example.txt
[0x00404800]> px 10 @ `ao~ptr[1]` >> example.txt
```

One of the most common task in automatization is looping through something. There are multiple ways to loop over something. First, most known one - loop over flags:

```
@@ flagname-regex
```

For example, we want to see function information with `afi` command:

```
[0x004047d6]> afi
#
offset: 0x004047d0
name: entry0
size: 42
realsz: 42
stackframe: 0
call-convention: amd64
cyclomatic-complexity: 1
bits: 64
type: fcn [NEW]
num-bbs: 1
edges: 0
end-bbs: 1
call-refs: 0x00402450 C
data-refs: 0x004136c0 0x00413660 0x004027e0
code-xrefs:
data-xrefs:
locals:0
args: 0
diff: type: new
[0x004047d6]>
```

But we need to see some field of it for all functions found by analysis, for example. We can do that with loop:

```
[0x004047d6]> afi @@ fcn.* ~name
```

This command will extract `name` field from `afi` output of every flag with name matching regexp `fcn.*`.

The second way to use loops - is to set array of the offsets, using syntax

```
@@=1 2 3 ... N
```

For example we want to see opcode information for 2 offsets: current one, and current + 2:

```
[0x004047d6]> ao @@= $$ $$+2
address: 0x4047d6
opcode: mov rdx, rsp
prefix: 0
bytes: 4889e2
refptr: 0
size: 3
type: mov
esil: rsp,rdx,=
stack: null
family: cpu
address: 0x4047d8
opcode: loop 0x404822
prefix: 0
bytes: e248
refptr: 0
size: 2
type: cjmp
esil: 1,rcx,-=,rcx,{,4212770,rip,=,}
jump: 0x00404822
fail: 0x004047da
stack: null
cond: al
family: cpu
[0x004047d6]>
```

Note, we're using `$$` variable which evaluates in the current offset. Also note, that `$$+2` evaluates before looping, so we can use the simple arithmetic expressions.

Also, those offsets can be loaded from some file. This file should be formatted with one offset per line.

```
[0x004047d0]> ?v $$ > offsets.txt
[0x004047d0]> ?v $$+2 >> offsets.txt
[0x004047d0]> !cat offsets.txt
4047d0
4047d2
[0x004047d0]> pi 1 @@.offsets.txt
xor ebp, ebp
mov r9, rdx
```

There are different `foreach` types. One of the most useful - looping through instructions of the selected function:

```
[0x004047d0]> pdf
F (fcn) entry0 42
| ; UNKNOWN XREF from 0x00400018 (unk)
| ; DATA XREF from 0x004064bf (sub.strlen_460)
| ; DATA XREF from 0x00406511 (sub.strlen_460)
| ; DATA XREF from 0x0040b080 (unk)
| ; DATA XREF from 0x0040b0ef (unk)
| 0x004047d0    31ed          xor    ebp,    ebp
| 0x004047d2    4989d1        mov    r9,    rdx
| 0x004047d5    5e             pop    rsi
| 0x004047d6    4889e2        mov    rdx,    rsp
| 0x004047d9    4883e4f0      and    rsp,    0xfffffffffffffff0
| 0x004047dd    50             push   rax
| 0x004047de    54             push   rsp
| 0x004047df    49c7c0c03641. mov    r8,    0x4136c0
| 0x004047e6    48c7c1603641. mov    rcx,    0x413660      ; "AWA..AVI..AU
I...ATL.%.. "
0x00413660 ; "AWA..AVI..AUI..ATL.%.. "
|           0x004047ed    48c7c7e02740. mov    rdi,    main       ; "AWAVAUATUH..
S..H...." @
0x4027e0
|           0x004047f4    e857dcffff  call   sym.imp.__libc_start_main
L           0x004047f9    f4             hlt

[0x004047d0]> pi 1 @@i
mov r9, rdx
pop rsi
mov rdx, rsp
and rsp, 0xfffffffffffffff0
push rax
push rsp
mov r8, 0x4136c0
mov rcx, 0x413660
mov rdi, main
call sym.imp.__libc_start_main
hlt
```

In this example command `pi 1` runs over all instructions in the current function (`entry0`).

The third way to use loops less flexible but still useful - we can loop through predefined iterator types:

- symbols
- imports
- registers
- threads
- comments
- functions
- flags

This is possible with `@@@` command. E.g., the previous example of listing information about functions can be done with it:

```
[0x004047d6]> afi @@@ functions ~name
```

This will extract `name` field from `afi` output and will output the huge list of function names. We can choose only second column, to remove redundant `name:` on every line:

```
[0x004047d6]> afi @@@ functions ~name[1]
```

Apart from simple sequencing and looping, radare2 allows to write simple macros, using this construction:

```
[0x00404800]> (qwe, pd 4, ao)
```

This will define a macro called 'qwe' which runs sequentially first 'pd 4' then 'ao'. Calling the macro using syntax `.(macro)` is simple:

```
[0x00404800]> (qwe, pd 4, ao)
[0x00404800]> .(qwe)
0x00404800      b827e66100    mov eax, 0x61e627      ; "tab"
0x00404805      55             push rbp
0x00404806      482d20e66100  sub rax, section_end.LOAD1
0x0040480c      4889e5        mov rbp, rsp

address: 0x404800
opcode: mov eax, 0x61e627
prefix: 0
bytes: b827e66100
ptr: 0x0061e627
refptr: 0
size: 5
type: mov
esil: 6415911,rax,=
stack: null
family: cpu
[0x00404800]>
```

To list available macros simply call `(* :`

```
[0x00404800]> (*
(qwe , pd 4, ao)
```

And if want to remove some macro, just add '-' before the name:

```
[0x00404800]> (-qwe)
Macro 'qwe' removed.
[0x00404800]>
```

Moreover, it's possible to create macro with arguments, which come in handy in some simple scripting. To create macro with arguments you need simply add them to macro definition. Be sure, if you're using characters like ';' quote the whole command for proper parsing.

```
[0x00404800]
[0x004047d0]> "(foo x y,pd $0; s +$1)"
[0x004047d0]> .(foo 5 6)
    ;-- entry0:
0x004047d0      31ed          xor    ebp,  ebp
0x004047d2      4989d1        mov    r9,   rdx
0x004047d5      5e             pop    rsi
0x004047d6      4889e2        mov    rdx,  rsp
0x004047d9      4883e4f0      and    rsp,  0xfffffffffffffff0
[0x004047d6]>
```

As you can see, arguments named by index, starting from 0: \$0, \$1, ...

# Rabin2 — Show Properties of a Binary

Under this bunny-arabic-like name, radare hides a powerful tool to handle binary files, to get information on imports, sections, headers etc. Rabin2 can present it in several formats accepted by other tools, including radare2 itself. Rabin2 understands many file formats: Java CLASS, ELF, PE, Mach-O, etc., and it is able to obtain symbol import/exports, library dependencies, strings of data sections, xrefs, entrypoint address, sections, architecture type.

```
$ rabin2 -h

Usage: rabin2 [-ACdehHiIjLMqrRsSvVxzZ] [-@ addr] [-a arch] [-b bits]
              [-B addr] [-c F:C:D] [-f str] [-m addr] [-n str] [-N len]
              [-o str] [-O str] file

-@ [addr]      show section, symbol or import at addr
-A             list archs
-a [arch]       set arch (x86, arm, .. or <arch>_<bits>)
-b [bits]       set bits (32, 64 ...)
-B [addr]       override base address (pie bins)
-c [fmt:C:D]   create [elf,mach0,pe] with Code and Data hexpairs (see -a)
-C             list classes
-d             show debug/dwarf information
-e             entrypoint
-f [str]        select sub-bin named str
-g             same as -SMRevsiz (show all info)
-h             this help
-H             header fields
-i             imports (symbols imported from libraries)
-I             binary info
-j             output in json
-l             linked libraries
-L             list supported bin plugins
-m [addr]       show source line at addr
-M             main (show address of main symbol)
-n [str]        show section, symbol or import named str
-N [minlen]    force minimum number of chars per string (see -z)
-o [str]        output file/folder for write operations (out by default)
-O [str]        write/extract operations (-O help)
-q             be quiet, just show fewer data
-r             radare output
-R             relocations
-s             symbols (exports)
-S             sections
-v             use vaddr in radare output (or show version if no file)
-x             extract bins contained in file
-z             strings (from data section)
-zz            strings (from raw bins [e bin.rawstr=1])
-Z             guess size of binary program
```



# File Properties Identification

File type identification is done using `-I`. With this option, rabin2 prints information on a binary's type, its encoding, endianness, class, operating system, etc.:

```
$ rabin2 -I /bin/ls
file    /bin/ls
type    EXEC (Executable file)
pic    false
has_va  true
root    elf
class   ELF64
lang    c
arch    x86
bits    64
machine AMD x86-64 architecture
os      linux
subsys  linux
 endian  little
strip   true
static  false
linenum false
lsyms   false
relocs  false
rpath   NONE
```

To make rabin2 output information in format that the main program, radare2, can understand, pass `-Ir` option to it:

```
$ rabin2 -Ir /bin/ls
e file.type=elf
e cfg.bigendian=false
e asm.os=linux
e asm.arch=x86
e anal.arch=x86
e asm.bits=64
e asm.dwarf=true
```

## Code Entrypoints

The `-e` option passed to rabin2 will show entrypoints for given binary. Two examples:

```
$ rabin2 -e /bin/ls
[Entrypoints]
addr=0x00004888 off=0x00004888 baddr=0x00000000

1 entrypoints

$ rabin2 -er /bin/ls
fs symbols
f entry0 @ 0x00004888
s entry0
```

# Imports

Rabin2 is able to find imported objects by an executable, as well as their offsets in its PLT. This information is useful, for example, to understand what external function is invoked by `call` instruction. Pass `-i` flag to rabin to get a list of imports. An example:

```
$ rabin2 -i /bin/ls |head  
[Imports]  
ordinal=001 plt=0x000021b0 bind=GLOBAL type=FUNC name=__ctype_toupper_loc  
ordinal=002 plt=0x000021c0 bind=GLOBAL type=FUNC name=__uflow  
ordinal=003 plt=0x000021d0 bind=GLOBAL type=FUNC name=getenv  
ordinal=004 plt=0x000021e0 bind=GLOBAL type=FUNC name=sigprocmask  
ordinal=005 plt=0x000021f0 bind=GLOBAL type=FUNC name=raise  
ordinal=006 plt=0x00002210 bind=GLOBAL type=FUNC name=localtime  
ordinal=007 plt=0x00002220 bind=GLOBAL type=FUNC name=__mempcpy_chk  
ordinal=008 plt=0x00002230 bind=GLOBAL type=FUNC name=abort  
ordinal=009 plt=0x00002240 bind=GLOBAL type=FUNC name=__errno_location  
(...)
```

# Symbols (Exports)

With rabin2, generated symbols list format is similar to imports list. Use `-s` option to get it:

```
$ rabin2 -s /bin/ls | head
[Symbols]
addr=0x0021a610 off=0x0021a610 ord=114 fwd=NONE sz=8 bind=GLOBAL type=OBJECT name=stdou
ut
addr=0x0021a600 off=0x0021a600 ord=115 fwd=NONE sz=0 bind=GLOBAL type=NOTYPE name=_eda
ta
addr=0x0021b388 off=0x0021b388 ord=116 fwd=NONE sz=0 bind=GLOBAL type=NOTYPE name=_end
addr=0x0021a600 off=0x0021a600 ord=117 fwd=NONE sz=8 bind=GLOBAL type=OBJECT name=__pr
ogramname
addr=0x0021a630 off=0x0021a630 ord=119 fwd=NONE sz=8 bind=UNKNOWN type=OBJECT name=pro
gram_invocation_name
addr=0x0021a600 off=0x0021a600 ord=121 fwd=NONE sz=0 bind=GLOBAL type=NOTYPE name=__bs
s_start
addr=0x0021a630 off=0x0021a630 ord=122 fwd=NONE sz=8 bind=GLOBAL type=OBJECT name=__pr
ogramname_full
addr=0x0021a600 off=0x0021a600 ord=123 fwd=NONE sz=8 bind=UNKNOWN type=OBJECT name=pro
gram_invocation_short_name
addr=0x00002178 off=0x00002178 ord=124 fwd=NONE sz=0 bind=GLOBAL type=FUNC name=_init
```

With `-sr` option rabin2 produces a radare2 script instead. It can be later passed to the core to automatically flag all symbols and to define corresponding byte ranges as functions and data blocks.

```
$ rabin2 -sr /bin/ls

fs symbols
Cd 8 @ 0x0021a610
f sym.stdout 8 0x0021a610
f sym._edata 0 0x0021a600
f sym._end 0 0x0021b388
Cd 8 @ 0x0021a600
f sym.__progname 8 0x0021a600
Cd 8 @ 0x0021a630
f sym.program_invocation_name 8 0x0021a630
f sym.__bss_start 0 0x0021a600
```

## List Libraries

Rabin2 can list libraries used by a binary with `-l` option:

```
$ rabin2 -l /bin/ls
[Linked libraries]
libselinux.so.1
librt.so.1
libacl.so.1
libc.so.6

4 libraries
```

If you compare outputs of `rabin2 -l` and `ldd`, you will notice that rabin2 lists fewer libraries than `ldd`. The reason is that rabin2 does not follow and does not show dependencies of libraries. Only original binary dependencies are shown.

# Strings

The `-z` option is used to list readable strings found in the `.rodata` section of ELF binaries, or the `.text` section of PE files. Example:

```
$ rabin2 -z /bin/ls |head
addr=0x00012487 off=0x00012487 ordinal=000 sz=9 len=9 section=.rodata type=A string=sr
c/ls.c
addr=0x00012490 off=0x00012490 ordinal=001 sz=26 len=26 section=.rodata type=A string=
sort_type != sort_version
addr=0x000124aa off=0x000124aa ordinal=002 sz=5 len=5 section=.rodata type=A string= %
lu
addr=0x000124b0 off=0x000124b0 ordinal=003 sz=7 len=14 section=.rodata type=W string=%
*lu ?
addr=0x000124ba off=0x000124ba ordinal=004 sz=8 len=8 section=.rodata type=A string=%s
%*s
addr=0x000124c5 off=0x000124c5 ordinal=005 sz=10 len=10 section=.rodata type=A string=
%*s, %*s
addr=0x000124cf off=0x000124cf ordinal=006 sz=5 len=5 section=.rodata type=A string= -
>
addr=0x000124d4 off=0x000124d4 ordinal=007 sz=17 len=17 section=.rodata type=A string=
cannot access %
addr=0x000124e5 off=0x000124e5 ordinal=008 sz=29 len=29 section=.rodata type=A string=
cannot read symbolic link %
addr=0x00012502 off=0x00012502 ordinal=009 sz=10 len=10 section=.rodata type=A string=
unlabeled
```

With `-zr` option, this information is represented as radare2 commands list. It can be used in a radare2 session to automatically create a flag space called "strings" pre-populated with flags for all strings found by rabin2. Furthermore, this script will mark corresponding byte ranges as strings instead of code.

```
$ rabin2 -zr /bin/ls |head
fs strings
f str.src_ls.c 9 @ 0x00012487
Cs 9 @ 0x00012487
f str.sort_type__sort_version 26 @ 0x00012490
Cs 26 @ 0x00012490
f str._lu_ 5 @ 0x000124aa
Cs 5 @ 0x000124aa
f str._lu_ 14 @ 0x000124b0
Cs 7 @ 0x000124b0
f str._s__s 8 @ 0x000124ba
(...)
```



# Program Sections

Rabin2 called with `-s` option gives complete information about sections of an executable. For each section its index, offset, size, alignment, type and permissions, are shown. The next example demonstrates it.

```
$ rabin2 -S /bin/ls
[Sections]
idx=00 addr=0x00000238 off=0x00000238 sz=28 vsz=28 perm=-r-- name=.interp
idx=01 addr=0x00000254 off=0x00000254 sz=32 vsz=32 perm=-r-- name=.note.ABI_tag
idx=02 addr=0x00000274 off=0x00000274 sz=36 vsz=36 perm=-r-- name=.note.gnu.build_id
idx=03 addr=0x00000298 off=0x00000298 sz=104 vsz=104 perm=-r-- name=.gnu.hash
idx=04 addr=0x00000300 off=0x00000300 sz=3096 vsz=3096 perm=-r-- name=.dynsym
idx=05 addr=0x00000f18 off=0x00000f18 sz=1427 vsz=1427 perm=-r-- name=.dynstr
idx=06 addr=0x000014ac off=0x000014ac sz=258 vsz=258 perm=-r-- name=.gnu.version
idx=07 addr=0x000015b0 off=0x000015b0 sz=160 vsz=160 perm=-r-- name=.gnu.version_r
idx=08 addr=0x00001650 off=0x00001650 sz=168 vsz=168 perm=-r-- name=.rela.dyn
idx=09 addr=0x000016f8 off=0x000016f8 sz=2688 vsz=2688 perm=-r-- name=.rela.plt
idx=10 addr=0x00002178 off=0x00002178 sz=26 vsz=26 perm=-r-x name=.init
idx=11 addr=0x000021a0 off=0x000021a0 sz=1808 vsz=1808 perm=-r-x name=.plt
idx=12 addr=0x000028b0 off=0x000028b0 sz=64444 vsz=64444 perm=-r-x name=.text
idx=13 addr=0x0001246c off=0x0001246c sz=9 vsz=9 perm=-r-x name=.fini
idx=14 addr=0x00012480 off=0x00012480 sz=20764 vsz=20764 perm=-r-- name=.rodata
idx=15 addr=0x0001759c off=0x0001759c sz=1820 vsz=1820 perm=-r-- name=.eh_frame_hdr
idx=16 addr=0x00017cb8 off=0x00017cb8 sz=8460 vsz=8460 perm=-r-- name=.eh_frame
idx=17 addr=0x00019dd8 off=0x00019dd8 sz=8 vsz=8 perm=-rw- name=.init_array
idx=18 addr=0x00019de0 off=0x00019de0 sz=8 vsz=8 perm=-rw- name=.fini_array
idx=19 addr=0x00019de8 off=0x00019de8 sz=8 vsz=8 perm=-rw- name=.jcr
idx=20 addr=0x00019df0 off=0x00019df0 sz=512 vsz=512 perm=-rw- name=.dynamic
idx=21 addr=0x00019ff0 off=0x00019ff0 sz=16 vsz=16 perm=-rw- name=.got
idx=22 addr=0x0001a000 off=0x0001a000 sz=920 vsz=920 perm=-rw- name=.got.plt
idx=23 addr=0x0001a3a0 off=0x0001a3a0 sz=608 vsz=608 perm=-rw- name=.data
idx=24 addr=0x0001a600 off=0x0001a600 sz=3464 vsz=3464 perm=-rw- name=.bss
idx=25 addr=0x0001a600 off=0x0001a600 sz=8 vsz=8 perm=---- name=.gnu_debuglink
idx=26 addr=0x0001a608 off=0x0001a608 sz=254 vsz=254 perm=---- name=.shstrtab

27 sections
```

With `-sr` option, rabin2 will flag start/end of every section, and will pass the rest of information as a comment.

```
$ rabin2 -Sr /bin/ls
fs sections
S 0x00000238 0x00000238 0x0000001c 0x0000001c .interp 4
f section..interp 28 0x00000238
f section_end..interp 0 0x00000254
CC [00] va=0x00000238 pa=0x00000238 sz=28 vsz=28 rwx=-r-- .interp @ 0x00000238
S 0x00000254 0x00000254 0x00000020 0x00000020 .note.ABI_tag 4
f section..note.ABI_tag 32 0x00000254
f section_end..note.ABI_tag 0 0x00000274
CC [01] va=0x00000254 pa=0x00000254 sz=32 vsz=32 rwx=-r-- .note.ABI_tag @ 0x00000254
S 0x00000274 0x00000274 0x00000024 0x00000024 .note.gnu.build_id 4
f section..note.gnu.build_id 36 0x00000274
f section_end..note.gnu.build_id 0 0x00000298
CC [02] va=0x00000274 pa=0x00000274 sz=36 vsz=36 rwx=-r-- .note.gnu.build_id @ 0x00000
274
S 0x00000298 0x00000298 0x00000068 0x00000068 .gnu.hash 4
f section..gnu.hash 104 0x00000298
f section_end..gnu.hash 0 0x00000300
CC [03] va=0x00000298 pa=0x00000298 sz=104 vsz=104 rwx=-r-- .gnu.hash @ 0x00000298
S 0x00000300 0x00000300 0x00000c18 0x00000c18 .dynsym 4
f section..dynsym 3096 0x00000300
f section_end..dynsym 0 0x00000f18
CC [04] va=0x00000300 pa=0x00000300 sz=3096 vsz=3096 rwx=-r-- .dynsym @ 0x00000300
S 0x00000f18 0x00000f18 0x00000593 0x00000593 .dynstr 4
f section..dynstr 1427 0x00000f18
f section_end..dynstr 0 0x000014ab
CC [05] va=0x00000f18 pa=0x00000f18 sz=1427 vsz=1427 rwx=-r-- .dynstr @ 0x00000f18
S 0x000014ac 0x000014ac 0x00000102 0x00000102 .gnu.version 4
f section..gnu.version 258 0x000014ac
f section_end..gnu.version 0 0x000015ae
(...)
```

# Binary Diffing

This section is based on <http://radare.today> article "binary diffing"

Without any parameters, `radiff2` by default shows what bytes are changed and their corresponding offsets:

```
$ radiff2 genuine cracked
0x0000081e0 85c00f94c0 => 9090909090 0x000081e0
0x0007c805 85c00f84c0 => 9090909090 0x0007c805

$ rasm2 -d 85c00f94c0
test eax, eax
sete al
```

Notice how the two jumps are nop'ed.

For bulk processing, you may want to have a higher-level overview of differences. This is why radare2 is able to compute the distance and the percentage of similarity between two files with the `-s` option:

```
$ radiff2 -s /bin/true /bin/false
similarity: 0.97
distance: 743
```


If you want more concrete data, it's also possible to count the differences, with the `-c` option:

```
$ radiff2 -c genuine cracked
2
```

If you are unsure whether you are dealing with similar binaries, with `-c` flag you can check there are matching functions. In this mode, it will give you three columns for all functions: "First file offset", "Percentage of matching" and "Second file offset".

```
$ radiff2 -C /bin/false /bin>true
entry0 0x4013e8 | MATCH (0.904762) | 0x4013e2 entry0
sym.imp._libc_start_main 0x401190 | MATCH (1.000000) | 0x401190 sym.imp
._libc_start_main
fcn.00401196 0x401196 | MATCH (1.000000) | 0x401196 fcn.00401196
fcn.0040103c 0x40103c | MATCH (1.000000) | 0x40103c fcn.0040103c
fcn.00401046 0x401046 | MATCH (1.000000) | 0x401046 fcn.00401046
[...]
```

And now a cool feature : radare2 supports graph-differing, à la [DarunGrim](#), with the `-g` option. You can either give it a symbol name, or specify two offsets, if the function you want to diff is named differently in compared files. For example, `radiff2 -g main /bin>true /bin/false | xdot -` will show differences in `main()` function of Unix `true` and `false` programs. You can compare it to `radiff2 -g main /bin/false /bin>true` (Notice the order of the arguments) to get the two versions. This is the result:



Parts in yellow indicate that some offsets do not match. The grey piece means a perfect match. The red one highlights a strong difference. If you look closely, you will see that the left part of the picture has `mov edi, 0x1; call sym.imp.exit`, while the right one has `xor edi, edi; call sym.imp.exit`.

Binary differencing is an important feature for reverse engineering. It can be used to analyze [security updates](#), infected binaries, firmware changes and more...

We have only shown the code analysis differencing functionality, but radare2 supports additional types of differencing between two binaries: at byte level, deltified similarities, and more to come.

We have plans to implement more kinds of bindiffing algorithms into r2, and why not, add support for ascii art graph differencing and better integration with the rest of the toolkit.

# Rasm2

`rasm2` is an inline assembler/disassembler. Initially, `rasm` tool was designed to be used for binary patching. Its main function is to get bytes corresponding to given machine instruction opcode.

```
$ rasm2 -h
Usage: rasm2 [-CdDehLBvw] [-a arch] [-b bits] [-o addr] [-s syntax]
              [-f file] [-F fil:ter] [-i skip] [-l len] 'code'|hex|-
-a [arch]      Set architecture to assemble/disassemble (see -L)
-b [bits]       Set CPU register size (8, 16, 32, 64) (RASM2_BITS)
-c [cpu]        Select specific CPU (depends on arch)
-C             Output in C format
-d, -D         Disassemble from hexpair bytes (-D show hexpairs)
-e             Use big endian instead of little endian
-f [file]       Read data from file
-F [in:out]     Specify input and/or output filters (att2intel, x86.pseudo, ...)
-h             Show this help
-i [len]        ignore/skip N bytes of the input buffer
-k [kernel]    Select operating system (linux, windows, darwin, ...)
-l [len]        Input/Output length
-L             List supported asm plugins
-o [offset]    Set start address for code (default 0)
-o [file]       Output file name (rasm2 -Bf a.asm -o a)
-s [syntax]    Select syntax (intel, att)
-B             Binary input/output (-l is mandatory for binary input)
-v             Show version information
-w             What's this instruction for? describe opcode
If '-l' value is greater than output length, output is padded with nops
If the last argument is '-' reads from stdin
```

Plugins for supported target architectures can be listed with the `-L` option. Knowing a plugin name, you can use it by specifying its name to the `-a` option

```
$ rasm2 -L
_d 16      8051      PD      8051 Intel CPU
_d 16 32    arc       GPL3    Argonaut RISC Core
ad 16 32 64 arm       GPL3    Acorn RISC Machine CPU
_d 16 32 64 arm.cs    BSD     Capstone ARM disassembler
_d 16 32    arm.winedbg LGPL2   WineDBG's ARM disassembler
_d 16 32    avr       GPL     AVR Atmel
ad 32      bf        LGPL3   Brainfuck
_d 16      cr16      LGPL3   cr16 disassembly plugin
_d 16      csr       PD      Cambridge Silicon Radio (CSR)
ad 32 64    dalvik    LGPL3   AndroidVM Dalvik
ad 16      dcemu16   PD      Mojang's DCPU-16
_d 32 64    ebc       LGPL3   EFI Bytecode
_d 8       gb        LGPL3   GameBoy(TM) (z80-like)
_d 16      h8300     LGPL3   H8/300 disassembly plugin
_d 8       i8080     BSD     Intel 8080 CPU
ad 32      java      Apache  Java bytecode
_d 32      m68k      BSD     Motorola 68000
_d 32      malbolge   LGPL3   Malbolge Ternary VM
ad 32 64    mips      GPL3   MIPS CPU
_d 16 32 64 mips.cs   BSD     Capstone MIPS disassembler
_d 16 32 64 msil      PD      .NET Microsoft Intermediate Language
_d 32      nios2     GPL3   NIOS II Embedded Processor
_d 32 64    ppc       GPL3   PowerPC
_d 32 64    ppc.cs    BSD     Capstone PowerPC disassembler
ad       rar       LGPL3   RAR VM
_d 32      sh        GPL3   SuperH-4 CPU
_d 32 64    sparc     GPL3   Scalable Processor Architecture
_d 32      tms320    LGPLv3  TMS320 DSP family
_d 32      ws        LGPL3   Whitespace esoteric VM
_d 16 32 64 x86      BSD     udis86 x86-16,32,64
_d 16 32 64 x86.cs   BSD     Capstone X86 disassembler
a_ 32 64    x86.nz   LGPL3   x86 handmade assembler
ad 32      x86.olly  GPL2   OllyDBG X86 disassembler
ad 8       z80      NC-GPL2 Zilog Z80
```

Note that "ad" in the first column means both assembler and disassembler are offered by a corresponding plugin. "*d*" indicates disassembler, "a" means only assembler is available.

# Assembler

`rasm2` can be used from the command-line to quickly copy-paste hexpairs that represent a given machine instruction.

```
$ rasm2 -a x86 -b 32 'mov eax, 33'  
b821000000  
  
$ echo 'push eax;nop;nop' | rasm2 -f -  
5090
```

Rasm2 is used by radare2 core to write bytes using `wa` command.

The assembler understands the following input languages and their flavors: x86 (Intel and AT&T variants), olly (OllyDBG syntax), powerpc (PowerPC), arm and java. For Intel syntax, rasm2 tries to mimic NASM or GAS.

There are several examples in the rasm2 source code directory. Consult them to understand how you can assemble a raw binary file from a rasm2 description.

```
$ cat selfstop.rasm
;
; Self-Stop shellcode written in rasm for x86
;
; --pancake
;

.arch x86
.equ base 0x8048000
.org 0x8048000 ; the offset where we inject the 5 byte jmp

selfstop:
    push 0x8048000
    pusha
    mov eax, 20
    int 0x80

    mov ebx, eax
    mov ecx, 19
    mov eax, 37
    int 0x80
    popa
    ret
;
; The call injection
;
ret

[0x0000000000]> e asm.bits = 32
[0x0000000000]> wx `!rasm2 -f a.rasm`
[0x0000000000]> pd 20
    0x00000000      6800800408  push 0x8048000 ; 0x08048000
    0x00000005      60          pushad
    0x00000006      b814000000  mov eax, 0x14 ; 0x00000014
    0x0000000b      cd80       int 0x80
        syscall[0x80][0]=?
    0x0000000d      89c3       mov ebx, eax
    0x0000000f      b913000000  mov ecx, 0x13 ; 0x00000013
    0x00000014      b825000000  mov eax, 0x25 ; 0x00000025
    0x00000019      cd80       int 0x80
        syscall[0x80][0]=?
    0x0000001b      61          popad
    0x0000001c      c3          ret
    0x0000001d      c3          ret
```

# Disassembler

Passing the `-d` option to rasm2 allows you to disassemble a hexpair string:

```
$ rasm2 -a x86 -b 32 -d '90'  
nop
```

# Data and Code Analysis

There are different commands to perform data and code analysis, to extract useful information from a binary, like pointers, string references, basic blocks, opcode data, jump targets, xrefs, etc. These operations are handled by the `a` (analyze) command family:

```
|Usage: a[?adffghoprsx]
| a8 [hexpairs]    analyze bytes
| aa              analyze all (fcns + bbs)
| ad              analyze data trampoline (wip)
| ad [from] [to]   analyze data pointers to (from-to)
| ae [expr]        analyze opcode eval expression (see ao)
| af[rnbcs1?+-*]  analyze Functions
| aF              same as above, but using graph.depth=1
| ag[?acgdlf]      output Graphviz code
| ah[?lba-]        analysis hints (force opcode size, ...)
| ao[e?] [len]     analyze Opcodes (or emulate it)
| ap              find and analyze function preludes
| ar[?ld-*]        manage refs/xrefs (see also afr?)
| as [num]         analyze syscall using dbg.reg
| at[trd+-*?] [. ] analyze execution Traces
|Examples:
| f ts @ `S*~text:0[3]`; f t @ section..text
| f ds @ `S*~data:0[3]`; f d @ section..data
| .ad t t+ts @ d:ds
```

# Code Analysis

Code analysis is a common technique used to extract information from assembly code. Radare uses internal data structures to identify basic blocks, function trees, to extract opcode-level information etc. The most common radare2 analysis command sequence is:

```
[0x08048440]> aa
[0x08048440]> pdf @ main

; DATA XREF from 0x08048457 (entry0)
/ (fcn) fcn.08048648 141
|     ;-- main:
|     0x08048648    8d4c2404    lea ecx, [esp+0x4]
|     0x0804864c    83e4f0      and esp, 0xffffffff0
|     0x0804864f    ff71fc      push dword [ecx-0x4]
|     0x08048652    55          push ebp
|     ; CODE (CALL) XREF from 0x08048734 (fcn.080486e5)
|     0x08048653    89e5          mov ebp, esp
|     0x08048655    83ec28      sub esp, 0x28
|     0x08048658    894df4      mov [ebp-0xc], ecx
|     0x0804865b    895df8      mov [ebp-0x8], ebx
|     0x0804865e    8975fc      mov [ebp-0x4], esi
|     0x08048661    8b19          mov ebx, [ecx]
|     0x08048663    8b7104      mov esi, [ecx+0x4]
|     0x08048666    c744240c000. mov dword [esp+0xc], 0x0
|     0x0804866e    c7442408010. mov dword [esp+0x8], 0x1 ; 0x00000001
|     0x08048676    c7442404000. mov dword [esp+0x4], 0x0
|     0x0804867e    c7042400000. mov dword [esp], 0x0
|     0x08048685    e852fdffff  call sym..imp.ptrace
|           sym..imp.ptrace(unk, unk)
|     0x0804868a    85c0          test eax, eax
|     ,=< 0x0804868c    7911          jns 0x804869f
|     | 0x0804868e    c70424cf870. mov dword [esp], str.Don_tuseadebuguer_ ; 0x80
487cf
|     | 0x08048695    e882fdffff  call sym..imp.puts
|     |     sym..imp.puts()
|     | 0x0804869a    e80dfdffff  call sym..imp.abort
|     |     sym..imp.abort()
|     `-> 0x0804869f    83fb02      cmp ebx, 0x2
|     ,==< 0x080486a2    7411          je 0x80486b5
|     | 0x080486a4    c704240c880. mov dword [esp], str.Youmustgiveapasswordforuset
hisprogram_ ; 0x804880c
|     | 0x080486ab    e86cfdffff  call sym..imp.puts
|     |     sym..imp.puts()
|     | 0x080486b0    e8f7fcffff  call sym..imp.abort
|     |     sym..imp.abort()
|     `--> 0x080486b5    8b4604      mov eax, [esi+0x4]
|     0x080486b8    890424      mov [esp], eax
|     0x080486bb    e8e5feffff  call fcn.080485a5
```

```
|           fcn.080485a5() ; fcn.080484c6+223
| 0x080486c0    b800000000    mov eax, 0x0
| 0x080486c5    8b4df4        mov ecx, [ebp-0xc]
| 0x080486c8    8b5df8        mov ebx, [ebp-0x8]
| 0x080486cb    8b75fc        mov esi, [ebp-0x4]
| 0x080486ce    89ec          mov esp, ebp
| 0x080486d0    5d             pop ebp
| 0x080486d1    8d61fc        lea esp, [ecx-0x4]
\ 0x080486d4    c3             ret
```

In this example, we analyze the whole file ( `aa` ) and then print disassembly of the `main()` function ( `pdf` ).

Functions (fcn.) are referenced by call , (sub.) subroutines use to be just part of a function, sometimes referenced by pointer tables, etc, (loc.) is for local.

# Obtaining Hashes within Radare2 Session

To calculate a checksum of current block when running radare2, use the '#' command. Pass an algorithm name to it as a parameter. An example session:

```
$ radare2 /bin/ls  
[0x08049790]> bf entry0  
[0x08049790]> #md5  
d2994c75adaa58392f953a448de5fba7
```

You can use all hashing algorithms supported by `rahash2` : md4, md5, crc16, crc32, sha1, sha256, sha384, sha512, par, xor, xorpair, mod255, hamdist, entropy. The `#` command accepts an optional numeric argument to specify length of byte range to be hashed, instead of default block size. For example:

```
[0x08049A80]> #md5 32  
9b9012b00ef7a94b5824105b7aaad83b  
[0x08049A80]> #md5 64  
a71b087d8166c99869c9781e2edcf183  
[0x08049A80]> #md5 1024  
a933cc94cd705f09a41ecc80c0041def  
[0x08049A80]>
```

## Rahash2

The rahash2 tool can be used to calculate checksums and has functions of byte streams, files, text strings.

```
$ rahash2 -h
Usage: rahash2 [-rBhLkv] [-b sz] [-a algo] [-s str] [-f from] [-t to] [file] ...
-a algo      comma separated list of algorithms (default is 'sha256')
-b bsize     specify the size of the block (instead of full file)
-B           show per-block hash
-e           swap endian (use little endian)
-f from     start hashing at given address
-i num       repeat hash N iterations
-S seed      use given seed (hexa or s:string) use ^ to prefix
-k           show hash using the openssh's randomkey algorithm
-q           run in quiet mode (only show results)
-L           list all available algorithms (see -a)
-r           output radare commands
-s string    hash this string instead of files
-t to        stop hashing at given address
-v           show version information
```

To obtain an MD5 hash value of a text string, use the `-s` option:

```
$ rahash2 -q -a md5 -s 'hello world'
5eb63bbbe01eede093cb22bb8f5acdc3
```

It is possible to calculate hash values for contents of files. But do not attempt to do it for large files, like complete disks. Before starting a calculation, rahash2 copies the whole input into a memory buffer.

To apply all algorithms known to rahash2, use `all` as an algorithm name:

```
$ rahash2 -a all /bin/ls
/bin/ls: 0x00000000-0x0001ae08 md5: b5607b4dc7d896c0fab5c4a308239161
/bin/ls: 0x00000000-0x0001ae08 sha1: c8f5032c2dce807c9182597082b94f01a3bec495
/bin/ls: 0x00000000-0x0001ae08 sha256: 978317d58e3ed046305df92a19f7d3e0bfcb3c70cad979f
24fee289ed1d266b0
/bin/ls: 0x00000000-0x0001ae08 sha384: 9e946efdbebb4e0ca00c86129ce2a71ee734ac30b620336
c381aa929dd222709e4cf7a800b25fbc7d06fe3b184933845
/bin/ls: 0x00000000-0x0001ae08 sha512: 076806cedb5281fd15c21e493e12655c55c52537fc1f36e
641b57648f7512282c03264cf5402b1b15cf03a20c9a60edfd2b4f76d4905fcecc777c297d3134f41f
/bin/ls: 0x00000000-0x0001ae08 crc16: 4b83
/bin/ls: 0x00000000-0x0001ae08 crc32: 6e316348
/bin/ls: 0x00000000-0x0001ae08 md4: 3a75f925a6a197d26bc650213f12b074
/bin/ls: 0x00000000-0x0001ae08 xor: 3e
/bin/ls: 0x00000000-0x0001ae08 xorpair: 59
/bin/ls: 0x00000000-0x0001ae08 parity: 01
/bin/ls: 0x00000000-0x0001ae08 entropy: 0567f925
/bin/ls: 0x00000000-0x0001ae08 hamdist: 00
/bin/ls: 0x00000000-0x0001ae08 pcprint: 23
/bin/ls: 0x00000000-0x0001ae08 mod255: 1e
/bin/ls: 0x00000000-0x0001ae08 xxhash: 138c936d
/bin/ls: 0x00000000-0x0001ae08 adler32: fca7131b
```

# Debugger

Debuggers are implemented as IO plugins. Therefore, radare can handle different URI types for spawning, attaching and controlling processes. The complete list of IO plugins can be viewed with `r2 -L`. Those that have "d" in the first column ("rwd") support debugging. For example:

```
r_d  debug      Debug a program or pid. dbg:///bin/ls, dbg://1388 (LGPL3)
rwd  gdb        Attach to gdbserver, 'qemu -s', gdb://localhost:1234 (LGPL3)
```

There are different backends for many target architectures and operating systems, e.g., GNU/Linux, Windows, MacOS X, (Net,Free,Open)BSD and Solaris.

A process memory is treated as a plain file. All mapped memory pages of a debugged program and its libraries can be read and interpreted as code, data structures etc.

Communication between radare and debugger IO layer is wrapped into `system()` calls, which accepts a string as an argument, and executes it as a command. An answer is then buffered in output console, its contents can be additionally processed by a script. This is how radare handles single `!` and double `!!` exclamation mark commands for calling

```
system():
```

```
[0x0000000000]> ds
[0x0000000000]> !!ls
```

The double exclamation mark `!!` tells radare to skip the IO plugin list, and to pass the rest of the command directly to shell. Using the single `!` to prepend a command will cause a walk through the IO plugin list to find one that handles it.

In general, debugger commands are portable between architectures and operating systems. Still, as radare tries to support the same functionality for all target architectures and operating systems, certain things have to be handled separately. They include injecting shellcodes and handling exceptions. For example, in MIPS targets there is no hardware-supported single-stepping feature. In this case, radare2 provides its own implementation for single-step by using a mix of code analysis and software breakpoints.

To get the basic help for debugger, type 'd?':

```
Usage: d[sbhcrbo] [arg]
dh [handler]    list or set debugger handler
dH [handler]    transplant process to a new handler
dd              file descriptors (!fd in r1)
ds[ol] N        step, over, source line
do              open process (reload, alias for 'oo')
dk [sig][=act]  list, send, get, set, signal handlers of child
di[s] [arg...]  inject code on running process and execute it (See gs)
dp[=?t][pid]   list, attach to process or thread id
dc[?]          continue execution. dc? for more
dr[?]          cpu registers, dr? for extended help
db[?]          breakpoints
dbt             display backtrace
dt[?r] [tag]    display instruction traces (dtr=reset)
dm[?*]         show memory maps
dw [pid]       block prompt until pid dies
```

To restart your debugging session, you can type `oo` or `oo+`, depending on desired behavior.

```
oo              reopen current file (kill+fork in debugger)
oo+             reopen current file in read-write
```

# Getting Started

## Small session in radare2 debugger

- `r2 -d /bin/ls` : Opens radare2 with file `/bin/ls` in debugger mode using the radare2 native debugger, but does not run the program. You'll see a prompt (radare2) - all examples are from this prompt.
- `db flag` : place a breakpoint at flag, where flag can be either an address or a function name
- `db - flag` : remove the breakpoint at flag, where flag can be either an address or a function name
- `db` : show list of breakpoint
- `dc` : run the program
- `dr` : Show registers state
- `drr` : Show registers references (telescoping) (like peda)
- `ds` : Step into instruction
- `dso` : Step over instruction
- `dbt` : Display backtrace
- `dm` : Show memory maps
- `dk <signal>` : Send KILL signal to child
- `ood` : reopen in debug mode
- `ood arg1 arg2` : reopen in debug mode with arg1 and arg2

# Registers

The registers are part of user area stored in the context structure used by the scheduler. This structure can be manipulated to get and set values of those registers, and, for example, on Intel hosts, it is possible to directly manipulate DR0-DR7 hardware registers to set hardware breakpoints.

There are different commands to get values of registers. For the General Purpose ones use:

```
[0x4A13B8C0]> dr
r15 = 0x0000000000
r14 = 0x0000000000
r13 = 0x0000000000
r12 = 0x0000000000
rbp = 0x0000000000
rbx = 0x0000000000
r11 = 0x0000000000
r10 = 0x0000000000
r9 = 0x0000000000
r8 = 0x0000000000
rax = 0x0000000000
rcx = 0x0000000000
rdx = 0x0000000000
rsi = 0x0000000000
rdi = 0x0000000000
oeax = 0x00000003b
rip = 0x7f20bf5df630
rsp = 0x7fff515923c0

[0x7f0f2dbae630]> dr?rip ; get value of 'rip'
0x7f0f2dbae630

[0x4A13B8C0]> dr rip = esp ; set 'rip' as esp
```

Interaction between a plugin and the core is done by commands returning radare instructions. This is used, for example, to set flags in the core to set values of registers.

```
[0x7f0f2dbae630]> dr*      ; Appending '*' will show radare commands
f r15 1 0x0
f r14 1 0x0
f r13 1 0x0
f r12 1 0x0
f rbp 1 0x0
f rbx 1 0x0
f r11 1 0x0
f r10 1 0x0
f r9 1 0x0
f r8 1 0x0
f rax 1 0x0
f rcx 1 0x0
f rdx 1 0x0
f rsi 1 0x0
f rdi 1 0x0
f oeax 1 0x3b
f rip 1 0x7fff73557940
f rflags 1 0x200
f rsp 1 0x7fff73557940

[0x4A13B8C0]> .dr* ; include common register values in flags
```

An old copy of registers is stored all the time to keep track of the changes done during execution of a program being analyzed. This old copy can be accessed with `oregs`.

```
[0x7f1fab84c630]> dro
r15 = 0x00000000
r14 = 0x00000000
r13 = 0x00000000
r12 = 0x00000000
rbp = 0x00000000
rbx = 0x00000000
r11 = 0x00000000
r10 = 0x00000000
r9 = 0x00000000
r8 = 0x00000000
rax = 0x00000000
rcx = 0x00000000
rdx = 0x00000000
rsi = 0x00000000
rdi = 0x00000000
oeax = 0x0000003b
rip = 0x7f1fab84c630
rflags = 0x00000200
rsp = 0x7fff386b5080
```

```
[0x7f1fab84c630]> dr
r15 = 0x00000000
r14 = 0x00000000
r13 = 0x00000000
r12 = 0x00000000
rbp = 0x00000000
rbx = 0x00000000
r11 = 0x00000000
r10 = 0x00000000
r9 = 0x00000000
r8 = 0x00000000
rax = 0x00000000
rcx = 0x00000000
rdx = 0x00000000
rsi = 0x00000000
rdi = 0x7fff386b5080
oeax = 0xfffffffffffffff
rip = 0x7f1fab84c633
rflags = 0x00000202
rsp = 0x7fff386b5080
```

Values stored in eax, oeax and eip have changed.

To store and restore register values you can just dump the output of 'dr\*' command to disk and then re-interpret it again:

```
[0x4A13B8C0]> dr* > regs.saved ; save registers
[0x4A13B8C0]> drp regs.saved ; restore
```

EFLAGS can be similarly altered. E.g., setting selected flags:

```
[0x4A13B8C0]> dr eflags = pst  
[0x4A13B8C0]> dr eflags = azsti
```

You can get a string which represents latest changes of registers using `drd` command (diff registers):

```
[0x4A13B8C0]> drd  
eax = 0x0000003b was 0x00000000 delta 59  
rip = 0x7f00e71282d0 was 0x00000000 delta -418217264  
rflags = 0x00000200 was 0x00000000 delta 512  
rsp = 0x7ffe85a09c0 was 0x00000000 delta -396752448
```

# Remote Access Capabilities

Radare can be run locally, or it can be started remotely just the same. It is possible because everything uses radare's IO subsystem that abstracts access to system(), cmd() and all basic IO operations through the network.

Help for commands useful for remote access to radare:

```
[0x00405a04]> =?
|Usage:  =[:!+-=hH] [...] # radare remote command execution protocol
|
rap commands:
| =          list all open connections
| <=[fd] cmd send output of local command to remote fd
| =[fd] cmd   exec cmd at remote 'fd' (last open is default one)
| != cmd     run command via r_io_system
| += [proto://]host add host (default=rap://, tcp://, udp://)
| -=[fd]      remove all hosts or host 'fd'
| ==[fd]      open remote session with host 'fd', 'q' to quit
|
rap server:
| :=port    listen on given port using rap protocol (o rap://9999)
| =:host:port cmd run 'cmd' command on remote server
|
http server:
| =h port   listen for http connections (r2 -qc=H /bin/ls)
| =h-       stop background webserver
| =h*       restart current webserver
| =h& port  start http server in background)
| =H port   launch browser and listen for http
| =H& port  launch browser and listen for http in background
```

You can learn radare2 remote capabilities by displaying the list of supported IO plugins:

```
radare2 -L .
```

A little example should help understanding. A typical remote session can be like this:

At the remote host1:

```
$ radare2 rap://:1234
```

At the remote host2:

```
$ radare2 rap://:1234
```

At localhost:

```
$ radare2 -
```

; Add hosts

```
[0x004048c5]> =+ rap://<host1>:1234//bin/ls
Connected to: <host1> at port 1234
waiting... ok

[0x004048c5]> =
0 - rap://<host1>:1234//bin/ls
```

You can open remote files in debug mode (or using any IO plugin) specifying URI when adding hosts:

```
[0x004048c5]> =+ =+ rap://<host2>:1234/dbg:///bin/ls
Connected to: <host2> at port 1234
waiting... ok
0 - rap://<host1>:1234//bin/ls
1 - rap://<host2>:1234/dbg:///bin/ls
```

To execute commands on host1:

```
[0x004048c5]> =0 px
[0x004048c5]> = s 0x666
```

To open a session with host2:

```
[0x004048c5]> ==1
fd:6> pi 1
...
fd:6> q
```

To remove hosts (and close connections):

```
[0x004048c5]> =-
```

If you can initialize a TCP or UDP server, add it with '==+ tcp://' or '==+ udp://'. Then redirect radare output to them. For instance:

```
[0x004048c5]> =+ tcp://<host>:<port>/  
Connected to: <host> at port <port>  
5 - tcp://<host>:<port>/  
[0x004048c5]> =<5 cmd...
```

The `=<' command will send result of a command's execution at the right to the remote connection number N (or the last one used if no id specified).

# Plugins

## IO plugins

All the access to files, network, debugger, etc.. is wrapped by an IO abstraction layer that allows to interpret all the data as if it was a single file.

IO plugins are the ones used to wrap the open, read, write and 'system' on virtual file systems. You can make radare understand anything as a plain file. E.g., a socket connection, a remote radare session, a file, a process, a device, a gdb session, etc..

So, when radare reads a block of bytes, it is the task of an IO plugin to get these bytes from any place and put them into internal buffer. An IO plugin is chosen by a file's URI to be opened. Some examples:

- Debugging URIs

```
$ r2 dbg:///bin/ls $ r2 pid://1927
```

- Remote sessions

```
$ r2 rap://:1234 $ r2 rap://:1234//bin/ls
```

- Virtual buffers

```
$ r2 malloc://512 shortcut for $ r2 -
```

You can get a list of the radare IO plugins by typing `radare2 -L :`

```
$ r2 -L
rw_ zip          Open zip files apk://foo.apk//MANIFEST or zip://foo.apk//theclasse/fun
.class, show files with: zip://foo.apk/, open all files with zipall:// (BSD)
rwd windbg       Attach to a KD debugger (LGPL3)
rw_ sparse        sparse buffer allocation (sparse://1024 sparse://) (LGPL3)
rw_ shm           shared memory resources (shm://key) (LGPL3)
rw_ self          read memory from myself using 'self://' (LGPL3)
rw_ rap           radare network protocol (rap://:port rap://host:port/file) (LGPL3)
rwd ptrace        ptrace and /proc/pid/mem (if available) io (LGPL3)
rw_ procpid      /proc/pid/mem io (LGPL3)
rw_ mmap          open file using mmap:// (LGPL3)
rw_ malloc        memory allocation (malloc://1024 hex://cd8090) (LGPL3)
r_ mach           mach debug io (unsupported in this platform) (LGPL)
rw_ ihex          Intel HEX file (ihex://eeproms.hex) (LGPL)
rw_ http          http get (http://radare.org/) (LGPL3)
rw_ gzip          read/write gzipped files (LGPL3)
rwd gdb           Attach to gdbserver, 'qemu -s', gdb://localhost:1234 (LGPL3)
r_d debug         Debug a program or pid. dbg:///bin/ls, dbg://1388 (LGPL3)
rw_ bfdbg         BrainFuck Debugger (bfdbg://path/to/file) (LGPL3)
```

# Crackmes

Crackmes (from "crack me" challenge) are the training ground for reverse engineering people. This section will go over tutorials on how to defeat various crackmes using r2.

# IOLI CrackMes

The IOLI crackme is a good starting point for learning r2. This is a set of tutorials based on the tutorial at [dustri](#)

The IOLI crackmes are available at a locally hosted [mirror](#)

# IOLI 0x00

This is the first IOLI crackme, and the easiest one.

```
$ ./crackme0x00
IOLI Crackme Level 0x00
Password: 1234
Invalid Password!
```

The first thing to check is if the password is just plaintext inside the file. In this case, we don't need to do any disassembly, and we can just use rabin2 with the -z flag to search for strings in the binary.

```
$ rabin2 -z ./crackme0x00
vaddr=0x08048568 paddr=0x00000568 ordinal=000 sz=25 len=24 section=.rodata type=a string=IOLI Crackme Level 0x00\n
vaddr=0x08048581 paddr=0x00000581 ordinal=001 sz=11 len=10 section=.rodata type=a string=Password:
vaddr=0x0804858f paddr=0x0000058f ordinal=002 sz=7 len=6 section=.rodata type=a string =250382
vaddr=0x08048596 paddr=0x00000596 ordinal=003 sz=19 len=18 section=.rodata type=a string=Invalid Password!\n
vaddr=0x080485a9 paddr=0x000005a9 ordinal=004 sz=16 len=15 section=.rodata type=a string=Password OK :)\n
```

So we know what the following section is, this section is the header shown when the application is run.

```
vaddr=0x08048568 paddr=0x00000568 ordinal=000 sz=25 len=24 section=.rodata type=a string=IOLI Crackme Level 0x00\n
```

Here we have the prompt for the password.

```
vaddr=0x08048581 paddr=0x00000581 ordinal=001 sz=11 len=10 section=.rodata type=a string=Password:
```

This is the error on entering an invalid password.

```
vaddr=0x08048596 paddr=0x00000596 ordinal=003 sz=19 len=18 section=.rodata type=a string=Invalid Password!\n
```

This is the message on the password being accepted.

```
vaddr=0x080485a9 paddr=0x000005a9 ordinal=004 sz=16 len=15 section=.rodata type=a string=Password OK :)\n
```

But what is this? It's a string, but we haven't seen it in running the application yet.

```
vaddr=0x0804858f paddr=0x0000058f ordinal=002 sz=7 len=6 section=.rodata type=a string=250382
```

Let's give this a shot.

```
$ ./crackme0x00
IOLI Crackme Level 0x00
Password: 250382
Password OK :)
```

So we now know that 250382 is the password, and have completed this crackme.

# IOLI 0x01

This is the second IOLI crackme.

```
$ ./crackme0x01
IOLI Crackme Level 0x01
Password: test
Invalid Password!
```

Let's check for strings with rabin2.

```
$ rabin2 -z ./crackme0x01
vaddr=0x08048528 paddr=0x00000528 ordinal=000 sz=25 len=24 section=.rodata type=a string=IOLI Crackme Level 0x01\n
vaddr=0x08048541 paddr=0x00000541 ordinal=001 sz=11 len=10 section=.rodata type=a string=Password:
vaddr=0x0804854f paddr=0x0000054f ordinal=002 sz=19 len=18 section=.rodata type=a string=Invalid Password!\n
vaddr=0x08048562 paddr=0x00000562 ordinal=003 sz=16 len=15 section=.rodata type=a string=Password OK :)\n
```

This isn't going to be as easy as 0x00. Let's try disassembly with r2.

```
$ r2 ./crackme0x01 -- Use `zoom.byte=printable` in zoom mode ('z' in Visual mode) to find strings
[0x08048330]> aa
[0x08048330]> pdf@main
/ (fcn) main 113
|     ; var int local_4 @ ebp-0x4
|     ; DATA XREF from 0x08048347 (entry0)
|     0x080483e4    55          push ebp
|     0x080483e5    89e5        mov ebp, esp
|     0x080483e7    83ec18    sub esp, 0x18
|     0x080483ea    83e4f0    and esp, -0x10
|     0x080483ed    b800000000  mov eax, 0
|     0x080483f2    83c00f    add eax, 0xf
|     0x080483f5    83c00f    add eax, 0xf
|     0x080483f8    c1e804    shr eax, 4
|     0x080483fb    c1e004    shl eax, 4
|     0x080483fe    29c4        sub esp, eax
|     0x08048400    c7042428850  mov dword [esp], str.IOLI_Crackme_Level_0x01_n ;
[0x8048528:4]=0x494c4f49 ; "IOLI Crackme Level 0x01." @ 0x8048528
|     0x08048407    e810ffff    call sym.imp.printf
|         sym.imp.printf(unk)
|     0x0804840c    c7042441850  mov dword [esp], str.Password_ ; [0x8048541:4]=0
x73736150 ; "Password: " @ 0x8048541
|     0x08048413    e804ffff    call sym.imp.printf
|         sym.imp.printf()
|     0x08048418    8d45fc    lea eax, dword [ebp + 0xfffffffffc]
|     0x0804841b    89442404  mov dword [esp + 4], eax ; [0x4:4]=0x10101
|     0x0804841f    c704244c850  mov dword [esp], 0x804854c ; [0x804854c:4]=0x490
06425 ; "%d" @ 0x804854c
|     0x08048426    e8e1feffff  call sym.imp.scanf
|         sym.imp.scanf()
|     0x0804842b    817dfc9a140  cmp dword [ebp + 0xfffffffffc], 0x149a
|     ,=< 0x08048432    740e        je 0x8048442
|     | 0x08048434    c704244f850  mov dword [esp], str.Invalid_Password_n ; [0x80
4854f:4]=0x61766e49 ; "Invalid Password!.." @ 0x804854f
|     | 0x0804843b    e8dcfeffff  call sym.imp.printf
|         sym.imp.printf()
|     ,==< 0x08048440    eb0c        jmp 0x804844e ; (main)
|     || ; JMP XREF from 0x08048432 (main)
|     |`-> 0x08048442    c7042462850  mov dword [esp], str.Password_OK____n ; [0x80485
62:4]=0x73736150 ; "Password OK :)." @ 0x8048562
|     | 0x08048449    e8cefefeff  call sym.imp.printf
|         sym.imp.printf()
|     | ; JMP XREF from 0x08048440 (main)
|     `--> 0x0804844e    b800000000  mov eax, 0
|     0x08048453    c9          leave
\     0x08048454    c3          ret
```

"aa" tells r2 to analyze the whole binary, which gets you symbol names, among things.

"pdf" stands for

- Print
- Disassemble
- Function

This will print the disassembly of the main function, or the `main()` that everyone knows. You can see several things as well: weird names, arrows, etc.

- "imp." stands for imports. Those are imported symbols, like `printf()`
- "str." stands for strings. Those are strings (obviously).

If you look carefully, you'll see a `cmp` instruction, with a constant, `0x149a`. `cmp` is an x86 compare instruction, and the `0x` in front of it specifies it is in base 16, or hex (hexadecimal).

```
0x0804842b      817dfc9a140. cmp dword [ebp + 0xfffffffffc], 0x149a
```

You can use radare2's `?`  command to get it in another numeric base.

```
[0x08048330]> ? 0x149a
5274 0x149a 012232 5.2K 0000:049a 5274 10011010 5274.0 0.000000
```

So now we know that `0x149a` is `5274` in decimal. Let's try this as a password.

```
$ ./crackme0x01
IOLI Crackme Level 0x01
Password: 5274
Password OK :)
```

Bingo, the password was `5274`. In this case, the password function at `0x0804842b` was comparing the input against the value, `0x149a` in hex. Since user input is usually decimal, it was a safe bet that the input was intended to be in decimal, or `5274`. Now, since we're hackers, and curiosity drives us, let's see what happens when we input in hex.

```
$ ./crackme0x01
IOLI Crackme Level 0x01
Password: 0x149a
Invalid Password!
```

It was worth a shot, but it doesn't work. That's because `scanf()` will take the `0` in `0x149a` to be a zero, rather than accepting the input as actually being the hex value.

And this concludes IOLI 0x01.



## .intro

After a few years of missing out on wargames at [Hacktivity](#), this year I've finally found the time to begin, and almost finish (yeah, I'm quite embarrassed about that unfinished webhack :)) one of them. There were 3 different games at the conf, and I've chosen the one that was provided by [avatao](#). It consisted of 8 challenges, most of them being basic web hacking stuff, one sandbox escape, one simple buffer overflow exploitation, and there were two reverse engineering exercises too. You can find these challenges on <https://platform.avatao.com>.

## .radare2

I've decided to solve the reversing challenges using [radare2](#), a free and open source reverse engineering framework. I have first learned about r2 back in 2011. during a huge project, where I had to reverse a massive, 11MB statically linked ELF. I simply needed something that I could easily patch Linux ELF's with. Granted, back then I've used r2 alongside IDA, and only for smaller tasks, but I loved the whole concept at first sight. Since then, radare2 evolved a lot, and I was planning for some time now to solve some crackmes with the framework, and write writeups about them. Well, this CTF gave me the perfect opportunity :)

Because this writeup aims to show some of r2's features besides how the crackmes can be solved, I will explain every r2 command I use in blockquote paragraphs like this one:

**r2 tip:** Always use ? or -h to get more information!

If you know r2, and just interested in the crackme, feel free to skip those parts! Also keep in mind please, that because of this tutorial style I'm going to do a lot of stuff that you just don't do during a CTF, because there is no time for proper bookkeeping (e.g. flag every memory area according to its purpose), and with such small executables you can succeed without doing these stuff.

A few advice if you are interested in learning radare2 (and frankly, if you are into RE, you should be interested in learning r2 :):

The framework has a lot of supplementary executables and a vast amount of functionality - and they are very well documented. I encourage you to read the available docs, and use the built-in help (by appending a ? to any command) extensively! E.g.:

```
[0x00000000]> ?
Usage: [.][times][cmd][~grep][@[@iter]addr!size][|>pipe] ; ...
Append '?' to any char command to get detailed help
Prefix with number to repeat command N times (f.ex: 3x)
|%var =valueAlias for 'env' command
| *off[=[0x]value]      Pointer read/write data/values (see ?v, wx, wv)
| (macro arg0 arg1)    Manage scripting macros
| .[-|(m)|f||!sh|cmd] Define macro or load r2, cparses or rlang file
| [= [cmd]              Run this command via rap://
| /                   Search for bytes, regexps, patterns, ..
| ! [cmd]              Run given command as in system(3)
| # [algo] [len]        Calculate hash checksum of current block
| #!lang [...]          Hashbang to run an rlang script
| a                   Perform analysis of code
| b                   Get or change block size

...
[0x00000000]> a?
|Usage: a[abcdefGhoprstc] [...]
| ab [hexpairs]      analyze bytes
| aa                 analyze all (fcns + bbs) (aa0 to avoid sub renaming)
| ac [cycles]        analyze which op could be executed in [cycles]
| ad                 analyze data trampoline (wip)
| ad [from] [to]     analyze data pointers to (from-to)
| ae [expr]          analyze opcode eval expression (see ao)
| af[rnbcsl?+-*]    analyze Functions
| aF                 same as above, but using anal.depth=1

...
```

Also, the project is under heavy development, there is no day without commits to the GitHub repo. So, as the readme says, you should always use the git version!

Some highly recommended reading materials:

- [Cheatsheet by pwntester](#)
- [Radare2 Book](#)
- [Radare2 Blog](#)
- [Radare2 Wiki](#)

## .first\_steps

OK, enough of praising r2, lets start reversing this stuff. First, you have to know your enemy:

```
[0x00 avatao]$ rabin2 -I reverse4
pic      false
canary   true
nx       true
crypto   false
va       true
intrp   /lib64/ld-linux-x86-64.so.2
bintype  elf
class    ELF64
lang     c
arch     x86
bits     64
machine AMD x86-64 architecture
os       linux
subsys   linux
 endian   little
stripped true
static   false
linenum  false
lsyms   false
relocs   false
rpath   NONE
binsz   8620
```

**r2 tip:** rabin2 is one of the handy tools that comes with radare2. It can be used to extract information (imports, symbols, libraries, etc.) about binary executables. As always, check the help (rabin2 -h)!

So, its a dynamically linked, stripped, 64bit Linux executable - nothing fancy here. Let's try to run it:

```
[0x00 avatao]$ ./reverse4
?
Size of data: 2623
pamparam
Wrong!

[0x00 avatao]$ "\x01\x00\x00\x00" | ./reverse4
Size of data: 1
```

OK, so it reads a number as a size from the standard input first, than reads further, probably "size" bytes/characters, processes this input, and outputs either "Wrong!", nothing or something else, presumably our flag. But do not waste any more time monkeyfuzzing the executable, let's fire up r2, because in asm we trust!

```
[0x00 avatao]$ r2 -A reverse4
-- Heisenbug: A bug that disappears or alters its behavior when one attempts to probe
or isolate it.
[0x00400720]>
```

**r2 tip:** The -A switch runs aa command at start to analyze all referenced code, so we will have functions, strings, XREFS, etc. right at the beginning. As usual, you can get help with ?.

It is a good practice to create a project, so we can save our progress, and we can come back at a later time:

```
[0x00400720]> Ps avatao_reverse4
avatao_reverse4
[0x00400720]>
```

**r2 tip:** You can save a project using Ps [file], and load one using Po [file]. With the -p option, you can load a project when starting r2.

We can list all the strings r2 found:

```
[0x00400720]> fs strings
[0x00400720]> f
0x00400e98 7 str.Wrong_
0x00400e9f 27 str.We_are_in_the_outer_space_
0x00400f80 18 str.Size_of_data:__u_n
0x00400f92 23 str.Such_VM__MuCH_rev3rse_
0x00400fa9 16 str.Use_everything_
0x00400fbb 9 str.flag.txt
0x00400fc7 26 str.You_won__The_flag_is:__s_n
0x00400fe1 21 str.Your_getting_closer_
[0x00400720]>
```

**r2 tip:** r2 puts so called flags on important/interesting offsets, and organizes these flags into flagspaces (strings, functions, symbols, etc.) You can list all flagspaces using *fs*, and switch the current one using *fs [flagspace]* (the default is \*, which means all the flagspaces). The command *f* prints all flags from the currently selected flagspace(s).

OK, the strings looks interesting, especially the one at 0x00400f92. It seems to hint that this crackme is based on a virtual machine. Keep that in mind!

These strings could be a good starting point if we were talking about a real-life application with many-many features. But we are talking about a crackme, and they tend to be small and simple, and focused around the problem to be solved. So I usually just take a look at the entry point(s) and see if I can figure out something from there. Nevertheless, I'll show you how to find where these strings are used:

```
[0x00400720]> axt @@=`f~[0]`  
d 0x400cb5 mov edi, str.Size_of_data:_u_n  
d 0x400d1d mov esi, str.Such_VM__MuCH_reV3rse_  
d 0x400d4d mov edi, str.Use_everything_  
d 0x400d85 mov edi, str.flag.txt  
d 0x400db4 mov edi, str.You_won__The_flag_is:_s_n  
d 0x400dd2 mov edi, str.Your_getting_closer_
```

**r2 tip:** We can list crossreferences to addresses using the `axt [addr]` command (similarly, we can use `axf` to list references from the address). The `@@` is an iterator, it just runs the command once for every arguments listed.

The argument list in this case comes from the command `f~[0]`. It lists the strings from the executable with `f`, and uses the internal grep command `~` to select only the first column (`[0]`) that contains the strings' addresses.

## .main

As I was saying, I usually take a look at the entry point, so let's just do that:


```
[0x00400720]> s main  
[0x00400c63]>
```

**r2 tip:** You can go to any offset, flag, expression, etc. in the executable using the `s` command (seek). You can use references, like `$$` (current offset), you can undo (`s-`) or redo (`s+`) seeks, search strings (`s/ [string]`) or hex values (`s/x 4142`), and a lot of other useful stuff. Make sure to check out `s?`!

Now that we are at the beginning of the main function, we could use `p` to show a disassembly (`pd`, `pdf`), but r2 can do something much cooler: it has a visual mode, and it can display graphs similar to IDA, but way cooler, since they are ASCII-art graphs :)

**r2 tip:** The command family `p` is used to print stuff. For example it can show disassembly (`pd`), disassembly of the current function (`pdf`), print strings (`ps`), hexdump (`px`), base64 encode/decode data (`p6e`, `p6d`), or print raw bytes (`pr`) so you can for example dump parts of the binary to other files. There are many more functionalities, check `?`!

R2 also has a minimap view which is incredibly useful for getting an overall look at a function:



**r2 tip:** With command `V` you can enter the so-called visual mode, which has several views. You can switch between them using `p` and `P`. The graph view can be displayed by hitting `V` in visual mode (or using `VV` at the prompt).

Hitting `p` in graph view will bring up the minimap. It displays the basic blocks and the connections between them in the current function, and it also shows the disassembly of the currently selected block (marked with `@@@@@` on the minimap). You can select the next or the previous block using the `*\*` and the `*\\*` keys respectively. You can also select the true or the false branches using the `t` and the `f` keys.

It is possible to bring up the prompt in visual mode using the `:` key, and you can use `o` to seek.

Lets read main node-by-node! The first block looks like this:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100% BB mouse:canvas-y movements-speed:5
0x400c63:
fcn) main 416
; arg int arg_1          @ rbp+0x8
; arg int arg_375        @ rbp+0xbb8
; var int local_0_1       @ rbp-0x1
; var int local_1         @ rbp-0x8
; var int local_8         @ rbp-0x40
; var int local_9         @ rbp-0x48
; var int local_10        @ rbp-0x50
; var int local_10_4       @ rbp-0x54
; var int size             @ rbp-0x56
; DATA XREF from 0x0040073d (main)
push rbp
mov rbp, rsp
sub rsp, 0x70
mov dword [rbp - 0x64], edi
mov qword [rbp - 0x70], rsi
mov rax, qword fs:[0x28] ; [0x28:8]=0x21b0  ; '('
mov qword [rbp-local_1], rax
xor eax, eax
lea rax, [rbp-size]
mov edx, 2
mov rsi, rax
mov edi, 0
mov eax, 0
call sym.imp.read ;[a]
movzx eax, word [rbp-size]
cmp ax, 0xbb8
jbe 0x400cac ;[b]
```

We can see that the program reads a word (2 bytes) into the local variable named `local_10_6`, and than compares it to `0xbb8`. Thats 3000 in decimal, btw:

```
[0x00400c63]> ? 0xbb8
3000 0xbb8 05670 2.9K 0000:0bb8 3000 10111000 3000.0 0.000000f 0.000000
```

**r2 tip:** yep, `?` will evaluate expressions, and print the result in various formats.


If the value is greater than 3000, then it will be forced to be 3000:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400ca6:
mov word [rbp-local_10_6], 0xbb8 ; [0xbb8:2]=0x45c7
```



There are a few things happening in the next block:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400cac:
movzx eax, word [rbp-local_10_6]
movzx eax, ax
mov esi, eax
mov edi, str.Size_of_data:_u_n ; "Size of data: %u." @ 0x400f80
mov eax, 0
call sym.imp.printf ;[c]
movzx eax, word [rbp-local_10_6]
movzx eax, ax
mov rdi, rax
call sym.imp.malloc ;[d]
mov qword [rbp-local_10], rax
movzx eax, word [rbp-local_10_6]
movzx edx, ax
mov rax, qword [rbp-local_10]
mov rsi, rax
mov edi, 0
mov eax, 0
call sym.imp.read ;[a]
mov edx, 0x200 ; "R.td." @ 0x200
mov esi, 0
mov edi, 0x602120 ; "ela.dyn" 0x00602120 ; "ela.dyn" @ 0x602120
call sym.imp.memset ;[e]
mov rax, qword [rbp-local_10]
mov rdi, rax
call fcn.00400a45 ;[f]
cmp eax, 0xa ; '*'
jne 0x400de8 ;[g]
```



First, the "Size of data: " message we saw when we run the program is printed. So now we know that the local variable *local\_10\_6* is the size of the input data - so lets name it accordingly (remember, you can open the r2 shell from visual mode using the : key!):

```
:> afvn local_10_6 input_size
```

**r2 tip:** The *af* command family is used to analyze functions. This includes manipulating arguments and local variables too, which is accessible via the *afv* commands. You can list function arguments (*afa*), local variables (*afv*), or you can even rename them (*afan*, *afvn*). Of course there are lots of other features too - as usual: use the "?", Luke!

After this an *input\_size* bytes long memory chunk is allocated, and filled with data from the standard input. The address of this memory chunk is stored in *local\_10* - time to use *afvn* again:

```
:> afvn local_10 input_data
```

We've almost finished with this block, there are only two things remained. First, an 512 (0x200) bytes memory chunk is zeroed out at offset 0x00602120. A quick glance at XREFS to this address reveals that this memory is indeed used somewhere in the application:

```
:> axt 0x00602120
d 0x400cf8 mov edi, 0x602120
d 0x400d22 mov edi, 0x602120
d 0x400dde mov edi, 0x602120
d 0x400a51 mov qword [rbp - 8], 0x602120
```

Since it probably will be important later on, we should label it:

```
:> f sym.memory 0x200 0x602120
```

**r2 tip:** Flags can be managed using the *f* command family. We've just added the flag *sym.memory* to a 0x200 bytes long memory area at 0x602120. It is also possible to remove (*f-name*), rename (*fr [old] [new]*), add comment (*fC [name] [cmt]*) or even color (*fc [name] [color]*) flags.

While we are here, we should also declare that memory chunk as data, so it will show up as a hexdump in disassembly view:

```
:> Cd 0x200 @ sym.memory
```

**r2 tip:** The command family C is used to manage metadata. You can set (CC) or edit (CC) comments, declare memory areas as data (Cd), strings (Cs), etc. These commands can also be issued via a menu in visual mode invoked by pressing *d*.

The only remaining thing in this block is a function call to 0x400a45 with the input data as an argument. The function's return value is compared to "\*", and a conditional jump is executed depending on the result.

Earlier I told you that this crackme is probably based on a virtual machine. Well, with that information in mind, one can guess that this function will be the VM's main loop, and the input data is the instructions the VM will execute. Based on this hunch, I've named this

function *vmloop*, and renamed *input\_data* to *bytecode* and *input\_size* to *bytecode\_length*. This is not really necessary in a small project like this, but it's a good practice to name stuff according to their purpose (just like when you are writing programs).

```
:> af vmloop 0x400a45
:> afvn input_size bytecode_length
:> afvn input_data bytecode
```

**r2 tip:** The *af* command is used to analyze a function with a given name at the given address. The other two commands should be familiar from earlier.

After renaming local variables, flagging that memory area, and renaming the VM loop function the disassembly looks like this:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5

0x400cac:
movzx eax, word [rbp-bytecode_length]
movzx eax, ax
mov esi, eax
mov edi, str.Size_of_data:_u_n ; "Size of data: %u." @ 0x400f80
mov eax, 0
call sym.imp.printf ;[c]
movzx eax, word [rbp-bytecode_length]
movzx eax, ax
mov rdi, rax
call sym.imp.malloc ;[d]
mov qword [rbp-bytecode], rax
movzx eax, word [rbp-bytecode_length]
movzx edx, ax
mov rax, qword [rbp-bytecode]
mov rsi, rax
mov edi, 0
mov eax, 0
call sym.imp.read ;[a]
mov edx, 0x200 ; "R.td." @ 0x200
mov esi, 0
mov edi, sym.memory ; "ela.dyn" @ 0x602120
call sym.imp.memset ;[e]
mov rax, qword [rbp-bytecode]
mov rdi, rax
call fcn.vmloop ;[f]
cmp eax, 0xa ; '*'
jne 0x400dde ;[g]
```

So, back to that conditional jump. If *vmloop* returns anything else than "\*", the program just exits without giving us our flag. Obviously we don't want that, so we follow the false branch.

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5

0x400d1d:
mov esi, str.Such_VM_MuCH_reV3rse_ ; "Such VM! MuCH reV3rse!" @ 0x400f92
mov edi, sym.memory ; "ela.dyn" @ 0x602120
call sym.imp.strcmp ;[i]
test eax, eax
jne 0x400dde ;[j]
```

Now we see that a string in that 512 bytes memory area (*sym.memory*) gets compared to "Such VM! MuCH reV3rse!". If they are not equal, the program prints the bytecode, and exits:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400dde:
mov edi, sym.memory ; "ela.dyn" @ 0x602120
call sym.imp.puts ;[k]

```

The minimap shows two nodes: `[_0d1d_]` and `[_0d34_]`. A dashed line connects them, indicating a flow or comparison between these points in the code.

OK, so now we know that we have to supply a bytecode that will generate that string when executed. As we can see on the minimap, there are still a few more branches ahead, which probably means more conditions to meet. Lets investigate them before we delve into *vmloop*!

If you take a look at the minimap of the whole function, you can probably recognize that there is some kind of loop starting at block `[0d34]`, and it involves the following nodes:

- `[0d34]`
- `[0d65]`
- `[0d3d]`
- `[0d61]`


Here are the assembly listings for those blocks. The first one puts 0 into local variable *local\_10\_4*:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400d34:
mov dword [rbp-i], 0      [_0dde_]
jmp 0x400d65 ;[l]          <@000000>

```

The minimap shows a complex loop structure. It starts at node `[_0d34_]`, goes to `[_0dde_]`, then to `<@000000>`, then to `[_0d65_]`, then to `[_0d3d_]`, then to `[_0d61_]`, then to `[_0d6b_]`, then to `[_0d4d_]`, then back to `[_0d34_]`. Nodes `[_0d65_]`, `[_0d3d_]`, `[_0d61_]`, and `[_0d6b_]` are highlighted with red boxes, indicating they are part of the loop.


And this one compares *local\_10\_4* to 8, and executing a conditional jump based on the result:




It's pretty obvious that *local\_10\_4* is the loop counter, so lets name it accordingly:

```
:> afvn local_10_4 i
```

Next block is the actual loop body:



The memory area at 0x6020e0 is treated as an array of dwds (4 byte values), and checked if the ith value of it is zero. If it is not, the loop simply continues:



If the value is zero, the loop breaks and this block is executed before exiting:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400d4d:
mov edi, str.Use_everything_ ; "Use everything!" @ 0x400fa9
call sym.imp.puts ;[k]
mov eax, 0
jmp 0x400ded ;[s]
```

It prints the following message: Use everything!" As we've established earlier, we are dealing with a virtual machine. In that context, this message probably means that we have to use every available instructions. Whether we executed an instruction or not is stored at 0x6020e0 - so lets flag that memory area:

```
:> f sym.instr_dirty 4*9 0x6020e0
```

Assuming we don't break out and the loop completes, we are moving on to some more checks:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400d6b:
mov eax, dword [rip + 0x201393] ; [0x602104:4]=0x762e756e ; "nu.version" @ 0x602104
test eax, eax
je 0x400dd2 ;[o]
```

This piece of code may look a bit strange if you are not familiar with x86\_64 specific stuff. In particular, we are talking about RIP-relative addressing, where offsets are described as displacements from the current instruction pointer, which makes implementing PIE easier. Anyways, r2 is nice enough to display the actual address (0x602104). Got the address, flag it!

```
:> f sym.good_if_ne_zero 4 0x602104
```

Keep in mind though, that if RIP-relative addressing is used, flags won't appear directly in the disassembly, but r2 displays them as comments:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400d6b:
mov eax, dword [rip + 0x201393] ; [0x602104:4]=0x762e756e LEA sym.good_if_ne_zero ; "nu.v
test eax, eax
je 0x400dd2 ;[o]
```

If *sym.good\_if\_ne\_zero* is zero, we get a message ("Your getting closer!"), and then the program exits. If it is non-zero, we move to the last check:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400d75:
mov eax, dword [rip + 0x201375] ; [0x6020f0:4]=0x642e0068 ; "h" @ 0x6020f0
cmp eax, 9
jg 0x400dd2 ;[o]
```

Here the program compares a dword at 0x6020f0 (again, RIP-relative addressing) to 9. If its greater than 9, we get the same "Your getting closer!" message, but if it's lesser, or equal to 9, we finally reach our destination, and get the flag:

```
[0x00400c63]> VV @ main (nodes 18 edges 25 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400d80:
mov esi, 0x400fb9           [_0d4d_]
mov edi, str.flag.txt ; "flag.txt" @ 0x400fb9
call sym.imp.fopen ;[p]
mov qword [rbp-local_9], rax
lea rdx, [rbp-local_8]
mov rax, qword [rbp-local_9]
mov esi, 0x400fc4
mov rdi, rax
mov eax, 0
call sym.imp._isoc99_fscanf ;[q]
lea rax, [rbp-local_8]
mov rsi, rax
mov edi, str.You_won__The_flag_is:_s_n ; "You won! The flag is: %s." @ 0x400fc7
mov eax, 0
call sym.imp.printf ;[c]
mov rax, qword [rbp-local_9]
mov rdi, rax
call sym.imp.fclose ;[r]
nop
jmp 0x400de8 ;[g]
```

As usual, we should flag 0x6020f0:

```
:> f sym.good_if_le_9 4 0x6020f0
```


Well, it seems that we have fully reversed the main function. To summarize it: the program reads a bytecode from the standard input, and feeds it to a virtual machine. After VM execution, the program's state have to satisfy these conditions in order to reach the goodboy code:

- *vmloop*'s return value has to be "/\*"
- *sym.memory* has to contain the string "Such VM! MuCH reV3rse!"
- all 9 elements of *sym.instr\_dirty* array should not be zero (probably means that all instructions had to be used at least once)
- *sym.good\_if\_ne\_zero* should not be zero
- *sym.good\_if\_le\_9* has to be lesser or equal to 9


This concludes our analysis of the main function, we can now move on to the VM itself.

## .vmloop

```
[offset]> fcn.vmloop
```



Well, that seems disappointingly short, but no worries, we have plenty to reverse yet. The thing is that this function uses a jump table at 0x00400a74,



and r2 can't yet recognize jump tables ([Issue 3201](#)), so the analysis of this function is a bit incomplete. This means that we can't really use the graph view now, so either we just use visual mode, or fix those basic blocks. The entire function is just 542 bytes long, so we certainly could reverse it without the aid of the graph mode, but since this writeup aims to include as much r2 wisdom as possible, I'm going to show you how to define basic blocks.

But first, lets analyze what we already have! First, *rdi* is put into *local\_3*. Since the application is a 64bit Linux executable, we know that *rdi* is the first function argument (as you may have recognized, the automatic analysis of arguments and local variables was not

entirely correct), and we also know that *vmloop*'s first argument is the bytecode. So lets rename local\_3:

```
:> afvn local_3 bytecode
```

Next, *sym.memory* is put into another local variable at *rbp-8* that r2 did not recognize. So let's define it!

```
:> afv 8 memory qword
```

**r2 tip:** The *afv [idx] [name] [type]* command is used to define local variable at [frame pointer - idx] with the name [name] and type [type]. You can also remove local variables using the *afv- [idx]* command.

In the next block, the program checks one byte of bytecode, and if it is 0, the function returns with 1.

```
[0x00400a45]> VV @ fcn.00400a45 (nodes 7 edges 7 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400c4d:
; JMP XREF from 0x00400a59 (fcn.00400a45)
mov rax, qword [_rbp-bytescode]
movzx eax, byte [rax]
test al, al
jne 0xa5e ;[e]
```

If that byte is not zero, the program subtracts 0x41 from it, and compares the result to 0x17. If it is above 0x17, we get the dreaded "Wrong!" message, and the function returns with 0. This basically means that valid bytecodes are ASCII characters in the range of "A" (0x41) through "X" (0x41 + 0x17). If the bytecode is valid, we arrive at the code piece that uses the jump table:

```
[0x00400a45]> VV @ fcn.00400a45 (nodes 7 edges 7 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400a74:
mov eax, eax
mov rax, qword [rax*8 + 0x400ec0] ; [0x400ec0:8]=0x400a80
jmp rax
```

The jump table's base is at 0x400ec0, so lets define that memory area as a series of qwords:

```
[0x00400a74]> s 0x00400ec0
[0x00400ec0]> Cd 8 @@= `?s $$ $$+8*0x17 8`
```

**r2 tip:** Except for the ?s, all parts of this command should be familiar now, but lets recap it! Cd defines a memory area as data, and 8 is the size of that memory area. @@ is an iterator that make the preceding command run for every element that @@ holds. In this example it holds a series generated using the ?s command. ?s simply generates a series from the current seek (\$\$) to current seek + 80x17 (\$\$+80x17) with a step of 8.

This is how the disassembly looks like after we add this metadata:

```
[0x00400ec0]> pd 0x18
; DATA XREF from 0x00400a76 (unk)
0x00400ec0 .qword 0x0000000000400a80
0x00400ec8 .qword 0x0000000000400c04
0x00400ed0 .qword 0x0000000000400b6d
0x00400ed8 .qword 0x0000000000400b17
0x00400ee0 .qword 0x0000000000400c04
0x00400ee8 .qword 0x0000000000400c04
0x00400ef0 .qword 0x0000000000400c04
0x00400ef8 .qword 0x0000000000400c04
0x00400f00 .qword 0x0000000000400aec
0x00400f08 .qword 0x0000000000400bc1
0x00400f10 .qword 0x0000000000400c04
0x00400f18 .qword 0x0000000000400c04
0x00400f20 .qword 0x0000000000400c04
0x00400f28 .qword 0x0000000000400c04
0x00400f30 .qword 0x0000000000400c04
0x00400f38 .qword 0x0000000000400b42
0x00400f40 .qword 0x0000000000400c04
0x00400f48 .qword 0x0000000000400be5
0x00400f50 .qword 0x0000000000400ab6
0x00400f58 .qword 0x0000000000400c04
0x00400f60 .qword 0x0000000000400c04
0x00400f68 .qword 0x0000000000400c04
0x00400f70 .qword 0x0000000000400c04
0x00400f78 .qword 0x0000000000400b99
```

As we can see, the address 0x400c04 is used a lot, and besides that there are 9 different addresses. Lets see that 0x400c04 first!

```
[0x00400ec0]> pd 4 @ 0x400c04
;-- not_instr:
0x00400c04 bf980e4000 mov edi, str.Wrong_ ; "Wrong!" @ 0x400e98
0x00400c09 e862faffff call sym.imp.puts
0x00400c0e b800000000 mov eax, 0
0x00400c13 eb4c jmp 0x400c61
[0x00400ec0]>
```

We get the message "Wrong!", and the function just returns 0. This means that those are not valid instructions (they are valid bytecode though, they can be e.g. parameters!) We should flag 0x400c04 accordingly:

```
[0x00400ec0]> f not_instr @ 0x00000000000400c04
```

As for the other offsets, they all seem to be doing something meaningful, so we can assume they belong to valid instructions. I'm going to flag them using the instructions' ASCII values:

```
[0x00400ec0]> f instr_A @ 0x00000000000400a80
[0x00400ec0]> f instr_C @ 0x00000000000400b6d
[0x00400ec0]> f instr_D @ 0x00000000000400b17
[0x00400ec0]> f instr_I @ 0x00000000000400aec
[0x00400ec0]> f instr_J @ 0x00000000000400bc1
[0x00400ec0]> f instr_P @ 0x00000000000400b42
[0x00400ec0]> f instr_R @ 0x00000000000400be5
[0x00400ec0]> f instr_S @ 0x00000000000400ab6
[0x00400ec0]> f instr_X @ 0x00000000000400b99
```

Ok, so these offsets were not on the graph, so it is time to define basic blocks for them!

**r2 tip:** You can define basic blocks using the *afb+* command. You have to supply what function the block belongs to, where does it start, and what is its size. If the block ends in a jump, you have to specify where does it jump too. If the jump is a conditional jump, the false branch's destination address should be specified too.

We can get the start and end addresses of these basic blocks from the full disasm of *vmloop*.

```
[0x00400ec0]> pdf @ fcn.vmloop
fcn.00400a45 542
    arg int arg_787492  @ rbp+0x602120
    var int local_0_1  @ rbp-0x1
    var qword memory  @ rbp-0x8
    var dword instr_ptr_step @ rbp-0xc
    var int bytecode   @ rbp-0x18
    ;-- fcn.vmloop:
    0x00400a45      55          push rbp
    0x00400a46      488e5       mov rbp, rsp
    0x00400a49      483ec20    sub rsp, 0x20
    0x00400a4d      4897de8    mov qword [rbp-bytecode], rdi
    0x00400a51      48c745f82021  mov qword [rbp-memory], sym.memory
    0x00400a59      e9ef01000  jmp 0x400c4d
    0x00400a5e      48804e8    mov rax, qword [rbp-bytecode]
    0x00400a62      0fb60      movzx eax, byte [rax]
    0x00400a65      0fbec0    movsx eax, al
    0x00400a68      83e81      sux eax, 0x41
    0x00400a6b      83f817    cmp eax, 0x17
    0x00400a6e      0f879001000  ja 0x400c04
    0x00400a74      89c0      mov eax, eax
    0x00400a76      488045c00e  mov rax, qword [rax*8 + 0x400ec0]
    0x00400a7e      ff00      jmp rax
    ;-- instr_A:
    0x00400a80      8b055162000  mov eax, dword [rip + 0x20165a]
    0x00400a86      83c001    add eax, 1
    0x00400a89      89055162000  mov dword [rip + 0x201651], eax
    0x00400a8f      488b4e8    mov rax, qword [rbp-bytecode]
    0x00400a93      488d5002    lea rdx, [rax + 2]
    0x00400a97      488b4e8    mov rax, qword [rbp-bytecode]
    0x00400a99      4883c001    add rax, 1
    0x00400a9f      4889d6      mov rsi, rdx
    0x00400aa2      4889c7      mov rdi, rax
    0x00400aa5      e863fdffff  call fcn.0040080d
    0x00400aaa      c745f403000  mov dword [rbp-instr_ptr_step], 3
    0x00400ab1      e95f01000  jmp 0x400c15
    ;-- instr_S:
    0x00400ab6      8b0520162000  mov eax, dword [rip + 0x201628]
    0x00400abc      83c001    add eax, 1
    0x00400abf      89051f162000  mov dword [rip + 0x20161f], eax
    0x00400ac5      48804e8    mov rax, qword [rbp-bytecode]
    0x00400ac9      488d5002    lea rdx, [rax + 2]
    0x00400acd      48804e8    mov rax, qword [rbp-bytecode]
    0x00400ad1      4883c001    add rax, 1
    0x00400ad5      4889d6      mov rsi, rdx
    0x00400ad8      4889c7      mov rdi, rax
    0x00400adb      e8b05fdffff  call fcn.0040080f
    0x00400ad9      c745f403000  mov dword [rbp-instr_ptr_step], 3
    0x00400ae7      e92501000  jmp 0x400c15
    ;-- instr_I:
    0x00400aec      8b05f6152000  mov eax, dword [rip + 0x2015f6]
    0x00400af2      83c001    add eax, 1
    0x00400af5      8905ed152000  mov dword [rip + 0x2015ed], eax
    0x00400afb      488b4e8    mov rax, qword [rbp-bytecode]
    0x00400aff      4883c001    add rax, 1
    0x00400b03      4889c7      mov rdi, rax
    0x00400b06      0e85feffff  call fcn.00400961
    0x00400b08      c745f402000  mov dword [rbp-instr_ptr_step], 2
    0x00400b12      e9f500000  jmp 0x400c15
    ;-- instr_D:
    0x00400b17      8b05cf152000  mov eax, dword [rip + 0x2015cf]
    0x00400b1d      83c001    add eax, 1
    0x00400b20      8905c6152000  mov dword [rip + 0x2015c6], eax
    0x00400b26      48804e8    mov rax, qword [rbp-bytecode]
    0x00400b2a      4883c001    add rax, 1
    0x00400b2e      4889c7      mov rdi, rax
    0x00400b31      e806feffff  call fcn.0040093c
    0x00400b35      c745f402000  mov dword [rbp-instr_ptr_step], 2
    0x00400b3d      e9d300000  jmp 0x400c15
    ;-- instr_P:
    0x00400b42      8b05a8152000  mov eax, dword [rip + 0x2015a8]
    0x00400b48      83c001    add eax, 1
    0x00400b4b      80059f152000  mov dword [rip + 0x20159f], eax
    0x00400b51      488b4e8    mov rax, qword [rbp-bytecode]
    0x00400b55      4883c001    add rax, 1
    0x00400b59      4889c7      mov rdi, rax
    0x00400b5c      e825feffff  call fcn.00400986
    0x00400b61      c745f402000  mov dword [rbp-instr_ptr_step], 2
    0x00400b66      e9a800000  jmp 0x400c15
    ;-- instr_C:
    0x00400b6d      8b0581152000  mov eax, dword [rip + 0x201581]
    0x00400b73      83c001    add eax, 1
    0x00400b76      890578152000  mov dword [rip + 0x201578], eax
    0x00400b7c      48804e8    mov rax, qword [rbp-bytecode]
    0x00400b80      4883c001    add rax, 1
    0x00400b84      0fb60      mov rsi, rax
    0x00400b87      0fbec0    mov rdi, rax
    0x00400b8a      890530152000  mov dword [rip + 0x201530], eax
    0x00400b90      c745f402000  mov dword [rbp-instr_ptr_step], 2
    0x00400b97      eb7c      jmp 0x400c15
    ;-- instr_X:
    0x00400b99      8b0559152000  mov eax, dword [rip + 0x201559]
    0x00400b9f      83c001    add eax, 1
    0x00400b92      890570152000  mov dword [rip + 0x201550], eax
    0x00400b98      488b4e8    mov rax, qword [rbp-bytecode]
    0x00400b9c      4883c001    add rax, 1
    0x00400b9b      4889c7      mov rdi, rax
    0x00400b93      e806feffff  call fcn.004009af
    0x00400b98      c745f402000  mov dword [rbp-instr_ptr_step], 2
    0x00400b9f      eb54      jmp 0x400c15
    ;-- instr_J:
    0x00400bc1      8b0535152000  mov eax, dword [rip + 0x201535]
    0x00400bc7      83c001    add eax, 1
    0x00400bc4      89052c152000  mov dword [rip + 0x20152c], eax
    0x00400bdd      48804e8    mov rax, qword [rbp-bytecode]
    0x00400bd4      4883c001    add rax, 1
    0x00400bd8      0fb60      mov rsi, rax
    0x00400bd1      4889c7      mov rdi, rax
    0x00400bd5      e8d8feffff  call fcn.004009b8
    0x00400be0      8945f4      mov dword [rbp-instr_ptr_step], eax
    0x00400be3      eb30      jmp 0x400c15
    ;-- instr_R:
    0x00400be5      8b0515152000  mov eax, dword [rip + 0x201515]
    0x00400beb      83c001    add eax, 1
    0x00400bec      8905c0152000  mov dword [rip + 0x20150c], eax
    0x00400bf4      48804e8    mov rax, qword [rbp-bytecode]
    0x00400bf3      4883c001    add rax, 1
    0x00400bf0      4889c7      mov rdi, rax
    0x00400bf9      0fbec0    mov rsi, rax
    0x00400b02      eb5d      jmp 0x400c61
    ;-- not_instr:
    0x00400b04      bf980e4000  mov edi, str.Wrong_
    0x00400b09      e802ffff    call sym.imp.puts
    0x00400b06      b800000000  mov eax, 0
    0x00400b13      eb4c      jmp 0x400c61
    0x00400b15      8b45f4      mov eax, dword [rbp-instr_ptr_step]
    0x00400b18      4898          cdqe
    0x00400b1a      480145e8    add qword [rbp-bytecode], rax
    0x00400b1c      4880b531420.  mov rax, qword [rip + 0x201463]
    0x00400b25      483d20216000  cmpl rax, sym.memory
    0x00400b2b      72f0      jb 0x400c3c
    0x00400b2d      4880b541420.  mov rax, qword [rip + 0x201454]
    0x00400b34      483d20236000  cmp rax, section_end.bss
    0x00400b3a      7211      jb 0x400c4d
    0x00400b3c      bf9f0e4000  mov edi, str.We_are_in_the_outer_space_
    0x00400b41      e820ffff    call sym.imp.puts
    0x00400b46      b800000000  mov eax, 0
    0x00400b4b      eb14      jmp 0x400c61
    0x00400b4d      48804e8    mov rax, qword [rbp-bytecode]
    0x00400b51      0fb60      movzx eax, byte [rax]
    0x00400b54      b800000000  test al, al
    0x00400b56      0fb502feffff  jne 0x400a5e
    0x00400b5c      b001000000  mov eax, 1
    0x00400b61      c9          leave
    0x00400b62      c3          ret
[0x00400ec0]>
```

As I've mentioned previously, the function itself is pretty short, and easy to read, especially with our annotations. But a promise is a promise, so here is how we can create the missing basic blocks for the instructions:


```
[0x00400ec0]> afb+ 0x00400a45 0x00400a80 0x00400ab6-0x00400a80 0x400c15  
[0x00400ec0]> afb+ 0x00400a45 0x00400ab6 0x00400aec-0x00400ab6 0x400c15  
[0x00400ec0]> afb+ 0x00400a45 0x00400aec 0x00400b17-0x00400aec 0x400c15  
[0x00400ec0]> afb+ 0x00400a45 0x00400b17 0x00400b42-0x00400b17 0x400c15  
[0x00400ec0]> afb+ 0x00400a45 0x00400b42 0x00400b6d-0x00400b42 0x400c15  
[0x00400ec0]> afb+ 0x00400a45 0x00400b6d 0x00400b99-0x00400b6d 0x400c15  
[0x00400ec0]> afb+ 0x00400a45 0x00400b99 0x00400bc1-0x00400b99 0x400c15  
[0x00400ec0]> afb+ 0x00400a45 0x00400bc1 0x00400be5-0x00400bc1 0x400c15  
[0x00400ec0]> afb+ 0x00400a45 0x00400be5 0x00400c04-0x00400be5 0x400c15
```

It is also apparent from the disassembly that besides the instructions there are three more basic blocks. Lets create them too!

```
[0x00400ec0]> afb+ 0x00400a45 0x00400c15 0x00400c2d-0x00400c15 0x400c3c 0x00400c2d  
[0x00400ec0]> afb+ 0x00400a45 0x00400c2d 0x00400c3c-0x00400c2d 0x400c4d 0x00400c3c  
[0x00400ec0]> afb+ 0x00400a45 0x00400c3c 0x00400c4d-0x00400c3c 0x400c61
```

Note that the basic blocks starting at 0x00400c15 and 0x00400c2d ending in a conditional jump, so we had to set the false branch's destination too!


And here is the graph in its full glory after a bit of manual restructuring:



I think it worth it, don't you? :) (Well, the restructuring did not really worth it, because it is apparently not stored when you save the project.)

**r2 tip:** You can move the selected node around in graph view using the HJKL keys. The ? documentation needs to be fixed on this part though: the move node (HJKL) and the move canvas (hjkl) keys are swapped there.

BTW, here is how IDA's graph of this same function looks like for comparison:



As we browse through the disassembly of the *instr\_LETTER* basic blocks, we should realize a few things. The first: all of the instructions starts with a sequence like these:

```
0x4000a80:
instr_A:
mov eax, dword [rip + 0x20165a] ; [0x6020e0:4]=0x646c6975 LEA sym.instr_dirty ; "uild-id" @ 0x6
add eax, 1
mov dword [rip + 0x201651], eax ; [0x6020e0:4]=0x646c6975 LEA sym.instr_dirty ; "uild-id" @ 0x6

0x400ab6:
instr_S:
mov eax, dword [rip + 0x201628] ; [0x6020e4:4]=0x64692d ; "-id" @ 0x6020e4
add eax, 1
mov dword [rip + 0x20161f], eax ; [0x6020e4:4]=0x64692d ; "-id" @ 0x6020e4
```

It became clear now that the 9 dwords at *sym.instr\_dirty* are not simply indicators that an instruction got executed, but they are used to count how many times an instruction got called. Also I should have realized earlier that *sym.good\_if\_le\_9* (0x6020f0) is part of this 9 dword array, but yeah, well, I didn't, I have to live with it... Anyways, what the condition "*sym.good\_if\_le\_9* have to be lesser or equal 9" really means is that *instr\_P* can not be executed more than 9 times:

```
0x400b42:
instr_P:
mov eax, dword [rip + 0x2015a8] ; [0x6020f0:4]=0x642e0068 LEA sym.good_if_le_9 ; "h" @ 0x6020f0
add eax, 1
mov dword [rip + 0x20159f], eax ; [0x6020f0:4]=0x642e0068 LEA sym.good_if_le_9 ; "h" @ 0x6020f0
```

Another similarity of the instructions is that 7 of them calls a function with either one or two parameters, where the parameters are the next, or the next two bytecodes. One parameter example:

```
0x400aec:
instr_I:
mov eax, dword [rip + 0x2015f6] ; [0x6020e8:4]=0x756e672e ; ".gnu.hash" @ 0x6020e8
add eax, 1
mov dword [rip + 0x2015ed], eax ; [0x6020e8:4]=0x756e672e ; ".gnu.hash" @ 0x6020e8
mov rax, qword [rbp-bytecode]
add rax, 1
mov rdi, rax
call fcn.00400961 ;[i]
mov dword [rbp-instr_ptr_step], 2
jmp 0x400c15 ;[d]
```

And a two parameters example:

```
0x400a80:
instr_A:
mov eax, dword [rip + 0x20165a] ; [0x6020e0:4]=0x646c6975 LEA sym.instr_dirty ; "uild-id" @ 0x6
add eax, 1
mov dword [rip + 0x201651], eax ; [0x6020e0:4]=0x646c6975 LEA sym.instr_dirty ; "uild-id" @ 0x6
mov rax, qword [rbp-bytecode]
lea rdx, [rax + 2] ; 0x2
mov rax, qword [rbp-bytecode]
add rax, 1
mov rsi, rdx
mov rdi, rax
call fcn.0040080d ;[c]
mov dword [rbp-instr_ptr_step], 3
jmp 0x400c15 ;[d]
```

We should also realize that these blocks put the number of bytes they eat up of the bytecode (1 byte instruction + 1 or 2 bytes arguments = 2 or 3) into a local variable at 0xc. r2 did not recognize this local var, so lets do it manually!

```
:> afv 0xc instr_ptr_step dword
```

If we look at *instr\_J* we can see that this is an exception to the above rule, since it puts the return value of the called function into *instr\_ptr\_step* instead of a constant 2 or 3:

```
0x400bc1:
instr_J:
mov eax, dword [rip + 0x201535] ; [0x6020fc:4]=0x74736e79 ; "ynstr" @ 0x6020fc
add eax, 1
mov dword [rip + 0x20152c], eax ; [0x6020fc:4]=0x74736e79 ; "ynstr" @ 0x6020fc
mov rax, qword [rbp-bytecode]
add rax, 1
mov rdi, rax
call fcn.004009b8 ;[m]
mov dword [rbp-instr_ptr_step], eax
jmp 0x400c15 ;[d]
```

And speaking of exceptions, here are the two instructions that do not call functions:

```
0x400be5:
instr_R:
mov eax, dword [rip + 0x201515] ; [0x602100:4]=0x672e0072 ; "r" 0x00602100 ; "r" @ 0x602100
add eax, 1
mov dword [rip + 0x20150c], eax ; [0x602100:4]=0x672e0072 ; "r" 0x00602100 ; "r" @ 0x602100
mov rax, qword [rbp-bytecode]
add rax, 1
movzx eax, byte [rax]
movsx eax, al
jmp 0x400c61 ;[f]
```

This one simply puts the next bytecode (the first the argument) into eax, and jumps to the end of *vmloop*. So this is the VM's *ret* instruction, and we know that *vmloop* has to return "", so "R\*" should be the last two bytes of our bytecode.

The next one that does not call a function:

```
0x400b6d:
instr_C:
mov eax, dword [rip + 0x201581] ; [0x6020f4:4]=0x79736e79 ; "ynsym" @ 0x6020f4
add eax, 1
mov dword [rip + 0x201578], eax ; [0x6020f4:4]=0x79736e79 ; "ynsym" @ 0x6020f4
mov rax, qword [rbp-bytecode]
add rax, 1
movzx eax, byte [rax]
movsx eax, al
mov dword [rip + 0x201530], eax ; [0x6020c0:4]=0x65746e69 LEA sym.written_by_instr_C ; "interp"
mov dword [rbp-instr_ptr_step], 2
jmp 0x400c15 ;[d]
```

This is a one argument instruction, and it puts its argument to 0x6020c0. Flag that address!

```
:> f sym.written_by_instr_C 4 @ 0x6020c0
```

Oh, and by the way, I do have a hunch that *instr\_C* also had a function call in the original code, but it got inlined by the compiler. Anyways, so far we have these two instructions:

- *instr\_R(a1)*: returns with *a1*
- *instr\_C(a1)*: writes *a1* to *sym.written\_by\_instr\_C*

And we also know that these accept one argument,

- *instr\_I*
- *instr\_D*
- *instr\_P*
- *instr\_X*
- *instr\_J*

and these accept two:

- *instr\_A*
- *instr\_S*

What remains is the reversing of the seven functions that are called by the instructions, and finally the construction of a valid bytecode that gives us the flag.

## instr\_A

The function this instruction calls is at offset 0x40080d, so lets seek there!

```
[offset]> 0x40080d
```

**r2 tip:** In visual mode you can just hit \ when the current line is a jump or a call, and r2 will seek to the destination address.

If we seek to that address from the graph mode, we are presented with a message that says "Not in a function. Type 'df' to define it here. This is because the function is called from a basic block r2 did not recognize, so r2 could not find the function either. Lets obey, and type `df!` A function is indeed created, but we want some meaningful name for it. So press `dr` while still in visual mode, and name this function `instr_A`!

```
[0x0040080d]> VV @ fcn.0040080d (nodes 9 edges 13 zoom 100%) BB mouse:canvas-y movements-speed:5
0x40080d:
(fcn) fcn.0040080d 146
; var int local_0      @ rbp-0x0
; var int local_0_1    @ rbp-0x1
; var int local_1      @ rbp-0x8
; var int local_2      @ rbp-0x10
; CALL XREF from 0x0040097f (fcn.0040080d)  [_0820_]
fcn.instr_A:
push rbp
mov rbp, rsp
mov qword [rbp-local_1], rdi
mov qword [rbp-local_2], rsi
cmp qword [rbp-local_1], 0
je 0x40089d ;[a]

[_0820_]
  f t
  |
  +--> [_0827_]
    f t
    |
    +--> [_0852_]
      t f
      |
      +--> [_087a_]
        f t
        |
        +--> [_0885_]
          v
          |
          +--> [_085d_]
            v
            |
            +--> [_0832_]
              v
              |
              +--> [_089d_]
                v
                |
                +--> <@000000>
                  f t
                  |
                  +--> '_'
                  |
                  +--> '_'
                  |
                  +--> '_'
```

**r2 tip:** You should realize that these commands are all part of the same menu system in visual mode I was talking about when we first used `Cd` to declare `sym.memory` as data.

Ok, now we have our shiny new `fcn.instr_A`, lets reverse it! We can see from the shape of the minimap that probably there is some kind cascading if-then-elif, or a switch-case statement involved in this function. This is one of the reasons the minimap is so useful: you can recognize some patterns at a glance, which can help you in your analysis (remember the easily recognizable for loop from a few paragraphs before?) So, the minimap is cool and useful, but I've just realized that I did not yet show you the full graph mode, so I'm going to do this using full graph. The first basic blocks:

```
[0x0040080d]> VV @ fcn.0040080d (nodes 9 edges 13 zoom 100%) BB mouse:canvas-y movements-speed:5

[0x40080d]
(fcn) fcn.0040080d 146
; var int local_0      @ rbp-0x0
; var int local_0_1    @ rbp-0x1
; var int local_1      @ rbp-0x8
; var int local_2      @ rbp-0x10
; CALL XREF from 0x0040097f (fcn.0040080d)
fcn.instr_A:
push rbp
mov rbp, rsp
mov qword [rbp-local_1], rdi
mov qword [rbp-local_2], rsi
cmp qword [rbp-local_1], 0
je 0x40089d ;[a]

          f t
          :
          :
0x400820
| cmp qword [rbp-local_2], 0
| je 0x40089d ;[a]
          f t
          :



```

The two function arguments (*rdi* and *rsi*) are stored in local variables, and the first is compared to 0. If it is, the function returns (you can see it on the minimap), otherwise the same check is executed on the second argument. The function returns from here too, if the argument is zero. Although this function is really tiny, I am going to stick with my methodology, and rename the local vars:

```
:> afvn local_1 arg1
:> afvn local_2 arg2
```

And we have arrived to the predicted switch-case statement, and we can see that *arg1*'s value is checked against "M", "P", and "C".

```
[0x0040080d]> VV @ fcn.0040080d (nodes 9 edges 13 zoom 100%) BB mouse:canvas-y movements-speed:
=====
| 0x400827
| mov rax, qword [rbp-arg1]
| movzx eax, byte [rax]
| cmp al, 0x4d ; 'M'
| jne 0x400852 ;[b]
=====
t f
|
=====
| 0x400852
| mov rax, qword [rbp-arg1]
| movzx eax, byte [rax]
| cmp al, 0x50 ; 'P'
| jne 0x40087a ;[c]
=====
t f
|
=====
| 0x40087a
| mov rax, qword [rbp-arg1]
| movzx eax, byte [rax]
| cmp al, 0x43 ; 'C'
| jne 0x40089d ;[a]
=====
f t
|
=====
```

This is the "M" branch:

```
[0x400832]
mov rax, qword [rip + 0x20184f] ; [0x602088:8]=0x602120 sym.memory ; " !`" @ 0x602088
mov rdx, qword [rip + 0x201848] ; [0x602088:8]=0x602120 sym.memory ; " !`" @ 0x602088
movzx edx, byte [rdx]
mov ecx, edx
mov rdx, qword [rbp-arg2]
movzx edx, byte [rdx]
add edx, ecx
mov byte [rax], dl
jmp 0x40089d ;[a]
=====
v
```

It basically loads an address from offset 0x602088 and adds *arg2* to the byte at that address. As r2 kindly shows us in a comment, 0x602088 initially holds the address of *sym.memory*, the area where we have to construct the "Such VM! MuCH reV3rse!" string. It is safe to assume that somehow we will be able to modify the value stored at 0x602088, so this "M" branch will be able to modify bytes other than the first. Based on this assumption, I'll flag 0x602088 as *sym.current\_memory\_ptr*.

```
:> f sym.current_memory_ptr 8 @ 0x602088
```

Moving on to the "P" branch:

```
[0x40085d]
mov rdx, qword [rip + 0x201824] ; [0x602088:8]=0x602120 sym.memory LEA sym.current_memory
mov rax, qword [rbp-arg2]
movzx eax, byte [rax]
movzx eax, al
add rax, rdx
mov qword [rip + 0x201810], rax ; [0x602088:8]=0x602120 sym.memory LEA sym.current_memory
jmp 0x40089d ;[a]
```

Yes, this is the piece of code that allows us to modify *sym.current\_memory\_ptr*: it adds *arg2* to it.

Finally, the "C" branch:

```
[0x400885]
mov rax, qword [rbp-arg2]
movzx eax, byte [rax]
movzx edx, al
mov eax, dword [rip + 0x20182b] ; [0x6020c0:4]=0x65746e69 LEA sym.written_by_instr_C ; "i"
add eax, edx
mov dword [rip + 0x201823], eax ; [0x6020c0:4]=0x65746e69 LEA sym.written_by_instr_C ; "i"
```

Well, it turned out that *instr\_C* is not the only instruction that modifies *sym.written\_by\_instr\_C*: this piece of code adds *arg2* to it.

And that was *instr\_A*, lets summarize it! Depending on the first argument, this instruction does the following:

- *arg1 == "M"*: adds *arg2* to the byte at *sym.current\_memory\_ptr*.
- *arg1 == "P"*: steps *sym.current\_memory\_ptr* by *arg2* bytes.
- *arg1 == "C"*: adds *arg2* to the value at *sym.written\_by\_instr\_C*.


## **instr\_S**

This function is not recognized either, so we have to manually define it like we did with *instr\_A*. After we do, and take a look at the minimap, scroll through the basic blocks, it is pretty obvious that these two functions are very-very similar. We can use *radiff2* to see the difference.


**r2 tip:** *radiff2* is used to compare binary files. There's a few options we can control the type of binary diffing the tool does, and to what kind of output format we want. One of the cool features is that it can generate [DarumGrim](#)-style bindiff graphs using the *-g* option.

Since now we want to diff two functions from the same binary, we specify the offsets with `-g`, and use `reverse4` for both binaries. Also, we create the graphs for comparing `instr_A` to `instr_S` and for comparing `instr_S` to `instr_A`.

```
[0x00 ~]$ radiff2 -g 0x40080d,0x40089f reverse4 reverse4 | xdot -
```



```
[0x00 ~]$ radiff2 -g 0x40089f,0x40080d reverse4 reverse4 | xdot -
```



A sad truth reveals itself after a quick glance at these graphs: `radiff2` is a liar! In theory, grey boxes should be identical, yellow ones should differ only at some offsets, and red ones should differ seriously. Well this is obviously not the case here - e.g. the larger grey boxes are clearly not identical. This is something I'm definitely going to take a deeper look at after I've finished this writeup.

Anyways, after we get over the shock of being lied to, we can easily recognize that `instr_S` is basically a reverse-`instr_A`: where the latter does addition, the former does subtraction. To summarize this:

- `arg1 == "M"`: subtracts `arg2` from the byte at `sym.current_memory_ptr`.
- `arg1 == "P"`: steps `sym.current_memory_ptr` backwards by `arg2` bytes.
- `arg1 == "C"`: subtracts `arg2` from the value at `sym.written_by_instr_C`.

## instr\_I

```
[0x00400961]> VV @ fcn.00400961 (nodes 1 edges 0 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400961:
(fcn) fcn.00400961 37
; var int local_0_1      @ rbp-0x1
; var int local_3      @ rbp-0x18
; CALL XREF from 0x004009b1 (fcn.00400961)
fcn.instr_I:
push rbp
mov rbp, rsp
sub rsp, 0x18
<@#####>
mov qword [rbp-local_3], rdi
mov byte [rbp-local_0_1], 1
lea rdx, [rbp-local_0_1]
mov rax, qword [rbp-local_3]
mov rsi, rdx
mov rdi, rax
call fcn.0040080d ;[a]
leave
ret
```

This one is simple, it just calls `instr_A(arg1, 1)`. As you may have noticed the function call looks like `call fcn.0040080d` instead of `call fcn.instr_A`. This is because when you save and open a project, function names get lost - another thing to examine and patch in r2!

## instr\_D

```
[0x0040093c]> VV @ fcn.0040093c (nodes 1 edges 0 zoom 100%) BB mouse:canvas-y movements-speed:5
0x40093c:
(fcn) fcn.0040093c 37
; var int local_0_1      @ rbp-0x1
; var int local_3      @ rbp-0x18
fcn.instr_D:
push rbp
mov rbp, rsp
sub rsp, 0x18
<@#####>
mov qword [rbp-local_3], rdi
mov byte [rbp-local_0_1], 1
lea rdx, [rbp-local_0_1]
mov rax, qword [rbp-local_3]
mov rsi, rdx
mov rdi, rax
call fcn.0040089f ;[a]
leave
ret
```

Again, simple: it calls `instr_S(arg1, 1)`.

## instr\_P

It's local var rename time again!

```
:> afvn local_0_1 const_M
:> afvn local_0_2 const_P
:> afvn local_3 arg1
```

```
[0x00400986]> VV @ fcn.00400986 (nodes 1 edges 0 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400986:
(fcn) fcn.00400986 50
; arg int arg_9_5      @ rbp+0x4d
; arg int arg_10     @ rbp+0x50
; var int const_M     @ rbp-0x1
; var int const_P     @ rbp-0x2
; var int arg1        @ rbp-0x18          <@@@@@@>
fcn.instr_P:
push rbp
mov rbp, rsp
sub rsp, 0x18
mov qword [rbp-arg1], rdi
mov byte [rbp-const_M], 0x4d ; [0x4d:1]=0 ; 'M'
mov byte [rbp-const_P], 0x50 ; [0x50:1]=64 ; 'P'
mov rax, qword [rip + 0x2016e7] ; [0x602088:8]=0x602120 sym.memory LEA sym.current_memory_ptr ;
mov rdx, qword [rbp-arg1]
movzx edx, byte [rdx]
mov byte [rax], dl
lea rax, [rbp-const_P]
mov rdi, rax
call fcn.00400961 ;[a]
leave
ret
```

This function is pretty straightforward also, but there is one oddity: `const_M` is never used. I don't know why it is there - maybe it is supposed to be some kind of distraction? Anyways, this function simply writes `arg1` to `sym.current_memory_ptr`, and than calls `instr_I("P")`. This basically means that `instr_P` is used to write one byte, and put the pointer to the next byte. So far this would seem the ideal instruction to construct most of the "Such VM! MuCH reV3rse!" string, but remember, this is also the one that can be used only 9 times!

## instr\_X

Another simple one, rename local vars anyways!

```
:> afvn local_1 arg1
```


```
[0x00400a1f]> VV @ fcn.00400a1f (nodes 1 edges 0 zoom 100%) BB mouse:canvas-y movements-speed:5
0x400a1f:
(fcn) fcn.00400a1f 38
; var int local_0_1    @ rbp-0x1
; var int arg1        @ rbp-0x8
fcn.instr_X:
push rbp
mov rbp, rsp          <@@@@@@>
mov qword [rbp-arg1], rdi
mov rax, qword [rip + 0x20165a] ; [0x602088:8]=0x602120 sym.memory LEA sym.current_memory_ptr ;
mov rdx, qword [rip + 0x201653] ; [0x602088:8]=0x602120 sym.memory LEA sym.current_memory_ptr ;
movzx ecx, byte [rdx]
mov rdx, qword [rbp-arg1]
movzx edx, byte [rdx]
xor edx, ecx
mov byte [rax], dl
pop rbp
ret
```

This function XORs the value at `sym.current_memory_ptr` with `arg1`.


## instr\_J

This one is not as simple as the previous ones, but it's not that complicated either. Since I'm obviously obsessed with variable renaming:

```
:> afvn local_3 arg1
:> afvn local_0_4 arg1_and_0x3f
```



After the result of `arg1 & 0x3f` is put into a local variable, `arg1 & 0x40` is checked against 0. If it isn't zero, `arg1_and_0x3f` is negated:



The next branching: if `arg1 >= 0`, then the function returns `arg1_and_0x3f`,

```
[0x004009b8]> VV @ fcn.004009b8 (nodes 10 edges 13 zoom 100%) BB mouse:canvas-y movements-speed
0x4009e4:
mov rax, qword [rbp-arg1]
movzx eax, byte [rax]
test al, al
jns 0x400a1a ;[b]
```

```
[0x004009b8]> VV @ fcn.004009b8 (nodes 10 edges 13 zoom 100%) BB mouse:canvas-y movements-speed
0x400a1a:
mov eax, dword [rbp-arg1_and_0x3f]    <@000000>
                                         v
                                         |<@000000>| [_09ef_]
                                         t f
```

else the function branches again, based on the value of *sym.written\_by\_instr\_C*:

```
[0x004009b8]> VV @ fcn.004009b8 (nodes 10 edges 13 zoom 100%) BB mouse:canvas-y movements-speed
0x4009ef:
mov eax, dword [rip + 0x2016cb] ; [0x6020c0:4]=0x65746e69 LEA sym.written_by_instr_C ; "interp
test eax, eax
je 0x400a13 ;[c]
```

If it is zero, the function returns 2,

```
[0x004009b8]> VV @ fcn.004009b8 (nodes 10 edges 13 zoom 100%) BB mouse:canvas-y movements-speed
0x400a13:
mov eax, 2
jmp 0x400a1d ;[d]
```


else it is checked if *arg1\_and\_0x3f* is a negative number,

```
[0x004009b8]> VV @ fcn.004009b8 (nodes 10 edges 13 zoom 100%) BB mouse:canvas-y movements-speed
0x4009f9:
cmp dword [rbp-arg1_and_0x3f], 0
jns 0x400a0e ;[e]
```

and if it is, *sym.good\_if\_ne\_zero* is incremented by 1:

```
[0x004009b8]> VV @ fcn.004009b8 (nodes 10 edges 13 zoom 100%) BB mouse:canvas-y movements-speed
0x4009ff:
mov eax, dword [rip + 0x2016ff] ; [0x602104:4]=0x762e756e LEA sym.good_if_ne_zero ; "nu.versio
add eax, 1
mov dword [rip + 0x2016f6], eax ; [0x602104:4]=0x762e756e LEA sym.good_if_ne_zero ; "nu.versio
```

After all this, the function returns with *arg1\_and\_0x3f*:

```
[0x004009b8]> VV @ fcn.004009b8 (nodes 10 edges 13 zoom 100%) BB mouse:canvas-y movements-speed  
0x400a0e:  
mov eax, dword [rbp-arg1_and_0x3f]  
jmp 0x400a1d ;[d]  

```

## .instructionset

We've now reversed all the VM instructions, and have a full understanding about how it works. Here is the VM's instruction set:

Instruction	1st arg	2nd arg	What does it do?
"A"	"M"	arg2	<code>*sym.current_memory_ptr += arg2</code>
	"P"	arg2	<code>sym.current_memory_ptr += arg2</code>
	"C"	arg2	<code>sym.written_by_instr_C += arg2</code>
"S"	"M"	arg2	<code>*sym.current_memory_ptr -= arg2</code>
	"P"	arg2	<code>sym.current_memory_ptr -= arg2</code>
	"C"	arg2	<code>sym.written_by_instr_C -= arg2</code>
"I"	arg1	n/a	<code>instr_A(arg1, 1)</code>
"D"	arg1	n/a	<code>instr_S(arg1, 1)</code>
"P"	arg1	n/a	<code>*sym.current_memory_ptr = arg1; instr_I("P")</code>
"X"	arg1	n/a	<code>*sym.current_memory_ptr ^= arg1</code>
"J"	arg1	n/a	<code>arg1_and_0x3f = arg1 &amp; 0x3f;</code> <code>if (arg1 &amp; 0x40 != 0)</code> <code>    arg1_and_0x3f *= -1</code> <code>if (arg1 &gt;= 0) return arg1_and_0x3f;</code> <code>else if (*sym.written_by_instr_C != 0) {</code> <code>    if (arg1_and_0x3f &lt; 0)</code> <code>        ++*sym.good_if_ne_zero;</code> <code>    return arg1_and_0x3f;</code> <code>} else return 2;</code>
"C"	arg1	n/a	<code>*sym.written_by_instr_C = arg1</code>
"R"	arg1	n/a	<code>return(arg1)</code>

## .bytecode

Well, we did the reverse engineering part, now we have to write a program for the VM with the instruction set described in the previous paragraph. Here is the program's functional specification:

- the program must return ""
- *sym.memory* has to contain the string "Such VM! MuCH reV3rse!" after execution
- all 9 instructions have to be used at least once
- *sym.good\_if\_ne\_zero* should not be zero
- *instr\_P* is not allowed to be used more than 9 times

Since this document is about reversing, I'll leave the programming part to the fellow reader :) But I'm not going to leave you empty-handed, I'll give you one advice: Except for "J", all of the instructions are simple, easy to use, and it should not be a problem to construct the "Such VM! MuCH reV3rse!" using them. "J" however is a bit complicated compared to the others. One should realize that its sole purpose is to make *sym.good\_if\_ne\_zero* bigger than zero, which is a requirement to access the flag. In order to increment *sym.good\_if\_ne\_zero*, three conditions should be met:

- *arg1* should be a negative number, otherwise we would return early
- *sym.written\_by\_instr\_C* should not be 0 when "J" is called. This means that "C", "AC", or "SC" instructions should be used before calling "J".
- *arg1\_and\_0x3f* should be negative when checked. Since 0x3f's sign bit is zero, no matter what *arg1* is, the result of *arg1* & 0x3f will always be non-negative. But remember that "J" negates *arg1\_and\_0x3f* if *arg1* & 0x40 is not zero. This basically means that *arg1*'s 6th bit should be 1 ( $0x40 = 01000000_b$ ). Also, because *arg1\_and\_0x3f* can't be 0 either, at least one of *arg1*'s 0th, 1st, 2nd, 3rd, 4th or 5th bits should be 1 ( $0x3f = 00111111_b$ ).

I think this is enough information, you can go now and write that program. Or, you could just reverse engineer the quick'n'dirty one I've used during the CTF:

```
\x90\x00PSAMuAP\x01AMcAP\x01AMhAP\x01AM AP\x01AMVAP\x01AMMAP\x01AM!AP\x01AM AP\x01AMMA
P\x01AMuAP\x01AMCAP\x01AMHAP\x01AM AP\x01AMrAP\x01AMeAP\x01AMVAP\x01AM3AP\x01AMrAP\x01
AMsAP\x01AMeIPAM!X\x00CAJ\xc1SC\x00DCR*
```

Keep in mind though, that it was written on-the-fly, parallel to the reversing phase - for example there are parts that was written without the knowledge of all possible instructions. This means that the code is ugly and inefficient.



## .outro

Well, what can I say? Such VM, much reverse! :)

What started out as a simple writeup for a simple crackme, became a rather lengthy writeup/r2 tutorial, so kudos if you've read through it. I hope you enjoyed it (I know I did), and maybe even learnt something from it. I've surely learnt a lot about r2 during the process, and I've even contributed some small patches, and got a few ideas of more possible improvements.

# Radare2 Reference Card

## Survival Guide

Command	Description
aa	Auto analyze
Content Cell	Content Cell
pdf@fcn(Tab)	Disassemble function
f fcn(Tab)	List functions
f str(Tab)	List strings
fr [flagname] [newname]	Rename flag
psz [offset]	Print string
arf [flag]	Find cross reference for a flag

## Flagspaces

Command	Description
fs	Display flagspaces
fs *	Select all flagspaces
fs [sections]	Select one flagspace

## Flags

Command	Description
f	List flags
fs *	Select all flagspaces
fs [sections]	Select one flagspace
fj	Display flags in JSON
fl	Show flag length
fx	Show hexdump of flag
fC [name] [comment]	Set flag comment

## Information

Command	Description
ii	Information on imports
il	Info on binary
ie	Display entrypoint
iS	Display sections
ir	Display relocations

## Print string

Command	Description
psz [offset]	Print zero terminated string
psb [offset]	Print strings in current block
psx [offset]	Show string with scaped chars
psp [offset]	Print pascal string
psw [offset]	Print wide string

## Visual mode

Command	Description
V	Enter visual mode
p/P	Rotate modes (hex, disasm, debug, words, buf)

c	Toggle (c)ursor
q	Back to Radare shell
hjkl	Move around (or HJKL) (left-down-up-right)
Enter	Follow address of jump/call
sS	Step/step over
o	Go/seek to given offset
.	Seek to program counter
/	In cursor mode, search in current block
:cmd	Run radare command
;[-]cmt	Add/remove comment
/*+[-]】	Change block size, 【 = resize hex.cols
>  <	Seek aligned to block size
i/a/A	(i)nsert hex, (a)ssemble code, visual (A)ssembler
b/B	Toggle breakpoint / automatic block size
d[f?]	Define function, data, code, ..
D	Enter visual diff mode (set diff.from/to)
e	Edit eval configuration variables
f/F	Set/unset flag
gG	Go seek to begin and end of file (0-\$s)
mK/K	Mark/go to Key (any key)
M	Walk the mounted filesystems
n/N	Seek next/prev function/flag/hit (scr.nkey)
o	Go/seek to given offset
C	Toggle (C)olors
R	Randomize color palette (ecr)
t	Track flags (browse symbols, functions..)
T	Browse anal info and comments
v	Visual code analysis menu
V/W	(V)iew graph (agv?), open (W)ebUI
uU	Undo/redo seek
x	Show xrefs to seek between them

yY	Copy and paste selection
z	Toggle zoom mode

## Searching

Command	Description
/ foo\00	Search for string 'foo\0'
/b	Search backwards
//	Repeat last search
/w foo	Search for wide string 'f\0o\0o\0'
/wi foo	Search for wide string ignoring case
!/ ff	Search for first occurrence not matching
/i foo	Search for string 'foo' ignoring case
/e /E.F/i	Match regular expression
/x ff0.23	Search for hex string
/x ff..33	Search for hex string ignoring some nibbles
/x ff43 ffd0	Search for hexpair with mask
/d 101112	Search for a deltified sequence of bytes
!x 00	Inverse hexa search (find first byte != 0x00)
/c jmp [esp]	Search for asm code (see search.asmstr)
/a jmp eax	Assemble opcode and search its bytes
/A	Search for AES expanded keys
/r sym.printf	Analyze opcode reference an offset
/R	Search for ROP gadgets
/P	Show offset of previous instruction
/m magicfile	Search for matching magic file
/p patternsize	Search for pattern of given size
/z min max	Search for strings of given size
/v[?248] num	Look for a asm.bigendian 32bit value

## Saving

Command	Description
Po [file]	Open project
Ps [file]	Save project
Pi [file]	Show project information

## Usable variables in expression

Command	Description
\$\$	Here (current virtual seek)
\$o	Here (current disk io offset)
\$s	File size
\$b	Block size
\$w	Get word size, 4 if asm.bits=32, 8 if 64
\$c,\$r	Get width and height of terminal
\$S	Section offset
\$SS	Section size
\$j	Jump address (jmp 0x10, jz 0x10 => 0x10)
\$f	Jump fail address (jz 0x10 => next instruction)
\$I	Number of instructions of current function
\$F	Current function size
\$Jn	Get nth jump of function
\$Cn	Get nth call of function
\$Dn	Get nth data reference in function
\$Xn	Get nth xref of function
\$m	Opcode memory reference (mov eax,[0x10] => 0x10)
\$l	Opcode length
\$e	1 if end of block, else 0
\$ev	Get value of eval config variable
\$?	Last comparison value

## License

This chapter is based on the Radare 2 reference card by Thanat0s, which is under the GNU GPL. Original license is as follows:

This card may be freely distributed under the terms of the GNU general public licence – Copyright c ぼべほま by Thanat0s - v0.1 -