Assembly Language Programming Lecture Notes

Volume 1 – Basic Concepts

Preface

Assembly language programming develops a very basic and low level understanding of the computer. In higher level languages there is a distance between the computer and the programmer. This is because higher level languages are designed to be closer and friendlier to the programmer, thereby creating distance with the machine. This distance is covered by translators called compilers and interpreters. The aim of programming in assembly language is to bypass these intermediates and talk directly with the computer.

There is a general impression that assembly language programming is a difficult chore and not everyone is capable enough to understand it. The reality is in contrast, as assembly language is a very simple subject. The wrong impression is created because it is very difficult to realize that the real computer can be so simple. Assembly language programming gives a freehand exposure to the computer and lets the programmer talk with it in its language. The only translator that remains between the programmer and the computer is there to symbolize the computer's numeric world for the ease of remembering.

To cover the practical aspects of assembly language programming, IBM PC based on Intel architecture will be used as an example. However this course will not be tied to a particular architecture as it is often done. In our view such an approach does not create versatile assembly language programmers. The concepts of assembly language that are common across all platforms will be developed in such a manner as to emphasize the basic low level understanding of the computer instead of the peculiarities of one particular architecture. Emphasis will be more on assembly language and less on the IBM PC.

Before attempting this course you should know basic digital logic operations of AND, OR, NOT etc. You should know binary numbers and their arithmetic. Apart from these basic concepts there is nothing much you need to know before this course. In fact if you are not an expert, you will learn assembly language quickly, as non-experts see things with simplicity and the basic beauty of assembly language is that it is exceptionally simple. Do not ever try to find a complication, as one will not be there. In assembly language what is written in the program is all that is there, no less and no more.

After successful completion of this course, you will be able to explain all the basic operations of the computer and in essence understand the psychology of the computer. Having seen the computer from so close, you will understand its limitations and its capabilities. Your logic will become fine grained and this is one of the basic objectives of teaching assembly language programming.

Then there is the question that why should we learn assembly language when there are higher level languages one better than the other; C, C++, Java, to name just a few, with a neat programming environment and a simple way to write programs. Then why do we need such a freehand with the computer that may be dangerous at times? The answer to this lies in a very simple example. Consider a translator translating from English to Japanese. The problem faced by the translator is that every language has its own vocabulary and grammer. He may need to translate a word into a sentence and destroy the beauty of the topic. And given that we do not know

PREFACE ii

Japanese, so we cannot verify that our intent was correctly conveyed or not. Compiler is such a translator, just a lot dumber, and having a scarce number of words in its target language, it is bound to produce a lot of garbage and unnecessary stuff as a result of its ignorance of our program logic. In normal programs such garbage is acceptable and the ease of programming overrides the loss in efficiency but there are a few situations where this loss is unbearable.

Think about a four color picture scanned at 300 dots per inch making 90000 pixels per square inch. Now a processing on this picture requires 360000 operations per square inch, one operation for each color of each pixel. A few extra instructions placed by the translator can cost hours of extra time. The only way to optimize this is to do it directly in assembly language. But this doesn't mean that the whole application has to be written in assembly language, which is almost never the case. It's only the performance critical part that is coded in assembly language to gain the few extra cycles that matter at that point.

Consider an arch just like the ones in mosques. It cannot be made of big stones alone as that would make the arch wildly jagged, not like the fine arch we are used to see. The fine grains of cement are used to smooth it to the desired level of perfection. This operation of smoothing is optimization. The core structure is built in a higher level language with the big blocks it provides and the corners that need optimization are smoothed with the fine grain of assembly language which allows extreme control.

Another use of assembly language is in a class of time critical systems called real time systems. Real time systems have time bound responses, with an upper limit of time on certain operations. For such precise timing requirement, we must keep the instructions in our total control. In higher level languages we cannot even tell how many computer instructions were actually used, but in assembly language we can have precise control over them. Any reasonable sized application or a serious development effort has nooks and corners where assembly language is needed. And at these corners if there is no assembly language, there can be no optimization and when there is no optimization, there is no beauty. Sometimes a useful application becomes useless just because of the carelessness of not working on these jagged corners.

The third major reason for learning assembly language and a major objective for teaching it is to produce fine grained logic in programmers. Just like big blocks cannot produce an arch, the big thick grained logic learnt in a higher level language cannot produce the beauty and fineness assembly language can deliver. Each and every grain of assembly language has a meaning, nothing is presumed. You have to put together these grains, the minimum number of them to produce the desired outcome. Just like a "for" loop in a higher level language is a block construct and has a hundred things hidden in it, but using the grains of assembly language we do a similar operation with a number of grains but in the process understand the minute logic hidden beside that simple "for" construct.

Assembly language cannot be learnt by reading a book or by attending a course. It is a language that must be tasted and enjoyed. There is no other way to learn it. You will need to try every example, observe and verify the things you are told about it, and experiment a lot with the computer. Only then you will know and become able to appreciate how powerful, versatile, and simple this language is; the three properties that are hardly ever present together.

Whether you program in C/C++ or Java, or in any programming paradigm be it object oriented or declarative, everything has to boil down to the bits and bytes of assembly language before the computer can even understand it.

Table of Contents

Preface	i
Table of Contents	iii
1 Introduction to Assembly Language	1
 1.1. Basic Computer Architecture 1.2. Registers 1.3. Instruction Groups 1.4. Intel iapx88 Architecture 1.5. History 1.6. Register Architecture 1.7. Our First Program 1.8. Segmented Memory Model 	1 3 5 6 6 7 9
2 Addressing Modes	17
 2.1. Data Declaration 2.2. Direct Addressing 2.3. Size Mismatch Errors 2.4. Register Indirect Addressing 2.5. Register + Offset Addressing 2.6. Segment Association 2.7. Address Wraparound 2.8. Addressing Modes Summary 	17 17 21 22 25 25 26 27
3 Branching	31
3.1. Comparison and Conditions 3.2. Conditional Jumps 3.3. Unconditional Jump 3.4. Relative Addressing 3.5. Types of Jump 3.6. Sorting Example	31 33 36 37 37 38
4 Bit Manipulations	43
 4.1. Multiplication Algorithm 4.2. Shifting and Rotations 4.3. Multiplication in Assembly Language 4.4. Extended Operations 4.5. Bitwise Logical Operations 4.6. Masking Operations 	43 43 46 47 50 51
5 Subroutines	55
5.1. Program Flow5.2. Our First Subroutine5.3. Stack5.4. Saving and Restoring Registers5.5. Parameter Passing Through Stack5.6. Local Variables	55 57 59 62 64 67

TARIE OF CONTENT	

iv

6 Display Memory	71
6.1. ASCII Codes	71
6.2. Display Memory Formation	72
6.3. Hello World in Assembly Language	74
6.4. Number Printing in Assembly	76
6.5. Screen Location Calculation	79
7 String Instructions	83
7.1. String Processing	83
7.2. STOS Example - Clearing the Screen	85
7.3. LODS Example – String Printing	86
7.4. SCAS Example – String Length	87
7.5. LES and LDS Example	89
7.6. MOVS Example - Screen Scrolling	90
7.7. CMPS Example – String Comparison	92

Introduction to Assembly Language

1.1. BASIC COMPUTER ARCHITECTURE

Address, Data, and Control Buses

A computer system comprises of a processor, memory, and I/O devices. I/O is used for interfacing with the external world, while memory is the processor's internal world. Processor is the core in this picture and is responsible for performing operations. The operation of a computer can be fairly described with processor and memory only. I/O will be discussed in a later part of the course. Now the whole working of the computer is performing an operation by the processor on data, which resides in memory.

The scenario that the processor executes operations and the memory contains data elements requires a mechanism for the processor to read that data from the memory. "That data" in the previous sentence much be rigorously explained to the memory which is a dumb device. Just like a postman, who must be told the precise address on the letter, to inform him where the destination is located. Another significant point is that if we only want to read the data and not write it, then there must be a mechanism to inform the memory that we are interested in reading data and not writing it. Key points in the above discussion are:


- There must be a mechanism to inform memory that we want to do the read operation
- There must be a mechanism to inform memory that we want to read precisely which element
- There must be a mechanism to transfer that data element from memory to processor

The group of bits that the processor uses to inform the memory about which element to read or write is collectively known as the *address bus*. Another important bus called the *data bus* is used to move the data from the memory to the processor in a read operation and from the processor to the memory in a write operation. The third group consists of miscellaneous independent lines used for control purposes. For example, one line of the bus is used to inform the memory about whether to do the read operation or the write operation. These lines are collectively known as the *control bus*.

These three buses are the eyes, nose, and ears of the processor. It uses them in a synchronized manner to perform a meaningful operation. Although the programmer specifies the meaningful operation, but to fulfill it the processor needs the collaboration of other units and peripherals. And that collaboration is made available using the three buses. This is the very basic description of a computer and it can be extended on the same lines to I/O but we are leaving it out just for simplicity for the moment.

The address bus is unidirectional and address always travels from processor to memory. This is because memory is a dumb device and cannot predict which element the processor at a particular instant of time needs. Data moves from both, processor to memory and memory to processor, so the data bus is bidirectional. Control bus is special and relatively complex, because different lines comprising it behave differently. Some take

information from the processor to a peripheral and some take information from the peripheral to the processor. There can be certain events outside the processor that are of its interest. To bring information about these events the data bus cannot be used as it is owned by the processor and will only be used when the processor grants permission to use it. Therefore certain processors provide control lines to bring such information to processor's notice in the control bus. Knowing these signals in detail is unnecessary but the general idea of the control bus must be conceived in full.



We take an example to explain the collaboration of the processor and memory using the address, control, and data buses. Consider that you want your uneducated servant to bring a book from the shelf. You order him to bring the fifth book from top of the shelf. All the data movement operations are hidden in this one sentence. Such a simple everyday phenomenon seen from this perspective explains the seemingly complex working of the three buses. We told the servant to "bring a book" and the one which is "fifth from top," precise location even for the servant who is much more intelligent then our dumb memory. The dumb servant follows the steps one by one and the book is in your hand as a result. If however you just asked him for a book or you named the book, your uneducated servant will stand there gazing at you and the book will never come in your hand.

Even in this simplest of all examples, mathematics is there, "fifth from top." Without a number the servant would not be able to locate the book. He is unable to understand your will. Then you tell him to put it with the seventh book on the right shelf. Precision is involved and only numbers are precise in this world. One will always be one and two will always be two. So we tell in the form of a number on the address bus which cell is needed out of say the 2000 cells in the whole memory.

A binary number is generated on the address bus, fifth, seventh, eighth, tenth; the cell which is needed. So the cell number is placed on the address bus. A memory cell is an n-bit location to store data, normally 8-bit also called a byte. The number of bits in a cell is called the *cell width*. The two dimensions, cell width and number of cells, define the memory completely just like the width and depth of a well defines it completely. 200 feet deep by 15 feet wide and the well is completely described. Similarly for memory we define two dimensions. The first dimension defines how many parallel bits are there in a single memory cell. The memory is called 8-bit or 16-bit for this reason and this is also the word size of the memory. This need not match the size of a processor word which has other parameters to define it. In general the memory cell cannot be wider than the width of the data bus. Best and simplest operation requires the same size of data bus and memory cell width.

As we previously discussed that the control bus carries the intent of the processor that it wants to read or to write. Memory changes its behavior in response to this signal from the processor. It defines the direction of data flow. If processor wants to read but memory wants to write, there will be no communication or useful flow of information. Both must be synchronized, like a speaker speaks and the listener listens. If both speak simultaneously or both listen there will be no communication. This precise synchronization between the processor and the memory is the responsibility of the control bus

Control bus is only the mechanism. The responsibility of sending the appropriate signals on the control bus to the memory is of the processor. Since the memory never wants to listen or to speak of itself. Then why is the control bus bidirectional. Again we take the same example of the servant and the book further to elaborate this situation. Consider that the servant went to fetch the book just to find that the drawing room door is locked. Now the servant can wait there indefinitely keeping us in surprise or come back and inform us about the situation so that we can act accordingly. The servant even though he was obedient was unable to fulfill our orders so in all his obedience, he came back to inform us about the problem. Synchronization is still important, as a result of our orders either we got the desired cell or we came to know that the memory is locked for the moment. Such information cannot be transferred via the address or the data bus. For such situations when peripherals want to talk to the processor when the processor wasn't expecting them to speak, special lines in the control bus are used. The information in such signals is usually to indicate the incapability of the peripheral to do something for the moment. For these reasons the control bus is a bidirectional bus and can carry information from processor to memory as well as from memory to processor.

1.2. REGISTERS

The basic purpose of a computer is to perform operations, and operations need operands. Operands are the data on which we want to perform a certain operation. Consider the addition operation; it involves adding two numbers to get their sum. We can have precisely one address on the address bus and consequently precisely one element on the data bus. At the very same instant the second operand cannot be brought inside the processor. As soon as the second is selected, the first operand is no longer there. For this reason there are temporary storage places inside the processor called registers. Now one operand can be read in a register and added into the other which is read directly from the memory. Both are made accessible at one instance of time. one from inside the processor and one from outside on the data bus. The result can be written to at a distinct location as the operation has completed and we can access a different memory cell. Sometimes we hold both operands in registers for the sake of efficiency as what we can do inside the processor is undoubtedly faster than if we have to go outside and bring the second operand.

Registers are like a scratch pad ram inside the processor and their operation is very much like normal memory cells. They have precise locations and remember what is placed inside them. They are used when we need more than one data element inside the processor at one time. The concept of registers will be further elaborated as we progress into writing our first program.

Memory is a limited resource but the number of memory cells is large. Registers are relatively very small in number, and are therefore a very scarce and precious resource. Registers are more than one in number, so we have to precisely identify or name them. Some manufacturers number their registers like r0, r1, r2, others name them like A, B, C, D. Naming is useful since the registers are few in number. This is called the nomenclature of the particular

architecture. Still other manufacturers name their registers according to their function like X stands for an index register. This also informs us that there are special functions of registers as well, some of which are closely associated to the particular architecture. For example index registers do not hold data instead they are used to hold the address of data. There are other functions as well and the whole spectrum of register functionalities is quite large. However most of the details will become clear as the registers of the Intel architecture are discussed in detail.

Accumulator

There is a central register in every processor called the accumulator. Traditionally all mathematical and logical operations are performed on the accumulator. The word size of a processor is defined by the width of its accumulator. A 32bit processor has an accumulator of 32 bits.

Pointer, Index, or Base Register

The name varies from manufacturer to manufacturer, but the basic distinguishing property is that it does not hold data but holds the address of data. The rationale can be understood by examining a "for" loop in a higher level language, zeroing elements in an array of ten elements located in consecutive memory cells. The location to be zeroed changes with every iteration. That is the address where the operation is performed is changing. Index register is used in such a situation to hold the address of the current array location. Now the value in the index register cannot be treated as data, but it is the address of data. In general whenever we need access to a memory location whose address is not known until runtime we need an index register. Without this register we would have needed to explicitly code each iteration separately.

In newer architectures the distinction between accumulator and index registers has become vague. They have general registers which are more versatile and can do both functions. They do have some specialized behaviors but basic operations can be done on all general registers.

Flags Register or Program Status Word

This is a special register in every architecture called the flags register or the program status word. Like the accumulator it is an 8, 16, or 32 bits register but unlike the accumulator it is meaningless as a unit, rather the individual bits carry different meanings. The bits of the accumulator work in parallel as a unit and each bit mean the same thing. The bits of the flags register work independently and individually, and combined its value is meaningless.

An example of a bit commonly present in the flags register is the carry flag. The carry can be contained in a single bit as in binary arithmetic the carry can only be zero or one. If a 16bit number is added to a 16bit accumulator, and the result is of 17 bits the 17th bit is placed in the carry bit of the flags register. Without this 17th bit the answer is incorrect. More examples of flags will be discussed when dealing with the Intel specific register set.

Program Counter or Instruction Pointer

Everything must translate into a binary number for our dumb processor to understand it, be it an operand or an operation itself. Therefore the instructions themselves must be translated into numbers. For example to add numbers we understand the word "add." We translate this word into a number to make the processor understand it. This number is the actual instruction for the computer. All the objects, inheritance and encapsulation constructs in higher level languages translate down to just a number in assembly language in the end. Addition, multiplication, shifting; all big

programs are made using these simple building blocks. A number is at the bottom line since this is the only thing a computer can understand.

A program is defined to be "an ordered set of instructions." Order in this definition is a key part. Instructions run one after another, first, second, third and so on. Instructions have a positional relationship. The whole logic depends on this positioning. If the computer executes the fifth instructions after the first and not the second, all our logic is gone. The processor should ensure this ordering of instructions. A special register exists in every processor called the program counter or the instruction pointer that ensures this ordering. "The program counter holds the address of the next instruction to be executed." A number is placed in the memory cell pointed to by this register and that number tells the processor which instruction to execute; for example 0xEA, 255, or 152. For the processor 152 might be the add instruction. Just this one number tells it that it has to add, where its operands are, and where to store the result. This number is called the opcode. The instruction pointer moves from one opcode to the next. This is how our program executes and progresses. One instruction is picked, its operands are read and the instruction is executed, then the next instruction is picked from the new address in instruction pointer and so on.

Remembering 152 for the add operation or 153 for the subtract operation is difficult. To make a simple way to remember difficult things we associate a symbol to every number. As when we write "add" everyone understands what we mean by it. Then we need a small program to convert this "add" of ours to 152 for the processor. Just a simple search and replace operation to translate all such symbols to their corresponding opcodes. We have mapped the numeric world of the processor to our symbolic world. "Add" conveys a meaning to us but the number 152 does not. We can say that add is closer to the programmer's thinking. This is the basic motive of adding more and more translation layers up to higher level languages like C++ and Java and Visual Basic. These symbols are called *instruction mnemonics*. Therefore the mnemonic "add a to b" conveys more information to the reader. The dumb translator that will convert these mnemonics back to the original opcodes is a key program to be used throughout this course and is called the *assembler*.

1.3. INSTRUCTION GROUPS

Usual opcodes in every processor exist for moving data, arithmetic and logical manipulations etc. However their mnemonics vary depending on the will of the manufacturer. Some manufacturers name the mnemonics for data movement instructions as "move," some call it "load" and "store" and still other names are present. But the basic set of instructions is similar in every processor. A grouping of these instructions makes learning a new processor quick and easy. Just the group an instruction belongs tells a lot about the instruction.

Data Movement Instructions

These instructions are used to move data from one place to another. These places can be registers, memory, or even inside peripheral devices. Some examples are:

mov ax, bx lda 1234

Arithmetic and Logic Instructions

Arithmetic instructions like addition, subtraction, multiplication, division and Logical instructions like logical and, logical or, logical xor, or complement are part of this group. Some examples are:

```
and ax, 1234
add bx, 0534
add bx, [1200]
```

The bracketed form is a complex variation meaning to add the data placed at address 1200. Addressing data in memory is a detailed topic and is discussed in the next chapter.

Program Control Instructions

The instruction pointer points to the next instruction and instructions run one after the other with the help of this register. We can say that the instructions are tied with one another. In some situations we don't want to follow this implied path and want to order the processor to break its flow if some condition becomes true instead of the spatially placed next instruction. In certain other cases we want the processor to first execute a separate block of code and then come back to resume processing where it left.

These are instructions that control the program execution and flow by playing with the instruction pointer and altering its normal behavior to point to the next instruction. Some examples are:

```
cmp ax, 0 jne 1234
```

We are changing the program flow to the instruction at 1234 address if the condition that we checked becomes true.

Special Instructions

Another group called special instructions works like the special service commandos. They allow changing specific processor behaviors and are used to play with it. They are used rarely but are certainly used in any meaningful program. Some examples are:

```
cli
```

Where cli clears the interrupt flag and sti sets it. Without delving deep into it, consider that the cli instruction instructs the processor to close its ears from the outside world and never listen to what is happening outside, possibly to do some very important task at hand, while sti restores normal behavior. Since these instructions change the processor behavior they are placed in the special instructions group.

1.4. INTEL IAPX88 ARCHITECTURE

Now we select a specific architecture to discuss these abstract ideas in concrete form. We will be using IBM PC based on Intel architecture because of its wide availability, because of free assemblers and debuggers available for it, and because of its wide use in a variety of domains. However the concepts discussed will be applicable on any other architecture as well; just the mnemonics of the particular language will be different.

Technically iAPX88 stands for "Intel Advanced Processor Extensions 88." It was a very successful processor also called 8088 and was used in the very first IBM PC machines. Our discussion will revolve around 8088 in the first half of the course while in the second half we will use iAPX386 which is very advanced and powerful processor. 8088 is a 16bit processor with its accumulator and all registers of 16 bits. 386 on the other hand, is a 32bit processor. However it is downward compatible with iAPX88 meaning that all code written for 8088 is valid on the 386. The architecture of a processor means the organization and functionalities of the registers it contains and the instructions that are valid on the processor. We will discuss the register architecture of 8088 in detail below while its instructions are discussed in the rest of the book at appropriate places.

1.5. HISTORY

Intel did release some 4bit processors in the beginning but the first meaningful processor was 8080, an 8bit processor. The processor became

popular due to its simplistic design and versatile architecture. Based on the experience gained from 8080, an advanced version was released as 8085. The processor became widely popular in the engineering community again due to its simple and logical nature.

Intel introduced the first 16bit processor named 8088 at a time when the concept of personal computer was evolving. With a maximum memory of 64K on the 8085, the 8088 allowed a whole mega byte. IBM embedded this processor in their personal computer. The first machines ran at 4.43 MHz; a blazing speed at that time. This was the right thing at the right moment. No one expected this to become the biggest success of computing history. IBM PC XT became so popular and successful due to its open architecture and easily available information.

The success was unexpected for the developers themselves. As when Intel introduced the processor it contained a timer tick count which was valid for five years only. They never anticipated the architecture to stay around for more than five years but the history took a turn and the architecture is there at every desk even after 25 years and the tick is to be specially handled every now and then.

1.6. REGISTER ARCHITECTURE

The iAPX88 architecture consists of 14 registers.

CS	
DS	
SS	
ES	
IP	
FLAGS	

S				
В				
S	I			
D				
AH	AL	(AX)		
ВН	BL	(BX)		
СН	CL	(CX)		
DH	DH DL			

General Registers (AX, BX, CX, and DX)

The registers AX, BX, CX, and DX behave as general purpose registers in Intel architecture and do some specific functions in addition to it. X in their names stand for extended meaning 16bit registers. For example AX means we are referring to the extended 16bit "A" register. Its upper and lower byte are separately accessible as AH (A high byte) and AL (A low byte). All general purpose registers can be accessed as one 16bit register or as two 8bit registers. The two registers AH and AL are part of the big whole AX. Any change in AH or AL is reflected in AX as well. AX is a composite or extended register formed by gluing together the two parts AH and AL.

The A of AX stands for Accumulator. Even though all general purpose registers can act as accumulator in most instructions there are some specific variations which can only work on AX which is why it is named the accumulator. The B of BX stands for Base because of its role in memory addressing as discussed in the next chapter. The C of CX stands for Counter as there are certain instructions that work with an automatic count in the CX register. The D of DX stands for Destination as it acts as the destination in I/O operations. The A, B, C, and D are in letter sequence as well as depict some special functionality of the register.

Index Registers (SI and DI)

SI and DI stand for source index and destination index respectively. These are the index registers of the Intel architecture which hold address of data and used in memory access. Being an open and flexible architecture, Intel allows many mathematical and logical operations on these registers as well like the general registers. The source and destination are named because of their implied functionality as the source or the destination in a special class of instructions called the string instructions. However their use is not at all restricted to string instructions. SI and DI are 16bit and cannot be used as 8bit register pairs like AX, BX, CX, and DX.

Instruction Pointer (IP)

This is the special register containing the address of the next instruction to be executed. No mathematics or memory access can be done through this register. It is out of our direct control and is automatically used. Playing with it is dangerous and needs special care. Program control instructions change the IP register.

Stack Pointer (SP)

It is a memory pointer and is used indirectly by a set of instructions. This register will be explored in the discussion of the system stack.

Base Pointer (BP)

It is also a memory pointer containing the address in a special area of memory called the stack and will be explored alongside SP in the discussion of the stack.

Flags Register

The flags register as previously discussed is not meaningful as a unit rather it is bit wise significant and accordingly each bit is named separately. The bits not named are unused. The Intel FLAGS register has its bits organized as follows:

15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
				0	D	I	Т	S	Z		А		P		С

The individual flags are explained in the following table.

С	Carry	When two 16bit numbers are added the answer can be 17 bits long or when two 8bit numbers are added the answer can be 9 bits long. This extra bit that won't fit in the target register is placed in the carry flag where it can be used and tested.			
Р	Parity	Parity is the number of "one" bits in a binary number. Parity is either odd or even. This information is normally used in communications to verify the integrity of data sent from the sender to the receiver.			
A	Auxiliary Carry	A number in base 16 is called a hex number and can be represented by 4 bits. The collection of 4 bits is called a nibble. During addition or subtraction if a carry goes from one nibble to the next this flag is set. Carry flag is for the carry from the whole addition while auxiliary carry is the carry from the first nibble to the second.			
Z	Zero Flag	The Zero flag is set if the last mathematical or logical instruction has produced a zero in its destination.			

S	Sign Flag	A signed number is represented in its two's complement form in the computer. The most significant bit (MSB) of a negative number in this representation is 1 and for a positive number it is zero. The sign bit of the last mathematical or logical operation's destination is copied into the sign flag.
Т	Trap Flag	The trap flag has a special role in debugging which will be discussed later.
I	Interrupt Flag	It tells whether the processor can be interrupted from outside or not. Sometimes the programmer doesn't want a particular task to be interrupted so the Interrupt flag can be zeroed for this time. The programmer rather than the processor sets this flag since the programmer knows when interruption is okay and when it is not. Interruption can be disabled or enabled by making this bit zero or one, respectively, using special instructions.
D	Direction Flag	Specifically related to string instructions, this flag tells whether the current operation has to be done from bottom to top of the block (D=0) or from top to bottom of the block (D=1).
0	Overflow Flag	The overflow flag is set during signed arithmetic, e.g. addition or subtraction, when the sign of the destination changes unexpectedly. The actual process sets the overflow flag whenever the carry into the MSB is different from the carry out of the MSB

Segment Registers (CS, DS, SS, and ES)

The code segment register, data segment register, stack segment register, and the extra segment register are special registers related to the Intel segmented memory model and will be discussed later.

1.7. OUR FIRST PROGRAM

The first program that we will write will only add three numbers. This very simple program will clarify most of the basic concepts of assembly language. We will start with writing our algorithm in English and then moving on to convert it into assembly language.

English Language Version

"Program is an ordered set of instructions for the processor." Our first program will be instructions manipulating AX and BX in plain English.

move 5 to ax move 10 to bx add bx to ax move 15 to bx add bx to ax

Even in this simple reflection of thoughts in English, there are some key things to observe. One is the concept of destination as every instruction has a "to destination" part and there is a source before it as well. For example the second line has a constant 10 as its source and the register BX as its destination. The key point in giving the first program in English is to convey that the concepts of assembly language are simple but fine. Try to understand them considering that all above is everyday English that you know very well and every concept will eventually be applicable to assembly language.

Assembly Language Version

Intel could have made their assembly language exactly identical to our program in plain English but they have abbreviated a lot of symbols to avoid unnecessarily lengthy program when the meaning could be conveyed with less effort. For example Intel has named their move instruction "mov" instead of "move." Similarly the Intel order of placing source and destination is opposite to what we have used in our English program, just a change of interpretation. So the Intel way of writing things is:

```
operation destination, source operation destination operation source
```

The later three variations are for instructions that have one or both of their operands implied or they work on a single or no operand. An implied operand means that it is always in a particular register say the accumulator, and it need not be mentioned in the instruction. Now we attempt to write our program in actual assembly language of the iapx88.

	Example 1.1					
001 002 003 004 005 006 007 008 009	; a program to add three numbers using registers [org 0x0100] mov ax, 5 ; load first number in ax mov bx, 10 ; load second number in bx add ax, bx ; accumulate sum in ax mov bx, 15 ; load third number in bx add ax, bx ; accumulate sum in ax mov ax, 0x4c00 ; terminate program int 0x21					
001	To start a comment a semicolon is used and the assembler ignores everything else on the same line. Comments must be extensively used in assembly language programs to make them readable.					
002	Leave the org directive for now as it will be discussed later.					
003	The constant 5 is loaded in one register AX.					
004	The constant 10 is loaded in another register BX.					
005	Register BX is added to register AX and the result is stored in register AX. Register AX should contain 15 by now.					
006	The constant 15 is loaded in the register BX.					
007	Register BX is again added to register AX now producing 15+15=30 in the AX register. So the program has computed 5+10+15=30.					
008	Vertical spacing must also be used extensively in assembly language programs to separate logical blocks of code.					
009-010	programs to separate logical blocks of code. The ending lines are related more to the operating system than to assembly language programming. It is a way to inform DOS that our program has terminated so it can display its command prompt again. The computer may reboot or behave improperly if this termination is not present.					

Assembler, Linker, and Debugger

We need an assembler to assemble this program and convert this into executable binary code. The assembler that we will use during this course is "Netwide Assembler" or NASM. It is a free and open source assembler. And the tool that will be most used will be the debugger. We will use a free debugger called "A fullscreen debugger" or AFD. These are the whole set of

weapons an assembly language programmer needs for any task whatsoever at hand.

To assemble we will give the following command to the processor assuming that our input file is named EX01.ASM.

```
nasm ex01.asm -o ex01.com -l ex01.lst
```

This will produce two files EX01.COM that is our executable file and EX01.LST that is a special listing file that we will explore now. The listing file produced for our example above is shown below with comments removed for neatness.

```
[org 0x0100]
   00000000 B80500
                                                     mov
                                                          ax, 5
   00000003 BB0A00
                                                          bx, 10
                                                     mov
   00000006 01D8
                                                     add
   00000008 BB0F00
                                                     mov
                                                          bx,
                                                              15
   0000000B 01D8
                                                     add
                                                          ax, bx
   0000000D B8004C
                                                     mov.
                                                          ax. 0x4c00
                                                          0x21
10 00000010 CD21
                                                     int
```

The first column in the above listing is offset of the listed instruction in the output file. Next column is the opcode into which our instruction was translated. In this case this opcode is B8. Whenever we move a constant into AX register the opcode B8 will be used. After it 0500 is appended which is the immediate operand to this instruction. An immediate operand is an operand which is placed directly inside the instruction. Now as the AX register is a word sized register, and one hexadecimal digit takes 4 bits so 4 hexadecimal digits make one word or two bytes. Which of the two bytes should be placed first in the instruction, the least significant or the most significant? Similarly for 32bit numbers either the order can be most significant, less significant, lesser significant, and least significant called the big-endian order used by Motorola and some other companies or it can be least significant, more significant, more significant, and most significant called the little-endian order and is used by Intel. The big-endian have the argument that it is more natural to read and comprehend while the littleendian have the argument that this scheme places the less significant value at a lesser address and more significant value at a higher address.

Because of this the constant 5 in our instruction was converted into 0500 with the least significant byte of 05 first and the most significant byte of 00 afterwards. When read as a word it is 0005 but when written in memory it will become 0500. As the first instruction is three bytes long, the listing file shows that the offset of the next instruction in the file is 3. The opcode BB is for moving a constant into the BX register, and the operand 0A00 is the number 10 in little-endian byte order. Similarly the offsets and opcodes of the remaining instructions are shown in order. The last instruction is placed at offset 0x10 or 16 in decimal. The size of the last instruction is two bytes, so the size of the complete COM file becomes 18 bytes. This can be verified from the directory listing, using the DIR command, that the COM file produced is exactly 18 bytes long.

Now the program is ready to be run inside the debugger. The debugger shows the values of registers, flags, stack, our code, and one or two areas of the system memory as data. Debugger allows us to step our program one instruction at a time and observe its effect on the registers and program data. The details of using the AFD debugger can be seen from the AFD manual.

After loading the program in the debugger observe that the first instruction is now at 0100 instead of absolute zero. This is the effect of the org directive at the start of our program. The first instruction of a COM file must be at

Commented [I1]: LEN used by Intel BEN used by Motorola offset 0100 (decimal 255) as a requirement. Also observe that the debugger is showing your program even though it was provided only the COM file and neither of the listing file or the program source. This is because the translation from mnemonic to opcode is reversible and the debugger mapped back from the opcode to the instruction mnemonic. This will become apparent for instructions that have two mnemonics as the debugger might not show the one that was written in the source file.

As a result of program execution either registers or memory will change. Since our program yet doesn't touch memory the only changes will be in the registers. Keenly observe the registers AX, BX, and IP change after every instruction. IP will change after every instruction to point to the next instruction while AX will accumulate the result of our addition.

1.8. SEGMENTED MEMORY MODEL

Rationale

In earlier processors like 8080 and 8085 the linear memory model was used to access memory. In linear memory model the whole memory appears like a single array of data. 8080 and 8085 could access a total memory of 64K using the 16 lines of their address bus. When designing iAPX88 the Intel designers wanted to remain compatible with 8080 and 8085 however 64K was too small to continue with, for their new processor. To get the best of both worlds they introduced the segmented memory model in 8088.

There is also a logical argument in favor of a segmented memory model in additional to the issue of compatibility discussed above. We have two logical parts of our program, the code and the data, and actually there is a third part called the program stack as well, but higher level languages make this invisible to us. These three logical parts of a program should appear as three distinct units in memory, but making this division is not possible in the linear memory model. The segmented memory model does allow this distinction.

Mechanism


The segmented memory model allows multiple functional windows into the main memory, a code window, a data window etc. The processor sees code from the code window and data from the data window. The size of one window is restricted to 64K. 8085 software fits in just one such window. It sees code, data, and stack from this one window, so downward compatibility is attained

However the maximum memory iAPX88 can access is 1MB which can be accessed with 20 bits. Compare this with the 64K of 8085 that were accessed using 16 bits. The idea is that the 64K window just discussed can be moved anywhere in the whole 1MB. The four segment registers discussed in the Intel register architecture are used for this purpose. Therefore four windows can exist at one time. For example one window that is pointed to by the CS register contains the currently executing code.

To understand the concept, consider the windows of a building. We say that a particular window is 3 feet above the floor and another one is 20 feet above the floor. The reference point, the floor is the base of the segment called the datum point in a graph and all measurement is done from that datum point considering it to be zero. So CS holds the zero or the base of code. DS holds the zero of data. Or we can say CS tells how high code from the floor is, and DS tells how high data from the floor is, while SS tells how high the stack is. One extra segment ES can be used if we need to access two distant areas of memory at the same time that both cannot be seen through the same window. ES also has special role in string instructions. ES is used as an extra data segment and cannot be used as an extra code or stack segment.


Revisiting the concept again, like the datum point of a graph, the segment registers tell the start of our window which can be opened anywhere in the megabyte of memory available. The window is of a fixed size of 64KB. Base and offset are the two key variables in a segmented address. Segment tells the base while offset is added into it. The registers IP, SP, BP, SI, DI, and BX all can contain a 16bit offset in them and access memory relative to a segment base.

The IP register cannot work alone. It needs the CS register to open a 64K window in the 1MB memory and then IP works to select code from this window as offsets. IP works only inside this window and cannot go outside of this 64K in any case. If the window is moved i.e. the CS register is changed, IP will change its behavior accordingly and start selecting from the new window. The IP register always works relatively, relative to the segment base stored in the CS register. IP is a 16bit register capable of accessing only 64K memory so how the whole megabyte can contain code anywhere. Again the same concept is there, it can access 64K at one instance of time. As the base is changed using the CS register, IP can be made to point anywhere is the whole megabyte. The process is illustrated with the following diagram.



Physical Address Calculation

Now for the whole megabyte we need 20 bits while CS and IP are both 16bit registers. We need a mechanism to make a 20bit number out of the two 16bit numbers. Consider that the segment value is stored as a 20 bit number with the lower four bits zero and the offset value is stored as another 20 bit number with the upper four bits zeroed. The two are added to produce a 20bit absolute address. A carry if generated is dropped without being stored anywhere and the phenomenon is called address wraparound. The process is explained with the help of the following diagram.



Therefore memory is determined by a segment-offset pair and not alone by any one register which will be an ambiguous reference. Every offset register is assigned a default segment register to resolve such ambiguity. For example the program we wrote when loaded into memory had a value of 0100 in IP register and some value say 1DDD in the CS register. Making both 20 bit numbers, the segment base is 1DDD0 and the offset is 00100 and adding them we get the physical memory address of 1DED0 where the opcode B80500 is placed.

Paragraph Boundaries


As the segment value is a 16bit number and four zero bits are appended to the right to make it a 20bit number, segments can only be defined a 16byte boundaries called paragraph boundaries. The first possible segment value is 0000 meaning a physical base of 00000 and the next possible value of 0001 means a segment base of 00010 or 16 in decimal. Therefore segments can only be defined at 16 byte boundaries.

Overlapping Segments

We can also observe that in the case of our program CS, DS, SS, and ES all had the same value in them. This is called overlapping segments so that we can see the same memory from any window. This is the structure of a COM file.

Using partially overlapping segments we can produce a number of segment, offset pairs that all access the same memory. For example 1DDD:0100 and IDED:0000 both point to the same physical memory. To test this we can open a data window at 1DED:0000 in the debugger and change the first three bytes to "90" which is the opcode for NOP (no operation). The change is immediately visible in the code window which is pointed to by CS containing 1DDD. Similarly IDCD:0200 also points to the same memory location. Consider this like a portion of wall that three different people on three different floors are seeing through their own windows. One of them painted the wall red; it will be changed for all of them though their perspective is different. It is the same phenomenon occurring here.

The segment, offset pair is called a logical address, while the 20bit address is a physical address which is the real thing. Logical addressing is a mechanism to access the physical memory. As we have seen three different logical addresses accessed the same physical address.



EXERCISES

- 1. How the processor uses the address bus, the data bus, and the control bus to communicate with the system memory?
- 2. Which of the following are unidirectional and which are bidirectional?
 - a. Address Bus
 - b. Data Bus
 - c. Control Bus
- 3. What are registers and what are the specific features of the accumulator, index registers, program counter, and program status word?
- 4. What is the size of the accumulator of a 64bit processor?
- 5. What is the difference between an instruction mnemonic and its opcode?
- 6. How are instructions classified into groups?
- 7. A combination of 8bits is called a byte. What is the name for 4bits and for 16bits?
- 8. What is the maximum memory 8088 can access?
- 9. List down the 14 registers of the 8088 architecture and briefly describe their uses.
- What flags are defined in the 8088 FLAGS register? Describe the function of the zero flag, the carry flag, the sign flag, and the overflow flag.
- 11. Give the value of the zero flag, the carry flag, the sign flag, and the overflow flag after each of the following instructions if AX is initialized with 0x1254 and BX is initialized with 0x0FFF.
 - a. add ax, 0xEDAB
 - b. add ax, bx
 - c. add bx, 0xF001
- 12. What is the difference between little endian and big endian formats? Which format is used by the Intel 8088 microprocessor?
- 13. For each of the following words identify the byte that is stored at lower memory address and the byte that is stored at higher memory address in a little endian computer.
 - a. 1234
 - b. ABFC
 - c. B100
 - d. B800

- 14. What are the contents of memory locations 200, 201, 202, and 203 if the word 1234 is stored at offset 200 and the word 5678 is stored at offset 202?
- 15. What is the offset at which the first exeutable instruction of a COM file must be placed?
- 16. Why was segmentation originally introduced in 8088 architecture?
- 17. Why a segment start cannot start from the physical address 55555.
- 18. Calculate the physical memory address generated by the following segment offset pairs.
 - a. 1DDD:0436 b. 1234:7920

 - c. 74F0:2123
 - d. 0000:6727
 - e. FFFF:4336
 - f. 1080:0100
 - g. AB01:FFFF
- 19. What are the first and the last physical memory addresses accessible using the following segment values?
 - a. 1000
 - b. OFFF
 - c. 1002d. 0001

 - e. E000
- 20. Write instructions that perform the following operations.
 - a. Copy BL into CL
 - b. Copy DX into AX
 - c. Store 0x12 into AL
 - d. Store 0x1234 into AX
 - e. Store 0xFFFF into AX
- 21. Write a program in assembly language that calculates the square of six by adding six to the accumulator six times.

Addressing Modes

2.1. DATA DECLARATION

The first instruction of our first assembly language program was "mov ax, 5." Here MOV was the opcode, AX was the destination operand, while 5 was the source operand. The value of 5 in this case was stored as part of the instruction encoding. In the opcode B80500, B8 was the opcode and 0500 was the operand stored immediately afterwards. Such an operand is called an immediate operand. It is one of the many types of operands available.

Writing programs using just the immediate operand type is difficult. Every reasonable program needs some data in memory apart from constants. Constants cannot be changed, i.e. they cannot appear as the destination operand. In fact placing them as destination is meaningless and illegal according to assembly language syntax. Only registers or data placed in memory can be changed. So real data is the one stored in memory, with a very few constants. So there must be a mechanism in assembly language to store and retrieve data from memory.

To declare a part of our program as holding data instead of instructions we need a couple of very basic but special assembler directives. The first directive is "define byte" written as "db."

```
db somevalue
```

As a result a cell in memory will be reserved containing the desired value in it and it can be used in a variety of ways. Now we can add variables instead of constants. The other directive is "define word" or "dw" with the same syntax as "db" but reserving a whole word of 16 bits instead of a byte. There are directives to declare a double or a quad word as well but we will restrict ourselves to byte and word declarations for now. For single byte we use db and for two bytes we use dw.

To refer to this variable later in the program, we need the address occupied by this variable. The assembler is there to help us. We can associate a symbol with any address that we want to remember and use that symbol in the rest of the code. The symbol is there for our own comprehension of code. The assembler will calculate the address of that symbol using our origin directive and calculating the instruction lengths or data declarations inbetween and replace all references to the symbol with the corresponding address. This is just like variables in a higher level language, where the compiler translates them into addresses; just the process is hidden from the programmer one level further. Such a symbol associated to a point in the program is called a label and is written as the label name followed by a colon.

2.2. DIRECT ADDRESSING

Now we will rewrite our first program such that the numbers 5, 10, and 15 are stored as memory variables instead of constants and we access them from there.

	Example 2.1
001 002 003	; a program to add three numbers using memory variables [org 0x0100]
003	mov ax, [num1] ; load first number in ax

```
; load second number in bx
                           bx, [num2]
                      add
                                               accumulate sum in ax
                           ax, bx
                           bx, [num3]
006
                                               load third number in bx
                      mov
007
                      add
                           ax,
                              bx
                                              ; accumulate sum in ax
008
                           [num4], ax
                                             ; store sum in num4
                      mov
009
                           ax. 0x4c00
                      mov.
                                             ; terminate program
011
                           0x21
                      int
012
        num1 ·
013
                      dw
014
        num2:
                           10
                      dw
        num3:
015
                           15
                      dw
016
        nıım4 •
                      dw
                           Ω
002
        Originate our program at 0100. The first executable instruction
        should be placed at this offset.
003
        The source operand is changed from constant 5 to [num1]. The
        bracket is signaling that the operand is placed in memory at address
        num1. The value 5 will be loaded in ax even though we did not
        specified it in our program code, rather the value will be picked from
        memory. The instruction should be read as "read the contents of
        memory location num1 in the ax register." The label num1 is a
        symbol for us but an address for the processor while the conversion
        is done by the assembler.
013
        The label num1 is defined as a word and the assembler is requested
        to place 5 in that memory location. The colon signals that num1 is a
        label and not an instruction.
```

Using the same process to assemble as discussed before we examine the listing file generated as a result with comments removed.

```
[org 0x0100]
   00000000 A1[1700]
                                                                   [num1]
   00000003 8B1E[1900]
                                                         mov
                                                              bx,
                                                                   [num2]
   00000007 01D8
                                                         add
                                                              ax, bx
   00000009 8B1E[1B00]
                                                              bx,
                                                                   [num3]
   0000000D 01D8
                                                         add
                                                              ax, bx
   0000000F A3[1D00]
                                                        mov
                                                              [num4], ax
10 00000012 B8004C
11 00000015 CD21
                                                              ax,
0x21
                                                                   0x4c00
                                                         int
13 00000017 0500
                                         num1:
                                                         dw
                                                              5
                                                              10
14 00000019 0A00
                                         num2:
                                                         dw
   0000001B 0F00
16 0000001D 0000
                                         num4:
                                                              0
                                                         dw
```

The first instruction of our program has changed from B80500 to A11700. The opcode B8 is used to move constants into AX, while the opcode A1 is used when moving data into AX from memory. The immediate operand to our new instruction is 1700 or as a word 0017 (23 decimal) and from the bottom of the listing file we can observe that this is the offset of num1. The assembler has calculated the offset of num1 and used it to replace references to num1 in the whole program. Also the value 0500 can be seen at offset 0017 in the file. We can say contents of memory location 0017 are 0005 as a word. Similarly num2, num3, and num4 are placed at 0019, 001B, and 001D addresses.

When the program is loaded in the debugger, it is loaded at offset 0100, which displaces all memory accesses in our program. The instruction A11700 is changed to A11701 meaning that our variable is now placed at 0117 offset. The instruction is shown as mov ax, [0117]. Also the data window can be used to verify that offset 0117 contains the number 0005.

Execute the program step by step and examine how the memory is read and the registers are updated, how the instruction pointer moves forward, and how the result is saved back in memory. Also observe inside the debugger code window below the code for termination, that the debugger is interpreting our data as code and showing it as some meaningless instructions. This is because the debugger sees everything as code in the code window and cannot differentiate our declared data from opcodes. It is our responsibility that we terminate execution before our data is executed as code.

Also observe that our naming of num1, num2, num3, and num4 is no longer there inside the debugger. The debugger is only showing the numbers 0117, 0119, 011B, and 011D. Our numerical machine can only work with numbers. We used symbols for our ease to label or tag certain positions in our program. The assembler converts these symbols into the appropriate numbers automatically. Also observe that the effect of "dw" is to place 5 in two bytes as 0005. Had we used "db" this would have been stored as 05 in one byte.

Given the fact that the assembler knows only numbers we can write the same program using a single label. As we know that num2 is two ahead of num1, we can use num1+2 instead of num2 and let the assembler calculate the sum during assembly process.

```
Example 2.2
001
        ; a program to add three numbers accessed using a single label
002
003
         [org 0x0100]
                                               ; load first number in ax
                            ax, [num1]
                      mov
004
                                               ; load second number in bx
                            bx, [num1+2]
                                               ; accumulate sum in ax
005
006
                       add
                            ax, bx
                           bx, [num1+4] ax, bx
                                              ; load third number in bx
                      mov
                                              ; accumulate sum in ax
008
                            [num1+6], ax
                                               ; store sum at num1+6
                       mov
009
010
                            ax, 0x4c00
                                               ; terminate program
011
                           0x21
                       int
012
013
014
                      dw
                            10
015
                            15
                       dw
016
                            0
004
        The second number is read from num1+2. Similarly the third
        number is read from num1+4 and the result is accessed at num1+6.
013-016 The labels num2, num3, and num4 are removed and the data there
        will be accessed with reference to num1.
```

Every location is accessed with reference to num1 in this example. The expression "num1+2" comprises of constants only and can be evaluated at the time of assembly. There are no variables involved in this expression. As we open the program inside the debugger we see a verbatim copy of the previous program. There is no difference at all since the assembler catered for the differences during assembly. It calculated 0117+2=0119 while in the previous it directly knew from the value of num2 that it has to write 0119, but the end result is a ditto copy of the previous execution.

Another way to declare the above data and produce exactly same results is shown in the following example.

```
005
                                               ; accumulate sum in ax
                      add
                           ax, bx
006
                           bx, [num1+4]
                                               ; load third number in bx
                      mov
007
                       add
                           ax, bx
                                               ; accumulate sum in ax
                      mov
                           [num1+6], ax
                                               ; store sum at num1+6
009
010
                           ax, 0x4c00
                                               ; terminate program
                      int
                           0 \times 21
012
013
        num1:
                      dw
                           5, 10, 15, 0
013
        As we do not need to place labels on individual variables we can save
        space and declare all data on a single line separated by commas.
        This declaration will declare four words in consecutive memory
        locations while the address of first one is num1.
```

The method used to access memory in the above examples is called direct addressing. In direct addressing the memory address is fixed and is given in the instruction. The actual data used is placed in memory and now that data can be used as the destination operand as well. Also the source and destination operands must have the same size. For example a word defined memory is read in a word sized register. A last observation is that the data 0500 in memory was corrected to 0005 when read in a register. So registers contain data in proper order as a word.

A last variation using direct addressing shows that we can directly add a memory variable and a register instead of adding a register into another that we were doing till now.

```
Example 2.4
01
02
03
04
05
06
07
08
09
          ; a program to add three numbers directly in memory [org 0 \times 0100]
                                                      ; load first number in ax
                                ax, [num1]
                                [num1+6], ax ax, [num1+2]
                                                      ; store first number in result
                          mov
                                                      ; load second number in ax
                          mov
                                                      ; add second number to result
                          mov
                                ax, [num1+4]
                                                      ; load third number in ax
                                                      ; add third number to result
                               [num1+6], ax
                          add
10
11
                          mov
                                ax, 0x4c00
                                                      ; terminate program
                               0x21
                          int
12
          num1:
                          dw
                                5, 10, 15, 0
```

We generate the following listing file as a result of the assembly process described previously. Comments are again removed.

```
[org 0x0100]
 3 00000000 A1[1900]
                                                            ax, [num1]
 4 00000003 A3[1F00]
                                                      mov
                                                            [num1+6], ax ax, [num1+2]
   00000006 A1[1B00]
                                                      mov
   00000009 0106[1F00]
                                                            [num1+6], ax
                                                      add
   0000000D A1[1D001
                                                      mov
                                                            ax. [num1+4]
   00000010 0106[1F00]
                                                            [num1+6], ax
                                                      add
10 00000014 B8004C
                                                      mov
                                                            ax. 0x4c00
11 00000017 CD21
                                                            0x21
                                                      int
13 00000019 05000A000F000000
                                       num1:
                                                      dw
                                                           5, 10, 15, 0
```

The opcode of add is changed because the destination is now a memory location instead of a register. No other significant change is seen in the listing file. Inside the debugger we observe that few opcodes are longer now and the location num1 is now translating to 0119 instead of 0117. This is done automatically by the assembler as a result of using labels instead of

hard coding addresses. During execution we observe that the word data as it is read into a register is read in correct order. The significant change in this example is that the destination of addition is memory. Method to access memory is direct addressing, whether it is the MOV instruction or the ADD instruction.

The first two instructions of the last program read a number into AX and placed it at another memory location. A quick thought reveals that the following might be a possible single instruction to replace the couple.

```
mov [num1+6], [num1] ; ILLEGAL
```

However this form is illegal and not allowed on the Intel architecture. None of the general operations of mov, add, sub etc. allow moving data from memory to memory. Only register to register, register to memory, memory to register, constant to memory, and constant to register operations are allowed. The other register to constant, memory to constant, and memory to memory are all disallowed. Only string instructions allow moving data from memory to memory and will be discussed in detail later. As a rule one instruction can have at most one operand in brackets, otherwise assembler will give an error.

2.3. SIZE MISMATCH ERRORS

If we change the directive in the last example from DW to DB, the program will still assemble and debug without errors, however the results will not be the same as expected. When the first operand is read 0A05 will be read in the register which was actually two operands place in consecutive byte memory locations. The second number will be read as 000F which is the zero byte of num4 appended to the 15 of num3. The third number will be junk depending on the current state of the machine. According to our data declaration the third number should be at 0114 but it is accessed at 011D calculated with word offsets. This is a logical error of the program. To keep the declarations and their access synchronized is the responsibility of the programmer and not the assembler. The assembler allows the programmer to do everything he wants to do, and that can possibly run on the processor. The assembler only keeps us from writing illegal instructions which the processor cannot execute. This is the difference between a syntax error and a logic error. So the assembler and debugger have both done what we asked them to do but the programmer asked them to do the wrong chore.

The programmer is responsible for accessing the data as word if it was declared as a word and accessing it as a byte if it was declared as a byte. The word case is shown in lot of previous examples. If however the intent is to treat it as a byte the following code shows the appropriate way.

	Example 2.5					
001 002 003 004 005 006 007 008 009 010 011 012	; a program to add three numbers using byte variables [org 0x0100] mov al, [num1] ; load first number in al mov bl, [num1+1] ; load second number in bl add al, bl ; accumulate sum in al mov bl, [num1+2] ; load third number in bl add al, bl ; accumulate sum in al mov [num1+3], al ; store sum at num1+3 mov ax, 0x4c00 ; terminate program int 0x21 num1: db 5, 10, 15, 0					
003	The number is read in AL register which is a byte register since the memory location read is also of byte size.					
005	The second number is now placed at num1+1 instead of num1+2 because of byte offsets.					

To declare data db is used instead of dw so that each data declared occupies one byte only.

Inside the debugger we observe that the AL register takes appropriate values and the sum is calculated and stored in num1+3. This time there is no alignment or synchronization error. The key thing to understand here is that the processor does not match defines to accesses. It is the programmer's responsibility. In general assembly language gives a lot of power to the programmer but power comes with responsibility. Assembly language programming is not a difficult task but a responsible one.

In the above examples, the processor knew the size of the data movement operation from the size of the register involved, for example in "mov ax, [num1]" memory can be accessed as byte or as word, it has no hard and fast size, but the AX register tells that this operation has to be a word operation. Similarly in "mov al, [num1]" the AL register tells that this operation has to be a byte operation. However in "mov ax, bl" the AX register tells that the operation has to be a word operation while BL tells that this has to be a byte operation. The assembler will declare that this is an illegal instruction. A 5Kg bag cannot fit inside a 1Kg bag and according to Intel a 1Kg cannot also fit in a 5Kg bag. They must match in size. The instruction "mov [num1], [num2]" is illegal as previously discussed not because of data movement size but because memory to memory moves are not allowed at all.

The instruction "mov [num1], 5" is legal but there is no way for the processor to know the data movement size in this operation. The variable num1 can be treated as a byte or as a word and similarly 5 can be treated as a byte or as a word. Such instructions are declared ambiguous by the assembler. The assembler has no way to guess the intent of the programmer as it previously did using the size of the register involved but there is no register involved this time. And memory is a linear array and label is an address in it. There is no size associated with a label. Therefore to resolve its ambiguity we clearly tell our intent to the assembler in one of the following ways.

```
mov byte [num1], 5
mov word [num1], 5
```

2.4. REGISTER INDIRECT ADDRESSING

We have done very elementary data access till now. Assume that the numbers we had were 100 and not just three. This way of adding them will cost us 200 instructions. There must be some method to do a task repeatedly on data placed in consecutive memory cells. The key to this is the need for some register that can hold the address of data. So that we can change the address to access some other cell of memory using the same instruction. In direct addressing mode the memory cell accessed was fixed inside the instruction. There is another method in which the address can be placed in a register so that it can be changed. For the following example we will take 10 instead of 100 numbers but the algorithm is extensible to any size.

There are four registers in iAPX88 architecture that can hold address of data and they are BX, BP, SI, and DI. There are minute differences in their working which will be discussed later. For the current example, we will use the BX register and we will take just three numbers and extend the concept with more numbers in later examples.

	Example 2.6		
001 002 003 004 005	; a program to add [org 0x100]	three numbers us	ing indirect addressing
003	mov	bx, num1	; point bx to first number
004	mov	ax, [bx]	; load first number in ax
005	add	bx, 2	; advance bx to second number

```
006
                                            ; add second number to ax
                     add
                          ax, [bx]
                                              advance bx to third number
                     add
                          bx, 2
                          ax, [bx]
008
                                              add third number to ax
                     add
009
                     add
                          bx,
                              2
                                              advance bx to result
010
                                             ; store sum at num1+6
                          [bx], ax
                     mov
011
012
                     mov.
                          ax. 0x4c00
                                            ; terminate program
013
                          0x21
                     int
014
                          5, 10, 15, 0
        num1 ·
015
                     dw
003
        Observe that no square brackets around num1 are used this time.
        The address is loaded in bx and not the contents. Value of num1 is
        0005 and the address is 0117. So BX will now contain 0117.
004
        Brackets are now used around BX. In iapx88 architecture brackets
        can be used around BX, BP, SI, and DI only. In iapx386 more
        registers are allowed. The instruction will be read as "move into ax
        the contents of the memory location whose address is in bx." Now
        since bx contains the address of num1 the contents of num1 are
        transferred to the ax register. Without square brackets the meaning
        of the instruction would have been totally different.
005
        This instruction is changing the address. Since we have words not
        bytes, we add two to bx so that it points to the next word in memory.
        BX now contains 0119 the address of the second word in memory.
        This was the mechanism to change addresses that we needed.
```

Inside the debugger we observe that the first instruction is "mov bx, 011C." A constant is moved into BX. This is because we did not use the square brackets around "num1." The address of "num1" has moved to 011C because the code size has changed due to changed instructions. In the second instruction BX points to 011C and the value read in AX is 0005 which can be verified from the data window. After the addition BX points to 011E containing 000A, our next word, and so on. This way the BX register points to our words one after another and we can add them using the same instruction "mov ax, [bx]" without fixing the address of our data in the instructions. We can also subtract from BX to point to previous cells. The address to be accessed is now in total program control.

One thing that we needed in our problem to add hundred numbers was the capability to change address. The second thing we need is a way to repeat the same instruction and a way to know that the repetition is done a 100 times, a terminal condition for the repetition. For the task we are introducing two new instructions that you should read and understand as simple English language concepts. For simplicity only 10 numbers are added in this example. The algorithm is extensible to any size.

```
Example 2.7
001
         ; a program to add ten numbers % \left( 1\right) =\left( 1\right) ^{2}
002
         [org 0x0100]
003
                               bx, num1
                                                    ; point bx to first number
004
                         mov.
                               cx, 10
                                                      load count of numbers in cx
005
                               ax, 0
                                                    ; initialize sum to zero
                         mov
006
007
         11.
                         add
                               ax, [bx]
                                                    : add number to ax
008
                         add
                                                    ; advance bx to next number
                               bx, 2
                               cx, 1
                                                    ; numbers to be added reduced
010
                                                    ; if numbers remain add next
                         jnz
011
012
                              [total], ax
                                                    ; write back sum in memory
                         mov
013
014
                         mov
                               ax. 0x4c00
                                                    ; terminate program
016
017
         num1:
                               10, 20, 30, 40, 50, 10, 20, 30, 40, 50
```

018	total: dw 0
006	Labels can be used on code as well. Just like data labels they remember the address at which they are used. The assembler does not differentiate between code labels and data labels. The programmer is responsible for using a data label as data and a code label as code. The label 11 in this case is the address of the following instruction.
009	\ensuremath{SUB} is the counterpart to ADD with the same rules as that of the ADD instruction.
010	JNZ stands for "jump if not zero." NZ is the condition in this instruction. So the instruction is read as "jump to the location 11 if the zero flag is not set." And revisiting the zero flag definition "the zero flag is set if the last mathematical or logical operation has produced a zero in its destination." For example "mov ax, 0" will not set the zero flag as it is not a mathematical or logical instruction. However subtraction and addition will set it. Also it is set even when the destination is not a register. Now consider the subtraction immediately preceding it. If the CX register becomes zero as a result of this subtraction the zero flag will be set and the jump will be taken. And jump to 11, the processor needs to be told each and everything and the destination is an important part of every jump. Just like when we ask someone to go, we mention go to this market or that house. The processor is much more logical than us and needs the destination in every instruction that asks it to go somewhere. The processor will load 11 in the IP register and resume execution from there. The processor will blindly go to the label we mention even if it contains data and not code.

The CX register is used as a counter in this example, BX contains the changing address, while AX accumulates the result. We have formed a loop in assembly language that executes until its condition remains true. Inside the debugger we can observe that the subtract instruction clears the zero flag the first nine times and sets it on the tenth time. While the jump instruction moves execution to address 11 the first nine times and to the following line the tenth time. The jump instruction breaks program flow.

The JNZ instruction is from the program control group and is a conditional jump, meaning that if the condition NZ is true (ZF=0) it will jump to the address mentioned and otherwise it will progress to the next instruction. It is a selection between two paths. If the condition is true go right and otherwise go left. Or we can say if the weather is hot, go this way, and if it is cold, go this way. Conditional jump is the most important instruction, as it gives the processor decision making capability, so it must be given a careful thought. Some processors call it branch, probably a more logical name for it, however the functionality is same. Intel chose to name it "jump."

An important thing in the above example is that a register is used to reference memory so this form of access is called register indirect memory access. We used the BX register for it and the B in BX and BP stands for base therefore we call register indirect memory access using BX or BP, "based addressing." Similarly when SI or DI is used we name the method "indexed addressing." They have the same functionality, with minor differences because of which the two are called base and index. The differences will be explained later, however for the above example SI or DI could be used as well, but we would name it indexed addressing instead of based addressing.

2.5. REGISTER + OFFSET ADDRESSING

Direct addressing and indirect addressing using a single register are two basic forms of memory access. Another possibility is to use different combinations of direct and indirect references. In the above example we used BX to access different array elements which were placed consecutively in memory like an array. We can also place in BX only the array index and not the exact address and form the exact address when we are going to access the actual memory. This way the same register can be used for accessing different arrays and also the register can be used for index comparison like the following example does.

```
Example 2.8
        ; a program to add ten numbers using register + offset addressing
002
003
        [org 0x0100]
                           bx, 0
                                              ; initialize array index to zero
                      mov
                                              ; load count of numbers in cx
                      mov
                           cx, 10
005
006
                           ax, 0
                                              ; initialize sum to zero
                      mov
                           ax, [num1+bx]
                                             ; add number to ax
008
                      add
                                              ; advance bx to next index
                           bx,
                           cx, 1
                                              ; numbers to be added reduced
                      sub
010
                                              ; if numbers remain add next
                      jnz
011
012
                                              : write back sum in memory
                      mov
                           [total], ax
013
014
                           ax, 0x4c00
                                              ; terminate program
015
                      int.
                           0 \times 21
016
017
        num1:
                      dw
                           10, 20, 30, 40, 50, 10, 20, 30, 40, 50
018
003
        This time BX is initialized to zero instead of array base
007
        The format of memory access has changed. The array base is added
        to BX containing array index at the time of memory access.
008
        As the array is of words, BX jumps in steps of two, i.e. 0, 2, 4.
        Higher level languages do appropriate incrementing themselves and
        we always use sequential array indexes. However in assembly
        language we always calculate in bytes and therefore we need to take
        care of the size of one array element which in this case is two.
```

Inside the debugger we observe that the memory access instruction is shown as "mov ax, [011F+bx]" and the actual memory accessed is the one whose address is the sum of 011F and the value contained in the BX register. This form of access is of the register indirect family and is called base + offset or index + offset depending on whether BX or BP is used or SI or DI is used.

2.6. SEGMENT ASSOCIATION

All the addressing mechanisms in iAPX88 return a number called *effective* address. For example in base + offset addressing, neither the base nor the offset alone tells the desired cell in memory to be accessed. It is only after the addition is done that the processor knows which cell to be accessed. This number which came as the result of addition is called the effective address. But the effective address is just an offset and is meaningless without a segment. Only after the segment is known, we can form the physical address that is needed to access a memory cell.

We discussed the segmented memory model of iAPX88 in reasonable detail at the end of previous chapter. However during the discussion of addressing modes we have not seen the effect of segments. Segmentation is there and it's all happening relative to a segment base. We saw DS, CS, SS, and ES inside the debugger. Everything is relative to its segment base, even though we have not explicitly explained its functionality. An offset alone is not complete without a segment. As previously discussed there is a default segment associated to every register which accesses memory. For example CS is associated to IP by default; rather it is tied with it. It cannot access memory in any other segment.

In case of data, there is a bit relaxation and nothing is tied. Rather there is a default association which can be overridden. In the case of register indirect memory access, if the register used is one of SI, DI, or BX the default segment is DS. If however the register used in BP the default segment used is SS. The stack segment has a very critical and fine use and there is a reason why BP is attached to SS by default. However these will be discussed in detail in the chapter on stack. IP is tied to CS while SP is tied to SS. The association of these registers cannot be changed; they are locked with no option. Others are not locked and can be changed.

To override the association for one instruction of one of the registers BX, BP, SI or DI, we use the segment override prefix. For example "mov ax, [cs:bx]" associates BX with CS for this one instruction. For the next instruction the default association will come back to act. The processor places a special byte before the instruction called a prefix, just like prefixes and suffixes in English language. No prefix is needed or placed for default association. For example for CS the byte 2E is placed and for ES the byte 26 is placed. Opcode has not changed, but the prefix byte has modified the default association to association with the desired segment register for this one instruction.

In all our examples, we never declared a segment or used it explicitly, but everything seemed to work fine. The important thing to note is that CS, DS, SS, and ES all had the same value. The value itself is not important but the fact that all had the same value is important. All four segment windows exactly overlap. Whatever segment register we use the same physical memory will be accessed. That is why everything was working without the mention of a single segment register. This is the formation of COM files in IBM PC. A single segment contains code, data, and the stack. This format is operating system dependant, in our case defined by DOS. And our operating system defines the format of COM files such that all segments have the same value. Thus the only meaningful thing that remains is the offset.

For example if BX=0100, SI=0200, and CS=1000 and the memory access under consideration is [cs:bx+si+0x0700], the effective address formed is bx+si+0700 = 0100 + 0200 + 0700 = 0A00. Now multiplying the segment value by 16 makes it 10000 and adding the effective address 00A00 forms the physical address 10A00.

2.7. ADDRESS WRAPAROUND

There are two types of wraparounds. One is within a single segment and the other is inside the whole physical memory. Segment wraparound occurs when during the effective address calculation a carry is generated. This carry is dropped giving the effect that when we try to access beyond the segment limit, we are actually wrapped around to the first cell in the segment. For example if BX=9100, DS=1500 and the access is [bx+0x7000] we form the effective address 9100 + 7000 = 10100. The carry generated is dropped forming the actual effective address of 0100. Just like a circle when we reached the end we started again from the beginning. An arc at 370 degrees is the same as an arc at 10 degrees. We tried to cross the segment boundary and it pushed us back to the start. This is called segment wraparound. The physical address in the above example will be 15100.

The same can also happen at the time of physical address calculation. For example BX=0100, DS=FFF0 and the access under consideration is [bx+0x0100]. The effective address will be 0200 and the physical address will

be 100100. This is a 21bit answer and cannot be sent on the address bus which is 20 bits wide. The carry is dropped and just like the segment wraparound our physical memory has wrapped around at its very top. When we tried to access beyond limits the actual access is made at the very start. This second wraparound is a bit different in newer processor with more address lines but that will be explained in later chapters.

2.8. ADDRESSING MODES SUMMARY

The iAPX88 processor supports seven modes of memory access. Remember that immediate is not an addressing mode but an operand type. Operands can be immediate, register, or memory. If the operand is memory one of the seven addressing modes will be used to access it. The memory access mechanisms can also be written in the general form "base + index + offset" and we can define the possible addressing modes by saying that any one, two, or none can be skipped from the general form to form a legal memory access

There are a few common mistakes done in forming a valid memory access. Part of a register cannot be used to access memory. Like BX is allowed to hold an address but BL or BH are not. Address is 16bit and must be contained in a 16bit register. BX-SI is not possible. The only thing that we can do is addition of a base register with an index register. Any other operation is disallowed. BS+BP and SI+DI are both disallowed as we cannot have two base or two index registers in one memory access. One has to be a base register and the other has to be an index register and that is the reason of naming them differently.

Direct

A fixed offset is given in brackets and the memory at that offset is accessed. For example "mov [1234], ax" stores the contents of the AX registers in two bytes starting at address 1234 in the current data segment. The instruction "mov [1234], al" stores the contents of the AL register in the byte at offset 1234.

Based Register Indirect

A base register is used in brackets and the actual address accessed depends on the value contained in that register. For example "mov [bx], ax" moves the two byte contents of the AX register to the address contained in the BX register in the current data segment. The instruction "mov [bp], al" moves the one byte content of the AL register to the address contained in the BP register in the current stack segment.

Indexed Register Indirect

An index register is used in brackets and the actual address accessed depends on the value contained in that register. For example "mov [si], ax" moves the contents of the AX register to the word starting at address contained in SI in the current data segment. The instruction "mov [di], ax" moves the word contained in AX to the offset stored in DI in the current data segment.

Based Register Indirect + Offset

A base register is used with a constant offset in this addressing mode. The value contained in the base register is added with the constant offset to get the effective address. For example "mov [bx+300], ax" stores the word contained in AX at the offset attained by adding 300 to BX in the current data segment. The instruction "mov [bp+300], ax" stores the word in AX to the offset attained by adding 300 to BP in the current stack segment.

Indexed Register Indirect + Offset

An index register is used with a constant offset in this addressing mode. The value contained in the index register is added with the constant offset to get the effective address. For example "mov [si+300], ax" moves the word contained in AX to the offset attained by adding 300 to SI in the current data segment and the instruction "mov [di+300], al" moves the byte contained in AL to the offset attained by adding 300 to DI in the current data segment.

Base + Index

One base and one index register is used in this addressing mode. The value of the base register and the index register are added together to get the effective address. For example "mov [bx+si], ax" moves the word contained in the AX register to offset attained by adding BX and SI in the current data segment. The instruction "mov [bp+di], al" moves the byte contained in AL to the offset attained by adding BP and DI in the current stack segment. Observe that the default segment is based on the base register and not on the index register. This is why base registers and index registers are named separately. Other examples are "mov [bx+di], ax" and "mov [bp+si], ax." This method can be used to access a two dimensional array such that one dimension is in a base register and the other is in an index register.

Base + Index + Offset

This is the most complex addressing method and is relatively infrequently used. A base register, an index register, and a constant offset are all used in this addressing mode. The values of the base register, the index register, and the constant offset are all added together to get the effective address. For example "mov [bx+si+300], ax" moves the word contents of the AX register to the word in memory starting at offset attained by adding BX, SI, and 300 in the current data segment. Default segment association is again based on the base register. It might be used with the array base of a two dimensional array as the constant offset, one dimension in the base register and the other in the index register. This way all calculation of location of the desired element has been delegated to the processor.

EXERCISES

- 1. What is a label and how does the assembler differentiates between code labels and data labels?
- 2. List the seven addressing modes available in the 8088 architecture.
- 3. Differentiate between effective address and physical address.
- 4. What is the effective address generated by the following instructions? Every instruction is independent of others. Initially BX=0x0100, num1=0x1001, [num1]=0x0000, and SI=0x0100
 - a. mov ax, [bx+12]
 - b. mov ax, [bx+num1]
 - c. mov ax, [num1+bx]
 - d. mov ax, [bx+si]
- What is the effective address generated by the following combinations if they are valid. If not give reason. Initially BX=0x0100, SI=0x0010, DI=0x0001, BP=0x0200, and SP=0xFFFF
 - a. bx-si
 - b. bx-bp
 - c. bx+10 d. bx-10
 - e. bx+sn
 - f. bx+di
- Identify the problems in the following instructions and correct them by replacing them with one or two instruction having the same effect.

- a. mov [02], [22]
- b. mov [wordvar], 20
- c. mov bx, ald. mov ax, [si+di+100]
- What is the function of segment override prefix and what changes it brings to the opcode?
- What are the two types of address wraparound? What physical address is accessed with [BX+SI] if FFFF is loaded in BX, SI, and DS.
- 9. Write instructions to do the following.
 - a. Copy contents of memory location with offset 0025 in the current data segment into AX.
 - b. Copy AX into memory location with offset OFFF in the current data segment.
 - c. Move contents of memory location with offset 0010 to memory location with offset 002F in the current data segment.
- 10. Write a program to calculate the square of 20 by using a loop that adds 20 to the accumulator 20 times.

3 Branching

3.1. COMPARISON AND CONDITIONS

Conditional jump was introduced in the last chapter to loop for the addition of a fixed number of array elements. The jump was based on the zero flag. There are many other conditions possible in a program. For example an operand can be greater than another operand or it can be smaller. We use comparisons and boolean expressions extensively in higher level languages. They must be available is some form in assembly language, otherwise they could not possibly be made available in a higher level language. In fact they are available in a very fine and purified form.

The basic root instruction for all comparisons is CMP standing for compare. The operation of CMP is to subtract the source operand from the destination operand, updating the flags without changing either the source or the destination. CMP is one of the key instructions as it introduces the capability of conditional routing in the processor.

A closer thought reveals that with subtraction we can check many different conditions. For example if a larger number is subtracted from a smaller number a borrow is needed. The carry flag plays the role of borrow during the subtraction operation. And in this condition the carry flag will be set. If two equal numbers are subtracted the answer is zero and the zero flag will be set. Every significant relation between the destination and source is evident from the sign flag, carry flag, zero flag, and the overflow flag. CMP is meaningless without a conditional jump immediately following it.

Another important distinction at this point is the difference between signed and unsigned numbers. In unsigned numbers only the magnitude of the number is important, whereas in signed numbers both the magnitude and the sign are important. For example -2 is greater than -3 but 2 is smaller than 3. The sign has affected our comparisons.

Inside the computer signed numbers are represented in two's complement notation. In essence a number in this representation is still a number, just that now our interpretation of this number will be signed. Whether we use jump above and below or we use jump greater or less will convey our intention to the processor. The jump above and greater operations at first sight seem to be doing the same operation, and similarly below and less operations seem to be similar. However for signed numbers JG and JL will work properly and for unsigned JA and JB will work properly and not the other way around.

It is important to note that at the time of comparison, the intent of the programmer to treat the numbers as signed or unsigned is not clear. The subtraction in CMP is a normal subtraction. It is only after the comparison, during the conditional jump operation, that the intent is conveyed. At that time with a specific combination of flags checked the intent is satisfied.

For example a number 2 is represented in a word as 0002 while the number -2 is represented as FFFE. In a byte they would be represented as 02 and FE. Now both have the same magnitude however the different sign has caused very different representation in two's complement form. Now if the intent is to use FFFE or decimal 65534 then the same data would be placed in the word as in case of -2. In fact if -2 and 65534 are compared the processor will set the zero flag signaling that they are exactly equal. As regards an unsigned comparison the number 65534 is much greater than 2.

So if a JA is taken after comparing -2 in the destination with 2 in the source the jump will be taken. If however JG is used after the same comparison the jump will not be taken as it will consider the sign and with the sign -2 is smaller than 2. The key idea is that -2 and 65534 were both stored in memory in the same form. It was the interpretation that treated it as a signed or as an unsigned number.

The unsigned comparisons see the numbers as 0 being the smallest and 65535 being the largest with the order that $0 < 1 < 2 \dots < 65535$. The signed comparisons see the number -32768 which has the same memory representation as 32768 as the smallest number and 32767 as the largest with the order -32768 < -32767 < ... < -1 < 0 < 1 < 2 < ... < 32767. All the negative numbers have the same representation as an unsigned number in the range 32768 ... 65535 however the signed interpretation of the signed comparisons makes them be treated as negative numbers smaller than zero.

All meaningful situations both for signed and unsigned numbers than occur after a comparison are detailed in the following table.

	1	1
DEST = SRC	ZF = 1	When the source is subtracted from the destination and both are equal the result is zero and therefore the zero flag is set. This works for both signed and unsigned numbers.
UDEST < USRC	CF = 1	When an unsigned source is subtracted from an unsigned destination and the destination is smaller, a borrow is needed which sets the carry flag.
UDEST ≤ USRC	ZF = 1 OR CF = 1	If the zero flag is set, it means that the source and destination are equal and if the carry flag is set it means a borrow was needed in the subtraction and therefore the destination is smaller.
UDEST ≥ USRC	CF = 0	When an unsigned source is subtracted from an unsigned destination no borrow will be needed either when the operands are equal or when the destination is greater than the source.
UDEST > USRC	ZF = 0 AND CF = 0	The unsigned source and destination are not equal if the zero flag is not set and the destination is not smaller since no borrow was taken. Therefore the destination is greater than the source.
SDEST < SSRC	SF ≠ OF	When a signed source is subtracted from a signed destination and the answer is negative with no overflow than the destination is smaller than the source. If however there is an overflow meaning that the sign has changed unexpectedly, the meanings are reversed and a

		positive number signals that the destination is smaller.
SDEST ≤ SSRC	ZF = 1 OR SF ≠ OF	If the zero flag is set, it means that the source and destination are equal and if the sign and overflow flags differ it means that the destination is smaller as described above.
SDEST ≥ SSRC	SF = OF	When a signed source is subtracted from a signed destination and the answer is positive with no overflow than the destination is greater than the source. When an overflow is there signaling that sign has changed unexpectedly, we interpret a negative answer as the signal that the destination is greater.
SDEST > SSRC	ZF = 0 AND SF = OF	If the zero flag is not set, it means that the signed operands are not equal and if the sign and overflow match in addition to this it means that the destination is greater than the source.

3.2. CONDITIONAL JUMPS

For every interesting or meaningful situation of flags, a conditional jump is there. For example JZ and JNZ check the zero flag. If in a comparison both operands are same, the result of subtraction will be zero and the zero flag will be set. Thus JZ and JNZ can be used to test equality. That is why there are renamed versions JE and JNE read as jump if equal or jump if not equal. They seem more logical in writing but mean exactly the same thing with the same opcode. Many jumps are renamed with two or three names for the same jump, so that the appropriate logic can be conveyed in assembly language programs. This renaming is done by Intel and is a standard for iAPX88. JC and JNC test the carry flag. For example we may need to test whether there was an overflow in the last unsigned addition or subtraction. Carry flag will also be set if two unsigned numbers are subtracted and the first is smaller than the second. Therefore the renamed versions JB, JNAE, and JNB, JAE are there standing for jump if below, jump if not above or equal, jump if not below, and jump if above or equal respectively. The operation of all jumps can be seen from the following table.

JC JB JNAE	Jump if carry Jump if below Jump if not above or equal	CF = 1	This jump is taken if the last arithmetic operation generated a carry or required a borrow. After a CMP it is taken if the unsigned source is smaller than the unsigned destination.
JNC	Jump if not carry	CF = 0	This jump is taken if
JNB	Jump if not below		the last arithmetic
JAE	Jump if above or equal		operation did not

			generated a carry or required a borrow. After a CMP it is taken if the unsigned source is larger or equal to the unsigned destination.
JE JZ	Jump if equal Jump if zero	ZF = 1	This jump is taken if the last arithmetic operation produced a zero in its destination. After a CMP it is taken if both operands were equal.
JNE JNZ	Jump if not equal Jump if not zero	ZF = 0	This jump is taken if the last arithmetic operation did not produced a zero in its destination. After a CMP it is taken if both operands were different.
JA JNBE	Jump if above Jump if not below or equal	ZF = 0 AND CF = 0	This jump is taken after a CMP if the unsigned source is larger than the unsigned destination.
JNA JBE	Jump if not above Jump if not below or equal	ZF = 1 OR CF = 1	This jump is taken after a CMP if the unsigned source is smaller than or equal to the unsigned destination.
JL JNGE	Jump if less Jump if not greater or equal	SF ≠ OF	This jump is taken after a CMP if the signed source is smaller than the signed destination.
JNL JGE	Jump if not less Jump if greater or equal	SF = OF	This jump is taken after a CMP if the signed source is larger than or equal to the signed destination.
JG JNLE	Jump if greater Jump if not less or equal	ZF = 0 AND SF = OF	This jump is taken after a CMP if the signed source is larger than the signed destination.
JNG JLE	Jump if not greater Jump if less or equal	ZF = 1 OR SF≠OF	This jump is taken after a CMP if the signed source is smaller than or equal to the signed destination.

JO	Jump if overflow.	OF = 1	This jump is taken if the last arithmetic operation changed the sign unexpectedly.
JNO	Jump if not overflow	OF = 0	This jump is taken if the last arithmetic operation did not change the sign unexpectedly.
JS	Jump if sign	SF = 1	This jump is taken if the last arithmetic operation produced a negative number in its destination.
JNS	Jump if not sign	SF = 0	This jump is taken if the last arithmetic operation produced a positive number in its destination.
JP JPE	Jump if parity Jump if even parity	PF = 1	This jump is taken if the last arithmetic operation produced a number in its destination that has even parity.
JNP JPO	Jump if not parity Jump if odd parity	PF = 0	This jump is taken if the last arithmetic operation produced a number in its destination that has odd parity.
JCXZ	Jump if CX is zero	CX = 0	This jump is taken if the CX register is zero.

The CMP instruction sets the flags reflecting the relation of the destination to the source. This is important as when we say jump if above, then what is above what. The destination is above the source or the source is above the destination.

The JA and JB instructions are related to unsigned numbers. That is our interpretation for the destination and source operands is unsigned. The 16th bit holds data and not the sign. In the JL and JG instructions standing for jump if lower and jump if greater respectively, the interpretation is signed. The 16th bit holds the sign and not the data. The difference between them will be made clear as an elaborate example will be given to explain the difference.

One jump is special that it is not dependent on any flag. It is JCXZ, jump if the CS register is zero. This is because of the special treatment of the CX register as a counter. This jump is regardless of the zero flag. There is no counterpart or not form of this instruction.

The adding numbers example of the last chapter can be a little simplified using the compare instruction on the BX register and eliminating the need for a separate counter as below.

```
Example 3.1
001
        ; a program to add ten numbers without a separate counter
002
        [org 0x0100]
                                             ; initialize array index to zero
004
                                             ; initialize sum to zero
                      mov ax, 0
006
                          ax, [num1+bx]
                                             ; add number to ax
        11:
                      add
007
                          bx, 2
                                             ; advance bx to next index
                      add
                      cmp
                          bx, 20
                                             ; are we beyond the last index
009
                                             ; if not add next number
                          11
                      jne
010
011
                      mov.
                          [total], ax
                                            ; write back sum in memory
012
013
                          ax, 0x4c00
                                             ; terminate program
014
                      int
                          0 \times 21
015
016
        num1:
                          10, 20, 30, 40, 50, 10, 20, 30, 40, 50
017
        total.
                      dw
                          Ω
006
        The format of memory access is still base + offset.
008
        BX is used as the array index as well as the counter. The offset of
        11th number will be 20, so as soon as BX becomes 20 just after the
        10th number has been added, the addition is stopped.
009
        The jump is displayed as JNZ in the debugger even though we have
        written JNE in our example. This is because it is a renamed jump
        with the same opcode as JNZ and the debugger has no way of
        knowing the mnemonic that we used after looking just at the
        opcode. Also every code and data reference that we used till now is
        seen in the opcode as well. However for the jump instruction we see
        an operand of F2 in the opcode and not 0116. This will be discussed
        in detail with unconditional jumps. It is actually a short relative
        jump and the operand is stored in the form of positive or negative
        offset from this instruction.
```

With conditional branching in hand, there are just a few small things left in assembly language that fills some gaps. Now there is just imagination and the skill to conceive programs that can make you write any program.

3.3. UNCONDITIONAL JUMP

Till now we have been placing data at the end of code. There is no such restriction and we can define data anywhere in the code. Taking the previous example, if we place data at the start of code instead of at the end and we load our program in the debugger. We can see our data placed at the start but the debugger is intending to start execution at our data. The COM file definition said that the first executable instruction is at offset 0100 but we have placed data there instead of code. So the debugger will try to interpret that data as code and showed whatever it could make up out of those opcodes.

We introduce a new instruction called JMP. It is the unconditional jump that executes regardless of the state of all flags. So we write an unconditional jump as the very first instruction of our program and jump to the next instruction that follows our data declarations. This time 0100 contains a valid first instruction of our program.

```
007
008
                                                ; initialize array index to zero
         start:
009
010
                                                ; initialize sum to zero
011
                                                ; add number to ax
                            ax, [num1+bx]
012
                            bx,
                       add
                                                  advance bx to next index
                                                : are we beyond the last index
                       cmp
                            bx, 20
014
                                                ; if not add next number
                            11
                       jne
015
016
                                                ; write back sum in memory
                       mov.
                            [total], ax
017
                            ax, 0x4c00
                                                ; terminate program
019
                       int
                            0 \times 21
003
         JMP jumps over the data declarations to the start label and
         execution resumes from there.
```


3.4. RELATIVE ADDRESSING

Inside the debugger the instruction is shown as JMP 0119 and the location 0119 contains the original first instruction of the logic of our program. This jump is unconditional, it will always be taken. Now looking at the opcode we see F21600 where F2 is the opcode and 1600 is the operand to it. 1600 is 0016 in proper word order. 0119 is not given as a parameter rather 0016 is given.

This is position relative addressing in contrast to absolute addressing. It is not telling the exact address rather it is telling how much forward or backward to go from the current position of IP in the current code segment. So the instruction means to add 0016 to the IP register. At the time of execution of the first instruction at 0100 IP was pointing to the next instruction at 0103, so after adding 16 it became 0119, the desired target location. The mechanism is important to know, however all calculations in this mechanism are done by the assembler and by the processor. We just use a label with the JMP instruction and are ensured that the instruction at the target label will be the one to be executed.

3.5. TYPES OF JUMP

The three types of jump, near, short, and far, differ in the size of instruction and the range of memory they can jump to with the smallest short form of two bytes and a range of just 256 bytes to the far form of five bytes and a range covering the whole memory.



Near Jump

When the relative address stored with the instruction is in 16 bits as in the last example the jump is called a near jump. Using a near jump we can jump anywhere within a segment. If we add a large number it will wrap around to

the lower part. A negative number actually is a large number and works this way using the wraparound behavior.

Short Jump

If the offset is stored in a single byte as in 75F2 with the opcode 75 and operand F2, the jump is called a short jump. F2 is added to IP as a signed byte. If the byte is negative the complement is negated from IP otherwise the byte is added. Unconditional jumps can be short, near, and far. The far type is yet to be discussed. Conditional jumps can only be short. A short jump can go +127 bytes ahead in code and -128 bytes backwards and no more. This is the limitation of a byte in singed representation.

Far Jump

Far jump is not position relative but is absolute. Both segment and offset must be given to a far jump. The previous two jumps were used to jump within a segment. Sometimes we may need to go from one code segment to another, and near and short jumps cannot take us there. Far jump must be used and a two byte segment and a two byte offset are given to it. It loads CS wit the segment part and IP with the offset part. Execution therefore resumes from that location in physical memory. The three instructions that have a far form are JMP, CALL, and RET, are related to program control. Far capability makes intra segment control possible.

3.6. SORTING EXAMPLE

Moving ahead from our example of adding numbers we progress to a program that can sort a list of numbers using the tools that we have accumulated till now. Sorting can be ascending or descending like if the largest number comes at the top, followed by a smaller number and so on till the smallest number the sort will be called descending. The other order starting with the smallest number and ending at the largest is called ascending sort. This is a common problem and many algorithms have been developed to solve it. One simple algorithm is the bubble sort algorithm.

In this algorithm we compare consecutive numbers. If they are in required order e.g. if it is a descending sort and the first is larger then the second, then we leave them as it is and if they are not in order, we swap them. Then we do the same process for the next two numbers and so on till the last two are compared and possibly swapped.

A complete iteration is called a pass over the array. We need N passes at least in the simplest algorithm if N is the number of elements to be sorted. A finer algorithm is to check if any swap was done in this pass and stop as soon as a pass goes without a swap. The array is now sorted as every pair of elements is in order.

For example if our list of numbers is 60, 55, 45, and 58 and we want to sort them in ascending order, the first comparison will be of 60 and 55 and as the order will be reversed to 55 and 60. The next comparison will be of 60 and 45 and again the two will be swapped. The next comparison of 60 and 58 will also cause a swap. At the end of first pass the numbers will be in order of 55, 45, 58, and 60. Observe that the largest number has bubbled down to the bottom. Just like a bubble at bottom of water. In the next pass 55 and 45 will be swapped. 55 and 58 will not be swapped and 58 and 60 will also not be swapped. In the next pass there will be no swap as the elements are in order i.e. 45, 55, 58, and 60. The passes will be stopped as the last pass did not cause any swap. The application of bubble sort on these numbers is further explained with the following illustration.

ag

No more passes since swap flag is Off

```
Example 3.3
 001
                ; sorting a list of ten numbers using bubble sort
002
003
004
005
006
007
008
009
010
012
013
014
017
018
019
020
021
022
023
024
025
026
027
028
                [org 0x0100]
                                         jmp start
                data:
                                                  60, 55, 45, 50, 40, 35, 25, 30, 10, 0
                swap:
                                         db
                                        mov bx, 0 ; initialize array index to zero mov byte [swap], 0 ; rest swap flag to no swaps
                                        mov ax, [data+bx]
cmp ax, [data+bx+2]
jbe noswap
                                                                                ; load number in ax
; compare with next number
; no swap if already in order
                loop1:
                                                                                 ; load second element in dx
; store first number in second
; store second number in first
; flag that a swap has been done
                                        mov dx, [data+bx+2]
mov [data+bx+2], ax
mov [data+bx], dx
                                         mov byte [swap], 1
                                        add bx, 2
cmp bx, 18
                                                                                  ; advance bx to next index
; are we at last index
; if not compare next two
                noswap:
                                         jne loop1
                                                                                  ; check if a swap has been done ; if yes make another pass
                                         cmp byte [swap], 1
                                         jе
                                                bsort
                                         mov ax, 0x4c00
                                                                                   ; terminate program
                                         int 0x21
```

003	The jump instruction is placed to skip over data.
006	The swap flag can be stored in a register but as an example it is stored in memory and also to extend the concept at a later stage.
011-012	One element is read in AX and it is compared with the next element because memory to memory comparisons are not allowed.
013	If the JBE is changed to JB, not only the unnecessary swap on equal will be performed, there will be a major algorithmic flaw due to a logical error as in the case of equal elements the algorithm will never stop. JBE won't swap in the case of equal elements.
015-017	The swap is done using DX and AX registers in such a way that the values are crossed. The code uses the information that one of the elements is already in the AX register.
021	This time BX is compared with 18 instead of 20 even though the number of elements is same. This is because we pick an element and compare it with the next element. When we pick the 9th element we compare it with the next element and this is the last comparison, since if we pick the 10th element we will compare it with the 11th element and there is no 11th element in our case.
024-025	If a swap is done we repeat the whole process for possible more swaps.

Inside the debugger we observe that the JBE is changed to JNA due to the same reason as discussed for JNE and JNZ. The passes change the data in the same manner as we presented in our illustration above. If JBE in the code is changed to JAE the sort will change from ascending to descending. For signed numbers we can use JLE and JGE respectively for ascending and descending sort.

To clarify the difference of signed and unsigned jumps we change the data array in the last program to include some negative numbers as well. When JBE will be used on this data, i.e. with unsigned interpretation of the data and an ascending sort, the negative numbers will come at the end after the largest positive number. However JLE will bring the negative numbers at the very start of the list to bring them in proper ascending order according to a signed interpretation, even though they are large in magnitude. The data used is shown as below.

```
data: dw 60, 55, 45, 50, -40, -35, 25, 30, 10, 0
```

This data includes some signed numbers as well. The JBE instruction will treat this data as an unsigned number and will cater only for the magnitude ignoring the sign. If the program is loaded in the debugger, the numbers will appear in their hexadecimal equivalent. The two numbers -40 and -35 are especially important as they are represented as FFD8 and FFDD. This data is not telling whether it is signed or unsigned. Our interpretation will decide whether it is a very large unsigned number or a signed number in two's complement form.

If the sorting algorithm is applied on the above data with JBE as the comparison instruction to sort in ascending order with unsigned interpretation, observe the comparisons of the two numbers FFD8 and FFDD. For example it will decide that FFDD > FFD8 since the first is larger in magnitude. At the end of sorting FFDD will be at the end of the list being declared the largest number and FFD8 will precede it to be the second largest.

If however the comparison instruction is changed to JLE and sorting is done on the same data it works similarly except on the two numbers FFDD and FFD8. This time JLE declares them to be smaller than every other number and also declares FFDD < FFD8. At the end of sorting, FFDD is

declared to be the smallest number followed by FFD8 and then 0000. This is in contrast to the last example where JBE was used. This happened because JLE interpreted our data as signed numbers, and as a signed number FFDD has its sign bit on signaling that it is a negative number in two's complement form which is smaller than 0000 and every positive number. However JBE did not give any significance to the sign bit and included it in the magnitude. Therefore it declared the negative numbers to be the largest numbers.

If the required interpretation was of signed numbers the result produced by JLE is correct and if the required interpretation was of unsigned numbers the result produced by JBE is correct. This is the very difference between signed and unsigned integers in higher level languages, where the compiler takes the responsibility of making the appropriate jump depending on the type of integer used. But it is only at this level that we can understand the actual mechanism going on. In assembly language, use of proper jump is the responsibility of the programmer, to convey the intentions to use the data as signed or as unsigned.

The remaining possibilities of signed descending sort and unsigned descending sort can be done on the same lines and are left as an exercise. Other conditional jumps work in the same manner and can be studied from the reference at the end. Several will be discussed in more detail when they are used in subsequent chapters.

EXERCISES

- 1. Which registers are changed by the CMP instruction?
- 2. What are the different types of jumps available? Describe position relative addressing.
- 3. If AX=8FFF and BX=0FFF and "cmp ax, bx" is executed, which of the following jumps will be taken? Each part is independent of others. Also give the value of Z, S, and C flags.
 - a. jg greater
 - b. il smaller
 - c. ja above
 - d. jb below
- 4. Write a program to find the maximum number and the minimum number from an array of ten numbers.
- 5. Write a program to search a particular element from an array using binary search. If the element is found set AX to one and otherwise to zero.
- Write a program to calculate the factorial of a number where factorial is defined as:

```
factorial(x) = x*(x-1)*(x-2)*...*1 factorial(0) = 1
```

Bit Manipulations

4.1. MULTIPLICATION ALGORITHM

With the important capability of decision making in our repertoire we move on to the discussion of an algorithm, which will help us uncover an important set of instructions in our processor used for bit manipulations.

Multiplication is a common process that we use, and we were trained to do in early schooling. Remember multiplying by a digit and then putting a cross and then multiplying with the next digit and putting two crosses and so on and summing the intermediate results in the end. Very familiar process but we never saw the process as an algorithm, and we need to see it as an algorithm to convey it to the processor.

To highlight the important thing in the algorithm we revise it on two 4bit binary numbers. The numbers are 1101 i.e. 13 and 0101 i.e. 5. The answer should be 65 or in binary 01000001. Observe that the answer is twice as long as the multiplier and the multiplicand. The multiplication is shown in the following figure.

```
1101 = 13

0101 = 5

-----

1101

0000x

1101xx

0000xxx

-----

01000001 = 65
```

We take the first digit of the multiplier and multiply it with the multiplicand. As the digit is one the answer is the multiplicand itself. So we place the multiplicand below the bar. Before multiplying with the next digit a cross is placed at the right most place on the next line and the result is placed shifted one digit left. However since the digit is zero, the result is zero. Next digit is one, multiplying with which, the answer is 1101. We put two crosses on the next line at the right most positions and place the result there shifted two places to the left. The fourth digit is zero, so the answer 0000 is placed with three crosses to its right.

Observe the beauty of binary base, as no real multiplication is needed at the digit level. If the digit is 0 the answer is 0 and if the digit is 1 the answer is the multiplicand itself. Also observe that for every next digit in the multiplier the answer is written shifted one more place to the left. No shifting for the first digit, once for the second, twice for the third and thrice for the fourth one. Adding all the intermediate answers the result is 01000001=65 as desired. Crosses are treated as zero in this addition.

Before formulating the algorithm for this problem, we need some more instructions that can shift a number so that we use this instruction for our multiplicand shifting and also some way to check the bits of the multiplier one by one.


4.2. SHIFTING AND ROTATIONS

The set of shifting and rotation instructions is one of the most useful set in any processor's instruction set. They simplify really complex tasks to a very

neat and concise algorithm. The following shifting and rotation operations are available in our processor.

Shift Logical Right (SHR)


The shift logical right operation inserts a zero from the left and moves every bit one position to the right and copies the rightmost bit in the carry flag. Imagine that there is a pipe filled to capacity with eight balls. The pipe is open from both ends and there is a basket at the right end to hold anything dropping from there. The operation of shift logical right is to force a white ball from the left end. The operation is depicted in the following illustration.



White balls represent zero bits while black balls represent one bits. Sixteen bit shifting is done the same way with a pipe of double capacity.

Shift Logical Left (SHL) / Shift Arithmetic Left (SAL)


The shift logical left operation is the exact opposite of shift logical right. In this operation the zero bit is inserted from the right and every bit moves one position to its left with the most significant bit dropping into the carry flag. Shift arithmetic left is just another name for shift logical left. The operation is again exemplified with the following illustration of ball and pipes.



Shift Arithmetic Right (SAR)

A signed number holds the sign in its most significant bit. If this bit was one a logical right shifting will change the sign of this number because of insertion of a zero from the left. The sign of a signed number should not change because of shifting.


The operation of shift arithmetic right is therefore to shift every bit one place to the right with a copy of the most significant bit left at the most significant place. The bit dropped from the right is caught in the carry basket. The sign bit is retained in this operation. The operation is further illustrated below.



The left shifting operation is basically multiplication by 2 while the right shifting operation is division by two. However for signed numbers division by two can be accomplished by using shift arithmetic right and not shift logical right. The left shift operation is equivalent to multiplication except when an important bit is dropped from the left. The overflow flag will signal this condition if it occurs and can be checked with JO. For division by 2 of a signed number logical right shifting will give a wrong answer for a negative number as the zero inserted from the left will change its sign. To retain the sign flag and still effectively divide by two the shift arithmetic right instruction must be used on signed numbers.


Rotate Right (ROR)

In the rotate right operation every bit moves one position to the right and the bit dropped from the right is inserted at the left. This bit is also copied into the carry flag. The operation can be understood by imagining that the pipe used for shifting has been molded such that both ends coincide. Now when the first ball is forced to move forward, every ball moves one step forward with the last ball entering the pipe from its other end occupying the first ball's old position. The carry basket takes a snapshot of this ball leaving one end of the pipe and entering from the other.



Rotate Left (ROL)


In the operation of rotate left instruction, the most significant bit is copied to the carry flag and is inserted from the right, causing every bit to move one position to the left. It is the reverse of the rotate right instruction. Rotation can be of eight or sixteen bits. The following illustration will make the concept clear using the same pipe and balls example.



Rotate Through Carry Right (RCR)


In the rotate through carry right instruction, the carry flag is inserted from the left, every bit moves one position to the right, and the right most bit is dropped in the carry flag. Effectively this is a nine bit or a seventeen bit rotation instead of the eight or sixteen bit rotation as in the case of simple rotations.

Imagine the circular molded pipe as used in the simple rotations but this time the carry position is part of the circle between the two ends of the pipe. Pushing the carry ball from the left causes every ball to move one step to its right and the right most bit occupying the carry place. The idea is further illustrated below.



Rotate Through Carry Left (RCL)

The exact opposite of rotate through carry right instruction is the rotate through carry left instruction. In its operation the carry flag is inserted from the right causing every bit to move one location to its left and the most significant bit occupying the carry flag. The concept is illustrated below in the same manner as in the last example.



4.3. MULTIPLICATION IN ASSEMBLY LANGUAGE

In the multiplication algorithm discussed above we revised the way we multiplied number in lower classes, and gave an example of that method on binary numbers. We make a simple modification to the traditional algorithm before we proceed to formulate it in assembly language.

In the traditional algorithm we calculate all intermediate answers and then sum them to get the final answer. If we add every intermediate answer to accumulate the result, the result will be same in the end, except that we do not have to remember a lot of intermediate answers during the whole multiplication. The multiplication with the new algorithm is shown below.

We try to identify steps of our algorithm. First we set the result to zero. Then we check the right most bit of multiplier. If it is one add the multiplicand to the result, and if it is zero perform no addition. Left shift the multiplicand before the next bit of multiplier is tested. The left shifting of the multiplicand is performed regardless of the value of the multiplier's right most bit. Just like the crosses in traditional multiplication are always placed to mark the ones, tens, thousands, etc. places. Then check the next bit and if it is one add the shifted value of the multiplicand to the result. Repeat for as many digits as there are in the multiplier, 4 in our example. Formulating the steps of the algorithm we get:

- Shift the multiplier to the right.
- If CF=1 add the multiplicand to the result.
- Shift the multiplicand to the right.
- Repeat the algorithm 4 times.

For an 8bit multiplication the algorithm will be repeated 8 times and for a sixteen bit multiplication it will be repeated 16 times, whatever the size of the multiplier is.

The algorithm uses the fact that shifting right forces the right most bit to drop in the carry flag. If we test the carry flag using JC we are effectively testing the right most bit of the multiplier. Another shifting will cause the next bit to drop in the next iteration and so on. So our task of checking bits one by one is satisfied using the shift operation. There are many other methods to do this bit testing as well, however we exemplify one of the methods in this example.

In the first iteration there is no shifting just like there is no cross in traditional multiplication in the first pass. Therefore we placed the left shifting of the multiplicand after the addition step. However the right shifting of multiplier must be before the addition as the addition step's execution depends upon its result.

We introduce an assembly language program to perform this 4bit multiplication. The algorithm is extensible to more bits but there are a few complications, which are left to be discussed later. For now we do a 4bit multiplication to keep the algorithm simple.

07 08	result:	db	0	; 8bit result
09	start:	mov	cl, 4	; initialize bit count to four
10		mov		; load multiplicand in bl
11		mov	dl, [multiplier]	; load multiplier in dl
12				
13	checkbit:		dl, 1	; move right most bit in carry
14 15		jnc	skip	; skip addition if bit is zero
16		add	[result], bl	; accumulate result
17		auu	[resure], br	, accumurace resurt
18	skip:	shl	bl, 1	; shift multiplicand left
19	•	dec	cl	; decrement bit count
20		jnz	checkbit	; repeat if bits left
21				
22			ax, 0x4c00	; terminate program
23		int	0x21	
07	fit in a byte we have used 4bit multiplication as our first example. Since addition by zero means nothing we skip the addition step if			
18	The multiplicand is left shifted in every iteration regardless of the multiplier bit.			
19	multiplier bit. DEC is a new instruction but its operation should be immediately understandable with the knowledge gained till now. It simply subtracts one from its single operand.			
20	The JNZ ins the multiplie		_	sorithm to repeat till any bits of

Inside the debugger observe the working of the SHR and SHL instructions. The SHR instruction is effectively dividing its operand by two and the remainder is stored in the carry flag from where we test it. The SHL instruction is multiplying its operand by two so that it is added at one place more towards the left in the result.

4.4. EXTENDED OPERATIONS

We performed a 4bit multiplication to explain the algorithm however the real advantage of the computer is when we ask it to multiply large numbers. Numbers whose multiplication takes real time. If we have an 8bit number we can do the multiplication in word registers, but are we limited to word operations? What if we want to multiply 32bit or even larger numbers? We are certainly not limited. Assembly language only provides us the basic building blocks. We build a plaza out of these blocks, or a building, or a classic piece of architecture is only dependant upon our imagination. With our logic we can extend these algorithms as much as we want.

Our next example will be multiplication of 16bit numbers to produce a 32bit answer. However for a 32bit answer we need a way to shift a 32bit number and a way to add 32bit numbers. We cannot depend on 16bit shifting as we have 16 significant bits in our multiplicand and shifting any bit towards the left may drop a valuable bit causing a totally wrong result. A valuable bit means any bit that is one. Dropping a zero bit doesn't cause any difference. So we place the 16it number in 32bit space with the upper 16 bits zeroed so that the sixteen shift operations don't cause any valuable bit to drop. Even though the numbers were 16bit we need 32bit operations to multiply correctly.

To clarify this necessity, we take example of a number 40000 or 9C40 in hexadecimal. In binary it is represented as 1001110001000000. To multiply

by two we shift it one place to the left. The answer we get is 0011100010000000 and the left most one is dropped in the carry flag. The answer should be the 17bit number 0x13880 but it is 0x3880, which is 14464 in decimal instead of the expected 80000. We should be careful of this situation whenever shifting is used.


Extended Shifting

Using our basic shifting and rotation instructions we can effectively shift a 32bit number in memory word by word. We cannot shift the whole number at once since our architecture is limited to word operations. The algorithm we use consists of just two instructions and we name it extended shifting.

The DD directive reserves a 32bit space in memory, however the value we placed there will fit in 16bits. So we can safely shift the number left 16 times. The least significant word is accessible at num1 and the most significant word is accessible at num1+2.

The two instructions are carefully crafted such that the first one shifts the lower word towards the left and the most significant bit of that word is dropped in carry. With the next instruction we push that dropped bit into the least significant bit of the next word effectively joining the two 16bit words. The final carry after the second instruction will be the most significant bit of the higher word, which for this number will always be zero.

The following illustration will clarify the concept. The pipe on the right contains the lower half and the pipe on the left contains the upper half. The first instruction forced a zero from the right into the lower half and the left most bit is saved in carry, and from there it is pushed into the upper half and the upper half is shifted as well.



For shifting right the exact opposite is done however care must be taken to shift right the upper half first and then rotate through carry right the lower half for obvious reasons. The instructions to do this are.

The same logic has worked. The shift placed the least significant bit of the upper half in the carry flag and it was pushed from right into the lower half. For a singed shift we would have used the shift arithmetic right instruction instead of the shift logical right instruction.

The extension we have done is not limited to 32bits. We can shift a number of any size say 1024 bits. The second instruction will be repeated a number of times and we can achieve the desired effect. Using two simple instructions we have increased the capability of the operation to effectively an unlimited number of bits. The actual limit is the available memory as even the segment limit can be catered with a little thought.

Extended Addition and Subtraction

We also needed 32bit addition for multiplication of 16bit numbers. The idea of extension is same here. However we need to introduce a new instruction at this place. The instruction is ADC or "add with carry." Normal addition has two operands and the second operand is added to the first

operand. However ADC has three operands. The third implied operand is the carry flag. The ADC instruction is specifically placed for extending the capability of ADD. Numbers of any size can be added using a proper combination of ADD and ADC. All basic building blocks are provided for the assembly language programmer, and the programmer can extend its capabilities as much as needed by using these fine instructions in appropriate combinations.

Further clarifying the operation of ADC, consider an instruction "ADC AX, BX." Normal addition would have just added BX to AX, however ADC first adds the carry flag to AX and then adds BX to AX. Therefore the last carry is also included in the result.

The algorithm should be apparent by now. The lower halves of the two numbers to be added are firsted added with a normal addition. For the upper halves a normal addition would lose track of a possible carry from the lower halves and the answer would be wrong. If a carry was generated it should go to the upper half. Therefore the upper halves are added with an addition with carry instruction.

Since one operand must be in register, ax is used to read the lower and upper halves of the source one by one. The destination is directly updated. The set of instructions goes here.

To further extend it more addition with carries will be used. However the carry from last addition will be wasted as there will always be a size limit where the results and the numbers are stored. This carry will remain in the carry flag to be tested for a possible overflow.

For subtraction the same logic will be used and just like addition with carry there is an instruction to subtract with borrow called SBB. Borrow in the name means the carry flag and is used just for clarity. Or we can say that the carry flag holds the carry for addition instructions and the borrow for subtraction instructions. Also the carry is generated at the 17th bit and the borrow is also taken from the 17th bit. Also there is no single instruction that needs borrow and carry in their independent meanings at the same time. Therefore it is logical to use the same flag for both tasks.

We extend subtraction with a very similar algorithm. The lower halves must be subtracted normally while the upper halves must be subtracted with a subtract with borrow instruction so that if the lower halves needed a borrow, a one is subtracted from the upper halves. The algorithm is as under.

Extended Multiplication

We use extended shifting and extended addition to formulate our algorithm to do extended multiplication. The multiplier is still stored in 16bits since we only need to check its bits one by one. The multiplicand however cannot be stored in 16bits otherwise on left shifting its significant bits might get lost. Therefore it has to be stored in 32bits and the shifting and addition used to accumulate the result must be 32bits as well.

```
; 16bit multiplication
02
         [org 0x0100]
03
                            start
04
05
        multiplicand: dd
                            1300
                                                ; 16bit multiplicand 32bit space
06
07
                            500
        multiplier:
                                                ; 16bit multiplier
        result.
                       dd
                                                : 32hit result
08
09
                            cl, 16
                                                ; initialize bit count to 16
                       mov
                            dx, [multiplier]
10
                       mov
                                               ; load multiplier in dx
11
                            dx, 1
12
        checkbit:
                                                ; move right most bit in carry
                       shr
13
                       jnc
                            skip
                                                ; skip addition if bit is zero
14
15
                            ax, [multiplicand]
16
17
                            [result], ax ; add less significant word
ax, [multiplicand+2]
                       add
                       mov
18
                            [result+2], ax
                                               ; add more significant word
19
20
        skip:
                            word [multiplicand], 1
                       shl
21
22
                            word [multiplicand+2], 1; shift multiplicand left
                       rcl
                                               ; decrement bit count
                       dec
                            c1
23
                                                ; repeat if bits left
                            checkbit
                       inz
24
25
                       mov
                            ax, 0x4c00
                                                ; terminate program
26
                            0x21
                       int
05-07
        The multiplicand and the multiplier are stored in 32bit space while
         the multiplier is stored as a word.
10
        The multiplier is loaded in DX where it will be shifted bit by bit. It
         can be directly shifted in memory as well.
15 - 18
        The multiplicand is added to the result using extended 32bit
        addition.
20-21
        The multiplicand is shifted left as a 32bit number using extended
        shifting operation.
```

The multiplicand will occupy the space from 0103-0106, the multiplier will occupy space from 0107-0108 and the result will occupy the space from 0109-010C. Inside the debugger observe the changes in these memory locations during the course of the algorithm. The extended shifting and addition operations provide the same effect as would be provided if there were 32bit addition and shifting operations available in the instruction set.

At the end of the algorithm the result memory locations contain the value 0009EB10 which is 65000 in decimal; the desired answer. Also observe that the number 00000514 which is 1300 in decimal, our multiplicand, has become 05140000 after being left shifted 16 times. Our extended shifting has given the same result as if a 32bit number is left shifted 16 times as a unit.

There are many other important applications of the shifting and rotation operations in addition to this example of the multiplication algorithm. More examples will come in coming chapters.

4.5. BITWISE LOGICAL OPERATIONS

The 8088 processor provides us with a few logical operations that operate at the bit level. The logical operations are the same as discussed in computer logic design; however our perspective will be a little different. The four basic operations are AND, OR, XOR, and NOT.

The important thing about these operations is that they are bitwise. This means that if "and ax, bx" instruction is given, then the operation of AND is applied on corresponding bits of AX and BX. There are 16 AND operations as a result; one for every bit of AX. Bit 0 of AX will be set if both its original value and Bit 0 of BX are set, bit 1 will be set if both its original value and Bit 1 of BX are set, and so on for the remaining bits. These operations are conducted in parallel on the sixteen bits. Similarly the operations of other logical operations are bitwise as well.

AND operation

AND performs the logical bitwise and of the two operands (byte or word) and returns the result to the destination operand. A bit in the result is set if both corresponding bits of the original operands are set; otherwise the bit is cleared as shown in the truth table. Examples are "and ax, bx" and "and byte [mem], 5." All possibilities that are legal for addition are also legal for the significant of the sign

X	Y	X and Y
0	0	0
0	1	0
1	0	0
1	1	1

possibilities that are legal for addition are also legal for the AND operation.

The different thing is the bitwise behavior of this operation.

OR operation

OR performs the logical bitwise "inclusive or" of the two operands (byte or word) and returns the result to the destination operand. A bit in the result is set if either or both corresponding bits in the original operands are set otherwise the result bit is cleared as shown in the truth table. Examples are "or ax, bx" and "or byte [mem], 5."

X	Y	X or Y
0	0	0
0	1	1
1	0	1
1	1	1

XOR operation

XOR (Exclusive Or) performs the logical bitwise "exclusive or" of the two operands and returns the result to the destination operand. A bit in the result is set if the corresponding bits of the original operands contain opposite values (one is set, the other is cleared) otherwise the result bit is cleared as shown in the truth table. XOR

X	Y	X xor Y
0	0	0
0	1	1
1	0	1
1	1	0

is a very important operation due to the property that it is a reversible operation. It is used in many cryptography algorithms, image processing, and in drawing operations. Examples are "xor ax, bx" and "xor byte [mem], 5."

NOT operation

NOT inverts the bits (forms the one's complement) of the byte or word operand. Unlike the other logical operations, this is a single operand instruction, and is not purely a logical operation in the sense the others are, but it is still traditionally counted in the same set. Examples are "not ax" and "not byte [mem], 5."

4.6. MASKING OPERATIONS

Selective Bit Clearing

Another use of AND is to make selective bits zero in its destination operand. The source operand is loaded with a mask containing one at positions which are retain their old value and zero at positions which are to be zeroed. The effect of applying this operation on the destination with mask in the source is to clear the desired bits. This operation is called masking. For example if the lower nibble is to be cleared then the operation can be applied with F0 in the source. The upper nibble will retain its old value and the lower nibble will be cleared.

Selective Bit Setting

The operation can be used as a masking operation to set selective bits. The bits in the mask are cleared at positions which are to retain their values, and are set at positions which are to be set. For example to set the lower nibble of the destination operand, the operation should be applied with a mask of 0F in the source. The upper nibble will retain its value and the lower nibble will be set as a result.

Selective Bit Inversion

XOR can also be used as a masking operation to invert selective bits. The bits in the mask are cleared at positions, which are to retain their values, and are set at positions, which are to be inverted. For example to invert the lower nibble of the destination operand, the operand should be applied with a mask of OF in the source. The upper nibble will retain its value and the lower nibble will be set as a result. Compare this with NOT which inverts everything. XOR on the other hand allows inverting selective bits.

Selective Bit Testing

AND can be used to check whether particular bits of a number are set or not. Previously we used shifting and JC to test bits one by one. Now we introduce another way to test bits, which is more powerful in the sense that any bit can be tested anytime and not necessarily in order. AND can be applied on a destination with a 1-bit in the desired position and a source, which is to be checked. If the destination is zero as a result, which can be checked with a JZ instruction, the bit at the desired position in the source was clear.

However the AND operation destroys the destination mask, which might be needed later as well. Therefore Intel provided us with another instruction analogous to CMP, which is non-destructive subtraction. This is the TEST instruction and is a non-destructive AND operation. It doesn't change the destination and only sets the flags according to the AND operation. By checking the flags, we can see if the desired bit was set or cleared.

We change our multiplication algorithm to use selective bit testing instead of checking bits one by one using the shifting operations.

	Example 4.3				
01 02	; 16bit multiplication using test for bit testing [org 0x0100]				
03	(org onoroo)	jmp	start		
04					
05	multiplicand:		1300	; 16bit multiplicand 32bit space	
06	multiplier:	dw	500	; 16bit multiplier	
07	result:	dd	0	; 32bit result	
08					
09	start:		cl, 16	; initialize bit count to 16	
10		mov	bx, 1	; initialize bit mask	
11					
12	checkbit:		<pre>bx, [multiplier]</pre>		
13		jz	skip	; skip addition if bit is zero	
14					
15			ax, [multiplicand		
16			[result], ax		
17			ax, [multiplicand		
18		adc	[result+2], ax	; add more significant word	
19					
20	skip:		word [multiplican		
21				d+2], 1; shift multiplicand left	
22			bx, 1		
23 24		dec	checkbit	; decrement bit count	
25		Jnz	cneckbit	; repeat if bits left	
2.6			ax, 0x4c00	; terminate program	
27			0x21	; terminate program	
21		TIIL	UXZI		
12	The test inst	ructio	n is used for bit t	esting. BX holds the mask and in	
				a, as our concerned bit is now the	
		Taulo	ii it is simunig icit	, as our concerned bit is now the	
	next bit.				
22-24	We can do without counting in this example. We can stop as soon as				
	our mask in BX becomes zero. These are the small tricks that				
	assembly allows us to do and optimize our code as a result.				
	assembly and	JWS U	is to do and optim	ize our code as a result.	

Inside the debugger observe that both the memory location and the mask in BX do not change as a result of TEST instruction. Also observe how our mask is shifting towards the left so that the next TEST instruction tests the next bit. In the end we get the same result of 0009EB10 as in the previous example.

EXERCISES

- 1. Write a program to swap every pair of bits in the AX register.
- 2. Give the value of the AX register and the carry flag after each of the following instructions.

```
stc
mov ax, <your rollnumber>
adc ah, <first character of your name>
cmc
xor ah, al
mov cl, 4
shr al, cl
rcr ah, cl
```

- 3. Write a program to swap the nibbles in each byte of the AX register.
- Calculate the number of one bits in BX and complement an equal number of least significant bits in AX.
 HINT: Use the XOR instruction
- 5. Write a program to multiply two 32bit numbers and store the answer in a 64bit location.
- 6. Declare a 32byte buffer containing random data. Consider for this problem that the bits in these 32 bytes are numbered from 0 to 255. Declare another byte that contains the starting bit number. Write a program to copy the byte starting at this starting bit number in the AX register. Be careful that the starting bit number may not be a multiple of 8 and therefore the bits of the desired byte will be split into two bytes.
- 7. AX contains a number between 0-15. Write code to complement the corresponding bit in BX. For example if AX contains 6; complement the 6th bit of BX.
- 8. AX contains a non-zero number. Count the number of ones in it and store the result back in AX. Repeat the process on the result (AX) until AX contains one. Calculate in BX the number of iterations it took to make AX one. For example BX should contain 2 in the following case:

```
AX = 1100 0101 1010 0011 (input - 8 ones)
```

AX = 0000 0000 0000 1000 (after first iteration – 1 one)

AX = 0000 0000 0000 0001 (after second iteration - 1 one) STOP

5 Subroutines

5.1. PROGRAM FLOW

Till now we have accumulated the very basic tools of assembly language programming. A very important weapon in our arsenal is the conditional jump instruction. During the course of last two chapters we used these tools to write two very useful algorithms of sorting and multiplication. The multiplication algorithm is useful even though there is a MUL instruction in the 8088 instruction set, which can multiply 8bit and 16bit operands. This is because of the extensibility of our algorithm, as it is not limited to 16bits and can do 32bit or 64bit multiplication with minor changes.


Both of these algorithms will be used a number of times in any program of a reasonable size and complexity. An application does not only need to multiply at a single point in code; it multiplies at a number of places. If multiplication or sorting is needed at 100 places in code, copying it 100 times is a totally infeasible solution. Maintaining such a code is an impossible task.

The straightforward solution to this problem using the concepts we have acquainted till now is to write the code at one place with a label, and whenever we need to sort we jump to this label. But there is problem with this logic, and the problem is that after sorting is complete how the processor will know where to go back. The immediate answer is to jump back to a label following the jump to bubble sort. But we have jumped to bubble sort from 100 places in code. Which of the 100 positions in code should we jump back? Jump back at the first invocation, but jump has a single fixed target. How will the second invocation work? The second jump to bubble sort will never have control back at the next line.

Instruction are tied to one another forming an execution thread, just like a knitted thread where pieces of cotton of different sizes are twisted together to form a thread. This thread of execution is our program. The jump instruction breaks this thread permanently, making a permanent diversion, like a turn on a highway. The conditional jump selects one of the two possible directions, like right or left turn on a road. So there is no concept of returning.

However there are roundabouts on roads as well that take us back from where we started after having traveled on the boundary of the round. This is the concept of a temporary diversion. Two or more permanent diversions can take us back from where we started, just like two or more road turns can take us back to the starting point, but they are still permanent diversions in their nature.

We need some way to implement the concept of temporary diversion in assembly language. We want to create a roundabout of bubble sort, another roundabout of our multiplication algorithm, so that we can enter into the roundabout whenever we need it and return back to wherever we left from after completing the round.



Key point in the above discussion is returning to where we left from, like a loop in a knitted thread. Diversion should be temporary and not permanent. The code of bubble sort written at one place, multiply at another, and we temporarily divert to that place, thus avoiding a repetition of code at a 100 places.

CALL and RET

In every processor, instructions are available to divert temporarily and to divert permanently. The instructions for permanent diversion in 8088 are the jump instructions, while the instruction for temporary diversion is the CALL instruction. The word call must be familiar to the readers from subroutine call in higher level languages. The CALL instruction allows temporary diversion and therefore reusability of code. Now we can place the code for bubble sort at one place and reuse it again and again. This was not possible with permanent diversion. Actually the 8088 permanent diversion mechanism can be tricked to achieve temporary diversion. However it is not possible without getting into a lot of trouble. The key idea in doing it this way is to use the jump instruction form that takes a register as argument. Therefore this is not impossible but this is not the way it is done.

The natural way to do this is to use the CALL instruction followed by a label, just like JMP is followed by a label. Execution will divert to the code following the label. Till now the operation has been similar to the JMP instruction. When the subroutine completes we need to return. The RET instruction is used for this purpose. The word return holds in its meaning that we are to return from where we came and need no explicit destination. Therefore RET takes no arguments and transfers control back to the instruction following the CALL that took us in this subroutine. The actual technical process that informs RET where to return will be discussed later after we have discussed the system stack.

CALL takes a label as argument and execution starts from that label, until the RET instruction is encountered and it takes execution back to the instruction following the CALL. Both the instructions are commonly used as a pair, however technically they are independent in their operation. The RET works regardless of the CALL and the CALL works regardless of the RET. If you CALL a subroutine it will not complain if there is no RET present and similarly if you RET without being called it won't complain. It is a logical pair and is used as a pair in every decent code. However sometimes we play tricks with the processor and we use CALL or RET alone. This will become clear when we need to play such tricks in later chapters.

Parameters

We intend to write the bubble sort code at one place and CALL it whenever needed. An immediately visible problem is that whenever we call this subroutine it will sort the same array in the same order. However in a real application we will need to sort various arrays of various sizes. We might sometimes need an ascending sort and descending at other times. Similarly our data may be signed or unsigned. Such pieces of information that may change from invocation to invocation and should be passed from the caller to the subroutine are called parameters.

There must be some way of passing these parameters to the subroutine. Revising the subroutine temporary flow breakage mechanism, the most straightforward way is to use registers. The CALL mechanism breaks the thread of execution and does not change registers, except IP which must change for processor to start executing at another place, and SP whose change will be discussed in detail later. Any of the other registers can hold parameters for the subroutine.

5.2. OUR FIRST SUBROUTINE

Now we want to modify the bubble sort code so that it works as a subroutine. We place a label at the start of bubble sort code, which works as the anchor point and will be used in the CALL instruction to call the subroutine. We also place a RET at the end of the algorithm to return from where we called the subroutine.

	Example 5.1				
01		ble sort algorithm as a subroutine			
02	[org 0x0100]				
03		jmp	start		
04					
05	data:			40, 35, 25, 30, 10, 0	
06	swap:	db	0		
07					
08	bubblesort:			; last element not compared	
09		shl	cx, 1	; turn into byte count	
10					
11	mainloop:	mov	si, 0	; initialize array index to zero	
12		mov	byte [swap], 0	; reset swap flag to no swaps	
13					
14	innerloop:		ax, [bx+si]	; load number in ax	
15				; compare with next number	
16		jbe	noswap	; no swap if already in order	
17			1 11 1 1 101		
18 19				; load second element in dx	
20				; store first number in second	
20				; store second number in first	
22		mov	byte [swap], 1	; flag that a swap has been done	
23	noswap:	244	oi 2	; advance si to next index	
24	noswap.		si, cx	; are we at last index	
25			innerloop	; if not compare next two	
26		Jile	Innerroop	, II not compare next two	
27		cmn	hute [ewan] 1	; check if a swap has been done	
28			mainloop		
29		Je	шатптоор	, ii yes make another pass	
30		ret		; go back to where we came from	
31		100		, go back to where we came from	
32	start:	mov	hx. data	; send start of array in bx	
33				; send count of elements in cx	
34				; call our subroutine	
35				,	
36		mov	ax, 0x4c00	; terminate program	
37			0x21		
08-08				t of alaments in CV. Since it malres	

08-09 The routine has received the count of elements in CX. Since it makes one less comparison than the number of elements it decrements it. Then it multiplies it by two since this a word array and each element

takes two bytes. Left shifting has been used to multiply by two.

Base+index+offset addressing has been used. BX holds the start of array, SI the offset into it and an offset of 2 when the next element is to be read. BX can be directly changed but then a separate counter would be needed, as SI is directly compared with CX in our case.

The code starting from the start label is our main program analogous to the main in the C language. BX and CX hold our parameters for the bubblesort subroutine and the CALL is made to invoke the subroutine.

Inside the debugger we observe the same unsigned data that we are so used to now. The number 0103 is passed via BX to the subroutine which is the start of our data and the number 000A via CX which is the number of elements in our data. If we step over the CALL instruction we see our data sorted in a single step and we are at the termination instructions. The processor has jumped to the bubblesort routine, executed it to completion, and returned back from it but the process was hidden due to the step over command. If however we trace into the CALL instruction, we land at the first instruction of our routine. At the end of the routine, when the RET instruction is executed, we immediately land back to our termination instructions, to be precise the instruction following the CALL.

Also observe that with the CALL instruction SP is decremented by two from FFFE to FFFC, and the stack windows shows 0150 at its top. As the RET is executed SP is recovered and the 0150 is also removed from the stack. Match it with the address of the instruction following the CALL which is 0150 as well. The 0150 removed from the stack by the RET instruction has been loaded into the IP register thereby resuming execution from address 0150. CALL placed where to return on the stack for the RET instruction. The stack is automatically used with the CALL and RET instructions. Stack will be explained in detail later, however the idea is that the one who is departing stores the address to return at a known place. This is the place using which CALL and RET coordinate. How this placed is actually used by the CALL and RET instructions will be described after the stack is discussed.

After emphasizing reusability so much, it is time for another example which uses the same bubblesort routine on two different arrays of different sizes.

```
Example 5.2
           ; bubble sort subroutine called twice
           [org 0x0100]
02
03
                            imp start
04
                                   60, 55, 45, 50, 40, 35, 25, 30, 10, 0
328, 329, 898, 8923, 8293, 2345, 10, 877, 355, 98
888, 533, 2000, 1020, 30, 200, 761, 167, 90, 5
0.5
           data:
06
           data2:
                            dw
07
           swap:
08
                            dh
09
10
           bubblesort:
                                                           ; last element not compared
11
                                   cx, 1
                                                           ; turn into byte count
                            shl
12
13
           mainloop:
                                                           ; initialize array index to zero
14
15
                                   byte [swap], 0
                                                           ; reset swap flag to no swaps
16
17
18
19
                                  ax, [bx+si]
                                                           ; load number in ax
           innerloop:
                            mov
                                                           ; compare with next number
                                   ax, [bx+si+2]
                            jbe
                                  noswap
                                                           ; no swap if already in order
20
21
22
                                                           ; load second element in dx
                                   dx, [bx+si+2]
                            mov
                                   [bx+si], dx
[bx+si+2], ax
                                                           ; store first number in second ; store second number in first
                            mov
23
                                   byte [swap], 1
                                                           ; flag that a swap has been done
24
                                                           ; advance si to next index
          noswap:
                            add si, 2
```

26 27 28			i, cx nnerloop		are we at last index if not compare next two
29			yte [swap], 1 ainloop		check if a swap has been done if yes make another pass
31 32 33		ret		;	go back to where we came from
34 35 36	start:	mov cx		;	send start of array in bx send count of elements in cx call our subroutine
37 38		mov bx,	, data2	;	send start of array in bx
39 40 41		mov cx,	, 20 ubblesort		send count of elements in cx call our subroutine again
42 43		mov ax	x, 0x4c00 x21	;	terminate program
05-07	the other of 20 elements. The second array is declared on two lines, where the second line is continuation of the first. No additional label				
34-40	is needed since they are situated consecutively in memory. The other change is in the main where the bubblesort subroutine is called twice, once on the first array and once on the second.				

Inside the debugger observe that stepping over the first call, the first array is sorted and stepping over the second call the second array is sorted. If however we step in SP is decremented and the stack holds 0178 which is the address of the instruction following the call. The RET consumes that 0178 and restores SP. The next CALL places 0181 on the stack and SP is again decremented. The RET consumes this number and execution resumes from the instruction at 0181. This is the coordinated function of CALL and RET using the stack.

In both of the above examples, there is a shortcoming. The subroutine to sort the elements is destroying the registers AX, CX, DX, and SI. That means that the caller of this routine has to make sure that it does not hold any important data in these registers before calling this function, because after the call has returned the registers will be containing meaningless data for the caller. With a program containing thousands of subroutines expecting the caller to remember the set of modified registers for each subroutine is unrealistic and unreasonable. Also registers are limited in number, and restricting the caller on the use of register will make the caller's job very tough. This shortcoming will be removed using the very important system stack.

5.3. STACK

Stack is a data structure that behaves in a first in last out manner. It can contain many elements and there is only one way in and out of the container. When an element is inserted it sits on top of all other elements and when an element is removed the one sitting at top of all others is removed first. To visualize the structure consider a test tube and put some balls in it. The second ball will come above the first and the third will come above the second. When a ball is taken out only the one at the top can be removed. The operation of placing an element on top of the stack is called pushing the element and the operation of removing an element from the top of the stack is called popping the element. The last thing pushed is popped out first; the last in first out behavior.

We can peek at any ball inside the test tube but we cannot remove it without removing every ball on top of it. Similarly we can read any element from the stack but cannot remove it without removing everything above it. The stack operations of pushing and popping only work at the top of the

stack. This top of stack is contained in the SP register. The physical address of the stack is obtained by the SS:SP combination. The stack segment registers tells where the stack is located and the stack pointer marks the top of stack inside this segment.

Whenever an element is pushed on the stack SP is decremented by two as the 8088 stack works on word sized elements. Single bytes cannot be pushed or popped from the stack. Also it is a decrementing stack. Another possibility is an incrementing stack. A decrementing stack moves from higher addresses to lower addresses as elements are added in it while an incrementing stack moves from lower addresses to higher addresses as elements are added. There is no special reason or argument in favor of one or another, and more or less depends on the choice of the designers. Another processor 8051 by the same manufacturer has an incrementing stack while 8088 has a decrementing one.

Memory is like a shelf numbered as zero at the top and the maximum at the bottom. If a decrementing stack starts at shelf 5, the first item is placed in shelf 5, the next item is placed in shelf 4, the next in shelf 3 and so on. The operations of placing items on the stack and removing them from there are called push and pop. The push operation copies its operand on the stack, while the pop operation makes a copy from the top of the stack into its operand. When an item is pushed on a decrementing stack, the top of the stack is first decremented and the element is then copied into this space. With a pop the element at the top of the stack is copied into the pop operand and the top of stack is incremented afterwards.

The basic use of the stack is to save things and recover from there when needed. For example we discussed the shortcoming in our last example that it destroyed the caller's registers, and the callers are not supposed to remember which registers are destroyed by the thousand routines they use. Using the stack the subroutine can save the caller's value of the registers on the stack, and recover them from there before returning. Meanwhile the subroutine can freely use the registers. From the caller's point of view if the registers contain the same value before and after the call, it doesn't matter if the subroutine used them meanwhile.

Similarly during the CALL operation, the current value of the instruction pointer is automatically saved on the stack, and the destination of CALL is loaded in the instruction pointer. Execution therefore resumes from the destination of CALL. When the RET instruction is executed, it recovers the value of the instruction pointer from the stack. The next instruction executed is therefore the one following the CALL. Observe how playing with the instruction pointer affects the program flow.

There is a form of the RET instruction called "RET n" where n is a numeric argument. After performing the operation of RET, it further increments the stack pointer by this number, i.e. SP is first incremented by two and then by n. Its function will become clear when parameter passing is discussed.

Now we describe the operation of the stack in CALL and RET with an example. The top of stack stored in the stack pointer is initialized at 2000. The space above SP is considered empty and free. When the stack pointer is decremented by two, we took a word from the empty space and can use it for our purpose. The unit of stack operations is a word. Some instructions push multiple words; however byte pushes cannot be made. Now the value 017B is stored in the word reserved on the stack. The RET will copy this value in the instruction pointer and increment the stack pointer by two making it 2000 again, thereby reverting the operation of CALL.

This is how CALL and RET behave for near calls. There is also a far version of these functions when the target routine is in another segment. This version of CALL takes a segment offset pair just like the far jump instruction. The CALL will push both the segment and the offset on the stack in this case, followed by loading CS and IP with the values given in the instruction.

The corresponding instruction RETF will pop the offset in the instruction pointer followed by popping the segment in the code segment register.

Apart from CALL and RET, the operations that use the stack are PUSH and POP. Two other operations that will be discussed later are INT and IRET. Regarding the stack, the operation of PUSH is similar to CALL however with a register other than the instruction pointer. For example "push ax" will push the current value of the AX register on the stack. The operation of PUSH is shown below.

```
SP ← SP - 2
```

The operation of POP is the reverse of this. A copy of the element at the top of the stack is made in the operand, and the top of the stack is incremented afterwards. The operation of "pop ax" is shown below.

```
AX \leftarrow [SP]
SP \leftarrow SP + 2
```

Making corresponding PUSH and POP operations is the responsibility of the programmer. If "push ax" is followed by "pop dx" effectively copying the value of the AX register in the DX register, the processor won't complain. Whether this sequence is logically correct or not should be ensured by the programmer. For example when PUSH and POP are used to save and restore registers from the stack, order must be correct so that the saved value of AX is reloaded in the AX register and not any other register. For this the order of POP operations need to be the reverse of the order of PUSH operations.

Now we consider another example that is similar to the previous examples, however the code to swap the two elements has been extracted into another subroutine, so that the formation of stack can be observed during nested subroutine calls.

```
Example 5.3
01
02
          ; bubble sort subroutine using swap subroutine
          [org 0x0100]
03
                         jmp start
04
                              60, 55, 45, 50, 40, 35, 25, 30, 10, 0
328, 329, 898, 8923, 8293, 2345, 10, 877, 355, 98
0.5
         data:
06
         data2:
                         dw
07
08
                               888, 533, 2000, 1020, 30, 200, 761, 167, 90, 5
         swapflag:
                         db
09
10
                         mov ax, [bx+si]
                                                    ; load first number in ax
                                                    ; exchange with second number
11
12
                         xchg ax, [bx+si+2]
                               [bx+si], ax
                                                    ; store second number in first
                         mov
13
                                                    ; go back to where we came from
14
15
         bubblesort:
                                                    ; last element not compared
                         dec
                              CX
16
17
18
                                                    ; turn into byte count
                               si, 0
                                                    ; initialize array index to zero
         mainloop:
                         mov
19
20
21
                              byte [swapflag], 0 ; reset swap flag to no swaps
                         mov
                              ax, [bx+si]
                                                    ; load number in ax
         innerloop:
                         mov
22
                              ax, [bx+si+2]
                                                    ; compare with next number
                         cmp
23
24
                              noswap
                         jbe
                                                    ; no swap if already in order
25
                                                    ; swaps two elements
26
27
28
                              byte [swapflag], 1; flag that a swap has been done
                         mov
                                                    ; advance si to next index
         noswap:
29
30
                                                    ; are we at last index
                               si, cx
                         cmp
                         ine
                             innerloop
                                                    ; if not compare next two
31
32
33
                              byte [swapflag], 1 ; check if a swap has been done
                               mainloop
                                                    ; if yes make another pass ; go back to where we came from
34
                         ret
35
36
         start:
                         mov
                              bx, data
                                                    ; send start of array in bx
                              cx, 10
                                                    ; send count of elements in cx
```

```
call bubblesort
                                            ; call our subroutine
39
40
41
                     mov bx, data2
                                            ; send start of array in bx
                     mov cx, 20
                                            ; send count of elements in cx
42
                     call bubblesort
                                            ; call our subroutine again
43
                     mov ax. 0x4c00
                                            ; terminate program
44
45
11
        A new instruction XCHG has been introduced. The instruction
        swaps its source and its destination operands however at most one
        of the operands could be in memory, so the other has to be loaded in
        a register. The instruction has reduced the code size by one
13
        The RET at the end of swap makes it a subroutine.
```

Inside the debugger observe the use of stack by CALL and RET instructions, especially the nested CALL.

5.4. SAVING AND RESTORING REGISTERS

The subroutines we wrote till now have been destroying certain registers and our calling code has been carefully written to not use those registers. However this cannot be remembered for a good number of subroutines. Therefore our subroutines need to implement some mechanism of retaining the callers' value of any registers used.

The trick is to use the PUSH and POP operations and save the callers' value on the stack and recover it from there on return. Our swap subroutine destroyed the AX register while the bubblesort subroutine destroyed AX, CX, and SI. BX was not modified in the subroutine. It had the same value at entry and at exit; it was only used by the subroutine. Our next example improves on the previous version by saving and restoring any registers that it will modify using the PUSH and POP operations.

```
Example 5.4
          ; bubble sort and swap subroutines saving and restoring registers
02
          [org 0x0100]
03
                          jmp start
04
                                60, 55, 45, 50, 40, 35, 25, 30, 10, 0
328, 329, 898, 8923, 8293, 2345, 10, 877, 355, 98
888, 533, 2000, 1020, 30, 200, 761, 167, 90, 5
05
06
07
          data2:
                          dw
08
          swapflag:
09
10
          swap:
                          push ax
                                                       ; save old value of ax
11
                                                     ; load first number in ax
12
13
                          mov ax, [bx+si]
                          xchg ax, [bx+si+2]
                                                      ; exchange with second number
; store second number in first
14
                          mov [bx+si], ax
15
16
17
                          pop ax
                                                       ; restore old value of ax
                                                       ; go back to where we came from
                          ret
18
19
20
                                                      ; save old value of ax
          bubblesort:
                          push ax
                                                       ; save old value of cx
                          push cx
21
22
23
                                                       ; save old value of si
                                                       ; last element not compared
                          dec
                               CX
24
25
26
                                                       ; turn into byte count
          mainloop:
                                si, 0
                                                       ; initialize array index to zero
                          mov
27
28
                          mov byte [swapflag], 0 ; reset swap flag to no swaps
29
                          mov ax, [bx+si]
                                                       ; load number in ax
          innerloop:
30
                                ax, [bx+si+2]
                                                       ; compare with next number
                          cmp
                                noswap
31
                          jbe
                                                       ; no swap if already in order
32
```

```
call swap
                                                  ; swaps two elements
34
                             byte [swapflag], 1; flag that a swap has been done
35
36
                                                  ; advance si to next index
                        add si, 2
         noswap:
37
                              si, cx
                                                  ; are we at last index
                        cmp
38
39
40
                             innerloop
                                                  ; if not compare next two
                             byte [swapflag], 1 ; check if a swap has been done
                        cmp
41
42
43
                                                  ; if yes make another pass
                                                  ; restore old value of si
                        pop
44
45
46
                                                   ; restore old value of cx
                        pop
                              ax
                                                   ; restore old value of ax
                        pop
                                                  ; go back to where we came from
47
48
49
                                                 ; send start of array in bx
; send count of elements in cx
         start.
                        mov bx, data
                              cx, 10
                        mov
50
51
52
                        call bubblesort
                                                  ; call our subroutine
                             bx, data2
                                                  ; send start of array in bx
                        mov
53
54
55
                              cx, 20
                                                  ; send count of elements in cx
                        call bubblesort
                                                  ; call our subroutine again
56
57
                        mov ax, 0x4c00
                                                  ; terminate program
                        int
                             0 \times 21
19-21
         When multiple registers are pushed, order is very important. If AX,
         CX, and SI are pushed in this order, they must be popped in the
```

CX, and SI are pushed in this order, they must be popped in the reverse order of SI, CX, and AX. This is again because the stack behaves in a Last In First Out manner.

Inside the debugger we can observe that the registers before and after the CALL operation are exactly identical. Effectively the caller can assume the registers are untouched. By tracing into the subroutines we can observe how their value is saved on the stack by the PUSH instructions and recovered from their before exit. Saving and restoring registers this way in subroutines is a standard way and must be followed.

PUSH

PUSH decrements SP (the stack pointer) by two and then transfers a word from the source operand to the top of stack now pointed to by SP. PUSH often is used to place parameters on the stack before calling a procedure; more generally, it is the basic means of storing temporary data on the stack.

POP

POP transfers the word at the current top of stack (pointed to by SP) to the destination operand and then increments SP by two to point to the new top of stack. POP can be used to move temporary variables from the stack to registers or memory.

Observe that the operand of PUSH is called a source operand since the data is moving to the stack from the operand, while the operand of POP is called destination since data is moving from the stack to the operand.

CALL

CALL activates an out-of-line procedure, saving information on the stack to permit a RET (return) instruction in the procedure to transfer control back to the instruction following the CALL. For an intrasegment direct CALL, SP is decremented by two and IP is pushed onto the stack. The target procedure's relative displacement from the CALL instruction is then added to the instruction pointer. For an intersegment direct CALL, SP is decremented by two, and CS is pushed onto the stack. CS is replaced by the segment word contained in the instruction. SP again is decremented by two. IP is pushed onto the stack and replaced by the offset word in the instruction.

The out-of-line procedure is the temporary division, the concept of roundabout that we discussed. Near calls are also called intrasegment calls, while far calls are called intersegment calls. There are also versions that are called indirect calls; however they will be discuss later when they are used.

RFT

RET (Return) transfers control from a procedure back to the instruction following the CALL that activated the procedure. RET pops the word at the top of the stack (pointed to by register SP) into the instruction pointer and increments SP by two. If RETF (intersegment RET) is used the word at the top of the stack is popped into the IP register and SP is incremented by two. The word at the new top of stack is popped into the CS register, and SP is again incremented by two. If an optional pop value has been specified, RET adds that value to SP. This feature may be used to discard parameters pushed onto the stack before the execution of the CALL instruction.

5.5. PARAMETER PASSING THROUGH STACK

Due to the limited number of registers, parameter passing by registers is constrained in two ways. The maximum parameters a subroutine can receive are seven when all the general registers are used. Also, with the subroutines are themselves limited in their use of registers, and this limited increases when the subroutine has to make a nested call thereby using certain registers as its parameters. Due to this, parameter passing by registers is not expandable and generalizable. However this is the fastest mechanism available for passing parameters and is used where speed is important.

Considering stack as an alternate, we observe that whatever data is placed there, it stays there, and across function calls as well. For example the bubble sort subroutine needs an array address and the count of elements. If we place both of these on the stack, and call the subroutine afterwards, it will stay there. The subroutine is invoked with its return address on top of the stack and its parameters beneath it.

To access the arguments from the stack, the immediate idea that strikes is to pop them off the stack. And this is the only possibility using the given set of information. However the first thing popped off the stack would be the return address and not the arguments. This is because the arguments were first pushed on the stack and the subroutine was called afterwards. The arguments cannot be popped without first popping the return address. If a heaving thing falls on someone's leg, the heavy thing is removed first and the leg is not pulled out to reduce the damage. Same is the case with our parameters on which the return address has fallen.

To handle this using PUSH and POP, we must first pop the return address in a register, then pop the operands, and push the return address back on the stack so that RET will function normally. However so much effort doesn't seem to pay back the price. Processor designers should have provided a logical and neat way to perform this operation. They did provided a way and infact we will do this without introducing any new instruction.

Recall that the default segment association of the BP register is the stack segment and the reason for this association had been deferred for now. The reason is to peek inside the stack using the BP register and read the parameters without removing them and without touching the stack pointer. The stack pointer could not be used for this purpose, as it cannot be used in an effective address. It is automatically used as a pointer and cannot be explicitly used. Also the stack pointer is a dynamic pointer and sometimes changes without telling us in the background. It is just that whenever we touch it, it is where we expect it to be. The base pointer is provided as a replacement of the stack pointer so that we can peek inside the stack without modifying the structure of the stack.

When the bubble sort subroutine is called, the stack pointer is pointing to the return address. Two bytes below it is the second parameter and four bytes below is the first parameter. The stack pointer is a reference point to these parameters. If the value of SP is captured in BP, then the return address is located at [bp+0], the second parameter is at [bp+2], and the first parameter is at [bp+4]. This is because SP and BP both had the same value and they both defaulted to the same segment, the stack segment.

This copying of SP into BP is like taking a snapshot or like freezing the stack at that moment. Even if more pushes are made on the stack decrementing the stack pointer, our reference point will not change. The parameters will still be accessible at the same offsets from the base pointer. If however the stack pointer increments beyond the base pointer, the references will become invalid. The base pointer will act as the datum point to access our parameters. However we have destroyed the original value of BP in the process, and this will cause problems in nested calls where both the outer and the ineer subroutines need to access their own parameters. The outer subroutine will have its base pointer destroyed after the call and will be unable to access its parameters.

To solve both of these problems, we reach at the standard way of accessing parameters on the stack. The first two instructions of any subroutines accessing its parameters from the stack are given below.

```
push bp
mov bp, sp
```

As a result our datum point has shifted by a word. Now the old value of BP will be contained in [bp] and the return address will be at [bp+2]. The second parameters will be [bp+4] while the first one will be at [bp+6]. We give an example of bubble sort subroutine using this standard way of argument passing through stack.

```
Example 5.5
          ; bubble sort subroutine taking parameters from stack
          [org 0x0100]
                          jmp start
03
                                60, 55, 45, 50, 40, 35, 25, 30, 10, 0
328, 329, 898, 8923, 8293, 2345, 10, 877, 355, 98
888, 533, 2000, 1020, 30, 200, 761, 167, 90, 5
05
          data:
06
07
          data2:
                          dw
                          dw
08
          swapflag:
09
10
          bubblesort:
                                                       ; save old value of bp
                          push bp
11
                                                      ; make bp our reference point
                          mov bp, sp
12
                          push ax
                                                       ; save old value of ax
13
14
                          push bx
                                                       ; save old value of bx
                                                       ; save old value of cx
                          push cx
15
16
17
                                                      ; save old value of si
                                bx, [bp+6]
                                                      ; load start of array in bx
                          mov
                                                       ; load count of elements in cx
18
                                cx, [bp+4]
19
20
                          dec
                                CX
                                                       ; last element not compared
                          shl cx, 1
                                                      ; turn into byte count
21
22
23
          mainloop:
                          mov
                                si. O
                                                       ; initialize array index to zero
                          mov byte [swapflag], 0 ; reset swap flag to no swaps
24
25
26
27
          innerloop:
                          mov ax, [bx+si]
                                                      ; load number in ax
                                ax, [bx+si+2]
                                                      ; compare with next number ; no swap if already in order
                          cmp
                                noswap
28
29
30
                          xchg ax, [bx+si+2]
                                                      ; exchange ax with second number
                                [bx+si], ax
                                                      ; store second number in first
31
32
                                byte [swapflag], 1 ; flag that a swap has been done
33
                                                       ; advance si to next index
          noswap:
                                                         are we at last index
34
                                si, cx
                                                       ; if not compare next two
35
                          jne innerloop
```

37		cmp	byte [swapflag], 1	;	check if a swap has been done	
38		je	mainloop		if yes make another pass	
39) 0	ainioop	′	11 yes mane ansener pass	
40		pop	a i		restore old value of si	
41					restore old value of cx	
			CX			
42		T - T	bx		restore old value of bx	
43		pop			restore old value of ax	
44		pop			restore old value of bp	
45		ret	4	;	go back and remove two params	
46						
47	start:	mov	ax, data			
48		push	ax	;	place start of array on stack	
49		mov	ax, 10			
50		push	ax	;	place element count on stack	
51		call	bubblesort	;	call our subroutine	
52						
53		mov	ax, data2			
54		push	ax	;	place start of array on stack	
55			ax, 20		1	
56		push		:	place element count on stack	
57			bubblesort		call our subroutine again	
58		0411	2022100010	′	call cal capitatine again	
59		mosz	ax, 0x4c00		terminate program	
60			0×21	′	colminate program	
		1110	UNZI			
11	The value of	the	stack nointer is car	٦tı	ared in the base pointer. With	
					will not and therefore we will	
	read parame	ters f	rom bp+4 and bp+6	5.		
45					ent is used causing four to be	
	The form of RET that takes an argument is used causing four to be added to SP after the return address has been popped in the					
	instruction p	oointe	er. This will effective	re1	y discard the parameters that	
	are still then				<u>.</u>	
47-50						
	the AX register on the stack.					

Inside the debugger, concentrate on the operation of BP and the stack. The parameters are placed on the stack by the caller, the subroutine accesses them using the base pointer, and the special form of RET removes them without any extra instruction. The value of stack pointer of FFF6 is turned into FFFE by the RET instruction. This was the value in SP before any of the parameters was pushed.

Stack Clearing by Caller or Callee

Parameters pushed for a subroutine are a waste after the subroutine has returned. They have to be cleared from the stack. Either of the caller and the callee can take the responsibility of clearing them from there. If the callee has to clear the stack it cannot do this easily unless RETn exists. That is why most general processors have this instruction. Stack clearing by the caller needs an extra instruction on behalf of the caller after every call made to the subroutine, unnecessarily increasing instructions in the program. If there are thousand calls to a subroutine the code to clear the stack is repeated a thousand times. Therefore the prevalent convention in most high level languages is stack clearing by the callee; even though the other convention is still used in some languages.

If RETn is not available, stack clearing by the callee is a complicated process. It will have to save the return address in a register, then remove the parameters, and then place back the return address so that RET will function. When this instruction was introduced in processors, only then high level language designers switched to stack clearing by the callee. This is also exactly why RETn adds n to SP after performing the operation of RET. The other way around would be totally useless for our purpose. Consider the stack condition at the time of RET and this will become clear why this will be

useless. Also observe that RETn has discarded the arguments rather than popping them as they were no longer of any use either of the caller or the callee.

The strong argument in favour of callee cleared stacks is that the arguments were placed on the stack for the subroutine, the caller did not needed them for itself, so the subroutine is responsible for removing them. Removing the arguments is important as if the stack is not cleared or is partially cleared the stack will eventually become full, SP will reach 0, and thereafter wraparound producing unexpected results. This is called stack overflow. Therefore clearing anything placed on the stack is very important.

5.6. LOCAL VARIABLES

Another important role of the stack is in the creation of local variables that are only needed while the subroutine is in execution and not afterwards. They should not take permanent space like global variables. Local variables should be created when the subroutine is called and discarded afterwards. So that the spaced used by them can be reused for the local variables of another subroutine. They only have meaning inside the subroutine and no meaning outside it.

The most convenient place to store these variables is the stack. We need some special manipulation of the stack for this task. We need to produce a gap in the stack for our variables. This is explained with the help of the swapflag in the bubble sort example.

The swapflag we have declared as a word occupying space permanently is only needed by the bubble sort subroutine and should be a local variable. Actually the variable was introduced with the intent of making it a local variable at this time. The stack pointer will be decremented by an extra two bytes thereby producing a gap in which a word can reside. This gap will be used for our temporary, local, or automatic variable; however we name it. We can decrement it as much as we want producing the desired space, however the decrement must be by an even number, as the unit of stack operation is a word. In our case we needed just one word. Also the most convenient position for this gap is immediately after saving the value of SP in BP. So that the same base pointer can be used to access the local variables as well; this time using negative offsets. The standard way to start a subroutine which needs to access parameters and has local variables is as under.

```
push bp
mov bp, sp
sub sp, 2
```

The gap could have been created with a dummy push, but the subtraction makes it clear that the value pushed is not important and the gap will be used for our local variable. Also gap of any size can be created in a single instruction with subtraction. The parameters can still be accessed at bp+4 and bp+6 and the swapflag can be accessed at bp-2. The subtraction in SP was after taking the snapshot; therefore BP is above the parameters but below the loacal variables. The parameters are therefore accessed using positive offsets from BP and the local variables are accessed using negative offsets.

We modify the bubble sort subroutine to use a local variable to store the swap flag. The swap flag remembered whether a swap has been done in a particular iteration of bubble sort.

```
888, 533, 2000, 1020, 30, 200, 761, 167, 90, 5
                       dw
08
09
         bubblesort:
                        push bp
                                                 ; save old value of bp
                       mov bp, sp
                                                 ; make bp our reference point
11
                        sub sp, 2
                                                 ; make two byte space on stack
12
13
14
                        push ax
                                                 ; save old value of ax
                        nush by
                                                 : save old value of bx
                        push cx
                                                 ; save old value of cx
15
16
17
                                                 ; save old value of si
                       mov bx, [bp+6]
                                                 ; load start of array in bx
18
                                                 ; load count of elements in cx
                        mov
                            cx, [bp+4]
19
20
                        dec
                             CX
                                                 ; last element not compared
                             cx, 1
                        shl
                                                 ; turn into byte count
21
22
23
                                                ; initialize array index to zero
; reset swap flag to no swaps
         mainloop:
                       mov si. O
                             word [bp-2], 0
                       mov
24
25
26
                       mov ax, [bx+si]
                                                ; load number in ax ; compare with next number
         innerloop:
                             ax, [bx+si+2]
                        cmp
27
28
29
                             noswap
                                                 ; no swap if already in order
                                                 ; exchange ax with second number
                        xchg ax, [bx+si+2]
30
                            [bx+si], ax
                                                 ; store second number in first
31
32
                             word [bp-2], 1
                       mov
                                                ; flag that a swap has been done
33
                        add
                                                 ; advance si to next index
34
35
                        cmp
                             si. cx
                                                 ; are we at last index
                                                 ; if not compare next two
                        ine
                             innerloop
36
37
38
                        cmp
                             word [bp-2], 1
                                                 ; check if a swap has been done
                                                 ; if ves make another pass
                        iе
                             mainloop
39
40
                        pop
                            si
                                                 ; restore old value of si
41
42
                        gog
                             CX
                                                 ; restore old value of cx
                                                 ; restore old value of bx
                        pop
43
44
45
                                                 ; restore old value of ax
                             ax
                             sp, bp
                                                 ; remove space created on stack ; restore old value of bp
                        mov
                             bp
                       gog
46
47
48
                                                 ; go back and remove two params
                        mov
                            ax, data
         start:
49
50
51
                        push ax
                                                 ; place start of array on stack
                       mov ax, 10
                                                 ; place element count on stack
                       push ax
52
53
54
                        call bubblesort
                                                 ; call our subroutine
                        mov ax, data2
55
56
57
                        push ax
                                                 ; place start of array on stack
                        mov ax, 20
                                                 ; place element count on stack
                        push ax
58
                        call bubblesort
                                                 ; call our subroutine again
59
60
                       mov ax, 0x4c00
                                                 ; terminate program
61
                        int 0x21
11
         A word gap has been created for swap flag. This is equivalent to a
         dummy push. The registers are pushed above this gap.
23
         The swapflag is accessed with [bp-2]. The parameters are accessed
         in the same manner as the last examples.
44
         We are removing the hole that we created. The hole is removed by
         restoring the value of SP that it had at the time of snapshot or at the
         value it had before the local variable was created. This can be
         replaced with "add sp, 2" however the one used in the code is
         prefereed since it does not require to remember how much space for
         local variables was allocated in the start. After this operation SP
         points to the old value of BP from where we can proceed as usual.
```

We needed memory to store the swap flag. The fact that it is in the stack segment or the data segment doesn't bother us. This will just change the addressing scheme.

EXERCISES

1. Replace the following valid instruction with a single instruction that has the same effect. Don't consider the effect on flags.

```
push word L1
jmp L2
T.1:
```

2. Replace the following invalid instructions with a single instruction that has the same effect.

```
a. pop ip
b. mov ip, L5
c. sub sp, 2
mov [ss:sp], ax
d. mov ax, [ss:sp]
add sp, 2
e. add sp, 6
mov ip, [ss:sp-6]
```

3. Write a recursive function to calculate the fibonaccii of a number. The number is passed as a parameter via the stack and the calculated fibonaccii number is returned in the AX register. A local variable should be used to store the return value from the first recursive call. Fibonaccii function is defined as follows:

```
fibonaccii(0) = 0
fibonaccii(1) = 1
fibonaccii(n) = fibonaccii(n-1) + fibonaccii(n-2)
```

4. Write the above fibonaccii function iteratively.

HINT: Use two registers to hold the current and the previous fibonaccii numbers in a loop.

5. Write a function switch_stack meant to change the current stack and will be called as below. The function should destroy no registers.

```
push word [new_stack_segment]
push word [new_stack_offset]
call switch stack
```

- 6. Write a function "addtoset" that takes offset of a function and remembers this offset in an array that can hold a maximum of 8 offsets. It does nothing if there are already eight offsets in the set. Write another function "callset" that makes a call to all functions in the set one by one.
- 7. Do the above exercise such that "callset" does not use a CALL or a JMP to invoke the functions.
 - HINT: Setup the stack appropriately such that the RET will execute the first function, its RET execute the next and so on till the last RET returns to the caller of "callset."
- 8. Make an array of 0x80 bytes and treat it as one of 0x400 bits. Write a function myalloc that takes one argument, the number of bits. It finds that many consecutive zero bits in the array, makes them one, and returns in AX the index of the first bit. Write another function myfree that takes two arguments, index of a bit in the array, and the number of bits. It makes that many consecutive bits zero, whatever their previous values are, starting from the index in the first argument.
- 9. [Circular Queue] Write functions to implement circular queues. Declare 16x32 words of data for 16 queues numbered from 0 to 15. Each queue has a front index, a rear index and 30 locations for data totaling to 32 words. Declare another word variable whose 16 bits correspond to the 16 queues and a 1 bit signals that the corresponding queue is used and a 0 bit signals that it is free. Write a function "qcreate" that returns a queue number after finding a free queue or -1 if it failed. Write a function "qdestroy" that marks the queue as free. Write two other functions "qadd" and "qremove" that

- can add and remove items from the circular queue. The two functions return 0 if they failed and 1 otherwise.
- 10. [Linked List] Declare 1024 nodes of four bytes each. The first 2 bytes will be used for data and the next 2 bytes for storing the offset of another node. Also declare a word variable "firstfree" to store the offset of the first free node. Write the following five functions:
 - a. "init" chains all 1024 nodes into a list with offset of first node in firstfree, offset of the second node in the later two bytes of the first node and so on. The later two bytes of the last node contains zero.
 - b. "createlist" returns the offset of the node stored in firstfree through AX. It sets firstfree to the offset stored in the later two bytes of that node, and it sets the later two bytes of that node to zero.
 - c. "insertafter" takes two parameters, the offset of a node and a word data. It removes one node from freelist just like "createlist" and inserts it after the said node and updates the new node's data part.
 - d. "deleteafter" takes a node as its parameter and removes the node immediately after it in the linked list if there is one.
 - e. "deletelist" takes a node as its parameters and traverses the linked list starting at this node and removes all nodes from it and add them back to the free list.

Display Memory

The debugger gives a very close vision of the processor. That is why every program written till now was executed inside the debugger. Also the debugger is a very useful tool in assembly language program development, since many bugs only become visible when each instruction is independently monitored the way the debugger allows us to do. We will now be using the display screen in character mode, the way DOS uses this screen. The way we will access this screen is specific to the IBM PC.

6.1. ASCII CODES

The computer listens, sees, and speaks in numbers. Even a character is a number inside the computer. For example the keyboard is labeled with characters however when we press 'A', a specific number is transferred from the keyboard to the computer. Our program interprets that number as the character 'A'. When the same number comes on display, the Video Graphics Adapter (VGA) in our computer shows the shape of 'A'. Even the shape is stored in binary numbers with a one bit representing a pixel on the screen that is turned on and a zero bit representing a pixel that is not glowing. This example is considering a white on black display and no colors. This is the way a shape is drawn on the screen. The interpretation of 'A' is performed by the VGA card, while the monitor or CRT (cathode ray tube) only glows the pixels on and turns them off. The keyboard has a key labeled 'A' and pressing it the screen shows 'A' but all that happened inside was in numbers

An 'A' on any computer and any operating system is an 'A' on every other computer and operating system. This is because a standard numeric representation of all commonly used characters has been developed. This is called the ASCII code, where ASCII stands for American Standard Code for Information Interchange. The name depicts that this is a code that allows the interchange of information; 'A' written on one computer will remain an 'A' on another. The ASCII table lists all defined characters and symbols and their standardized numbers. All ASCII based computers use the same code. There are few other standards like EBCDIC and gray codes, but ASCII has become the most prevalent standard and is used for Internet communication as well. It has become the de facto standard for global communication. The character mode displays of our computer use the ASCII standard. Some newer operating systems use a new standard Unicode but it is not relevant to us in the current discussion.

Standard ASCII has 128 characters with assigned numbers from 0 to 127. When IBM PC was introduced, they extended the standard ASCII and defined 128 more characters. Thus extending the total number of symbols from 128 to 256 numbered from 0 to 255 fitting in an 8-bit byte. The newer characters were used for line drawing, window corners, and some non-English characters. The need for these characters was never felt on teletype terminals, but with the advent of IBM PC and its full screen display, these semi-graphics characters were the need of the day. Keep in mind that at that time there was no graphics mode available.

The extended ASCII code is just a de facto industry standard but it is not defined by an organization like the standard ASCII. Printers, displays, and all other peripherals related to the IBM PC understand the ASCII code. If the

code for 'A' is sent to the printer, the printer will print the shape of 'A', if it is sent to the display, the VGA card will form the shape of 'A' on the CRT. If it is sent to another computer via the serial port, the other computer will understand that this is an 'A'.

The important thing to observe in the ASCII table is the contiguous arrangement of the uppercase alphabets (41-5A), the lowercase alphabets (61-7A), and the numbers (30-39). This helps in certain operations with ASCII, for example converting the case of characters by adding or subtracting 0x20 from it. It also helps in converting a digit into its ASCII representation by adding 0x30 to it.

6.2. DISPLAY MEMORY FORMATION

We will explore the working of the display with ASCII codes, since it is our immediately accessible hardware. When 0x40 is sent to the VGA card, it will turn pixels on and off in such a way that a visual representation of 'A' appears on the screen. It has no reality, just an interpretation. In later chapters we will program the VGA controller to display a new shape when the ASCII of 'A' is received by it.

The video device is seen by the computer as a memory area containing the ASCII codes that are currently displayed on the screen and a set of I/O ports controlling things like the resolution, the cursor height, and the cursor position. The VGA memory is seen by the computer just like its own memory. There is no difference; rather the computer doesn't differentiate, as it is accessible on the same bus as the system memory. Therefore if that appropriate block of the screen is cleared, the screen will be cleared. If the ASCII of 'A' is placed somewhere in that block, the shape of 'A' will appear on the screen at a corresponding place.

This correspondence must be defined as the memory is a single dimensional space while the screen is two dimensional having 80 rows and 25 columns. The memory is linearly mapped on this two dimensional space, just like a two dimensional is mapped in linear memory. There is one word per character in which a byte is needed for the ASCII code and the other byte is used for the character's attributes discussed later. Now the first 80 words will correspond to the first row of the screen and the next 80 words will correspond to the next row. By making the memory on the video controller accessible to the processor via the system bus, the processor is now in control of what is displayed on the screen.

The three important things that we discussed are.

- One screen location corresponds to a word in the video memory
- The video controller memory is accessible to the processor like its own memory.
- ASCII code of a character placed at a cell in the VGA memory will cause the corresponding ASCII shape to be displayed on the corresponding screen location.

Display Memory Base Address

The memory at which the video controller's memory is mapped must be a standard, so that the program can be written in a video card independent manner. Otherwise if different vendors map their video memory at different places in the address space, as was the problem in the start, writing software was a headache. BIOS vendors had a problem of dealing with various card vendors. The IBM PC text mode color display is now fixed so that system software can work uniformly. It was fixed at the physical memory location of B8000. The first byte at this location contains the ASCII for the character displayed at the top left of the video screen. Dropping the zero we can load the rest in a segment register to access the video memory. If we do something in this memory, the effect can be seen on the screen. For example we can

write a virus that makes any character we write drop to the bottom of the screen.

Attribute Byte

The second byte in the word designated for one screen location holds the foreground and background colors for the character. This is called its video attribute. So the pair of the ASCII code in one byte and the attribute in the second byte makes the word that corresponds to one location on the screen. The lower address contains the code while the higher one contains the attribute. The attribute byte as detailed below has the RGB for the foreground and the background. It has an intensity bit for the foreground color as well thus making 16 possible colors of the foreground and 8 possible colors for the background. When bit 7 is set the character keeps on blinking on the screen. This bit has some more interpretations like background intensity that has to be activated in the video controller through its I/O ports.

7	6	5	4	3	2	1	0
---	---	---	---	---	---	---	---

- 7 Blinking of foreground character
- 6 Red component of background color
- 5 Green component of background color
- 4 Blue component of background color
- 3 Intensity component of foreground color
- 2 Red component of foreground color
- 1 Green component of foreground color
- 0 Blue component of foreground color

Display Examples

Both DS and ES can be used to access the video memory. However we commonly keep DS for accessing our data, and load ES with the segment of video memory. Loading a segment register with an immediate operand is not allowed in the 8088 architecture. We therefore load the segment register via a general purpose register. Other methods are loading from a memory location and a combination of push and pop.

```
mov ax, 0xb800
mov es, ax
```

This operation has opened a window to the video memory. Now the following instruction will print an 'A' on the top left of the screen in white color on black background.

```
mov word [es:0], 0 \times 0741
```

The segment override is used since ES is pointing to the video memory. Since the first word is written to, the character will appear at the top left of the screen. The 41 that goes in the lower byte is the ASCII code for 'A'. The 07 that goes in the higher byte is the attribute with I=0, R=1, G=1, B=1 for the foreground, meaning white color in low intensity and R=0, G=0, B=0 for the background meaning black color and the most significant bit cleared so that there is no blinking. Now consider the following instruction.

```
mov word [es:160], 0x1230
```

This is displayed 80 words after the start and there are 80 characters in one screen row. Therefore this is displayed on the first column of the second line. The ASCII code used is 30, which represents a '0' while the attribute byte is 12 meaning green color on black background.

We take our first example to clear the screen.

```
; clear the screen
02
         [org 0x0100]
03
                       mov
                            ax, 0xb800
                                               ; load video base in ax
                       mov es, ax mov di, 0
                                               ; point es to video base
05
                                               ; point di to top left column
06
07
08
                       mov word [es:di], 0x0720 ; clear next char on screen
        nextchar.
                           di, 2
di, 4000
                                               ; move to next screen location
                       add
09
10
                                               ; has the whole screen cleared
                       ine
                            nextchar
                                               ; if no clear next position
11
12
                       mov
                            ax, 0x4c00
                                               ; terminate program
13
                       int
                            0 \times 21
07
        The code for space is 20 while 07 is the normal attribute of low
         intensity white on black with no blinking. Even to clear the screen or
         put a blank on a location there is a numeric code.
0.8
         DI is incremented twice since each screen location corresponds to
         two byte in video memory.
         DI is compared with 80*25*2=4000. The last word location that
         corresponds to the screen is 3998.
```

Inside the debugger the operation of clearing the screen cannot be observed since the debugger overwrites whatever is displayed on the screen. Directly executing the COM file from the command prompt*, we can see that the screen is cleared. The command prompt that reappeared is printed after the termination of our application. This is the first application that can be directly executed to see some output on the screen.

6.3. HELLO WORLD IN ASSEMBLY LANGUAGE

To declare a character in assembly language, we store its ASCII code in a byte. The assembler provides us with another syntax that doesn't forces us to remember the ASCII code. The assembler also provides a syntax that simplifies declaration of consecutive characters, usually called a string. The three ways used below are identical in their meaning.

```
db 0x61, 0x61, 0x63
db 'a', 'b', 'c'
db 'abc'
```

When characters are stored in any high level or low level language the actual thing stored in a byte is their ASCII code. The only thing the language helps in is a simplified declaration.

Traditionally the first program in higher level languages is to print "hello world" on the screen. However due to the highly granular nature of assembly language, we are only now able to write it in assembly language. In writing this program, we make a generic routine that can print any string on the screen.

```
Example 6.2
         ; hello world in assembly
02
         [org 0x0100]
03
                       jmp start
05
         message:
                       db
                            'hello world'
                                                ; string to be printed
06
07
         length:
                           11
                                                ; length of the string
                       dw
08
         ; subroutine to clear the screen
09
                       push es
                       push ax
                       push di
```

^{*} Remember that if this example is run in a DOS window on some newer operating systems, a full screen DOS application must be run before this program so that screen access is enabled.

```
13
                              ax, 0xb800
14
15
                        mov
                                                   ; point es to video base
                                                   ; point di to top left column
                        mov
                              di, 0
16
17
18
19
         nextloc:
                        mov
                              word [es:di], 0x0720 ; clear next char on screen
                             di, 2
di, 4000
                                         ; move to next screen location ; has the whole screen cleared
                        add
                        cmp
20
21
22
                              nextloc
                                                   ; if no clear next position
                              di
                        pop
23
24
25
                        pop
                        pop
                              es
                        ret
26
27
28
         ; subroutine to print a string at top left of screen ; takes address of string and its length as parameters
29
30
31
                        push bp
                        mov bp, sp
                        push es
32
33
34
                        push ax
                         push cx
                        push si
35
                        push di
36
37
                        mov ax, 0xb800
38
                                                   ; point es to video base
                              es, ax
39
40
                        mov
                              di, 0
                                                   ; point di to top left column
                                                   ; point si to string
                              si, [bp+6]
                        mov
41
                                                   ; load length of string in cx
                              cx, [bp+4]
42
43
                        mov
                              ah, 0x07
                                                   ; normal attribute fixed in al
44
45
46
47
         nextchar:
                                                   ; load next char of string
                        mov
                              [es:di], ax
                                                   ; show this char on screen
                                                  ; move to next screen location ; move to next char in string
                        add
                              di, 2
                              si, 1
48
49
50
                        loop nextchar
                                                  ; repeat the operation cx times
                        gog
51
52
53
                              si
                        pop
                        gog
                              CX
                        gog
                              ax
54
55
56
                              es
                        pop
                        pop
                              bp
                        ret
57
58
59
         start:
                        call clrscr
                                                   ; call the clrscr subroutine
60
                        mov ax, message
61
62
                        push ax
                                                  ; push address of message
                        push word [length]
                                                   ; push message length
                         call printstr
63
                                                   ; call the printstr subroutine
64
65
                        mov ax, 0x4c00
                                                   ; terminate program
66
                         int 0x21
05-06
         The string definition syntax discussed above is used to declare a
         string "hello world" of 11 bytes and the length is stored in a separate
09-25
         The code to clear the screen from the last example is written in the
         form of a subroutine. Since the subroutine had no parameters, only
         modified registers are saved and restored from the stack.
29-35
         The standard subroutine format with parameters received via stack
         and all registers saved and restored is used.
37-42
         ES is initialized to point to the video memory via the AX register.
         Two pointer registers are used; SI to point to the string and DI to
         point to the top left location of the screen. CX is loaded with the
         length of the string. Normal attribute of low intensity white on black
         with no blinking is loaded in the AH register.
44-45
         The next character from the string is loaded into AL. Now AH holds
         the attribute and AL the ASCII code of the character. This pair is
```

46-47	written on the video memory using DI with the segment override prefix for ES to access the video memory segment.
	The string pointer is incremented by one while the video memory
	pointer is incremented by two since one char corresponds to a word
48	on the screen.
	The loop instruction used is equivalent to a combination of "dec cx"
50-56	and "jnz nextchar." The loop is executed CX times.
	The registers pushed on the stack are recovered in opposite order
	and the "ret 4" instruction removes the two parameters placed on
	the stack.
62	Memory can be directly pushed on the stack.

When the program is executed, screen is cleared and the greetings is displayed on the top left of the screen. This screen location and the attribute used were hard coded in the program and can also be made variable. Then we will be able to print anywhere on the screen.

6.4. NUMBER PRINTING IN ASSEMBLY

Another problem related to the display is printing numbers. Every high level language allows some simple way to print numbers on the screen. As we have seen, everything on the screen is a pair of ASCII code and its attribute and a number is a raw binary number and not a collection of ASCII codes. For example a 10 is stored as a 10 and not as the ASCII code of 1 followed by the ASCII code of 0. If this 10 is stored in a screen location, the output will be meaningless, as the character associate to ASCII code 10 will be shown on the screen. So there is a process that converst a number in its ASCII representation. This process works for any number in any base. We will discuss our examples with respect to the decimal base and later observe the effect of changing to different bases.

Number Printing Algorithm

The key idea is to divide the number by the base number, 10 in the case of decimal. The remainder can be from 0-9 and is the right most digit of the original number. The remaining digits fall in the quotient. The remainder can be easily converted into its ASCII equivalent and printed on the screen. The other digits can be printed in a similar manner by dividing the quotient again by 10 to separate the next digit and so on.

However the problem with this approach is that the first digit printed is the right most one. For example 253 will be printed as 352. The remainder after first division was 3, after second divison was 5 and after the third division was 2. We have to somehow correct the order so that the actual number 253 is displayed, and the trick is to use the stack since the stack is a Last In First Out structure so if 3, 5, and 2 are pushed on it, 2, 5, and 3 will come out in this order. The steps of our algorithm are outlined below.

- Divide the number by base (10 in case of decimal)
- · The remainder is its right most digit
- Convert the digit to its ASCII representation (Add 0x30 to the remainder in case of decimal)
- · Save this digit on stack
- If the quotient is non-zero repeat the whole process to get the next digit, otherwise stop
- Pop digits one by one and print on screen left to right

DIV Instruction

The divison used in the process is integer divison and not floating point divison. Integer divison gives an integer quotient and an integer remainder. A divison algorithm is now needed. Fortunately or unfortunely there is a DIV

instruction available in the 8088 processor. There are two forms of the DIV instruction. The first form divides a 32bit number in DX:AX by its 16bit operand and stores the 16bit quotient in AX and the 16bit remainder in DX. The second form divides a 16bit number in AX by its 8bit operand and stores the 8bit quotient in AL and the 8bit remainder in AH. For example "DIV BL" has an 8bit operand, so the implied dividend is 16bit and is stored in the AX register and "DIV BX" has a 16bit operand, so the implied dividend is 32bit and is therefore stored in the concatentation of the DX and AX registers. The higher word is stored in DX and the lower word in AX.

If a large number is divided by a very small number it is possible that the quotient is larger than the space provided for it in the implied destination. In this case an interrupt is automatically generated and the program is usually terminated as a result. This is called a divide overflow error; just like the calculator shows an -E- when the result cannot be displayed. This interrupt will be discussed later in the discussion of interrupts.

DIV (divide) performs an unsigned division of the accumulator (and its extension) by the source operand. If the source operand is a byte, it is divided into the two-byte dividend assumed to be in registers AL and AH. The byte quotient is returned in AL, and the byte remainder is returned in AH. If the source operand is a word, it is divided into the two-word dividend in registers AX and DX. The word quotient is returned in AX, and the word remainder is returned in DX. If the quotient exceeds the capacity of its destination register (FF for byte source, FFFF for word source), as when division by zero is attempted, a type 0 interrupt is generated, and the quotient and remainder are undefined.

Number Printing Example

The next example introduces a subroutine that can print a number received as its only argument at the top left of the screen using the algorithm just discussed.

```
Example 6.3
         ; number printing algorithm
002
003
         [org 0x0100]
                        imp start
005-022 ;;;;; COPY LINES 008-025 FROM EXAMPLE 6.2 (clrscr) ;;;;
023
         ; subroutine to print a number at top left of screen
025
         ; takes the number to be printed as its parameter
026
                        push bp
         printnum:
027
                        mov bp, sp
028
                        push es
029
                        push ax
030
                        push bx
                        push cx
                        push dx
032
033
                        push di
034
035
                        mov
                             ax, 0xb800
036
                                                 ; point es to video base
                        mov
                             es, ax
                                                 ; load number in ax
                             ax, [bp+4]
                                                 ; use base 10 for division
038
                        mov
                             bx, 10
039
                             cx, 0
                                                 ; initialize count of digits
                        mov
041
042
         nextdigit:
                        mov
                             dx, 0
                                                 ; zero upper half of dividend
                        div bx
                                                 ; divide by 10
                             dl, 0x30
                                                 ; convert digit into ascii value
                                                 ; save ascii value on stack
; increment count of values
044
                        push dx
045
                        inc cx
                                                   is the quotient zero
                        cmp
047
                            nextdigit
                                                 ; if no divide it again
048
                        mov di, 0
                                                 ; point di to top left column
050
```

```
051
                                               ; remove a digit from the stack
        nextpos:
                            dh, 0x07
                                               ; use normal attribute
053
054
                       mov [es:di], dx
                                               ; print char on screen
                       add di, 2
                                               ; move to next screen location
055
                                               ; repeat for all digits on stack
                       loop nextpos
056
057
                       pop di
058
                           dx
                       pop
059
                       pop
060
                       pop
                           hx
061
                           ax
                       pop
062
                       pop
063
                           bp
                       pop
064
                       ret
065
066
067
        start.
                      call clrscr
                                               ; call the clrscr subroutine
                       mov ax, 4529
                                               ; place number on stack
; call the printnum subroutine
069
                       push ax
070
                       call printnum
071
072
                       mov ax, 0x4c00
                                               ; terminate program
073
                       int 0x21
<sup>026-033</sup> The registers are saved as an essential practice. The only parameter
        received is the number to be printed.
035-039 ES is initialzed to video memory. AX holds the number to be printed.
        BX is the desired base, and can be loaded from a parameter. CX
        holds the number of digits pushed on the stack. This count is
        initialized to zero, incremented with every digit pushed and is used
        when the digits are popped one by one.
041-042 DX must be zeroed as our dividend is in AX and we want a 32bit
        divison. After the divison AX holds the quotient and DX holds the
        remainder. Actually the remainder is only in DL since the remainder
        can be from 0 to 9.
<sup>043-045</sup> The remainder is converted into its ASCII representation and saved
        on the stack. The count of digits on the stack is incremented as well.
046-047
        If the quotient is zero, all digits have been saved on the stack and if
        it is non-zero, we have to repeat the process to print the next digit.
049
        DI is initialized to point to the top left of the screen, called the cursor
        home. If the screen location is to become a parameter, the value
        loaded in DI will change.
051-053 A digit is popped off the stack, the attribute byte is appended to it
        and it is displayed on the screen.
<sup>054-055</sup> The next screen location is two bytes ahead so DI is incremented by
        two. The process is repeated CX times which holds the number of
        digits pushed on the stack.
057-064 We pop the registers pushed and "ret 2" to discard the only
        parameter on the stack.
<sup>066-070</sup> The main program clears the screen and calls the printnum
        subroutine to print 4529 on the top left of the screen.
```

When the program is executed 4529 is printed on the top left of the screen. This algorithm is versatible in that the base number can be changed and the printing will be in the desired base. For example if "mov bx, 10" is changed to "mov bx, 2" the output will be in binary as 001000110110001. Similarly changing it to "mov bx, 8" outputs the number in octal as 10661. Printing it in hexadecimal is a bit tricky, as the ASCII codes for A-F do not consecutively start after the codes for 0-9. Inside the debugger observe the working of the algorithm is just as described in the above illustration. The digits are

separated one by one and saved on the stack. From bottom to top, the stack holds 0034, 0035, 0032, and 0039 after the first loop is completed. The next loop pops them one by one and routes them to the screen.

6.5. SCREEN LOCATION CALCULATION

Until now our algorithms used a fixed attribute and displayed at a fixed screen location. We will change that to use any position on the screen and any attribute. For mapping from the two dimensional coordinate system of the screen to the one dimensional memory, we need to multiply the row number by 80 since there are 80 columns per row and add the column number to it and again multiply by two since there are 2 bytes for each character.

For this purpose the multiplication routine written previously can be used. However we introduce an instruction of the 8088 microprocessor at this time that can multiply 8bit or 16bit numbers.

MUL Instruction

MUL (multiply) performs an unsigned multiplication of the source operand and the accumulator. If the source operand is a byte, then it is multiplied by register AL and the double-length result is returned in AH and AL. If the source operand is a word, then it is multiplied by register AX, and the double-length result is returned in registers DX and AX.

String Printing at Desired Location

We modify the string printing program to take the x-position, the y-position, and the attribute as parameters. The desired location on the screen can be calculated with the following formulae.

```
location = (ypos * 80 + xpos) * 2
```

```
Example 6.4
          ; hello world at desired screen location
          [org 0x0100]
03
                         jmp start
04
05
                         db
                               'hello world'
                                                    ; string to be printed
         message:
06
07
                             11
         length:
                         dw
                                                    ; length of the string
08-25
         ;;;;; COPY LINES 008-025 FROM EXAMPLE 6.2 (clrscr) ;;;;
26
27
          ; subroutine to print a string at top left of screen
28
           takes x position, y position, string attribute, address of string
29
30
          ; and its length as parameters
                         push bp
         printstr:
31
                         mov bp, sp
32
33
                         push es
                         push ax
34
                         push cx
35
36
                         push si
                         push di
37
38
                         mov ax, 0xb800
39
40
                              es, ax
al, 80
                                                    ; point es to video base
                         mov
                                                    ; load al with columns per row
                         mov
41
42
                              byte [bp+10]
                                                    ; multiply with y position
                                                    ; add x position
; turn into byte offset
                         add
                              ax, [bp+12]
43
                         shl
                              ax, 1
44
45
                                                      point di to required location
                         mov
                               di,ax
                         mov si, [bp+6]
mov cx, [bp+4]
                                                    ; point si to string
; load length of string in cx
46
47
48
                              ah, [bp+8]
                                                      load attribute in ah
49
                                                    ; load next char of string
                              al, [si]
         nextchar:
                         mov
50
                                                      show this char on screen
                               [es:di], ax
51
                         add
                              di, 2
                                                    ; move to next screen location
```

```
add si, 1
                                                ; move to next char in string
53
                       loop nextchar
                                                ; repeat the operation cx times
54
55
56
                       pop di
                            si
                       pop
57
58
59
                            CX
                       gog
                            ax
                            es
                       pop
60
61
62
                       pop
                       ret
63
64
65
        start:
                       call clrscr
                                                ; call the clrscr subroutine
                       mov ax, 30
66
67
68
                       push ax
                                                ; push x position
                       mov ax, 20
                       push ax
                                               ; push y position
69
70
71
72
73
74
75
76
77
                                                ; blue on black attribute
                       push ax
                                                ; push attribute
                       mov ax, message
                                               ; push address of message
                                               ; push message length
                       push word [length]
                                               ; call the printstr subroutine
                       call printstr
                       mov ax, 0x4c00
                                               ; terminate program
                       int
41
        Push and pop operations always operate on words; however data
        can be read as a word or as a byte. For example we read the lower
        byte of the parameter y-position in this case.
        Shifting is used for multiplication by two, which should always be
43
        the case when multiplication or divison by a power of two is desired.
61
        The subroutine had 5 parameters so "ret 10" is used.
65-74
        The main program pushes 30 as x-position, 20 as y-position
        meaning 30th column on 20th row. It pushes 1 as the attribute
        meaning low intensity blue on black with no blinking.
```

When the program is executed hello world is displayed at the desired screen location in the desired color. The x-position, y-position, and attribute parameters can be changed and their effect be seen on the screen. The important difference in this example is the use of MUL instruction and the calculation of screen location given the x and y positions.

EXERCISES

1. Replace the following valid instruction with a single instruction that has the same effect. Don't consider the effect on flags.

- Write an infinite loop that shows two asterisks moving from right and left centers of the screen to the middle and then back. Use two empty nested loops with large counters to introduce some delay so that the movement is noticeable.
- 3. Write a function "printaddr" that takes two parameters, the segment and offset parts of an address, via the stack. The function should print the physical address corresponding to the segment offset pair passed at the top left of the screen. The address should be printed in hex and will therefore occupy exactly five columns. For example, passing 5600 and 7800 as parameters should result in 5D800 printed at the top left of the screen.
- 4. Write code that treats an array of 500 bytes as one of 4000 bits and for each blank position on the screen (i.e. space) sets the corresponding bit to zero and the rest to one.

5. Write a function "drawrect" that takes four parameters via the stack. The parameters are top, left, bottom, and right in this order. The function should display a rectangle on the screen using the characters + - and |.

*S*tring Instructions

7.1. STRING PROCESSING

Till now very simple instructions of the 8088 microprocessor have been introduced. In this chapter we will discuss a bit more powerful instructions that can process blocks of data in one go. They are called block processing or string instructions. This is the appropriate place to discuss these instructions as we have just introduced a block of memory, which is the video memory. The vision of this memory for the processor is just a block of memory starting at a special address. For example the clear screen operation initializes this whole block to 0741.

There are just 5 block processing instructions in 8088. In the primitive form, the instructions themselves operate on a single cell of memory at one time. However a special prefix repeats the instruction in hardware called the REP prefix. The REP prefix allows these instructions to operate on a number of data elements in one instruction. This is not like a loop; rather this repetition is hard coded in the processor. The five instructions are STOS, LODS, CMPS, SCAS, and MOVS called store string, load string, compare string, scan string, and move string respectively. MOVS is the instruction that allows memory to memory moves, as was discussed in the exceptions to the memory to memory movement rules. String instructions are complex instruction in that they perform a number of tasks against one instruction. And with the REP prefix they perform the task of a complex loop in one instruction. This causes drastic speed improvements in operations on large blocks of memory. The reduction in code size and the improvement in speed are the two reasons why these instructions were introduced in the 8088 processor.

There are a number of common things in these instructions. Firstly they all work on a block of data. DI and SI are used to access memory. SI and DI are called source index and destination index because of string instructions. Whenever an instruction needs a memory source, DS:SI holds the pointer to it. An override is possible that can change the association from DS but the default is DS. Whenever a string instruction needs a memory destination, ES:DI holds the pointer to it. No override is possible in this case. Whenever a byte register is needed, AL holds the value. Whenever a word register is used AX holds the value. For example STOS stores a register in memory so AL or AX is the register used and ES:DI points to the destination. The LODS instruction loads from memory to register so the source is pointed to by DS:SI and the register used is AL or AX.

String instructions work on a block of data. A block has a start and an end. The instructions can work from the start towards the end and from the end towards the start. In fact they can work in both directions, and they must be allowed to work in both directions otherwise certain operations with overlapping blocks become impossible. This problem is discussed in detail later. The direction of movement is controlled with the Direction Flag (DF) in the flags register. If this flag is cleared the direction is from lower addresses towards higher addresses and if this flag is set the direction is from higher addresses to lower addresses. If DF is cleared, this is called the autoincrement mode of string instruction, and if DF is set, this is called the autodecrement mode. There are two instructions to set and clear the direction flag.

```
cld ; clear direction flag
std ; set direction flag
```

Every string instruction has two variants; a byte variant and a word variant. For example the two variants of STOS are STOSB and STOSW. Similarly the variants for the other string instructions are attained by appending a B or a W to the instruction name. The operation of each of the string instructions and each of the repetition prefixes is discussed below.

STOS

STOS transfers a byte or word from register AL or AX to the string element addressed by ES:DI and updates DI to point to the next location. STOS is often used to clear a block of memory or fill it with a constant.

The implied source will always be in AL or AX. If DF is clear, SI will be incremented by one or two depending of whether STOSB or STOSW is used. If DF is set SI will be decremented by one or two depending of whether STOSB or STOSW is used. If REP is used before this instruction, the process will be repeated CX times. CX is called the counter register because of the special treatment given to it in the LOOP and JCXZ instructions and the REP set of prefixes. So if REP is used with STOS the whole block of memory will be filled with a constant value. REP will always decrement CX like the LOOP instruction and this cannot be changed with the direction flag. It is also independent of whether the byte or the word variant is used. It always decrements by one; therefore CX has count of repetitions and not the count of bytes.

LODS

LODS transfers a byte or word from the source location DS:SI to AL or AX and updates SI to point to the next location. LODS is generally used in a loop and not with the REP prefix since the value previously loaded in the register is overwritten if the instruction is repeated and only the last value of the block remains in the register.

SCAS

SCAS compares a source byte or word in register AL or AX with the destination string element addressed by ES:DI and updates the flags. DI is updated to point to the next location. SCAS is often used to locate equality or in-equality in a string through the use of an appropriate prefix.

SCAS is a bit different from the other instructions. This is more like the CMP instruction in that it does subtraction of its operands. The prefixes REPE (repeat while equal) and REPNE (repeat while not equal) are used with this instruction. The instruction is used to locate a byte in AL in the block of memory. When the first equality or inequality is encountered; both have uses. For example this instruction can be used to search for a 0 in a null terminated string to calculate the length of the string. In this form REPNE will be used to repeat while the null is not there.

MOVS

MOVS transfers a byte or word from the source location DS:SI to the destination ES:DI and updates SI and DI to point to the next locations. MOVS is used to move a block of memory. The DF is important in the case of overlapping blocks. For example when the source and destination blocks overlap and the source is below the destination copy must be done upwards while if the destination is below the source copy must be done downwards. We cannot perform both these copy operations properly if the direction flag was not provided. If the source is below the destination and an upwards copy is used the source to be copied is destroyed. If however the copy is done downwards the portion of source destroyed is the one that has already been

copied. Therefore we need the control of the direction flag to handle this problem. This problem is further detailed in a later example.

CMPS

CMPS subtracts the source location DS:SI from the destination location ES:DI. Source and Destination are unaffected. SI and DI are updated accordingly. CMPS compares two blocks of memory for equality or inequality of the block. It subtracts byte by byte or word by word. If used with a REPE or a REPNE prefix is repeats as long as the blocks are same or as long as they are different. For example it can be used for find a substring. A substring is a string that is contained in another string. For example "has" is contained in "Mary has a little lamp." Using CMPS we can do the operation of a complex loop in a single instruction. Only the REPE and REPNE prefixes are meaningful with this instruction.

REP Prefix

REP repeats the following string instruction CX times. The use of CX is implied with the REP prefix. The decrement in CX doesn't affect any flags and the jump is also independent of the flags, just like JCXZ.

REPE and REPNE Prefixes

REPE or REPZ repeat the following string instruction while the zero flag is set and REPNE or REPNZ repeat the following instruction while the zero flag is not set. REPE or REPNE are used with the SCAS or CMPS instructions. The other string instructions have nothing to do with the condition since they are performing no comparison. Also the initial state of flags before the string instruction does not affect the operation. The most complex operation of the string instruction is with these prefixes.

7.2. STOS EXAMPLE - CLEARING THE SCREEN

We take the example of clearing the screen and observe that how simple and fast this operation is with the string instructions. Even if there are three instructions in a loop they have to be fetched and decoded with every iteration and the time of three instructions is multiplied by the number of iterations of the loop. In the case of string instructions, many operations are short circuited. The instruction is fetched and decoded once and only the execution is repeated CX times. That is why string instructions are so efficient in their operation. The program to clear the screen places 0720 on the 2000 words on the screen.

```
Example 7.1
001
           clear screen using string instructions
          [org 0x0100]
003
                         jmp start
004
005
          ; subroutine to clear the screen
                         push es
006
007
          clrscr:
                         push ax
009
010
                         push di
011
                               ax, 0xb800
012
013
                                                     ; point es to video base
                         mov
                               es, ax
                                                    ; point di to top left column ; space char in normal attribute
                         xor di, di
                               ax, 0x0720
                         mov
015
                               cx, 2000
                                                     ; number of screen locations
                         mov
016
                                                     ; auto increment mode
018
                               stosw
                                                     ; clear the whole screen
                          rep
019
                         pop di
```

```
021
                           СX
022
                           ax
                      pop
023
                      pop
                       ret
025
026
        start:
                      call clrscr
                                              ; call clrscr subroutine
027
028
                      mov ax, 0x4c00
                                              ; terminate program
029
                      int 0x21
013
        A space efficient way to zero a 16bit register is to XOR it with itself.
        Remember that exclusive or results in a zero whenever the bits at
        the source and at the destination are same. This instruction takes
        just two bytes compared to "mov di, 0" which would take three. This
        is a standard way to zero a 16bit register.
```

Inside the debugger the operation of the string instruction can be monitored. The trace into command can be used to monitor every repetition of the string instruction. However screen will not be cleared inside the debugger as the debugger overwrites its display on the screen. CX decrements with every iteration, DI increments by 2. The first access is made at B800:0000 and the second at B800:0002 and so on. A complex and inefficient loop is replaced with a fast and simple instruction that does the same operation many times faster.

7.3. LODS EXAMPLE - STRING PRINTING

The use of LODS with the REP prefix is not meaningful as only the last value loaded will remain in the register. It is normally used in a loop paired with a STOS instruction to do some block processing. We use LODS to pick the data, do the processing, and then use STOS to put it back or at some other place. For example in string printing, we will use LODS to read a character of the string, attach the attribute byte to it, and use STOS to write it on the video memory.

The following example will print the string using string instructions.

```
Example 7.2
001
          ; hello world printing using string instructions
002
          [org 0x0100]
003
004
005
                                 'hello world'
                          db
                                                      ; string to be printed
          message:
006
                                                       ; length of string
          length:
008-027 ;;;;; COPY LINES 005-024 FROM EXAMPLE 7.1 (clrscr) ;;;;
028
          ; subroutine to print a string ; takes the {\bf x} position, {\bf y} position, attribute, address of string and ; its length as parameters
029
030
031
          printstr:
032
                          push bp
033
                          mov bp, sp
034
                          push es
                           push ax
035
036
                          push cx
037
038
039
                          push di
                          mov ax, 0xb800
040
041
042
                          mov
                                es, ax
                                                       ; point es to video base
                          mov
                                al, 80
                                                         load al with columns per row
043
                                                         multiply with y position
                                byte [bp+10]
044
                           add
                                ax, [bp+12]
                                                         add x position
                                                         turn into byte offset
045
                          shl
                                ax, 1
046
                                di,ax
                                                         point di to required location
                          mov
047
                                si, [bp+6]
                                                         point si to string
                          mov
048
                          mov
                                cx, [bp+4] ah, [bp+8]
                                                         load length of string in cx load attribute in ah
```

```
050
051
                                               ; auto increment mode
052
        nextchar:
                      lodsb
                                               ; load next char in al
053
                                               ; print char/attribute pair
                       stosw
054
                      loop nextchar
                                               ; repeat for the whole string
055
056
                      pop di
057
                           si
                      pop
058
                           СХ
                      pop
059
                       pop
                           ax
060
                           es
                      pop
061
                      pop
0.62
                       ret
                           10
063
        start:
                      call clrscr
                                              ; call the clrscr subroutine
065
066
                      mov ax, 30
                      push ax
                                              ; push x position
068
                      mov ax, 20
069
                      push ax
                                              ; push y position
070
071
072
                                               ; blue on black attribute
                      push ax
                                              ; push attribute
                      mov ax, message
073
                      push ax
                                              ; push address of message
                                              ; push message length
074
                       push word [length]
075
                                              ; call the printstr subroutine
                      call printstr
076
077
                      mov ax, 0x4c00
                                              ; terminate program
078
                           0x21
                      int
051
        Both operations are in auto increment mode.
        DS is automatically initialized to our segment. ES points to video
        memory. SI points to the address of our string. DI points to the
        screen location. AH holds the attribute. Whenever we read a
        character from the string in AL, the attribute byte is implicitly
        attached and the pair is present in AX. The same effect could not be
        achieved with a REP prefix as the REP will repeat LODS and then
        start repeating STOS, but we need to alternate them.
054
        CX holds the length of the string. Therefore LOOP repeats for each
        character of the string.
```

Inside the debugger we observe how LODS and STOS alternate and CX is only used by the LOOP instruction. In the original code there were four instructions inside the loop; now there are only two. This is how string instructions help in reducing code size.

7.4. SCAS EXAMPLE - STRING LENGTH

Many higher level languages do not explicitly store string length; rather they use a null character, a character with an ASCII code of zero, to signal the end of a string. In assembly language programs, it is also easier to store a zero at the end of the string, instead of calculating the length of string, which is very difficult process for longer strings. So we delegate length calculation to the processor and modify our string printing subroutine to take a null terminated string and no length. We use SCASB with REPNE and a zero in AL to find a zero byte in the string. In CX we load the maximum possible size, which is 64K bytes. However actual strings will be much smaller. An important thing regarding SCAS and CMPS is that if they stop due to equality or inequality, the index registers have already incremented. Therefore when SCAS will stop DI would be pointing past the null character.

	Example 7.3
001 002	; hello world printing with a null terminated string [org 0×0100]

```
003
                         jmp start
004
005
         message:
                         db 'hello world', 0 ; null terminated string
007-026 ;;;;; COPY LINES 005-024 FROM EXAMPLE 7.1 (clrscr) ;;;;
027
028
         ; subroutine to print a string
029
         ; takes the x position, y position, attribute, and address of a null
030
         ; terminated string as parameters
031
         printstr:
                         push bp
032
                         mov bp, sp
033
034
                         push es
                         push ax
035
                         push cx
036
                         push si
037
                         push di
038
039
                         push ds
040
                         pop es
mov di, [bp+4]
                                                   ; load ds in es
041
                                                   ; point di to string
042
                         mov cx, 0xffff
                                                   ; load maximum number in cx
043
                         xor al, al
                                                   ; load a zero in al
044
                                                   ; find zero in the string
                         repne scasb
045
                         mov ax, 0xffff
                                                   ; load maximum number in ax
046
047
                                                   ; find change in cx
; exclude null from length
                         sub ax, cx
                         dec ax
048
                                                   ; no printing if string is empty
                         jz
049
050
                                                   ; load string length in cx
                         mov cx, ax
051
                         mov ax, 0xb800
                         mov es, ax mov al, 80
                                                   ; point es to video base
; load al with columns per row
052
053
054
                             byte [bp+8]
                                                   ; multiply with y position
                         mul
055
                         add ax, [bp+10]
                                                   ; add x position
056
057
                                                   ; turn into byte offset
; point di to required location
                         shl ax, 1
                              di,ax
                         mov
058
059
                                                  ; point si to string
; load attribute in ah
                         mov
                              si, [bp+4]
                         mov ah, [bp+6]
060
061
062
                         cld
                                                   ; auto increment mode
         nextchar:
                         lodsb
                                                   ; load next char in al
063
                                                   ; print char/attribute pair
                         stosw
064
065
                         loop nextchar
                                                   ; repeat for the whole string
066
         exit:
                         pop di
067
068
                             si
                         pop
                         pop cx
069
                             ax
                         gog
070
071
                         pop
                         pop
                              bp
072
                         ret
073
074
         start:
                         call clrscr
                                                   ; call the clrscr subroutine
075
076
077
                         mov ax, 30
                         push ax
                                                   ; push x position
078
                         mov ax, 20
                         push ax
                                                   ; push y position
080
                         mov ax, 1
                                                   ; blue on black attribute
081
                         push ax
                                                   ; push attribute
                         mov ax, message
                                                   ; push address of message
; call the printstr subroutine
083
                         push ax
084
                         call printstr
085
086
                         mov ax, 0x4c00
int 0x21
                                                   ; terminate program
039-040 Another way to load a segment register is to use a combination of
         push and pop. The processor doesn't match pushes and pops. ES is
         equalized to DS in this pair of instructions.
```

Inside the debugger observe the working of the code for length calculation after SCASB has completed its operation.

LES and LDS Instructions

Since the string instructions need their source and destination in the form of a segment offset pair, there are two special instructions that load a segment register and a general purpose register from two consecutive memory locations. LES loads ES while LDS loads DS. Both these instructions have two parameters, one is the general purpose register to be loaded and the other is the memory location from which to load these registers. The major application of these instructions is when a subroutine receives a segment offset pair as an argument and the pair is to be loaded in a segment and an offset register. According to Intel rules of significance the word at higher address is loaded in the segment register while the word at lower address is loaded in the offset register. As parameters segment should be pushed first so that it ends up at a higher address and the offset should be pushed afterwards. When loading the lower address will be given. For example "lds si, [bp+4]" will load SI from BP+4 and DS from BP+6.

7.5. LES AND LDS EXAMPLE

We modify the string length calculation subroutine to take the segment and offset of the string and use the LES instruction to load that segment offset pair in ES and DI.

```
Example 7.4
0.01
         ; hello world printing with length calculation subroutine
002
         [org 0x0100]
003
                        imp start
004
005
                        db
                            'hello world', 0
                                                 ; null terminated string
         message:
006
007-026 ;;;; COPY LINES 005-024 FROM EXAMPLE 7.1 (clrscr) ;;;;
027
028
         ; subroutine to calculate the length of a string
029
         ; takes the segment and offset of a string as parameters strlen: push bp
030
031
                            bp,sp
032
                        push es
033
                        push cx
034
                        push di
035
036
                        les di, [bp+4]
                                                  ; point es:di to string
037
                        mov cx, 0xffff
                                                  ; load maximum number in cx
038
039
                        xor al, al
                                                  ; load a zero in al
                                                  ; find zero in the string
                        repne scasb
040
                        mov ax, 0xffff
                                                    load maximum number in ax
041
                        sub ax, cx
                                                  ; find change in cx
042
                                                  ; exclude null from length
                        dec ax
043
044
                             di
045
                        pop
                             CX
046
                             es
                        pop
047
                        pop
048
049
050
         ; subroutine to print a string
         ; takes the x position, y position, attribute, and address of a null; terminated string as parameters
051
052
053
                        push bp
054
055
                        mov bp, sp
                        push es
056
                        push ax
057
                        push cx
058
                        push si
059
                        push di
060
061
                        push ds
                                                  ; push segment of string
                        mov ax, [bp+4]
                        push ax
063
                                                  ; push offset of string
064
                        call strlen
                                                  ; calculate string length
```

```
; is the string empty
                        cmp
                             ax, 0
066
                                                  ; no printing if string is empty
                             exit
067
                                                  ; save length in cx
068
069
                             ax, 0xb800
                        mov
070
071
                                                 ; point es to video base
                        mov
                                                 ; load al with columns per row ; multiply with y position
                        mov.
                             al. 80
072
                            byte [bp+8]
                        mul
073
074
                        add
                             ax, [bp+10]
                                                  ; add x position
                                                  ; turn into byte offset
                        shl
                             ax. 1
075
                                                 ; point di to required location
                             di,ax
                        mov
076
077
                                                 ; point si to string
                             si, [bp+4]
                        mov.
                             ah, [bp+6]
                                                 ; load attribute in ah
078
079
                        cld
                                                  ; auto increment mode
080
         nextchar.
                        lodsh
                                                 ; load next char in al
081
                                                 ; print char/attribute pair
                        stosw
                        loop nextchar
082
                                                  ; repeat for the whole string
083
084
         exit:
                        pop di
085
                        pop
086
                        pop
                             CX
087
                        gog
                             ax
088
                        pop
089
                             bp
                        pop
090
                        ret
091
092
         start:
                        call clrscr
                                                 ; call the clrscr subroutine
093
                        mov ax, 30
095
                        push ax
                                                 ; push x position
096
                        mov ax, 20
097
                        push ax
                                                 ; push y position
098
                        mov ax, 0x71
                                                 ; blue on white attribute
099
                        push ax
                                                 ; push attribute
100
                        mov ax, message
101
102
                        push ax
                                                  ; push address of message
                        call printstr
                                                  ; call the printstr subroutine
103
104
                        mov ax, 0x4c00
105
                             0 \times 21
036
         The LES instruction is used to load the DI register from BP+4 and
         the ES register from BP+6.
0.65
         The convention to return a value from a subroutine is to use the AX
         register. That is why AX is not saved and restored in the subroutine.
```

Inside the debugger observe that the segment register is pushed followed by the offset. The higher address FFE6 contains the segment and the lower address FFE4 contains the offset. This is because we have a decrementing stack. Then observe the loading of ES and DI from the stack.

7.6. MOVS EXAMPLE - SCREEN SCROLLING

MOVS has the two forms MOVSB and MOVSW. REP allows the instruction to be repeated CX times allowing blocks of memory to be copied. We will perform this copy of the video screen.

Scrolling is the process when all the lines on the screen move one or more lines towards the top of towards the bottom and the new line that appears on the top or the bottom is cleared. Scrolling is a process on which string movement is naturally applicable. REP with MOVS will utilize the full processor power to do the scrolling in minimum time.

In this example we want to scroll a variable number of lines given as argument. Therefore we have to calculate the source address, which is 160 times the number of lines to clear. The destination address is 0, which is the top left of the screen. The lines that scroll up are discarded so the source pointer is placed after them. An equal number of lines at the bottom are cleared. These lines have actually been copied above.

```
Example 7.5
          ; scroll up the screen
001
002
          [org 0x0100]
                         imp start
004
005
          ; subroutine to scroll up the screen
006
007
          ; take the number of lines to scroll as parameter
         scrollup:
                         push bp
008
                         mov bp,sp
009
010
011
                         push ax
                         push cx
012
                         push di
                         push es
014
                         push ds
015
016
                         mov
                               ax, 80
                                                    ; load chars per row in ax
017
                                                    ; calculate source position
                              byte [bp+4]
018
019
                         mov
                              si, ax
                                                    ; load source position in si
                         push si
                                                    ; save position for later use
020
                         shl si, 1
                                                    ; convert to byte offset
021
022
                                                    ; number of screen locations
                         mov
                               cx, 2000
                         sub
                              cx, ax
                                                    ; count of words to move
                               ax, 0xb800
023
                         mov
024
025
                         mov
                               es, ax
                                                    ; point es to video base
                         mov
                              ds, ax
                                                    ; point ds to video base ; point di to top left column
026
                         xor
027
028
                         cld
                                                     ; set auto increment mode
                         rep
                               movsw
                                                    ; scroll up
029
                                                    ; space in normal attribute
                         mov
                               ax, 0x0720
030
031
                         pop
                               СХ
                                                    ; count of positions to clear
                         rep
                              stosw
                                                    ; clear the scrolled space
032
033
034
                               ds
                         pop
                               es
035
                         pop
036
037
                         pop
                               si
                         pop
                               CX
038
                         pop
                               ax
039
                         pop
                               bp
040
                         ret
041
042
         start:
                         mov ax,5
                         push ax
043
                                                    ; push number of lines to scroll ; call the scroll up subroutine
044
                         call scrollup
045
                                                    ; terminate program
                         mov.
                              ax. 0x4c00
                         int 0x21
```

The beauty of this example is that the two memory blocks are overlapping. If the source and destination in the above algorithm are swapped in an expectation to scroll down the result is strange. For example if 5 lines were to scroll down, the top five lines of the screen are repeated on the whole screen. This is where the use of the direction flag comes in.

When the source is five lines below the destination, the first five lines are copied on the first five lines of the destination. However the next five lines to be copied from the source have been destroyed in the process; because they were the same as the first five lines of the destination. The same is the problem with every set of five lines as the source is destroyed during the previous copy. In this situation we must go from bottom of the screen towards the top. Now the last five lines are copied to the last five lines of the destination. The next five lines are copied to next five lines of the destination destroying the last five lines of source; but now these lines are no longer needed and have been previously copied. Therefore the copy will be appropriately done in this case.

We give an example of scrolling down with this consideration. Now we have to calculate the end of the block instead of the start.

```
Example 7.6
001
         ; scroll down the screen
002
         [org 0x0100]
003
                         jmp start
004
         ; subroutine to scrolls down the screen
006
         ; take the number of lines to scroll as parameter
007
008
          scrolldown: push bp
                         mov bp,sp
009
                         push ax
010
011
012
                         push cx
                         push si
                         push di
013
014
015
                         push es
                         push ds
016
017
                                                  ; load chars per row in ax
                         mul byte [bp+4]
                                                   ; calculate source position
018
                         push ax
                                                   ; save position for later use
019
                         shl ax, 1
                                                   ; convert to byte offset
020
021
                         mov si, 3998
                                                   ; last location on the screen
                         sub si, ax
                                                   ; load source position in si
022
                             cx, 2000
                                                   ; number of screen locations
023
                         sub cx, ax
                                                   ; count of words to move
024
                         mov ax, 0xb800
025
026
027
                              es, ax
                                                  ; point es to video base
                                                   ; point ds to video base
; point di to lower right column
                         mov ds, ax
                         mov di, 3998
028
                                                   ; set auto decrement mode
029
030
031
                         rep
                              movsw
                                                   ; scroll up
                         mov ax, 0x0720
                                                  ; space in normal attribute
; count of positions to clear
                         pop
032
033
034
                         rep
                             stosw
                                                   ; clear the scrolled space
                         pop
035
036
037
                         pop
                              es
                              di
                         gog
                         pop
038
                         pop
                              СХ
                         pop
                              ax
040
                         pop
                              bp
041
                         ret
042
043
                         mov ax,5
         start:
044
                                                   ; push number of lines to scroll
                         call scrolldown
                                                   ; call scroll down subroutine
046
047
                         mov ax, 0x4c00
                                                   ; terminate program
048
                              0x21
```

7.7. CMPS EXAMPLE - STRING COMPARISON

For the last string instruction, we take string comparison as an example. The subroutine will take two segment offset pairs containing the address of the two null terminated strings. The subroutine will return 0 if the strings are different and 1 if they are same. The AX register will be used to hold the return value.

```
Example 7.7
         ; comparing null terminated strings
001
002
         [org 0x0100]
                        jmp start
003
004
005
                             'hello world', 0
         msg1:
006
007
                             'hello WORLD', 0
'hello world', 0
                        db
         msq3:
                        db
008
009-031 ;;;;; COPY LINES 028-050 FROM EXAMPLE 7.4 (strlen) ;;;;
032
033
         ; subroutine to compare two strings
034
         ; takes segment and offset pairs of two strings to compare
```

```
; returns 1 in ax if they match and 0 other wise
035
036
                         push bp
         strcmp:
037
                         mov bp,sp
                         push cx
039
                         push si
040
041
042
                         push di
                         push es
                         push ds
043
044
045
                                                  ; point ds:si to first string
                         lds si, [bp+4]
                         les di, [bp+8]
                                                   ; point es:di to second string
046
047
048
                         push ds
                                                   ; push segment of first string
; push offset of first string
                         push si
                                                  ; calculate string length
; save length in cx
049
050
051
                         call strlen
                         mov cx, ax
                                                  ; push segment of second string
052
                         push es
053
054
                         push di
                                                   ; push offset of second string
                         call strlen
                                                   ; calculate string lenth
055
056
057
                         cmp cx, ax
                                                  ; compare length of both strings
; return 0 if they are unequal
                         jne
                             exitfalse
058
                                                   ; store 1 in ax to be returned
                                                   ; compare both strings
059
                         repe cmpsb
060
                         jcxz exitsimple
                                                   ; are they successfully compared
061
062
063
                                                   ; store 0 to mark unequal
         exitfalse.
                         mov ax, 0
         exitsimple:
                         pop
065
066
                         pop
                              es
                             di
                         gog
067
068
069
070
                              si
                         pop
                              СX
                         pop
ret
                              pd
071
072
                                                   ; push segment of first string
         start:
                         push ds
073
                         mov ax, msg1
074
075
                         push ax
                                                   ; push offset of first string
                         push ds
                                                   ; push segment of second string
076
                         mov ax, msg2
077
078
                         push ax
                                                   ; push offset of second string
                         call strcmp
                                                   ; call strcmp subroutine
079
080
081
                         push ds
                                                   ; push segment of first string
                         mov ax, msg1
push ax
082
                                                   ; push offset of first string
083
084
                         push ds
                                                   ; push segment of third string
                         mov ax, msg3
push ax
085
                                                   ; push offset of third string
                         call strcmp
086
                                                   ; call strcmp subroutine
087
088
                         mov ax, 0x4c00
                                                   ; terminate program
089
                         int 0x21
005-007 Three strings are declared out of which two are equal and one is
         different.
044-045 LDS and LES are used to load the pointers to the two strings in
         DS:SI and ES:DI.
070
         Since there are 4 parameters to the subroutine "ret 8" is used.
```

Inside the debugger we observe that REPE is shown as REP. This is because REP and REPE are represented with the same prefix byte. When used with STOS, LODS, and MOVS it functions as REP and when used with SCAS and CMPS it functions as REPE.

EXERCISES

1. Write code to find the byte in AL in the whole megabyte of memory such that each memory location is compared to AL only once.

- 2. Write a far procedure to reverse an array of 64k words such that the first element becomes the last and the last becomes the first and so on. For example if the first word contained 0102h, this value is swapped with the last word. The next word is swapped with the second last word and so on. The routine will be passed two parameters through the stack; the segment and offset of the first element of the array.
- 3. Write a near procedure to copy a given area on the screen at the center of the screen without using a temporary array. The routine will be passed top, left, bottom, and right in that order through the stack. The parameters passed will always be within range the height will be odd and the width will be even so that it can be exactly centered.
- 4. Write code to find two segments in the whole memory that are exactly the same. In other words find two distinct values which if loaded in ES and DS then for every value of SI [DS:SI]=[ES:SI].
- 5. Write a function writechar that takes two parameters. The first parameter is the character to write and the second is the address of a memory area containing top, left, bottom, right, current row, current column, normal attribute, and cursor attribute in 8 consecutive bytes. These define a virtual window on the screen.

 The function writes the passed character at (current row, current column) using the normal attribute. It then increments current column, If current column goes outside the window, it makes it zero and increments current row. If current row gets out of window, it scrolls the window one line up, and blanks out the new line in the
- 6. Write a function "strcpy" that takes the address of two parameters via stack, the one pushed first is source and the second is the destination. The function should copy the source on the destination including the null character assuming that sufficient space is reserved starting at destination.

current column) to cursor attribute.

window. In the end, it sets the attribute of the new (current row,