

CIS Apache Tomcat 8 Benchmark

v1.0.0 - 03-17-2016

This work is licensed under a Creative Commons Attribution-NonCommercial-ShareAlike 4.0 International Public License. The link to the license terms can be found at https://creativecommons.org/licenses/by-nc-sa/4.0/legalcode

To further clarify the Creative Commons license related to CIS Benchmark content, you are authorized to copy and redistribute the content for use by you, within your organization and outside your organization for non-commercial purposes only, provided that (i) appropriate credit is given to CIS, (ii) a link to the license is provided. Additionally, if you remix, transform or build upon the CIS Benchmark(s), you may only distribute the modified materials if they are subject to the same license terms as the original Benchmark license and your derivative will no longer be a CIS Benchmark. Commercial use of CIS Benchmarks is subject to the prior approval of the Center for Internet Security.

Table of Contents

Overview	5
Intended Audience	5
Consensus Guidance	5
Typographical Conventions	
Scoring Information	6
Profile Definitions	7
Acknowledgements	8
Recommendations	9
1 Remove Extraneous Resources	9
1.1 Remove extraneous files and directories (Scored)	9
1.2 Disable Unused Connectors (Not Scored)	11
2 Limit Server Platform Information Leaks	13
2.1 Alter the Advertised server info String (Scored)	13
2.2 Alter the Advertised server.number String (Scored)	15
2.3 Alter the Advertised server.built Date (Scored)	17
2.4 Disable X-Powered-By HTTP Header and Rename the Server Value for all Connectors (Scored)	19
2.5 Disable client facing Stack Traces (Scored)	
2.6 Turn off TRACE (Scored)	
3 Protect the Shutdown Port	
3.1 Set a nondeterministic Shutdown command value (Scored)	25
3.2 Disable the Shutdown port (Not Scored)	
4 Protect Tomcat Configurations	28
4.1 Restrict access to \$CATALINA_HOME (Scored)	28
4.2 Restrict access to \$CATALINA_BASE (Scored)	

4.3 Restrict access to Tomcat configuration directory (Scored)	30
4.4 Restrict access to Tomcat logs directory (Scored)	32
4.5 Restrict access to Tomcat temp directory (Scored)	33
4.6 Restrict access to Tomcat binaries directory (Scored)	34
4.7 Restrict access to Tomcat web application directory (Scored)	35
4.8 Restrict access to Tomcat catalina.policy (Scored)	
4.9 Restrict access to Tomcat catalina.properties (Scored)	38
4.10 Restrict access to Tomcat context.xml (Scored)	40
4.11 Restrict access to Tomcat logging.properties (Scored)	42
4.12 Restrict access to Tomcat server.xml (Scored)	44
4.13 Restrict access to Tomcat tomcat-users.xml (Scored)	46
4.14 Restrict access to Tomcat web.xml (Scored)	
5 Configure Realms	49
5.1 Use secure Realms (Scored)	
5.2 Use LockOut Realms (Scored)	50
6 Connector Security	51
6.1 Setup Client-cert Authentication (Scored)	51
6.2 Ensure SSLEnabled is set to True for Sensitive Connectors (Not Scored)	53
6.3 Ensure scheme is set accurately (Scored)	54
6.4 Ensure secure is set to true only for SSL-enabled Connectors (Scored)	55
6.5 Ensure SSL Protocol is set to TLS for Secure Connectors (Scored)	56
7 Establish and Protect Logging Facilities	57
7.1 Application specific logging (Scored)	57
7.2 Specify file handler in logging.properties files (Scored)	58
7.3 Ensure className is set correctly in context.xml (Scored)	59
7.4 Ensure directory in context.xml is a secure location (Scored)	60
7.5 Ensure pattern in context.xml is correct (Scored)	61
7.6 Ensure directory in logging.properties is a secure location (Scored)	62
7.7 Configure log file size limit (Scored)	63
8 Configure Catalina Policy	64

8.1 Restrict runtime access to sensitive packages (Scored)	64	
9 Application Deployment	65	
9.1 Starting Tomcat with Security Manager (Scored)	65	
9.2 Disabling auto deployment of applications (Scored)		
9.3 Disable deploy on startup of applications (Scored)		
10 Miscellaneous Configuration Settings	68	
10.1 Ensure Web content directory is on a separate partition from the Tomcat system files (Not Scored)	68	
10.2 Restrict access to the web administration (Not Scored)	69	
10.3 Restrict manager application (Not Scored)	70	
10.4 Force SSL when accessing the manager application (Scored)	71	
10.5 Rename the manager application (Scored)	72	
10.6 Enable strict servlet Compliance (Scored)	74	
10.7 Turn off session façade recycling (Scored)	75	
10.8 Do not allow additional path delimiters (Scored)	76	
10.9 Do not allow custom header status messages (Scored)	77	
10.10 Configure connectionTimeout (Scored)	78	
10.11 Configure maxHttpHeaderSize (Scored)	79	
10.12 Force SSL for all applications (Scored)	80	
10.14 Do not allow symbolic linking (Scored)	81	
10.15 Do not run applications as privileged (Scored)	82	
10.16 Do not allow cross context requests (Scored)	83	
10.17 Do not resolve hosts on logging valves (Scored)	84	
10.18 Enable memory leak listener (Scored)	85	
10.19 Setting Security Lifecycle Listener (Scored)	86	
10.20 use the logEffectiveWebXml and metadata-complete settings for deploying applications in production (Scored)	_	
Appendix: Change History	92	

Overview

This document, Security Configuration Benchmark for Apache Tomcat 8.0, provides prescriptive guidance for establishing a secure configuration posture for Apache Tomcat versions 8.0 running on Linux. This guide was tested against Apache Tomcat 8.0 as installed by tar packages provided by Apache. To obtain the latest version of this guide, please visit http://cisecurity.org. If you have questions, comments, or have identified ways to improve this guide, please write us at feedback@cisecurity.org.

Intended Audience

This document is intended for system and application administrators, security specialists, auditors, help desk, and platform deployment personnel who plan to develop, deploy, assess, or secure solutions that incorporate Apache Tomcat on a Linux platform.

Consensus Guidance

This benchmark was created using a consensus review process comprised of subject matter experts. Consensus participants provide perspective from a diverse set of backgrounds including consulting, software development, audit and compliance, security research, operations, government, and legal.

Each CIS benchmark undergoes two phases of consensus review. The first phase occurs during initial benchmark development. During this phase, subject matter experts convene to discuss, create, and test working drafts of the benchmark. This discussion occurs until consensus has been reached on benchmark recommendations. The second phase begins after the benchmark has been published. During this phase, all feedback provided by the Internet community is reviewed by the consensus team for incorporation in the benchmark. If you are interested in participating in the consensus process, please visit https://community.cisecurity.org.

Typographical Conventions

The following typographical conventions are used throughout this guide:

Convention	Meaning
Stylized Monospace font	Used for blocks of code, command, and script examples.
	Text should be interpreted exactly as presented.
Monospace font	Used for inline code, commands, or examples. Text should
	be interpreted exactly as presented.
<italic brackets="" font="" in=""></italic>	Italic texts set in angle brackets denote a variable
	requiring substitution for a real value.
Italic font	Used to denote the title of a book, article, or other
	publication.
Note	Additional information or caveats

Scoring Information

A scoring status indicates whether compliance with the given recommendation impacts the assessed target's benchmark score. The following scoring statuses are used in this benchmark:

Scored

Failure to comply with "Scored" recommendations will decrease the final benchmark score. Compliance with "Scored" recommendations will increase the final benchmark score.

Not Scored

Failure to comply with "Not Scored" recommendations will not decrease the final benchmark score. Compliance with "Not Scored" recommendations will not increase the final benchmark score.

Profile Definitions

The following configuration profiles are defined by this Benchmark:

• Level 1

Items in this profile intend to:

- o be practical and prudent;
- o provide a clear security benefit; and
- o not inhibit the utility of the technology beyond acceptable means.

• Level 2

This profile extends the "Level 1" profile. Items in this profile exhibit one or more of the following characteristics:

- o are intended for environments or use cases where security is paramount
- o acts as defense in depth measure
- o may negatively inhibit the utility or performance of the technology

Acknowledgements

This benchmark exemplifies the great things a community of users, vendors, and subject matter experts can accomplish through consensus collaboration. The CIS community thanks the entire consensus team with special recognition to the following individuals who contributed greatly to the creation of this guide:

Editor

Alex Dong Sherif Mansour

Recommendations

1 Remove Extraneous Resources

1.1 Remove extraneous files and directories (Scored)

Profile Applicability:

• Level 2

Description:

The installation may provide example applications, documentation, and other directories which may not serve a production use.

Rationale:

Removing sample resources is a defense in depth measure that reduces potential exposures introduced by these resources.

Audit:

Perform the following to determine the existence of extraneous resources:

1. List all files extraneous files. The following should yield no output:

```
$ ls -1 $CATALINA_HOME/webapps/docs \
$CATALINA_HOME/webapps/examples
```

Remediation:

Perform the following to remove extraneous resources:

1. The following should yield no output:

```
$ rm -rf $CATALINA_HOME/webapps/docs \
    $CATALINA_HOME/webapps/examples
```

If the Manager application is not utilized, also remove the following resources:

```
$ rm -rf $CATALINA_HOME/webapps/host-manager \
    $CATALINA_HOME/webapps/manager \
    $CATALINA_HOME/conf/Catalina/localhost/manager.xml
```

Default Value:

"docs", "examples", "manager" and "host-manager" are default web applications shipped with Tomcat.



1.2 Disable Unused Connectors (Not Scored)

Profile Applicability:

• Level 2

Description:

The default installation of Tomcat includes connectors with default settings. These are traditionally set up for convenience. It is best to remove these connectors and enable only what is needed.

Rationale:

Improperly configured or unnecessarily installed Connectors may lead to a security exposure.

Audit:

Perform the following to identify configured Connectors:

1. Execute the following command to find configured Connectors. Ensure only those required are present and not commented out:

```
$ grep "Connector" $CATALINA HOME/conf/server.xml
```

Remediation:

Perform the following to disable unused Connectors:

1. Within \$CATALINA_HOME/conf/server.xml, remove or comment each unused Connector. For example, to disable an instance of the HTTPConnector, remove the following:

```
<Connector className="org.apache.catalina.connector.http.HttpConnector"
...
connectionTimeout="60000"/>
```

Default Value:

\$CATALINA_HOME/conf/server.xml, has the following connectors defined by default:

- A non-SSL Connector bound to port 8080
- An AJP 1.3 Connector bound to port 8009

References:

 $1. \ \ \, \underline{http://tomcat.apache.org/tomcat-8.0-doc/config/http.html\#Connector\ Comparison}$



2 Limit Server Platform Information Leaks

Limiting Server Platform Information Leaks make it harder for attackers to determine which vulnerabilities affect the server platform.

2.1 Alter the Advertised server.info String (Scored)

Profile Applicability:

• Level 2

Description:

The server.info attribute contains the name of the application service. This value is presented to Tomcat clients when clients connect to the tomcat server.

Rationale:

Altering the server.info attribute may make it harder for attackers to determine which vulnerabilities affect the server platform.

Audit:

Perform the following to determine if the server.info value has been changed:

1. Extract the ServerInfo.properties file and examine the server.info attribute.

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
$ grep server.info org/apache/catalina/util/ServerInfo.properties
```

Remediation:

Perform the following to alter the server platform string that gets displayed when clients connect to the tomcat server.

1. Extract the ServerInfo.properties file from the catalina.jar file:

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
```

2. Navigate to the util directory that was created

```
cd org/apache/catalina/util
```

- 3. Open ServerInfo.properties in an editor
- 4. Update the server info attribute in the ServerInfo.properties file.

server.info=<SomeWebServer>

5. Update the catalina.jar with the modified ServerInfo.properties file.

\$ jar uf catalina.jar org/apache/catalina/util/ServerInfo.properties

Impact:

Altering the server.info attribute may make it harder for attackers to determine which vulnerabilities affect the server platform.

Default Value:

The default value for the server.info attribute is Apache Tomcat/.. For example, Apache Tomcat/7.0.

References:

1. http://www.owasp.org/index.php/Securing tomcat

2.2 Alter the Advertised server.number String (Scored)

Profile Applicability:

• Level 2

Description:

The server.number attribute represents the specific version of Tomcat that is executing. This value is presented to Tomcat clients when connect.

Rationale:

Advertising a valid server version may provide attackers with information useful for locating vulnerabilities that affect the server platform. Altering the server version string may make it harder for attackers to determine which vulnerabilities affect the server platform.

Audit:

Perform the following to determine if the server.number value has been changed:

1. Extract the ServerInfo.properties file and examine the server.number attribute.

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
$ grep server.number org/apache/catalina/util/ServerInfo.properties
```

Remediation:

Perform the following to alter the server version string that gets displayed when clients connect to the server.

1. Extract the ServerInfo.properties file from the catalina.jar file:

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
```

2. Navigate to the util directory that was created

```
$ cd org/apache/Catalina/util
```

- 3. Open ServerInfo.properties in an editor
- 4. Update the server.number attribute

```
server.number=<someversion>
```

5. Update the catalina.jar with the modified ServerInfo.properties file.

\$ jar uf catalina.jar org/apache/catalina/util/ServerInfo.properties

Default Value:

The default value for the server.number attribute is a four part version number, such as 5.5.20.0.



2.3 Alter the Advertised server.built Date (Scored)

Profile Applicability:

• Level 2

Description:

The server built date represents the date which Tomcat was compiled and packaged. This value is presented to Tomcat clients when clients connect to the server.

Rationale:

Altering the server built string may make it harder for attackers to fingerprint which vulnerabilities affect the server platform.

Audit:

Perform the following to determine if the server built value has been changed:

1. Extract the ServerInfo.properties file and examine the server.built attribute.

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
$ grep server.built org/apache/catalina/util/ServerInfo.properties
```

Remediation:

Perform the following to alter the server version string that gets displayed when clients connect to the server.

1. Extract the ServerInfo.properties file from the catalina.jar file:

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
```

2. Navigate to the util directory that was created

```
$ cd org/apache/Catalina/util
```

- 3. Open ServerInfo.properties in an editor
- 4. Update the server built attribute in the ServerInfo.properties file.

```
server.built=
```

5. Update the catalina iar with the modified ServerInfo properties file.

Default Value:

The default value for the server built attribute is build date and time. For example, Jul 8 $2008\ 11:40:35.$



2.4 Disable X-Powered-By HTTP Header and Rename the Server Value for all Connectors (Scored)

Profile Applicability:

• Level 2

Description:

The xpoweredBy setting determines if Apache Tomcat will advertise its presence via the XPowered-By HTTP header. It is recommended that this value be set to false. The server attribute overrides the default value that is sent down in the HTTP header further masking Apache Tomcat.

Rationale:

Preventing Tomcat from advertising its presence in this manner may make it harder for attackers to determine which vulnerabilities affect the server platform.

Audit:

Perform the following to determine if the server platform, as advertised in the HTTP Server header, has been changed:

- 1. Locate all Connector elements in \$CATALINA_HOME/conf/server.xml.
- 2. Ensure each Connector has a server attribute and that the server attribute does not reflect Apache Tomcat. Also, make sure that the xpoweredBy attribute is NOT set to true.

Remediation:

Perform the following to prevent Tomcat from advertising its presence via the X-PoweredBy HTTP header.

1. Add the xpoweredBy attribute to each Connector specified in \$CATALINA_HOME/conf/server.xml. Set the xpoweredBy attributes value to false.

```
<Connector
...
xpoweredBy="false" />
```

Alternatively, ensure the xpoweredBy attribute for each Connector specified in \$CATALINA_HOME/conf/server.xml is absent.

2. Add the server attribute to each Connector specified in \$CATALINA_HOME/conf/server.xml. Set the server attribute value to anything except a blank string.

Default Value:

The default value is false.

References:

1. http://tomcat.apache.org/tomcat-8.0-doc/config/http.html

2.5 Disable client facing Stack Traces (Scored)

Profile Applicability:

• Level 1

Description:

When a runtime error occurs during request processing, Apache Tomcat will display debugging information to the requestor. It is recommended that such debug information be withheld from the requestor.

Rationale:

Debugging information, such as that found in call stacks, often contains sensitive information that may useful to an attacker. By preventing Tomcat from providing this information, the risk of leaking sensitive information to a potential attacker is reduced.

Audit:

Perform the following to determine if Tomcat is configured to prevent sending debug information to the requestor

- 1. Ensure an <error-page> element is defined in\$ CATALINA_HOME/conf/web.xml.
- 2. Ensure the <error-page> element has an <exception-type> child element with a value of java.lang.Throwable.
- 3. Ensure the <error-page> element has a <location> child element.

Note: Perform the above for each application hosted within Tomcat. Per application instances of web.xml can be found at \$CATALINA_HOME/webapps/<APP_NAME>/WEB-INF/web.xml

Remediation:

Perform the following to prevent Tomcat from providing debug information to the requestor during runtime errors:

- 1. Create a web page that contains the logic or message you wish to invoke when encountering a runtime error. For example purposes, assume this page is located at /error.isp.
- 2. Add a child element, <error-page>, to the <web-app>element, in the \$CATALINA_HOME/conf/web.xml file.
- 3. Add a child element, <exception-type>, to the <error-page> element. Set the value of the <exception-type> element to java.lang. Throwable.

4. Add a child element, <location>, to the <error-page> element. Set the value of the <location> element to the location of page created in #1.

The resulting entry will look as follows:

```
<error-page>
  <exception-type>java.lang.Throwable</exception-type>
  <location>/error.jsp</location>
  </error-page>
```

Default Value:

Tomcat's default configuration does not include an <error-page> element in \$CATALINA_HOME/conf/web.xml. Therefore, Tomcat will provide debug information to the requestor by default.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/api/org/apache/tomcat/util/descriptor/web/ErrorPage.html

2.6 Turn off TRACE (Scored)

Profile Applicability:

• Level 1

Description:

The HTTP TRACE verb provides debugging and diagnostics information for a given request.

Rationale:

Diagnostic information, such as that found in the response to a TRACE request, often contains sensitive information that may useful to an attacker. By preventing Tomcat from providing this information, the risk of leaking sensitive information to a potential attacker is reduced.

Audit:

Perform the following to determine if the server platform, as advertised in the HTTP Server header, has been changed:

- 1. Locate all Connector elements in \$CATALINA HOME/conf/server.xml.
- 2. Ensure each Connector does not have a allowTrace attribute or if the allowTrace attribute is not set true.

Note: Perform the above for each application hosted within Tomcat. Per application instances of web.xml can be found at \$CATALINA_HOME/webapps/<APP_NAME>/WEBINF/web.xml

Remediation:

Perform the following to prevent Tomcat from accepting a TRACE request:

- 1. Set the allowTrace attributes to each Connector specified in \$CATALINA HOME/conf/server.xml to false.
- 2. <Connector ... allowTrace="false" />

Alternatively, ensure the allowTrace attribute for each Connector specified in \$CATALINA_HOME/conf/server.xml is absent.

Default Value:

Tomcat does not allow the TRACE HTTP verb by default. Tomcat will only allow TRACE if the allowTrace attribute is present and set to true.

References:

1. http://tomcat.apache.org/tomcat-8.0-doc/config/http.html



3 Protect the Shutdown Port

Tomcat listens on TCP port 8005 to accept shutdown requests. By connecting to this port and sending the SHUTDOWN command, all applications within Tomcat are halted.

3.1 Set a nondeterministic Shutdown command value (Scored)

Profile Applicability:

• Level 1

Description:

Tomcat listens on TCP port 8005 to accept shutdown requests. By connecting to this port and sending the SHUTDOWN command, all applications within Tomcat are halted. The shutdown port is not exposed to the network as it is bound to the loopback interface. It is recommended that a nondeterministic value be set for the shutdown attribute in \$CATALINA_HOME/conf/server.xml.

Rationale:

Setting the shutdown attribute to a nondeterministic value will prevent malicious local users from shutting down Tomcat.

Audit:

Perform the following to determine if the shutdown port is configured to use the default shutdown command:

1. Ensure the shutdown attribute in \$CATALINA_HOME/conf/server.xml is not set to SHUTDOWN.

```
$ cd $CATALINA_HOME/conf
$ grep 'shutdown[[:space:]]*=[[:space:]]*"SHUTDOWN"' server.xml
```

Remediation:

Perform the following to set a nondeterministic value for the shutdown attribute.

- 1. Update the shutdown attribute in \$CATALINA_HOME/conf/server.xml as follows:
- 2. <Server port="8005" shutdown="NONDETERMINISTICVALUE">

Note: NONDETERMINISTICVALUE should be replaced with a sequence of random characters.

Default Value:

The default value for the shutdown attribute is SHUTDOWN.

References:

1. http://tomcat.apache.org/tomcat-8.0-doc/config/server.html

3.2 Disable the Shutdown port (Not Scored)

Profile Applicability:

• Level 2

Description:

Tomcat listens on TCP port 8005 to accept shutdown requests. By connecting to this port and sending the SHUTDOWN command, all applications within Tomcat are halted. The shutdown port is not exposed to the network as it is bound to the loopback interface. If this functionality is not used, it is recommended that the Shutdown port be disabled.

Rationale:

Disabling the Shutdown port will eliminate the risk of malicious local entities using the shutdown command to disable the Tomcat server.

Audit:

Perform the following to determine if the shutdown port has been disabled:

1. Ensure the port attribute in \$CATALINA_HOME/conf/server.xml is set to -1.

```
2. $ cd $CATALINA_HOME/conf/
$ grep '<Server[[:space:]]\+[^>]*port[[:space:]]*=[[:space:]]*"-1"' server.xml
```

Remediation:

Perform the following to disable the Shutdown port.

1. Set the port to -1 in the \$CATALINA_HOME/conf/server.xml file:

```
<Server port="-1" shutdown="SHUTDOWN">
```

Default Value:

The shutdown port is enabled on TCP port 8005, bound to the loopback address.

References:

1. http://tomcat.apache.org/tomcat-8.0-doc/config/server.html

4 Protect Tomcat Configurations

The security of processes and data that traverse or depend on Tomcat may become compromised if the is not Tomcat configurations are not secured.

4.1 Restrict access to \$CATALINA_HOME (Scored)

Profile Applicability:

• Level 1

Description:

\$CATALINA_HOME is the environment variable which holds the path to the root Tomcat directory. It is important to protect access to this in order to protect the Tomcat binaries and libraries from unauthorized modification. It is recommended that the ownership of \$CATALINA_HOME be tomcat_admin:tomcat. It is also recommended that the permission on \$CATALINA_HOME prevent read, write, and execute for the world (o-rwx) and prevent write access to the group (g-w).

Rationale:

The security of processes and data that traverse or depend on Tomcat may become compromised if the \$CATALINA_HOME is not secured.

Audit:

Perform the following to ensure the permission on the \$CATALINA_HOME directory prevent unauthorized modification.

```
$ cd $CATALINA_HOME
$ find . -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g=w ! -user tomcat_admin \) -ls
```

The above command should not emit any output.

Remediation:

Perform the following to establish the recommended state:

- 1. Set the ownership of the \$CATALINA_HOME to tomcat_admin:tomcat.
- 2. Remove read, write, and execute permissions for the world
- 3. Remove write permissions for the group.

```
# chown tomcat_admin.tomcat $CATALINA_HOME
# chmod g-w,o-rwx $CATALINA_HOME
```

4.2 Restrict access to \$CATALINA BASE (Scored)

Profile Applicability:

• Level 1

Description:

\$CATALINA_BASE is the environment variable that specifies the base directory which most relative paths are resolved. \$CATALINA_BASE is usually used when there is multiple instances of Tomcat running. It is important to protect access to this in order to protect the Tomcat-related binaries and libraries from unauthorized modification. It is recommended that the ownership of \$CATALINA_BASE be tomcat_admin:tomcat. It is also recommended that the permission on \$CATALINA_BASE prevent read, write, and execute for the world (orwx) and prevent write access to the group (g-w).

Rationale:

The security of processes and data that traverse or depend on Tomcat may become compromised if the \$CATALINA_BASE is not secured.

Audit:

Perform the following to ensure the permission on the \$CATALINA_BASE directory prevent unauthorized modification.

```
$ cd $CATALINA_BASE
$ find . -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g=w ! -user tomcat_admin \) -ls
```

The above command should not emit any output.

Remediation:

Perform the following to establish the recommended state:

- 1. Set the ownership of the \$CATALINA BASE to tomcat admin:tomcat.
- 2. Remove read, write, and execute permissions for the world
- 3. Remove write permissions for the group.

```
# chown tomcat_admin.tomcat $CATALINA_BASE
# chmod g-w,o-rwx $CATALINA_BASE
```

4.3 Restrict access to Tomcat configuration directory (Scored)

Profile Applicability:

• Level 1

Description:

The Tomcat \$CATALINA_HOME/conf/ directory contains Tomcat configuration files. It is recommended that the ownership of this directory be tomcat_admin:tomcat. It is also recommended that the permissions on this directory prevent read, write, and execute for the world (o-rwx) and prevent write access to the group (g-w).

Rationale:

Restricting access to these directories will prevent local users from maliciously or inadvertently altering Tomcat's configuration.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/conf are securely configured.

1. Change to the location of the \$CATALINA_HOME/conf and execute the following:

```
# cd $CATALINA_HOME/conf
# find catalina.policy -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g=w ! -
user tomcat_admin \) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to Tomcat configuration files:

- 1. Set the ownership of the \$CATALINA_HOME/conf to tomcat_admin:tomcat.
- 2. Remove read, write, and execute permissions for the world
- 3. Remove write permissions for the group.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf
# chmod g-w,o-rwx $CATALINA_HOME/conf
```

Default Value:



4.4 Restrict access to Tomcat logs directory (Scored)

Profile Applicability:

• Level 1

Description:

The Tomcat \$CATALINA_HOME/logs/ directory contains Tomcat logs. It is recommended that the ownership of this directory be tomcat_admin:tomcat. It is also recommended that the permissions on this directory prevent read, write, and execute for the world (o-rwx).

Rationale:

Restricting access to these directories will prevent local users from maliciously or inadvertently altering Tomcat's logs.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/logs are securely configured.

1. Change to the location of the \$CATALINA_HOME/logs and execute the following:

```
# cd $CATALINA_HOME
# find logs -follow -maxdepth 0 \( -perm -o+rwx ! -user tomcat_admin \) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to Tomcat log files:

- 1. Set the ownership of the \$CATALINA_HOME/logs to tomcat_admin:tomcat.
- 2. Remove read, write, and execute permissions for the world

```
# chown tomcat_admin:tomcat $CATALINA_HOME/logs
# chmod o-rwx $CATALINA_HOME/logs
```

Default Value:

4.5 Restrict access to Tomcat temp directory (Scored)

Profile Applicability:

• Level 1

Description:

The Tomcat \$CATALINA_HOME/temp/ directory is used by Tomcat to persist temporary information to disk. It is recommended that the ownership of this directory be tomcat_admin:tomcat. It is also recommended that the permissions on this directory prevent read, write, and execute for the world (o-rwx).

Rationale:

Restricting access to these directories will prevent local users from maliciously or inadvertently affecting the integrity of Tomcat processes.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/temp are securely configured.

1. Change to the location of the \$CATALINA_HOME/temp and execute the following:

```
# cd $CATALINA_HOME
# find temp -follow -maxdepth 0 \( -perm -o+rwx ! -user tomcat_admin \) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to Tomcat log files:

- 1. Set the ownership of the \$CATALINA_HOME/logs to tomcat_admin:tomcat.
- 2. Remove read, write, and execute permissions for the world

```
# chown tomcat_admin:tomcat $CATALINA_HOME/temp
# chmod o-rwx $CATALINA_HOME/temp
```

Default Value:

4.6 Restrict access to Tomcat binaries directory (Scored)

Profile Applicability:

• Level 1

Description:

The Tomcat \$CATALINA_HOME/bin/ directory contains executes that are part of the Tomcat run-time. It is recommended that the ownership of this directory be tomcat_admin:tomcat. It is also recommended that the permission on \$CATALINA_HOME prevent read, write, and execute for the world (o-rwx) and prevent write access to the group (g-w).

Rationale:

Restricting access to these directories will prevent local users from maliciously or inadvertently affecting the integrity of Tomcat processes.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/bin are securely configured.

1. Change to the location of the \$CATALINA_HOME/bin and execute the following:

```
# cd $CATALINA_HOME
# find bin -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g=w ! -user tomcat_admin \) -
ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to Tomcat log files:

- 1. Set the ownership of the \$CATALINA HOME/logs to tomcat admin:tomcat.
- 2. Remove read, write, and execute permissions for the world

```
# chown tomcat_admin:tomcat $CATALINA_HOME/bin
# chmod g-w,o-rwx $CATALINA_HOME/bin
```

Default Value:

4.7 Restrict access to Tomcat web application directory (Scored)

Profile Applicability:

• Level 1

Description:

The Tomcat \$CATALINA_HOME/webapps directory contains web applications that are deployed through Tomcat. It is recommended that the ownership of this directory be tomcat_admin:tomcat. It is also recommended that the permission on \$CATALINA_HOME/webapps prevent read, write, and execute for the world (o-rwx) and prevent write access to the group (g-w).

Rationale:

Restricting access to these directories will prevent local users from maliciously or inadvertently affecting the integrity of web applications.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/webapps are securely configured.

1. Change to the location of the \$CATALINA_HOME/webapps and execute the following:

```
# cd $CATALINA_HOME
# find webapps -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g=w ! -user
tomcat_admin \( ) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to Tomcat log files:

- 1. Set the ownership of the \$CATALINA_HOME/webapps to tomcat_admin:tomcat.
- 2. Remove read, write, and execute permissions for the world.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/webapps
# chmod g-w,o-rwx $CATALINA_HOME/webapps
```

Default Value:

The default permissions of the top-level directories is 770.



4.8 Restrict access to Tomcat catalina.policy (Scored)

Profile Applicability:

• Level 1

Description:

The catalina.policy file is used to configure security policies for Tomcat. It is recommended that access to this file has the proper permissions to properly protect from unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/conf/catalina.policy care securely configured.

1. Change to the location of the \$CATALINA_HOME/ and execute the following:

```
# cd $CATALINA_HOME/conf/
# find catalina.policy -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g+rwx ! -
user tomcat_admin -group tomcat -perm /770 \) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to \$CATALINA_HOME/conf/catalina.policy.

1. Set the owner and group owner of the contents of \$CATALINA_HOME/ to tomcat_admin and tomcat, respectively.

```
# chmod 770 $CATALINA_HOME/conf/catalina.policy
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/catalina.policy
```

Default Value:

The default permissions of catalina.policy is 600.

4.9 Restrict access to Tomcat catalina.properties (Scored)

Profile Applicability:

• Level 1

Description:

catalina.properties is a Java properties files that contains settings for Tomcat including class loader information, security package lists, and performance properties. It is recommended that access to this file has the proper permissions to properly protect from unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/conf/catalina.properties care securely configured.

1. Change to the location of the \$CATALINA_HOME/ and execute the following:

```
# cd $CATALINA_HOME/conf/
# find catalina.properties -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g=w !
-user tomcat_admin \) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to catalina.policy:

- 1. Set the ownership of the \$CATALINA_HOME/conf/catalina.policy to tomcat admin:tomcat.
- 2. Remove read, write, and execute permissions for the world.
- 3. Remove write permissions for the group.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/catalina.properties
# chmod g-w,o-rwx $CATALINA_HOME/conf/catalina.properties
```

Default Value:

The default permissions of the top-level directories is 600.



4.10 Restrict access to Tomcat context.xml (Scored)

Profile Applicability:

• Level 1

Description:

The context.xml file is loaded by all web applications and sets certain configuration options. It is recommended that access to this file has the proper permissions to properly protect from unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/conf/context.xml care securely configured.

1. Change to the location of the \$CATALINA_HOME/conf and execute the following:

```
# cd $CATALINA_HOME/conf
# find context.xml -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g=w ! -user
tomcat admin \) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to context.xml:

- Set the ownership of the \$CATALINA_HOME/conf/context.xml to tomcat_admin:tomcat.
- 2. Remove read, write, and execute permissions for the world.
- 3. Remove write permissions for the group.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/context.xml
# chmod g-w,o-rwx $CATALINA_HOME/conf/context.xml
```

Default Value:

The default permissions of context.xml are 600.



4.11 Restrict access to Tomcat logging.properties (Scored)

Profile Applicability:

• Level 1

Description:

logging.properties is a Tomcat files which specifies the logging configuration. It is recommended that access to this file has the proper permissions to properly protect from unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/conf/logging.properties care securely configured.

1. Change to the location of the \$CATALINA_HOME/conf and execute the following:

```
# cd $CATALINA_HOME/conf/
# find logging.properties -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g=w ! -
user tomcat_admin \) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to logging properties:

- 1. Set the ownership of the \$CATALINA_HOME/conf/logging.properties to tomcat_admin:tomcat.
- 2. Remove read, write, and execute permissions for the world.
- 3. Remove write permissions for the group.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/logging.properties
# chmod g-w,o-rwx $CATALINA_HOME/conf/logging.properties
```

Default Value:

The default permissions are 600.



4.12 Restrict access to Tomcat server.xml (Scored)

Profile Applicability:

• Level 1

Description:

server.xml contains Tomcat servlet definitions and configurations. It is recommended that access to this file has the proper permissions to properly protect from unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/conf/server.xml care securely configured.

1. Change to the location of the \$CATALINA_HOME/conf and execute the following:

```
# cd $CATALINA_HOME/conf/
# find server.xml -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g=w ! -user
tomcat_admin \( ) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to server.xml:

- 1. Set the ownership of the \$CATALINA_HOME/conf/server.xml to tomcat_admin:tomcat.
- 2. Remove read, write, and execute permissions for the world.
- 3. Remove write permissions for the group.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/server.xml
# chmod g-w,o-rwx $CATALINA_HOME/conf/server.xml
```

Default Value:

The default permissions of the top-level directories is 600.



4.13 Restrict access to Tomcat tomcat-users.xml (Scored)

Profile Applicability:

• Level 1

Description:

tomcat-users.xml contains authentication information for Tomcat applications. It is recommended that access to this file has the proper permissions to properly protect from unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/conf/tomcat-users.xml care securely configured.

1. Change to the location of the \$CATALINA_HOME/conf and execute the following:

```
# cd $CATALINA_HOME/conf/
# find tomcat-users.xml -follow -maxdepth 0 \( -perm -o-rwx -o -perm -g-w ! -
user tomcat admin \) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to tomcat-users.xml:

- Set the ownership of the \$CATALINA_HOME/conf/tomcat-users.xml to tomcat_admin:tomcat.
- 2. Remove read, write, and execute permissions for the world.
- 3. Remove write permissions for the group.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/tomcat-users.xml
# chmod g-w,o-rwx $CATALINA_HOME/conf/tomcat-users.xml
```

Default Value:

The default permissions of the top-level directories is 600.



4.14 Restrict access to Tomcat web.xml (Scored)

Profile Applicability:

• Level 1

Description:

web.xml is a Tomcat configuration file that stores application configuration settings. It is recommended that access to this file has the proper permissions to properly protect from unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA_HOME/conf/web.xml care securely configured.

1. Change to the location of the \$CATALINA_HOME/conf and execute the following:

```
# cd $CATALINA_HOME/conf/
# find web.xml -follow -maxdepth 0 \( -perm -o+rwx -o -perm -g=w ! -user
tomcat_admin \( ) -ls
```

Note: If the ownership and permission are set correctly, no output should be displayed when executing the above command.

Remediation:

Perform the following to restrict access to web.xml:

- 1. Set the ownership of the \$CATALINA HOME/conf/web.xml to tomcat admin:tomcat.
- 2. Remove read, write, and execute permissions for the world.
- 3. Remove write permissions for the group.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/web.xml
# chmod g-w,o-rwx $CATALINA_HOME/conf/web.xml
```

Default Value:

The default permissions of web.xml is 400.

5 Configure Realms

A Tomcat realm is a database of usernames and passwords used to identify valid users of web applications.

5.1 Use secure Realms (Scored)

Profile Applicability:

• Level 2

Description:

A realm is a database of usernames and passwords used to identify valid users of web applications. Review the Realms configuration to ensure Tomcat is configured to use JDBCRealm, UserDatabaseRealm, or JAASRealm. Specifically, Tomcat should not utilize MemoryRealm.

Rationale:

According to the Tomcat documentation, MemoryRealm, JDBCRealm are not designed for production usage and could result in reduced availability, the UserDatabaseRealm is not intended for large-scale installations, the JAASRealm is not widely used and therefore the code is not as mature as the other realms.

Audit:

Perform the following to ensure improper realm is not in use:

```
# grep "Realm className" $CATALINA_HOME/conf/server.xml | grep MemoryRealm
# grep "Realm className" $CATALINA_HOME/conf/server.xml | grep JDBCRealm
# grep "Realm className" $CATALINA_HOME/conf/server.xml | grep UserDatabaseRealm
# grep "Realm className" $CATALINA_HOME/conf/server.xml | grep JAASRealm
```

The above commands should not emit any output.

Remediation:

Set the Realm className setting in \$CATALINA_HOME/conf/server.xml to one of the appropriate realms.

- 1. http://tomcat.apache.org/tomcat-8.0-doc/realm-howto.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/security-howto.html

5.2 Use LockOut Realms (Scored)

Profile Applicability:

• Level 2

Description:

A LockOut realm wraps around standard realms adding the ability to lock a user out after multiple failed logins.

Rationale:

Locking out a user after multiple failed logins slows down attackers from brute forcing logins.

Audit:

Perform the following to check to see if a LockOut realm is being used:

```
# grep "LockOutRealm" $CATALINA_HOME/conf/server.xml
```

Remediation:

Create a lockout realm wrapping the main realm like the example below:

- 1. http://tomcat.apache.org/tomcat-8.0-doc/realm-howto.html
- 2. http://tomcat.apache.org/tomcat-8.0-doc/config/realm.html

6 Connector Security

Tomcat Connector Security will ensure applications built on Tomcat have an accurate depiction of the context and security guarantees provided to them.

6.1 Setup Client-cert Authentication (Scored)

Profile Applicability:

• Level 2

Description:

Client-cert authentication requires that each client connecting to the server has a certificate used to authenticate. This is generally regarded as strong authentication than a password as it requires the client to have the cert and not just know a password.

Rationale:

Certificate based authentication is more secure than password based authentication.

Audit:

Review the Connector configuration in server.xml and ensure the clientAuth parameter is set to true.

Remediation:

In the Connector element, set the clientAuth parameter to true.

```
<-- Define a SSL Coyote HTTP/1.1 Connector on port 8443 -->

<Connector
   port="8443" minProcessors="5" maxProcessors="75"
   enableLookups="true" disableUploadTimeout="true"
   acceptCount="100" debug="0" scheme="https" secure="true";
   clientAuth="true" sslProtocol="TLS"/>
```

Default Value:

Not configured

- https://tomcat.apache.org/tomcat-8.0-doc/config/http.html
 http://tomcat.apache.org/tomcat-8.0-doc/ssl-howto.html



6.2 Ensure SSLEnabled is set to True for Sensitive Connectors (Not Scored)

Profile Applicability:

• Level 1

Description:

The SSLEnabled setting determines if SSL is enabled for a specific Connector. It is recommended that SSL be utilized for any Connector that sends or receives sensitive information, such as authentication credentials or personal information.

Rationale:

The SSLEnabled setting ensures SSL is active, which will in-turn ensure the confidentiality and integrity of sensitive information while in transit.

Audit:

Review server.xml and ensure all Connectors sending or receiving sensitive information have the SSLEnabled attribute set to true.

Remediation:

In server.xml, set the SSLEnabled attribute to true for each Connector that sends or receives sensitive information

```
<Connector
...
SSLEnabled="true"
...
/>
```

Default Value:

SSLEnabled is set to false.

- 1. http://tomcat.apache.org/tomcat-8.0-doc/ssl-howto.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html

6.3 Ensure scheme is set accurately (Scored)

Profile Applicability:

• Level 1

Description:

The scheme attribute is used to indicate to callers of request.getScheme() which scheme is in use by the Connector. Ensure the scheme attribute is set to http for Connectors operating over HTTP. Ensure the scheme attribute is set to https for Connectors operating of HTTPS.

Rationale:

Maintaining parity between the scheme in use by the Connector and advertised by request.getScheme() will ensure applications built on Tomcat have an accurate depiction of the context and security guarantees provided to them.

Audit:

Review server.xml to ensure the Connector's scheme attribute is set to http for Connectors operating over HTTP. Also ensure the Connector's scheme attribute is set to https for Connectors operating over HTTPS.

Remediation:

In server.xml, set the Connector's scheme attribute to http for Connectors operating over HTTP. Set the Connector's scheme attribute to https for Connectors operating of HTTPS.

```
<Connector
...
scheme="https"
...
/>
```

Default Value:

The scheme attribute is set to http.

- 1. http://tomcat.apache.org/tomcat-8.0-doc/ssl-howto.html
- 2. http://tomcat.apache.org/tomcat-8.0-doc/config/http.html

6.4 Ensure secure is set to true only for SSL-enabled Connectors (Scored)

Profile Applicability:

• Level 1

Description:

The secure attribute is used to convey Connector security status to applications operating over the Connector. This is typically achieved by calling request.isSecure(). Ensure the secure attribute is only set to true for Connectors operating with the SSLEnabled attribute set to true.

Rationale:

Accurately reporting the security state of the Connector will help ensure that applications built on Tomcat are not unknowingly relying on security controls that are not in place.

Audit:

Review server.xml and ensure the secure attribute is set to true for those Connectors having SSLEnabled set to true. Also, ensure the secure attribute set to false for those Connectors having SSLEnabled set to false.

Remediation:

For each Connector defined in server.xml, set the secure attribute to true for those Connectors having SSLEnabled set to true. Set the secure attribute set to false for those Connectors having SSLEnabled set to false.

```
<Connector SSLEnabled="true"
    ...
    secure="true"
    ...
/>
```

Default Value:

The secure attribute is set to false.

- 1. http://tomcat.apache.org/tomcat-8.0-doc/ssl-howto.html
- 2. http://tomcat.apache.org/tomcat-8.0-doc/config/http.html

6.5 Ensure SSL Protocol is set to TLS for Secure Connectors (Scored)

Profile Applicability:

• Level 1

Description:

The sslProtocol setting determines which protocol Tomcat will use to protect traffic. It is recommended that sslProtocol attribute be set to TLS.

Rationale:

The TLS protocol does not contain weaknesses that affect other secure transport protocols, such as SSLv1 or SSLv2. Therefore, TLS is leveraged to protect the confidentiality and integrity of data while in transit.

Audit:

Review server.xml to ensure the sslProtocol attribute is set to TLS for all Connectors having SSLEngine set to on.

Remediation:

In server.xml, set the sslProtocol attribute to "TLS" for Connectors having SSLEnabled set to true.

```
<Connector
...
sslProtocol="TLS"
...
/>
```

Default Value:

If not specified, the default value of "TLS" will be used.

- 1. http://tomcat.apache.org/tomcat-8.0-doc/ssl-howto.html
- 2. http://tomcat.apache.org/tomcat-8.0-doc/config/http.html

7 Establish and Protect Logging Facilities

Enable logging and ensure logs are properly protected

7.1 Application specific logging (Scored)

Profile Applicability:

• Level 2

Description:

By default, java.util.logging does not provide the capabilities to configure per-web application settings, only per VM. In order to overcome this limitation Tomcat implements JULI as a wrapper for java.util.logging. JULI provides additional configuration functionality so you can set each web application with different logging specifications.

Rationale:

Establishing per application logging profiles will help ensure that each application's logging verbosity is set to an appropriate level in order to provide appropriate information when needed for security review.

Audit:

Ensure a logging.properties file is locate at \$CATALINA_BASE\webapps\<app_name>\WEB-INF\classes.

Remediation:

Create a logging.properties file and place that into your application WEB-INF\classes directory. Note: By default, installing Tomcat places a logging.properties file in \$CATALINA_HOME\conf. This file can be used as base for an application specific logging properties file

Default Value:

By default, per application logging is not configured.

7.2 Specify file handler in logging.properties files (Scored)

Profile Applicability:

• Level 1

Description:

Handlers specify where log messages are sent. Console handlers send log messages to the Java console and File handlers specify logging to a file.

Rationale:

Utilizing file handlers will ensure that security event information is persisted to disk.

Audit:

Review each application's logging.properties file located in the applications \$CATALINA_BASE\webapps\<app name>\WEB-INF\classes directory and determine if the file handler properties are set.

```
$ grep handlers \
$CATALINA_BASE\webapps\<app name>\WEB-INF\classes\logging.properties
```

In the instance where an application specific logging has not been created, the logging.properties file will be located in \$CATALINA_BASE\conf

```
$ grep handlers $CATALINA_BASE\conf\logging.properties
```

Remediation:

Add the following entries to your logging properties file if they do not exist.

```
handlers=org.apache.juli.FileHandler, java.util.logging.ConsoleHandler
```

Ensure logging is not off and set the logging level to the desired level such as:

```
org.apache.juli.FileHandler.level=FINEST
```

Default Value:

No value for new applications by default.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/logging.html

7.3 Ensure className is set correctly in context.xml (Scored)

Profile Applicability:

• Level 2

Description:

Ensure the className attribute is set to AccessLogValve. The className attribute determines the access log valve to be used for logging.

Rationale:

Some log valves are not suited for production and should not be used. Apache recommends org.apache.catalina.valves.AccessLogValve

Audit:

Execute the following to ensure className is set properly:

```
# grep org.apache.catalina.valves.AccessLogValve $CATALINA_BASE\webapps\<app
name>\META-INF\context.xml
```

Remediation:

Add the following statement into the \$CATALINA_BASE\webapps\<app name>\META-INF\context.xml file if it does not already exist.

```
<Valve
className="org.apache.catalina.valves.AccessLogValve"
directory="$CATALINA_HOME/logs/"
prefix="access_log"
fileDateFormat="yyyy-MM-dd.HH"
suffix=".log"
pattern="%t %H cookie:%{SESSIONID}c request:%{SESSIONID}r %m %U %s %q %r"
/>
```

Default Value:

Does not exist by default.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/valve.html

7.4 Ensure directory in context.xml is a secure location (Scored)

Profile Applicability:

• Level 1

Description:

The directory attribute tells Tomcat where to store logs. It is recommended that the location pointed to by the directory attribute be secured.

Rationale:

Securing the log location will help ensure the integrity and confidentiality of web application activity.

Audit:

Review the permissions of the directory specified by the directory setting to ensure the permissions are o-rwx and owned by tomcat_admin:tomcat:

```
# grep directory context.xml
# ls -ld <log location>
```

Remediation:

Perform the following:

1. Add the following statement into the \$CATALINA_BASE\webapps\<app-name>\META-INF\context.xml file if it does not already exist.

```
<Valve className="org.apache.catalina.valves.AccessLogValve"
directory="$CATALINA_HOME/logs/"
prefix="access_log" fileDateFormat="yyyy-MM-dd.HH" suffix=".log" pattern="%t %H
cookie:%{SESSIONID}c request:%{SESSIONID}r %m %U %s %q %r"
/>
```

2. Set the location pointed to by the directory attribute to be owned by tomcat_admin:tomcat with permissions of o-rwx.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/logs
# chmod o-rwx $CATALINA_HOME/logs
```

Default Value:

Does not exist by default

7.5 Ensure pattern in context.xml is correct (Scored)

Profile Applicability:

• Level 1

Description:

The pattern setting informs Tomcat what information should be logged per applications. At a minimum, enough information to uniquely identify a request, what was requested, where the requested originated from, and when the request occurred should be logged. The following will log the request date and time (%t), the requested URL (%U), the remote IP address (%a), the local IP address (%A), the request method (%m), the local port (%p), query string, if present, (%q), and the HTTP status code of the response (%s).

```
pattern="%t %U %a %A %m %p %q %s"
```

Rationale:

The level of logging detail prescribed will assist in identifying correlating security events or incidents.

Audit:

Review the pattern settings to ensure it contains all the variables required by the installation.

```
# grep pattern $CATALINA_BASE\webapps\<app-name>\META-INF\context.xml
```

Remediation:

Add the following statement into the \$CATALINA_BASE\webapps\<app-name>\META-INF\context.xml file if it does not already exist.

```
<Valve
className="org.apache.catalina.valves.AccessLogValve" directory="$CATALINA_HOME/logs/"
prefix="access_log" fileDateFormat="yyyy-MM-dd.HH" suffix=".log"
pattern="%h %t %H cookie:%{SESSIONID}c request:%{SESSIONID}r %m %U %s %q %r"
/>
```

Default Value:

Does not exist by default

References:

1. http://tomcat.apache.org/tomcat-8.0-doc/config/valve.html

7.6 Ensure directory in logging.properties is a secure location (Scored)

Profile Applicability:

• Level 1

Description:

The directory attribute tells Tomcat where to store logs. The directory value should be a secure location with restricted access.

Rationale:

Securing the log location will help ensure the integrity and confidentiality of web application activity records.

Audit:

Review the permissions of the directory specified by the directory setting to ensure the permissions are o-rwx and owned by tomcat_admin:tomcat:

```
# grep directory logging.properties
# ls -ld <log_location>
```

Remediation:

Perform the following:

1. Add the following properties into your logging.properties file if they do not exist

```
<application_name>.org.apache.juli.FileHandler.directory=<log_location>
<application_name>.org.apache.juli.FileHandler.prefix=<application_name>
```

2. Set the location pointed to by the directory attribute to be owned by tomcat_admin:tomcat with permissions of o-rwx.

```
# chown tomcat_admin:tomcat <log_location>
# chmod o-rwx <log_location>
```

Default Value:

The directory location is configured to store logs in \$CATALINA_BASE/logs

7.7 Configure log file size limit (Scored)

Profile Applicability:

• Level 2

Description:

By default, the logging.properties file will have no defined limit for the log file size. This is a potential denial of service attack as it would be possible to fill a drive or partition containing the log files.

Rationale:

Establishing a maximum log size that is smaller than the partition size will help mitigate the risk of an attacker maliciously exhausting disk space.

Audit:

Validate the max file limit is not greater than the size of the partition where the log files are stored.

Remediation:

Create the following entry in your logging.properties file. This field is specified in bytes.

java.util.logging.FileHandler.limit=10000

Default Value:

No limit by default.

References:

1. https://docs.oracle.com/javase/8/docs/api/java/util/logging/FileHandler.html

8 Configure Catalina Policy

Configuring Catalina Policy prevents web applications from accessing restricted or unknown packages which may be malicious or dangerous to the application.

8.1 Restrict runtime access to sensitive packages (Scored)

Profile Applicability:

• Level 1

Description:

package.access grants or revokes access to listed packages during runtime. It is recommended that application access to certain packages be restricted.

Rationale:

Prevent web applications from accessing restricted or unknown packages which may be malicious or dangerous to the application.

Audit:

Review package.access list in \$CATALINA_BASE/conf/catalina.properties to ensure only allowed packages are defined.

Remediation:

Edit \$CATALINA_BASE/conf/catalina.properties by adding allowed packages to the package.access list:

```
package.access = sun.,org.apache.catalina.,org.apache.coyote.,org.apache.tomcat.,
org.apache.jasper
```

Default Value:

The default package.access value within \$CATALINA_BASE/conf/catalina.properties is:

package.access = sun.,org.apache.catalina.,org.apache.coyote.,org.apache.tomcat., org.apache.jasper

9 Application Deployment

By running Tomcat with the Security Manager, applications are run in a sandbox which can prevent untrusted code from accessing files on the file system.

9.1 Starting Tomcat with Security Manager (Scored)

Profile Applicability:

• Level 1

Description:

Configure application to run in a sandbox using the Security Manager. The Security Manager restricts what classes Tomcat can access thus protecting your server from mistakes, Trojans, and malicious code.

Rationale:

By running Tomcat with the Security Manager, applications are run in a sandbox which can prevent untrusted code from accessing files on the file system.

Audit:

Review the start up configuration in /etc/init.d for Tomcat to ascertain if Tomcat is started with the -security option

Remediation:

The security policies implemented by the Java SecurityManager are configured in the \$CATALINA_HOME/conf/catalina.policy file. Once you have configured the catalina.policy file for use with a SecurityManager, Tomcat can be started with a SecurityManager in place by using the --security option:

```
$ $CATALINA_HOME/bin/catalina.sh start -security (Unix)
C:\> %CATALINA HOME%\bin\catalina start -security (Windows)
```

Default Value:

By default the -security option is not utilized.

References:

1. http://tomcat.apache.org/tomcat-8.0-doc/security-manager-howto.html

9.2 Disabling auto deployment of applications (Scored)

Profile Applicability:

• Level 2

Description:

Tomcat allows auto deployment of applications while Tomcat is running. It is recommended that this capability be disabled.

Rationale:

This could allow malicious or untested applications to be deployed and should be disabled.

Audit:

Perform the following to ensure autoDeploy is set to false.

grep "autoDeploy" \$CATALINA HOME/conf/server.xml

Remediation:

In the \$CATALINA_HOME/conf/server.xml file, change autoDeploy to false.

autoDeploy="false"

Default Value:

autoDeploy is set to true

- 1. http://tomcat.apache.org/tomcat-8.0-doc/deployer-howto.html#Deploying on a running Tomcat server
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/host.html

9.3 Disable deploy on startup of applications (Scored)

Profile Applicability:

• Level 2

Description:

Tomcat allows auto deployment of applications. It is recommended that this capability be disabled.

Rationale:

This could allow malicious or untested applications to be deployed and should be disabled.

Audit:

Perform the following to ensure deployOnStartup is set to false.

grep "deployOnStartup" \$CATALINA HOME/conf/server.xml

Remediation:

In the \$CATALINA HOME/conf/server.xml file, change deployOnStartup to false.

deployOnStartup="false"

Default Value:

deployOnStartup is set to true

- 1. http://tomcat.apache.org/tomcat-8.0-doc/deployer-howto.html#Deployment_on_Tomcat_startup
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/host.html#Automatic Application Deployment
- 3. https://tomcat.apache.org/tomcat-8.0-doc/config/host.html

10 Miscellaneous Configuration Settings

Store web content on a separate partition from Tomcat system files.

10.1 Ensure Web content directory is on a separate partition from the Tomcat system files (Not Scored)

Profile Applicability:

• Level 1

Description:

Store web content on a separate partition from Tomcat system files.

Rationale:

The web document directory is where the files which are severed to the end user reside. In the past, directory traversal exploits have allowed malicious users to play havoc on a web server including executing code, uploading files, and reading sensitive data. Even if you do not have any directory traversal exploits in your server or code at this time, that doesn't mean they won't be introduced in the future. Moving your web document directory onto a different partition will prevent these kinds of attacks from doing more damage to other part of the file system.

Audit:

Locate the Tomcat system files and web content directory. Review the system partitions and ensure the system files and web content directory are on separate partitions.

```
# df $CATALINA_HOME/webapps
# df $CATALINA HOME
```

Note: Use the default value "webapps" which is defined by "appBase" attribute here.

Remediation:

Move the web content files to a separate partition from the tomcat system files and update your configuration.

Default Value:

Not Applicable

10.2 Restrict access to the web administration (Not Scored)

Profile Applicability:

• Level 2

Description:

Limit access to the web administration application to only those with a required needed.

Rationale:

Limiting access to the least privilege required will ensure only those people with required need have access to a resource. The web administration application should be limited to only administrators.

Audit:

Review \$CATALINA_HOME/conf/server.xml to ascertain that the RemoteAddrValve option is uncommented and configured to only allow access to systems required to connect.

Remediation:

For the administration application, edit \$CATALINA_HOME/conf/server.xml and uncomment the following:

<Valve className="org.apache.catalina.valves.RemoteAddrValve" allow="127\.0\.0\.1"/>

Note: The RemoteAddrValve property expects a regular expression, therefore periods and other regular expression meta-characters must be escaped.

Default Value:

By default, this configuration is not present.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/valve.html

10.3 Restrict manager application (Not Scored)

Profile Applicability:

• Level 2

Description:

Limit access to the manager application to only those with a required needed.

Rationale:

Limiting access to the least privilege required will ensure only those people with required need have access to a resource. The manager application should be limited to only administrators.

Audit:

Review \$CATALINA_HOME/webapps/host-manager/manager.xml to ascertain that the RemoteAddrValve option is uncommented and configured to only allow access to systems required to connect.

Remediation:

For the manager application, edit \$CATALINA_HOME/webapps/host-manager/manager.xml, and add the bolded line:

Add hosts, comma separated, which are allowed to access the admin application. Note: The RemoteAddrValve property expects a regular expression, therefore periods and other regular expression meta-characters must be escaped.

Default Value:

By default this setting is not present

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/valve.html

10.4 Force SSL when accessing the manager application (Scored)

Profile Applicability:

• Level 1

Description:

Use the transport-guarantee attribute to ensure SSL protection when accessing the manager application.

Rationale:

By default, when accessing the manager application, login information is sent over the wire in plain text. By using the transport-guarantee attribute within web.xml, SSL is enforced. NOTE: This requires SSL to be configured.

Audit:

Ensure \$CATALINA_HOME/webapps/manager/WEB-INF/web.xml has the <transport-guarantee> attribute set to CONFIDENTIAL.

```
# grep transport-guarantee $CATALINA HOME/webapps/manager/WEB-INF/web.xml
```

Remediation:

Set \$CATALINA_HOME/webapps/manager/WEB-INF/web.xml:

```
<security-constraint>
  <user-data-constraint>
    <transport-guarantee>CONFIDENTIAL</transport-guarantee>
    <user-data-constraint>
  </security-constraint>
```

Default Value:

By default this configuration is not present.

References:

1. https://www.owasp.org/index.php/Securing tomcat

10.5 Rename the manager application (Scored)

Profile Applicability:

• Level 2

Description:

The manager application allows administrators to manage Tomcat remotely via a web interface. The manager application should be renamed to make it harder for attackers or automated scripts to locate.

Rationale:

Obscurity can be helpful when used with other security measures. By relocating the manager applications, an attacker will need to guess its location rather than simply navigate to the standard location in order to carry out an attack.

Audit:

Ensure \$CATALINA_HOME/conf/Catalina/localhost/manager.xml, \$CATALINA_HOME/webapps/host-manager/manager.xml, \$CATALINA_HOME/webapps/manager and \$CATALINA_HOME/webapps/manager do not exsist.

Remediation:

Perform the following to rename the manager application:

1. Rename the manager application XML file:

```
# mv $CATALINA_HOME/webapps/host-manager/manager.xml \
$CATALINA_HOME/webapps/host-manager/new-name.xml
```

- 2. Update the docBase attribute within \$CATALINA_HOME/webapps/host-manager/new-name.xml to \${catalina.home}/webapps/new-name
- 3. Move \$CATALINA_HOME/webapps/manager to \$CATALINA_HOME/webapps/newname

mv \$CATALINA HOME/webapps/manager \$CATALINA HOME/webapps/new-name

Default Value:

The default name of the manager application is "manager" and is located at:

\$CATALINA_HOME/webapps/manager

References:

1. https://www.owasp.org/index.php/Securing tomcat



10.6 Enable strict servlet Compliance (Scored)

Profile Applicability:

• Level 1

Description:

The STRICT_SERVLET_COMPLIANCE influences Tomcat's behavior in several subtle ways. See the References below for the complete list. It is recommended that STRICT_SERVLET_COMPLIANCE be set to true.

Rationale:

When STRICT_SERVLET_COMPLIANCE is set to true, Tomcat will always send an HTTP Content-type header when responding to requests. This is significant as the behavior of web browsers is inconsistent in the absence of the Content-type header. Some browsers will attempt to determine the appropriate content-type by sniffing

Audit:

Ensure the above parameter is added to the startup script which by default is located at \$CATALINA_HOME\bin\catalina.sh.

Remediation:

Start Tomcat with strict compliance enabled. Add the following to your startup script.

-Dorg.apache.catalina.STRICT SERVLET COMPLIANCE=true

Default Value:

By default, this configuration parameter is not present.

References:

10.7 Turn off session façade recycling (Scored)

Profile Applicability:

• Level 1

Description:

The RECYCLE_FACADES can specify if a new façade will be created for each request. If a new façade is not created there is a potential for information leakage from other sessions.

Rationale:

When RECYCLE_FACADES is set to true, Tomcat will recycle the session façade between requests. This will allow for information leakage between requests.

Audit:

Ensure the above parameter is added to the startup script which by default is located at \$CATALINA_HOME\bin\catalina.sh.

Remediation:

Start Tomcat with RECYCLE_FACADES set to false. Add the following to your startup script.

-Dorg.apache.catalina.connector.RECYCLE_FACADES=false

Impact:

By default, recycling of facades is set to false. If this is true or if a security manager is in use a new facade object will be created for each request.

Default Value:

If not specified, the default value of false will be used.

References:

10.8 Do not allow additional path delimiters (Scored)

Profile Applicability:

• Level 2

Description:

Being able to specify different path-delimiters on Tomcat creates the possibility that an attacker can access applications that were previously blocked a proxy like mod_proxy

Rationale:

Allowing additional path-delimiters allows for an attacker to get an application or area that was not previously visible.

Audit:

Ensure the above parameters are added to the startup script which by default is located at \$CATALINA_HOME\bin\catalina.sh.

Remediation:

Start Tomcat with ALLOW_BACKSLASH set to false and ALLOW_ENCODED_SLASH set to false. Add the following to your startup script.

-Dorg.apache.catalina.connector.CoyoteAdapter.ALLOW_BACKSLASH=false -Dorg.apache.tomcat.util.buf.UDecoder.ALLOW_ENCODED_SLASH=false

Default Value:

By default, allowing additional parameters is set to false.

References:

10.9 Do not allow custom header status messages (Scored)

Profile Applicability:

• Level 2

Description:

Being able to specify custom status messages opens up the possibility for additional headers to be injected. If custom header status messages are required, make sure it is only in US-ASCII and does not include any user-supplied data.

Rationale:

Allowing user-supplied data into a header allows the possibility of XSS.

Audit:

Ensure the above parameter is added to the startup script which by default is located at \$CATALINA_HOME\bin\catalina.sh.

Remediation:

Start Tomcat with USE_CUSTOM_STATUS_MSG_IN_HEADER set to false. Add the following to your startup script.

-Dorg.apache.coyote.USE_CUSTOM_STATUS_MSG_IN_HEADER=false

Default Value:

By default, allowing custom header status messages is set to false.

References:

10.10 Configure connectionTimeout (Scored)

Profile Applicability:

• Level 2

Description:

The connectionTimeout setting allows Tomcat to close idle sockets after a specific amount of time to save system resources.

Rationale:

Closing idle sockets reduces system resource usage thus can provide better performance and help protect against Denial of Service attacks.

Audit:

Locate each connectionTimeout setting in \$CATALINA_HOME/conf/server.xml and verify the setting is correct.

grep connectionTimeout \$CATALINA HOME/conf/server.xml

Remediation:

Within \$CATALINA_HOME/conf/server.xml ensure each connector is configured to the connectionTimeout setting that is optimal based on hardware resources, load, and number of concurrent connections.

connectionTimeout="60000"

Default Value:

connectionTimeout is set to 60000

References:

10.11 Configure maxHttpHeaderSize (Scored)

Profile Applicability:

• Level 2

Description:

The maxHttpHeaderSize limits the size of the request and response headers defined in bytes. If not specified, the default is 8192 bytes.

Rationale:

Limiting the size of the header request can help protect against Denial of Service requests.

Audit:

Locate each maxHttpHeaderSize setting in \$CATALINA_HOME/conf/server.xml and verify that they are set to 8192.

grep maxHttpHeaderSize \$CATALINA HOME/conf/server.xml

Remediation:

Within \$CATALINA_HOME/conf/server.xml ensure each connector is configured to the appropriate maxHttpHeaderSize setting.

maxHttpHeaderSize="8192"

Default Value:

maxHttpHeaderSize is set to 8192

References:

10.12 Force SSL for all applications (Scored)

Profile Applicability:

• Level 2

Description:

Use the transport-guarantee attribute to ensure SSL protection when accessing all applications. This can be overridden to be disabled on a per application basis in the application configuration.

Rationale:

By default, when accessing applications SSL will be enforced to protect information sent over the network. By using the transport-guarantee attribute within web.xml, SSL is enforced.

NOTE: This requires SSL to be configured.

Audit:

Ensure \$CATALINA_HOME/conf/web.xml has theattribute set to CONFIDENTIAL.

grep transport-guarantee \$CATALINA_HOME/conf/web.xml

Remediation:

In \$CATALINA_HOME/conf/web.xml, set the following:

<user-data-constraint>
 <transport-guarantee>CONFIDENTIAL</transport-guarantee>
<user-data-constraint>

Default Value:

By default, this configuration is not present.

References:

1. http://www.owasp.org/index.php/Securing tomcat

10.14 Do not allow symbolic linking (Scored)

Profile Applicability:

• Level 1

Description:

Symbolic links allows one application to include the libraries from another. This allows for re-use of code but also allows for potential security issues when applications include libraries from other applications they should not have access to.

Rationale:

Allowing symbolic links opens up Tomcat to directory traversal vulnerability. Also there is a potential that an application could link to another application it should not be linking too. On case-insensitive operating systems there is also the threat of source code disclosure.

Audit:

Ensure all context.xml have the allowLinking attribute set to false or allowLinking does not exist.

```
# find . -name context.xml | xargs grep "allowLinking"
```

Remediation:

In all context.xml, set the allowLinking attribute to false:

```
<Context
...
      <Resources ... allowLinking="false" />
...
      </Context>
```

Default Value:

By default, allowLinking has a value of false

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/resources.html
- 2. http://tomcat.apache.org/tomcat-8.0-doc/config/context.html

10.15 Do not run applications as privileged (Scored)

Profile Applicability:

• Level 1

Description:

Setting the privileged attribute for an application changes the class loader to the Server class loader instead of the Shared class loader.

Rationale:

Running an application in privileged mode allows an application to load the manager libraries.

Audit:

Ensure all context.xml have the privileged attribute set to false or privileged does not exist.

```
# find . -name context.xml | xargs grep "privileged"
```

Remediation:

In all context.xml, set the privileged attribute to false unless it is required like the manager application:

```
<Context ... privileged="false" />
```

Default Value:

By default, privileged has a value of false.

References:

1. http://tomcat.apache.org/tomcat-8.0-doc/config/context.html

10.16 Do not allow cross context requests (Scored)

Profile Applicability:

• Level 1

Description:

Setting crossContext to true allows for an application to call ServletConext.getContext to return a dispatcher for another application.

Rationale:

Allowing crossContext creates the possibility for a malicious application to make requests to a restricted application.

Audit:

Ensure all context.xml have the crossContext attribute set to false or crossContext does not exist.

```
# find . -name context.xml | xargs grep "crossContext"
```

Remediation:

In all context.xml, set the crossContext attribute to false:

```
<Context ... crossContext="false" />
```

Default Value:

By default crossContext has a value of false.

References:

1. http://tomcat.apache.org/tomcat-8.0-doc/config/context.html

10.17 Do not resolve hosts on logging valves (Scored)

Profile Applicability:

• Level 2

Description:

Setting enableLookups to true on Connector requires a DNS look-up before logging the information. This adds additional resources when logging.

Rationale:

Allowing enableLookups adds additional overhead that is rarely needed.

Audit:

Ensure Connector elements have the enableLookups attribute set to false or enableLookups does not exist.

grep enableLookups \$CATALINA HOME/conf/server.xml

Remediation:

In Connector elements, set the enableLookups attribute to false or remove it.

<Connector ... enableLookups="false" />

Default Value:

By default, DNS lookups are disabled.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/valve.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html

10.18 Enable memory leak listener (Scored)

Profile Applicability:

• Level 1

Description:

The JRE Memory Leak Prevention Listener provides work-around for known places where the Java Runtime environment uses the context class loader to load a singleton as this will cause a memory leak if a web application class loader happens to be the context class loader at the time. The work-around is to initialize these singletons when this listener starts as Tomcat's common class loader is the context class loader at that time. It also provides work-around for known issues that can result in locked JAR files.

Rationale:

Enable the JRE Memory Leak Prevention Listener provides work-around for preventing memory leak.

Audit:

Review the \$CATALINA_HOME/conf/server.xml and see whether JRE Memory Leak Prevention Listener is enabled.

Remediation:

Uncomment the JRE Memory Leak Prevention Listener in \$CATALINA_HOME/conf/server.xml

<Listener className="org.apache.catalina.core.JreMemoryLeakPreventionListener" />

Impact:

A memory leak is the repetitive allocation of memory without consequential release of it when no longer used, leading to the consumption of ever increasing memory limited by external measures not controlled by the program possibly rendering the execution to a degraded state.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/listeners.html#JRE Memory Leak Prevention Listener-org.apache.catalina.core.JreMemoryLeakPreventionListener

10.19 Setting Security Lifecycle Listener (Scored)

Profile Applicability:

• Level 1

Description:

The Security Lifecycle Listener performs a number of security checks when Tomcat starts and prevents Tomcat from starting if they fail.

Rationale:

Enable the **Security Lifecycle Listener** can

- Enforce a blacklist of OS users that must not be used to start Tomcat.
- set the least restrictive umask before Tomcat start

Audit:

Review server.xml to ensure the Security Lifecycle Listener element is uncommented and checkedOsUsers, minimumUmask attributes are set with expected value.

Remediation:

To enabled it uncomment the listener in \$CATALINA_BASE/conf/server.xml. If the operating system supports umask then the line in \$CATALINA_HOME/bin/catalina.sh that obtains the umask also needs to be uncommented.

Within Server elements add:

- checkedOsUsers: A comma separated list of OS users that must not be used to start Tomcat. If not specified, the default value of **root** is used.
- minimumUmask: The least restrictive umask that must be configured before Tomcat will start. If not specified, the default value of **0007** is used.

```
<Listener className="org.apache.catalina.security.SecurityListener"
checkedOsUsers="alex,bob" minimumUmask="0007" />
```

Default Value:

The Security Lifecycle Listener is not enabled by default. For checkedOsUsers, If not specified, the default value of root is used. For minimumUmask, if not specified, the default value of 0007 is used.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/listeners.html#Security Lifecycle Listener-org.apache.catalina.security.SecurityListener



10.20 use the logEffectiveWebXml and metadata-complete settings for deploying applications in production (Scored)

Profile Applicability:

• Level 1

Description:

Both Fragments and annotations give rise to security concerns. web.xml contains a metadata-complete attribute in the web-app element whose binary value defines whether other sources of metadata should be considered when deploying this web application, this includes annotations on class files (@WebServlet, but also @WebListener, @WebFilter, ...), web-fragment.xml as well as classes located in WEB-INF/classes. In addition, Tomcat 7 could allow you to log the effective web.xml, when an application starts, and the effective web.xml is the result of taking the main web.xml for your application merging in all the fragments applying all the annotations. By logging that you are able to review it, and see if that is in fact what you actually want.

Rationale:

Enable "logEffectiveWebXml" will allow you to log the effective web.xml and you are able to see if that is in fact what you actually want. Enable "metadata-complete" so that the web.xml is the only metadata considered.

Audit:

1. Review each application's web.xml file located in the applications \$CATALINA_BASE\<app name>\WEB-INF\web.xml and determine if the metadata-complete property is set.

```
<web-app
...
metadata-complete="true"
...
>
```

2. Review each application's context.xml file located in the applications \$CATALINA_BASE\<app name>\META-INF\context.xml and determine if the metadata-complete property is set.

```
<Context
...
logEffectiveWebXml="true"
...
>
```

Remediation:

• Set the metadata-complete value in the web.xml in each of applications to true, the web.xml contains a metadata-complete attribute in the web-app element whose binary value defines whether other sources of metadata should be considered when deploying this web application, this includes annotations on class files (@WebServlet, but also @WebListener, @WebFilter, ...), web-fragment.xml as well as classes located in WEB-INF/classes. If set to true all of these will be ignored and web.xml is the only metadata considered.

NOTE: "The metadata-complete option is not enough to disable all of annotation scanning. If there is a ServletContainerInitializer with a @HandlesTypes annotation, Tomcat has to scan your application for classes that use annotations or interfaces specified in that annotation.

• Set the logEffectiveWebXml value in the context.xml in each of applications to true

Default Value:

If logEffectiveWebXml not specified, the default value of false is used; If metadatacomplete not specified, the default value of false is used

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/context.html
- 2. https://alexismp.wordpress.com/2010/07/28/servlet-3-0-fragments-and-web-xml-to-rule-them-all/

Control			Set Correctly	
1	Remove Extraneous Resources	Yes	No	
1.1	Remove extraneous files and directories (Scored)			
1.2			片	
2	Disable Unused Connectors (Not Scored) Limit Server Platform Information Leaks	Ш	Ш	
2.1				
2.1	Alter the Advertised server info String (Scored)			
	Alter the Advertised server.number String (Scored)		-	
2.3	Alter the Advertised server.built Date (Scored)			
2.4	Disable X-Powered-By HTTP Header and Rename the Server			
2.5	Value for all Connectors (Scored)			
2.5	Disable client facing Stack Traces (Scored)			
2.6	Turn off TRACE (Scored)			
3	Protect the Shutdown Port			
3.1	Set a nondeterministic Shutdown command value (Scored)			
3.2	Disable the Shutdown port (Not Scored)			
4	Protect Tomcat Configurations	1		
4.1	Restrict access to \$CATALINA_HOME (Scored)			
4.2	Restrict access to \$CATALINA_BASE (Scored)			
4.3	Restrict access to Tomcat configuration directory (Scored)			
4.4	Restrict access to Tomcat logs directory (Scored)			
4.5	Restrict access to Tomcat temp directory (Scored)			
4.6	Restrict access to Tomcat binaries directory (Scored)			
4.7	Restrict access to Tomcat web application directory			
	(Scored)			
4.8	Restrict access to Tomcat catalina.policy (Scored)			
4.9	Restrict access to Tomcat catalina.properties (Scored)			
4.10	Restrict access to Tomcat context.xml (Scored)			
4.11	Restrict access to Tomcat logging.properties (Scored)			
4.12	Restrict access to Tomcat server.xml (Scored)			
4.13	Restrict access to Tomcat tomcat-users.xml (Scored)			
4.14	Restrict access to Tomcat web.xml (Scored)			
5	Configure Realms			
5.1	Use secure Realms (Scored)			
5.2	Use LockOut Realms (Scored)			
6	Connector Security			
6.1	Setup Client-cert Authentication (Scored)			
6.2	Ensure SSLEnabled is set to True for Sensitive Connectors			
	(Not Scored)			
6.3	Ensure scheme is set accurately (Scored)			
6.4	Ensure secure is set to true only for SSL-enabled Connectors			
	(Scored)			

6.5	Ensure SSL Protocol is set to TLS for Secure Connectors (Scored)					
7	Establish and Protect Logging Facilities					
7.1	Application specific logging (Scored)					
7.2	Specify file handler in logging.properties files (Scored)					
7.3	Ensure className is set correctly in context.xml (Scored)					
7.4	Ensure directory in context.xml is a secure location (Scored)					
7.5	Ensure pattern in context.xml is correct (Scored)					
7.6	Ensure directory in logging.properties is a secure location (Scored)					
7.7	Configure log file size limit (Scored)					
8	Configure Catalina Policy					
8.1	Restrict runtime access to sensitive packages (Scored)					
9	Application Deployment					
9.1	Starting Tomcat with Security Manager (Scored)					
9.2	Disabling auto deployment of applications (Scored)					
9.3	Disable deploy on startup of applications (Scored)					
10	Miscellaneous Configuration Settings					
10.1	Ensure Web content directory is on a separate partition					
	from the Tomcat system files (Not Scored)					
10.2	Restrict access to the web administration (Not Scored)					
10.3	Restrict manager application (Not Scored)					
10.4	Force SSL when accessing the manager application (Scored)					
10.5	Rename the manager application (Scored)					
10.6	Enable strict servlet Compliance (Scored)					
10.7	Turn off session façade recycling (Scored)					
10.8	Do not allow additional path delimiters (Scored)					
10.9	Do not allow custom header status messages (Scored)					
10.10	Configure connectionTimeout (Scored)					
10.11	Configure maxHttpHeaderSize (Scored)					
10.12	Force SSL for all applications (Scored)					
10.14	Do not allow symbolic linking (Scored)					
10.15	Do not run applications as privileged (Scored)					
10.16	Do not allow cross context requests (Scored)					
10.17	Do not resolve hosts on logging valves (Scored)					
10.18	Enable memory leak listener (Scored)					
10.19	Setting Security Liftcycle Listener (Scored)					
10.20	use the logEffectiveWebXml and metadata-complete settings for deploying applications in production (Scored)					

Appendix: Change History

Date	Version	Changes for this version
3-17-16	1.0.0	Initial Version

