

CIS IBM AIX 5.3-6.1 Benchmark

v1.1.0

The CIS Security Benchmarks division provides consensus-oriented information security products, services, tools, metrics, suggestions, and recommendations (the "SB Products") as a public service to Internet users worldwide. Downloading or using SB Products in any way signifies and confirms your acceptance of and your binding agreement to these CIS Security Benchmarks Terms of Use.

CIS SECURITY BENCHMARKS TERMS OF USE

BOTH CIS SECURITY BENCHMARKS DIVISION MEMBERS AND NON-MEMBERS MAY:

- Download, install, and use each of the SB Products on a single computer, and/or
- Print one or more copies of any SB Product that is in a .txt, .pdf, .doc, .mcw, or .rtf format, but only if each such copy is printed in its entirety and is kept intact, including without limitation the text of these CIS Security Benchmarks Terms of Use.

UNDER THE FOLLOWING TERMS AND CONDITIONS:

- SB Products Provided As Is. CIS is providing the SB Products "as is" and "as available" without: (1) any representations, warranties, or covenants of any kind whatsoever (including the absence of any warranty regarding: (a) the effect or lack of effect of any SB Product on the operation or the security of any network, system, software, hardware, or any component of any of them, and (b) the accuracy, utility, reliability, timeliness, or completeness of any SB Product); or (2) the responsibility to make or notify you of any corrections, updates, upgrades, or fixes.
- **Intellectual Property and Rights Reserved**. You are not acquiring any title or ownership rights in or to any SB Product, and full title and all ownership rights to the SB Products remain the exclusive property of CIS. All rights to the SB Products not expressly granted in these Terms of Use are hereby reserved.
- Restrictions. You acknowledge and agree that you may not: (1) decompile, dis-assemble, alter, reverse engineer, or otherwise attempt to derive the source code for any software SB Product that is not already in the form of source code; (2) distribute, redistribute, sell, rent, lease, sublicense or otherwise transfer or exploit any rights to any SB Product in any way or for any purpose; (3) post any SB Product on any website, bulletin board, ftp server, newsgroup, or other similar mechanism or device; (4) remove from or alter these CIS Security Benchmarks Terms of Use on any SB Product; (5) remove or alter any proprietary notices on any SB Product; (6) use any SB Product or any component of an SB Product with any derivative works based directly on an SB Product or any component of an SB Product; (7) use any SB Product or any component of an SB Product or any component for any part of their functionality; (8) represent or claim a particular level of compliance or consistency with any SB Product; or (9) facilitate or otherwise aid other individuals or entities in violating these CIS Security Benchmarks Terms of Use.
- Your Responsibility to Evaluate Risks. You acknowledge and agree that: (1) no network, system, device, hardware, software, or component can be made fully secure; (2) you have the sole responsibility to evaluate the risks and benefits of the SB Products to your particular circumstances and requirements; and (3) CIS is not assuming any of the liabilities associated with your use of any or all of the SB Products.
- **CIS Liability**. You acknowledge and agree that neither CIS nor any of its employees, officers, directors, agents or other service providers has or will have any liability to you whatsoever (whether based in contract, tort, strict liability or otherwise) for any direct, indirect, incidental, consequential, or special damages that arise out of or are connected in any way with your use of any SB Product.
- **Indemnification**. You agree to indemnify, defend, and hold CIS and all of CIS's employees, officers, directors, agents and other service providers harmless from and against any liabilities, costs and expenses incurred by any of them in connection with your violation of these CIS Security Benchmarks Terms of Use.
- **Jurisdiction**. You acknowledge and agree that: (1) these CIS Security Benchmarks Terms of Use will be governed by and construed in accordance with the laws of the State of Maryland; (2) any action at law or in equity arising out of or relating to these CIS Security Benchmarks Terms of Use shall be filed only in the courts located in the State of Maryland; and (3) you hereby consent and submit to the personal jurisdiction of such courts for the purposes of litigating any such action.
- U.S. Export Control and Sanctions laws. Regarding your use of the SB Products with any non-U.S. entity or country, you acknowledge that it is your responsibility to understand and abide by all U.S. sanctions and export control laws as set from time to time by the U.S. Bureau of Industry and Security (BIS) and the U.S. Office of Foreign Assets Control (OFAC).

SPECIAL RULES FOR CIS MEMBER ORGANIZATIONS: CIS reserves the right to create special rules for: (1) CIS Members; and (2) Non-Member organizations and individuals with which CIS has a written contractual relationship. CIS hereby grants to each CIS Member Organization in good standing the right to distribute the SB Products within such Member's own organization, whether by manual or electronic means. Each such Member Organization acknowledges and agrees that the foregoing grants in this paragraph are subject to the terms of such Member's membership arrangement with CIS and may, therefore, be modified or terminated by CIS at any time.

Table of Contents

Table of Contents	3
Overview	9
Consensus Guidance	9
Intended Audience	9
Acknowledgements	10
Typographic Conventions	
Configuration Levels	10
Level-I Benchmark settings/actions	
Level-II Benchmark settings/actions	
Scoring Status	
Scorable	
Not Scorable	
Introduction	
Scope	
Approach	
Maintenance Cadence	
Considerations	
Summary	
AIX Security Expert Introduction	
Security Levels	
Low Level Security	
Medium Level Security	
High Level Security	
Custom Level Security	
Implementing the Custom Level Policy	
1. AIX Security Expert Recommendations	
1.1 AIX Security Expert – Password Policy	
1.1.1 /etc/security/user - mindiff (Level 1, Scorable)	17
1.1.2 /etc/security/user - minage (Level 1, Scorable)	
1.1.3 /etc/security/user - maxage (Level 1, Scorable)	
1.1.4 /etc/security/user - minlen (Level 1, Scorable)	
1.1.5 /etc/security/user - minalpha (Level 1, Scorable)	
1.1.6 /etc/security/user- minother (Level 1, Scorable)	
1.1.7 /etc/security/user - maxrepeats (Level 1, Scorable)	
1.1.8 /etc/security/user - histexpire (Level 1, Scorable)	22
1.1.9 /etc/security/user - histsize (Level 1, Scorable)	
1.1.10 /etc/security/user - maxexpired (Level 1, Scorable)	
1.1.11 /etc/security/login.cfg – pwd_algorithm (AIX 5.3 TL-07 +) (Level 2, Scorable)	
1.2 AIX Security Expert – Login Policy	
1.2.1 /etc/security/login.cfg - logininterval (Level 1, Scorable)	
1.2.2 /etc/security/login.cfg - logindisable (Level 1, Scorable)	
1.2.3 /etc/security/login.cfg - loginreenable (Level 1, Scorable)	
1.2.4 /etc/security/login.cfg - logintimeout (Level 1, Scorable)	29

1.2.5 /etc/security/login.cfg - logindelay (Level 1, Scorable)	29
1.2.6 /etc/security/user - loginretries (Level 1, Scorable)	30
1.2.7 /etc/security/user - rlogin (Level 1, Scorable)	31
1.2.8 /etc/security/user - sugroups (Level 1, Scorable)	32
1.2.9 System account lockdown (Level 2, Scorable)	33
3 AIX Security Expert - System Services Management	34
1.3.1 /etc/inittab - qdaemon (Level 2, Scorable)	34
1.3.2 /etc/inittab - lpd (Level 2, Scorable)	35
1.3.3 /etc/inittab - piobe (Level 2, Scorable)	37
1.3.4 /etc/inittab - dt (Level 2, Scorable)	38
1.3.5 /etc/inittab - rcnfs (Level 2, Scorable)	39
1.3.6 /etc/rc.tcpip - sendmail (Level 2, Scorable)	40
1.3.7 /etc/rc.tcpip - snmpd (Level 2, Scorable)	41
1.3.8 /etc/rc.tcpip - dhcpcd (Level 2, Scorable)	43
1.3.9 /etc/rc.tcpip - dhcprd (Level 2, Scorable)	44
1.3.10 /etc/rc.tcpip - dhcpsd (Level 2, Scorable)	
1.3.11 /etc/rc.tcpip – autoconf6 (Level 2, Scorable)	46
1.3.12 /etc/rc.tcpip – gated (Level 2, Scorable)	47
1.3.13 /etc/rc.tcpip – mrouted (Level 2, Scorable)	
1.3.14 /etc/rc.tcpip – named (Level 2, Scorable)	50
1.3.15 /etc/rc.tcpip – routed (Level 2, Scorable)	
1.3.16 /etc/rc.tcpip - rwhod (Level 2, Scorable)	52
1.3.17 /etc/rc.tcpip – timed (Level 2, Scorable)	
1.3.18 /etc/rc.tcpip – dpid2 (Level 2, Scorable)	
1.3.19 /etc/rc.tcpip – hostmibd (Level 2, Scorable)	
1.3.20 /etc/rc.tcpip – snmpmibd (Level 2, Scorable)	
1.3.21 /etc/rc.tcpip – aixmibd (Level 2, Scorable)	
1.3.22 /etc/rc.tcpip - ndpd-host (Level 2, Scorable)	
1.3.23 /etc/rc.tcpip – ndpd-router (Level 2, Scorable)	61
1.3.24 /etc/inetd.conf - telnet (Level 2, Scorable)	
1.3.25 /etc/inetd.conf – exec (Level 2, Scorable)	
1.3.26 /etc/inetd.conf – daytime (Level 2, Scorable)	
1.3.27 /etc/inetd.conf – shell (Level 2, Scorable)	
1.3.28 /etc/inetd.conf – cmsd (Level 2, Scorable)	
1.3.29 /etc/inetd.conf – ttdbserver (Level 2, Scorable)	
1.3.30 /etc/inetd.conf – uucp (Level 2, Scorable)	
1.3.31 /etc/inetd.conf – time (Level 2, Scorable)	
1.3.32 /etc/inetd.conf – login (Level 2, Scorable)	
1.3.33 /etc/inetd.conf – talk (Level 2, Scorable)	
1.3.34 /etc/inetd.conf - ntalk (Level 2, Scorable)	75
1.3.35 /etc/inetd.conf - ftp (Level 2, Scorable)	
1.3.36 /etc/inetd.conf - chargen (Level 2, Scorable)	
1.3.37 /etc/inetd.conf – discard (Level 2, Scorable)	
1.3.38 /etc/inetd.conf – dtspc (Level 2, Scorable)	
1.3.39 /etc/inetd.conf – echo (Level 2, Scorable)	
1.3.40 /etc/inetd.conf - pcnfs (Level 2, Scorable)	82

1.3.41 /etc/inetd.conf - rstatd (Level 2, Scorable)	83
1.3.42 /etc/inetd.conf - rusersd (Level 2, Scorable)	84
1.3.43 /etc/inetd.conf - rwalld (Level 2, Scorable)	
1.3.44 /etc/inetd.conf - sprayd (Level 2, Scorable)	87
1.3.45 /etc/inetd.conf - klogin (Level 2, Scorable)	88
1.3.46 /etc/inetd.conf - kshell (Level 2, Scorable)	89
1.3.47 /etc/inetd.conf - rquotad (Level 2, Scorable)	90
1.3.48 /etc/inetd.conf - tftp (Level 2, Scorable)	
1.3.49 /etc/inetd.conf - imap (Level 2, Scorable)	92
1.3.50 /etc/inetd.conf - pop3 (Level 2, Scorable)	
1.3.51 /etc/inetd.conf - fingerd (Level 2, Scorable)	94
1.3.52 /etc/inetd.conf - instsrv (Level 2, Scorable)	95
1.3.53 /etc/inetd.conf – permissions and ownership (Level 1, Scorable)	
1.4 AIX Security Expert - Disabling Remote Services	97
1.4.1 Remote command lockdown (Level 2, Scorable)	98
1.4.2 Remote daemon lockdown (Level 2, Scorable)	
1.5 AIX Security Expert - Automated Authentication	101
1.5.1 Removal of .rhosts and .netrc files (Level 2, Scorable)	101
1.5.2 Removal of entries from /etc/hosts.equiv (Level 2, Scorable)	102
1.6 AIX Security Expert – TCP/IP Hardening	
1.6.1 TCP/IP Tuning - ipsrcrouteforward (Level 2, Scorable)	103
1.6.2 TCP/IP Tuning - ipignoreredirects (Level 2, Scorable)	
1.6.3 TCP/IP Tuning - clean_partial_conns (Level 2, Scorable)	
1.6.4 TCP/IP Tuning - ipsrcroutesend (Level 2, Scorable)	
1.6.5 TCP/IP Tuning - ipforwarding (Level 2, Scorable)	
1.6.6 TCP/IP Tuning - ipsendredirects (Level 2, Scorable)	110
1.6.7 TCP/IP Tuning - ip6srcrouteforward (Level 2, Scorable)	
1.6.8 TCP/IP Tuning - directed_broadcast (Level 2, Scorable)	
1.6.9 TCP/IP Tuning - tcp_pmtu_discover (Level 2, Scorable)	
1.6.10 TCP/IP Tuning - bcastping (Level 2, Scorable)	
1.6.11 TCP/IP Tuning – icmpaddressmask (Level 2, Scorable)	
1.6.12 TCP/IP Tuning – udp_pmtu_discover (Level 2, Scorable)	
1.6.13 TCP/IP Tuning – ipsrcrouterecv (Level 2, Scorable)	
1.6.14 TCP/IP Tuning – nonlocsrcroute (Level 2, Scorable)	
1.6.15 TCP/IP Tuning -tcp_tcpsecure (Level 2, Scorable)	
1.6.16 TCP/IP Tuning – sockthresh (Level 2, Scorable)	
1.6.17 TCP/IP Tuning - rfc1323 (Level 2, Scorable)	
1.6.18 TCP/IP Tuning - tcp_sendspace (Level 2, Scorable)	
1.6.19 TCP/IP Tuning - tcp_recvspace (Level 2, Scorable)	
1.6.20 TCP/IP Tuning - tcp_mssdflt (Level 2, Scorable)	128
1.6.21 TCP/IP Tuning - nfs_use_reserved_ports (Level 2, Scorable)	
1.7 AIX Security Expert – Miscellaneous Enhancements	
1.7.1 Miscellaneous Enhancements – crontab access (Level 2, Scorable)	
1.7.2 Miscellaneous Enhancements – at access (Level 2, Scorable)	
1.7.3 Miscellaneous Enhancements – /etc/ftpusers (Level 1, Scorable)	
1.7.4 Miscellaneous Enhancements – login herald (Level 1, Scorable)	134

	1.7.5 Miscellaneous Enhancements – guest account removal (Level 1, Scorable)	135
	1.7.6 Miscellaneous Enhancements - crontab permissions (Level 1, Scorable)	136
	1.7.7 Miscellaneous Enhancements – default umask (Level 2, Scorable)	137
	1.7.8 Miscellaneous Enhancements - disabling core dumps (Level 2, Scorable)	139
	1.7.9 Miscellaneous Enhancements - AIX Auditing (Level 2, Scorable)	141
2.	. Non AIX Security Expert Managed Recommendations	144
	2.1 Configuring syslog	144
	2.1.1 Configuring syslog - local logging (Level 2, Scorable)	144
	2.1.2 Configuring syslog – remote logging (Level 2, Scorable)	146
	2.1.3 Configuring syslog - remote messages (Level 2, Scorable)	147
	2.2 Secure Remote Access	
	2.2.1 Configuring SSH – installation (Level 2, Scorable)	149
	2.2.2 Configuring SSH - disabling direct root access (Level 1, Scorable)	150
	2.2.3 Configuring SSH – server protocol 2 (Level 1, Scorable)	
	2.2.4 Configuring SSH – client protocol 2 (Level 1, Scorable)	
	2.2.5 Configuring SSH – banner configuration (Level 1, Scorable)	
	2.2.6 Configuring SSH – ignore .shosts and .rhosts (Level 1, Scorable)	
	2.2.7 Configuring SSH – disable null passwords (Level 1, Scorable)	
	2.2.8 Configuring SSH – disallow host based authentication (Level 2, Scorable)	
	2.2.9 Configuring SSH – set privilege separation (Level 1, Scorable)	
	2.2.10 Configuring SSH - sshd_config permissions lockdown (Level 1, Scorable)	
	2.2.11 Configuring SSH – ssh_config permissions lockdown (Level 1, Scorable)	
	2.2.12 Configuring SSH – removal of .shosts files (Level 2, Scorable)	
	2.2.13 Configuring SSH – removal of /etc/shosts.equiv (Level 2, Scorable)	
	2.3 Sendmail Configuration	
	2.3.1 /etc/mail/sendmail.cf - SmtpGreetingMessage (Level 1, Scorable)	
	2.3.2 /etc/mail/sendmail.cf – permissions and ownership (Level 1, Scorable)	
	2.3.3 /var/spool/mqueue – permissions and ownership (Level 1, Scorable)	
	2.4 Common Desktop Environment (CDE)	
	2.4.1 CDE – de-installing CDE (Level 2, Scorable)	
	2.4.2 CDE – disabling dtlogin (Level 2, Scorable)	164
	2.4.3 CDE – sgid/suid binary lockdown (Level 1, Scorable)	
	2.4.4 CDE – remote GUI login disabled (Level 2, Scorable)	
	2.4.5 CDE – screensaver lock (Level 1, Scorable)	
	2.4.6 CDE – /etc/dt/config/Xconfig permissions and ownership (Level 1, Scorable)	
	2.4.7 CDE – /etc/dt/config/Xservers permissions and ownership (Level 1, Scorable	
	2.4.8 CDE – login screen hostname masking (Level 1, Scorable)	
	2.4.9 CDE – /etc/dt/config/*/Xresources permissions and ownership (Level 1, Sco	-
	O. F. N. D.G.	
	2.5 NFS	
	2.5.1 NFS – de-install NFS (Level 2, Scorable)	
	2.5.2 NFS – nosuid on NFS client mounts (Level 1, Scorable)	
	2.5.3 NFS – localhost removal (Level 1, Scorable)	
	2.5.4 NFS – restrict NFS access (Level 2, Scorable)	
	2.5.5 NFS – no_root_squash option (Level 1, Scorable)	
	2.5.6 NFS – secure NFS (Level 2, Scorable)	1/6

2.6 NIS	.177
2.6.1 NIS - disable NIS client (Level 2, Scorable)	.178
2.6.2 NIS - disable NIS server (Level 2, Scorable)	.178
2.6.3 NIS - remove NIS markers from password and group files (Level 2, Scorable)	
2.6.4 NIS - restrict NIS server communication (Level 2, Scorable)	.180
2.7 SNMP	.181
2.7.1 SNMP - disable private community string (Level 2, Scorable)	.181
2.7.2 SNMP – disable system community string (Level 2, Scorable)	.182
2.7.3 SNMP – disable public community string (Level 2, Scorable)	.183
2.7.4 SNMP – restrict community access (Level 2, Scorable)	.184
2.7.5 SNMP - disable Readwrite community access (Level 2, Scorable)	
2.8 Securing inetd	
2.8.1 inetd - disabling inetd (Level 2, Scorable)	.186
2.9 Portmap Lockdown	
2.9.1 /etc/rc.tcpip - portmap (Level 2, Scorable)	.187
2.10 TCP Wrappers	
2.10.1 TCP Wrappers – installing TCP Wrappers (Level 2, Scorable)	.188
2.10.2 TCP Wrappers – creating a hosts.deny file (Level 1, Scorable)	
2.10.3 TCP Wrappers – creating a hosts allow file (Level 1, Scorable)	
2.10.4 TCP Wrappers – wrapping inetd services (Level 2, Scorable)	
2.11 Permissions and Ownership	
2.11.1 Permissions and Ownership – /etc/security (Level 1, Scorable)	
2.11.2 Permissions and Ownership – /etc/group (Level 1, Scorable)	
2.11.3 Permissions and Ownership – /etc/passwd (Level 1, Scorable)	
2.11.4 Permissions and Ownership – /etc/security/audit (Level 1, Scorable)	
2.11.5 Permissions and Ownership – /audit (Level 1, Scorable)	
2.11.6 Permissions and Ownership – /smit.log (Level 1, Scorable)	
2.11.7 Permissions and Ownership – /var/adm/cron/log (Level 1, Scorable)	
2.11.8 Permissions and Ownership – /var/spool/cron/crontabs (Level 1, Scorable)	
2.11.9 Permissions and Ownership – /var/adm/cron/at.allow (Level 1, Scorable)	
2.11.10 Permissions and Ownership - /var/adm/cron/cron.allow (Level 1, Scorable).	
2.11.11 Permissions and Ownership – /etc/motd (Level 1, Scorable)	
2.11.12 Permissions and Ownership – /var/adm/ras (Level 1, Scorable)	
2.11.13 Permissions and Ownership – /var/ct/RMstart.log (Level 1, Scorable)	
2.11.14 Permissions and Ownership – /var/tmp/dpid2.log (Level 1, Scorable)	
2.11.15 Permissions and Ownership – /var/tmp/hostmibd.log (Level 1, Scorable)	
2.11.16 Permissions and Ownership –/var/tmp/snmpd.log (Level 1, Scorable)	
2.11.17 Permissions and Ownership –/var/adm/sa (Level 1, Scorable)	
2.11.18 Permissions and Ownership – world/group writable directory in root PATH	
(Level 1, Scorable)	.202
2.11.19 Permissions and Ownership – home directory configuration files (Level 1,	
Scorable)	.204
2.11.20 Permissions and Ownership – home directory permissions (Level 1, Scorable)	
2.12 Miscellaneous Configuration Changes	
2.12.1 Miscellaneous Config – serial port restriction (Level 2, Scorable)	
2.12.2 Miscellaneous Config – disable i4ls (Level 2, Scorable)	
(-:- , , , , , , , , ,	-

2.12.3 Miscellaneous Config – disable NCS (Level 2, Scorable)	208
2.12.4 Miscellaneous Config - disable httpdlite (Level 2, Scorable)	209
2.12.5 Miscellaneous Config - disable pmd (Level 2, Scorable)	
2.12.6 Miscellaneous Config - disable writesry (Level 2, Scorable)	210
2.12.7 Miscellaneous Config – block talk/write (Level 2, Scorable)	211
2.12.8 Miscellaneous Config - enable sar accounting (Level 2, Scorable)	212
2.12.9 Miscellaneous Config - /etc/ftpusers (Level 2, Scorable)	213
2.12.10 Miscellaneous Config - ftp umask (Level 1, Scorable)	214
2.12.11 Miscellaneous Config - ftp banner (Level 1, Scorable)	215
2.12.12 Miscellaneous Config - /etc/motd (Level 1, Scorable)	216
2.12.13 Miscellaneous Config - authorized users in at.allow (Level 1, Scorable)	217
2.12.14 Miscellaneous Config – authorized users in cron.allow (Level 1, Scorable)	218
2.12.15 Miscellaneous Config – all unlocked accounts must have a password (Level 1	
Scorable)	
2.12.16 Miscellaneous Config - all user id must be unique (Level 1, Scorable)	
2.12.17 Miscellaneous Config – all group id must be unique (Level 1, Scorable)	
2.12.18 Miscellaneous Config - unnecessary user and group removal (Level 2, Scoral	-
2.12.19 Miscellaneous Config - removing current working directory from root's PAT	
(Level 1, Scorable)	222
2.12.20 Miscellaneous Config – removing current working directory from default	000
/etc/environment PATH (Level 1, Scorable)	
2.13 Privileged Command Management	
2.13.1 PCM - sudo (Level 2, Scorable)	
2.13.2 PCM – enhanced RBAC (AIX 6.1 only) (Level 2, Not Scorable)	
2.14 Encrypted Filesystems (EFS) (AIX 6.1 only)	
2.14.1 EFS - implementation (AIX 6.1 only) (Level 2, Scorable)	
2.15 Trusted Execution (TE) (AIX 6.1 only)	
2.15.1 TE - implementation (AIX 6.1 only) (Level 2, Scorable)	
2.16 General Permissions Management	
2.16.1 General Permissions Management - suid and sgid files and programs (Level 2,	
Scorable)	231
Scorable)	222
2.16.3 General Permissions Management - world writable files and directories (Leve	
Scorable)	
3. Final Steps2	
3.1 System Reboot and Backup	
Appendix A: References	
Appendix B: Change History	
Appendix D. Grange motory	

Overview

This document, Security Configuration Benchmark for AIX 5.3 and AIX 6.1, provides prescriptive guidance for establishing a secure configuration posture for AIX versions 5.3 and 6.1 running on the Power Systems platform. This guide was tested against AIX 5.3 TL-05 / TL-07 and AIX 6.1 TL-01, installed from IBM base installation media. To obtain the latest version of this guide, please visit http://benchmarks.cisecurity.org. If you have questions, comments, or have identified ways to improve this guide, please write us at feedback@cisecurity.org.

Consensus Guidance

This benchmark was created using a consensus review process comprised of volunteer and contract subject matter experts. Consensus participants provide perspective from a diverse set of backgrounds including consulting, software development, audit and compliance, security research, operations, government, and legal.

Each CIS benchmark undergoes two phases of consensus review. The first phase occurs during initial benchmark development. During this phase, subject matter experts convene to discuss, create, and test working drafts of the benchmark. This discussion occurs until consensus has been reached on benchmark recommendations. The second phase begins after the benchmark has been released to the public Internet. During this phase, all feedback provided by the Internet community is reviewed by the consensus team for incorporation in to the CIS benchmark. If you are interested in participating in the consensus review process, please send us a note to feedback@cisecurity.org.

Intended Audience

This document is intended for system and application administrators, security specialists, auditors, help desk, and platform deployment personnel, who plan to develop, deploy, assess, or secure solutions that incorporate AIX 5.3 and AIX 6.1 on the Power Systems platform.

A working knowledge of vi is assumed in order to implement some of the configuration changes.

Acknowledgements

This benchmark exemplifies the great things a community of users, vendors, and subject matter experts can accomplish through consensus collaboration. The CIS community thanks the entire consensus team with special recognition to the following individuals who contributed greatly to the creation of this guide:

Authors

Paul Sharpe

Contributors and Reviewers

Shailesh Athalye, Symantec Inc.
Christiane Cuculo, CPqD
Blake Frantz, Center for Internet Security
Gary Harwood
Huibert Kivits
Boris Kleiman, Lightening International
Nikhil Mittal
Steve Parham, IBM
Ely Pinto
Jeff Saxon, IBM

Typographic Conventions

The following typographical conventions are used throughout this guide:

Convention	Meaning
Stylized Monospace font	Used for blocks of code, command, and script examples.
	Text should be interpreted exactly as presented.
Monospace font	Used for inline code, commands, or examples. Text should
	be interpreted exactly as presented.
<italic brackets="" font="" in=""></italic>	Italic texts set in angle brackets denote a variable
	requiring substitution for a real value.
Italic font	Used to denote the title of a book, article, or other
	publication.
Note	Additional information or caveats

Configuration Levels

This section defines the configuration levels that are associated with each benchmark recommendation. Configuration levels represent increasing levels of security assurance.

Level-I Benchmark settings/actions

Level-I Benchmark recommendations are intended to:

- be practical and prudent;
- provide a clear security benefit; and
- do not negatively inhibit the utility of the technology beyond acceptable means

Level-II Benchmark settings/actions

Level-II Benchmark recommendations exhibit one or more of the following characteristics:

- are intended for environments or use cases where security is paramount
- acts as defense in depth measure
- may negatively inhibit the utility or performance of the technology

Scoring Status

This section defines the scoring statuses used within this document. The scoring status indicates whether compliance with the given recommendation is discernable in an automated manner.

Scorable

The platform's compliance with the given recommendation can be determined via automated means.

Not Scorable

The platform's compliance with the given recommendation cannot be determined via automated means.

Introduction

Scope

This guide provides security configuration guidance for use during the configuration of AIX 5.3 and 6.1 Operating Systems. There is a particular emphasis on the configuration of AIX 6.1, but as there is common affinity between the two releases much of the guide is relevant regardless of version specifics. Where function is not available for AIX 5.3, this will be clearly highlighted and where there is a different approach, this will be clearly defined.

The scope of the guide is applicable to AIX 5.3 TL-05+ and AIX 6.1. The reason for the minimum version requirement of AIX 5.3 TL-05 is because the AIX Security Expert tool will be used to automate a large proportion of the best practice and recommendations and this is the AIX 5.3 Technology Level in which the tool was first released.

Approach

The suggested approach in terms of implementing this guide would be to install a vanilla AIX image, via NIM or the AIX product CD/DVD's, followed by the recommendations detailed in this guide and any other corporate standardization i.e. software installation and filesystem and user creation. Once completed, a mksysb backup of the system could then be taken and this image could be deployed via NIM for any subsequent operating system builds. This would provide a standard build mechanism, ensuring 100% compliance to all company standards and the best practice recommendations detailed in this benchmark.

Within the AIX Base Operating System Installation Menus it is recommended that the following options are selected:

- 64-bit kernel
- JFS2 filesystems
- All devices and kernels are installed = yes *
- Trusted Computing Base Install = yes **

Maintenance Cadence

Considerations

Before entering into the recommendation section of this paper it is important to put into context the relevance of an AIX software maintenance strategy. It is imperative that regular Technology Level (TL) and Service Pack (SP) updates are applied to an AIX estate, to ensure that all known security vulnerabilities are addressed and to remain within a supported TL stream.

The current IBM software maintenance strategy revolves around the release of Technology Levels and Service Packs. Technology Levels are released twice per year, one in the spring and the other in fall. They introduce support for new hardware, new functionality, and new features and contain cumulative fixes since the release of the previous TL. The fix support window for a given TL is two years from its release date.

Service Packs are released throughout the lifecycle of the TL and address security vulnerabilities and other critical fixes. They are typically released every 12 weeks; obviously this timeframe is dependant on the number and criticality of the issues found.

It is recommended that full TL's or SP's are applied rather than individual fixes, due to the far more rigorous certification and testing process. The large and complex matrix of possible fix combinations are not subjected to the same degree of testing and therefore installing individual fixes is not recommended.

A security fix will be initially released as an interim fix, which is installed and maintained via the <code>emgr</code> framework. It is recommended that, unless it is an extremely critical security issue, to wait and apply the fix as part of a full SP release to ensure maximum system stability.

Summary

The recommended maintenance strategy is as follows:-

• Stay current and refresh the TL of each system at least once a year – For maximum system stability wait until SP3 is released on the newer TL and then migrate.

^{*} This is to ensure that all device drivers are contained within the standard build image for deploying to different server hardware configurations.

^{**} For AIX 5.3 systems only, it is recommended that Trusted Computing Base (TCB) is installed. This is an install time only option.

- Review the Service Packs for any security or critical fixes apply these regularly throughout the life cycle of a TL.
- Do not apply interim fixes or individual fixes unless there is an urgent requirement to do so. Instead apply full TL's and SP's for maximum stability.
- There should be a monthly review of the security advisory bulletins to remain apprised of all known security issues. These can currently be viewed at the following URL:

http://www14.software.ibm.com/webapp/set2/subscriptions/pgvcmjd

The security fixes published in the vulnerability advisories are posted here for download:

ftp://aix.software.ibm.com/aix/efixes/security

When any new AIX operating system images are deployed, review the latest available TL and SP releases and update where required. The information regarding the latest fixes can be gleaned from the IBM Fix Central website:

http://www-933.ibm.com/support/fixcentral/

• Further details on the IBM recommended maintenance strategies can be found in The "IBM AIX Operating System Service Strategy Details and Best Practices" guide:

http://www14.software.ibm.com/webapp/set2/sas/f/best/home.html

AIX Security Expert Introduction

This section will focus on the AIX Security Expert framework. The tool has been introduced to standardize and simplify the security hardening process in AIX, with over 300 settings and commands within its scope. It can be used to replace in-house security scripts and procedures.

Security Levels

There are three standard security levels, other than default, and the ability to create a customized hybrid policy.

Low Level Security

This policy implements common non-disruptive security enhancements.

Typically this is suited to servers residing in an internal and secure local network environment. It provides a basic security lockdown, from a minimal default level.

Medium Level Security

This policy implements more advanced hardening parameters than the Low Level. These include: port scan protection and an enhanced password management policy. This security level does allow clear text password protocol access, e.g. ftp, rlogin, and telnet.

Typically, this is suited to servers residing in a corporate network protected by a firewall.

High Level Security

This policy implements the highest possible security hardening standards. These include: port scan protection and no access for any clear text password protocols. It assumes that the local network is not trusted and is potentially unsafe.

Typically, this is suited to servers residing in an unsafe network. For example, those which are internet facing.

Within modern IT infrastructure, internal firewalls are typically implemented to separate the internal network from any corporate or internet environments and external firewalls to further protect these environments from the outside world. These firewall devices are typically only configured to allow access to the systems on the required core application or database ports. Therefore, port shunning and scan protection are typically something implemented by a firewall, rather than at the operating system level.

Custom Level Security

The approach of this benchmark is to implement a hybrid policy, which contains a combination of recommended settings from both the Medium and High Level default policies. A customized XML file provides the ultimate flexibility in terms of being able to choose whether or not to implement every recommended AIX Security Expert controlled setting in this benchmark e.g. whether clear text password protocols are allowed. This policy can be easily modified depending on the environmental requirements. A simple edit of the customized XML file, prior to it being implemented, is all that is required. This flexibility is not present within the default Low, Medium and High Level policies which provide a pre-defined rigid level of security hardening standards.

Implementing the Custom Level Policy

There are two tar files provided with this benchmark, one for each AIX release, as there are XML format differences between the two operating system versions. Both files are in tar format, have an absolute path and can be extracted via the following commands:-

AIX 5.3:

tar -xvf <PATH to tar file>/CIS_IBM_AIX_5.3-6.1_Benchmark_v1.0.0_AIXPERT_5.3.tar

AIX 6.1:

```
tar -xvf <PATH to tar file>/CIS_IBM_AIX_5.3-6.1_Benchmark_v1.0.0_AIXPERT_6.1.tar
```

This will place the customized XML file into its default location:-

For AIX 5.3:

```
/etc/security/aixpert/custom/custom_5.3.xml
```

For AIX 6.1:

```
/etc/security/aixpert/custom/custom_6.1.xml
```

Prior to implementing the AIX Security Expert customized settings, please review the benchmark recommendations in the next section. If there are any settings that need to be changed from a recommended value, based on environmental requirements, edit the XML file using the <code>vi</code> command. All AIX Security Expert managed Level 2 recommendations have a procedure detailing which applicable setting to change for reversion, if required.

As much of the guide as possible has been automated within the AIX Security Expert customized XML file. This includes a number of recommendations normally outside the remit of the tool. In these instances the <code>execmds</code> functionality has been used to execute the appropriate commands and implement the recommendations.

One of the recommendations within this benchmark is to setup and configure AIX auditing (1.7.11). In the introductory section of this document, it was recommended that the Operating System be installed utilizing jfs2 filesystems. The default AIX Security Expert scripts (AIX 5.3 TL-07) created a jfs based /audit filesystem during testing, so to ensure that a jfs2 audit filesystem is utilized, it can be manually created.

If the system was installed utilizing jfs filesystems, or if auditing is not to be implemented, the commands below can be ignored:

```
mklv -y auditlv -t jfs2 -u 2 -c 1 rootvg 1 hdisk0
crfs -v jfs2 -d auditlv -m /audit -A yes -t no
mount /audit
chfs -a size=256M /audit
```

NOTE: The chfs resizing is only valid when the physical partition size of rootvg is less than 256MB. The logical volume name can be changed from the example to reflect any internal standards.

Once the recommendations have been reviewed, implementation of the customized XML file should be performed in the following way:

AIX 5.3:

aixpert -f /etc/security/aixpert/custom/custom 5.3.xml

AIX 6.1:

```
aixpert -f /etc/security/aixpert/custom/custom 6.1.xml
```

Once the XML has been successfully implemented, the applied settings are placed in the following file:

```
cat /etc/security/aixpert/core/appliedaixpert.xml
```

The values set by the customized XML file can be validated via:

```
aixpert -c
```

This compares the settings, defined in the appliedaixpert.xml file, to those currently set on the system. If there is deviation from these standards i.e. a setting has been changed, it will be reported in the following log file:

```
cat /etc/security/aixpert/check report.txt
```

Any deviations can be corrected manually, or the AIX Security Expert Customized XML file can be re-applied.

During the customized XML implementation, the following files are copied prior to being changed:

```
cp -p /etc/inittab /etc/inittab.orig.$date
cp -p /etc/rc.tcpip /etc/rc.tcpip.orig.$date
cp -p /etc/inetd.conf /etc/inetd.conf.orig.$date
```

1. AIX Security Expert Recommendations

This section provides details of the recommended settings controlled within the AIX Security Expert framework. The settings within this section can all be automatically applied, utilizing the <code>aixpert</code> command to implement the customized XML file.

1.1 AIX Security Expert – Password Policy

This section provides guidance on the configuration of the password policy. This includes recommended length, complexity, re-use and expiration.

The recommendations in this section affect the parameters of the default user stanza. The values set are only applicable if specific values are not defined during the creation of a user. It is therefore recommended to not set any of these values explicitly, unless there is a specific requirement to do so when a user is created.

1.1.1 /etc/security/user - mindiff (Level 1, Scorable)

Description:

Defines the minimum number of characters that are required in a new password which were not in the old password.

Rationale:

In setting the mindiff attribute, it ensures that users are not able to reuse the same or similar passwords.

Remediation:

In /etc/security/user, set the default user stanza mindiff attribute to be greater than or equal to 4.

This means that when a user password is set it needs to comprise of at least 4 characters not present in the previous password.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/user -s default -a mindiff=4
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/user -s default -a mindiff
```

The above command should yield the following output:

default mindiff=4

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy mindiff=4 Medium Level policy mindiff =3 Low Level policy No effect

1.1.2 /etc/security/user - minage (Level 1, Scorable)

Description:

Defines the minimum number of weeks before a password can be changed.

Rationale:

In setting the minage attribute, it prohibits users changing their password until a set number of weeks have passed.

Remediation:

In /etc/security/user, set the default user stanza minage attribute to 1.

This means that a user cannot change their password until at least a week after being set.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/user -s default -a minage=1
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/user -s default -a minage
```

The above command should yield the following output:

default minage=1

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy minage=1 Medium Level policy minage =4 Low Level policy No effect

1.1.3 /etc/security/user - maxage (Level 1, Scorable)

Description:

Defines the maximum number of weeks that a password is valid.

Rationale:

In setting the maxage attribute, it enforces regular password changes.

Remediation:

In /etc/security/user, set the default user stanza maxage attribute to a number greater than 0 but less than or equal to 13

This means that a user password must be changed 13 weeks after being set. If 0 is set then this effectively disables password aging.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/user -s default -a maxage=13
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/user -s default -a maxage
```

The above command should yield the following output:

```
default maxage=13
```

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy maxage = 13 Medium Level policy maxage = 13 Low Level policy maxage = 52

1.1.4 /etc/security/user - minlen (Level 1, Scorable)

Description:

Defines the minimum length of a password.

Rationale:

In setting the minlen attribute, it ensures that passwords meet the required length criteria.

Remediation:

In /etc/security/user, set the default user stanza minlen attribute to be greater than or equal to 8.

This means that all user passwords must be at least 8 characters in length.

NOTE: If a password length greater than 8 is required, an enhanced password hashing algorithm must be selected as detailed in section 1.1.11. The default crypt algorithm only supports 8 character passwords.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsec -f /etc/security/user -s default -a minlen=8

Audit:

From the command prompt, execute the following command:

lssec -f /etc/security/user -s default -a minlen

The above command should yield the following output:

default minlen=8

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy minlen = 8 Medium Level policy minlen = 8 Low Level policy minlen = 8

1.1.5 /etc/security/user - minalpha (Level 1, Scorable)

Description:

Defines the minimum number of alphabetic characters in a password.

Rationale:

In setting the minalpha attribute, it ensures that passwords have a minimum number of alphabetic characters.

Remediation:

In /etc/security/user, set the default user stanza minalpha attribute to be greater than or equal to 2.

This means that there must be at least 2 alphabetic characters within an 8 character user password.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsec -f /etc/security/user -s default -a minalpha=2

Audit:

From the command prompt, execute the following command:

lssec -f /etc/security/user -s default -a minalpha

The above command should yield the following output:

default minalpha=2

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy minalpha = 2 Medium Level policy minalpha = 1 Low Level policy No effect

1.1.6 /etc/security/user- minother (Level 1, Scorable)

Description:

Defines the number of characters within a password which must be non-alphabetic.

Rationale:

In setting the minother attribute, it increases password complexity by enforcing the use of non-alphabetic characters in every user password.

Remediation:

In /etc/security/user, set the default user stanza minother attribute to be greater than or equal to 2.

This means that there must be at least 2 non-alphabetic characters within an 8 character user password.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsec -f /etc/security/user -s default -a minother=2

Audit:

From the command prompt, execute the following command:

lssec -f /etc/security/user -s default -a minother

The above command should yield the following output:

default minother=2

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy minother = 2 Medium Level policy minother = 1

1.1.7 /etc/security/user - maxrepeats (Level 1, Scorable)

Description:

Defines the maximum number of times a character may appear in a password.

Rationale:

In setting the ${\tt maxrepeats}$ attribute, it enforces a maximum number of character repeats within a password

Remediation:

In /etc/security/user, set the default user stanza maxrepeats attribute to 2.

This means that a user may not use the same character more than twice in a password.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsec -f /etc/security/user -s default -a maxrepeats=2

Audit:

From the command prompt, execute the following command:

lssec -f /etc/security/user -s default -a maxrepeats

The above command should yield the following output:

default maxrepeats=2

Default Value: 8

Default AIX Security Expert policy values:

High Level policy maxrepeats = 2 Medium Level policy no effect Low Level policy no effect

1.1.8 /etc/security/user - histexpire (Level 1, Scorable)

Description:

Defines the period of time in weeks that a user will not be able to reuse a password.

Rationale:

In setting the histexpire attribute, it ensures that a user cannot reuse a password within a set period of time.

Remediation:

In /etc/security/user, set the default user stanza histexpire attribute to be less than or equal to 13.

This means that a user will not be able to re-use any password set in the last 13 weeks.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/user -s default -a histexpire=13
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/user -s default -a histexpire
```

The above command should yield the following output:

```
default histexpire=13
```

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy histexpire = 13 Medium Level policy histexpire = 13 Low Level policy histexpire = 26

1.1.9 /etc/security/user - histsize (Level 1, Scorable)

Description:

Defines the number of previous passwords that a user may not reuse.

Rationale:

In setting the histsize attribute, it enforces a minimum number of previous passwords a user cannot reuse.

Remediation:

In /etc/security/user, set the default user stanza histsize attribute to be greater than or equal to 20.

This means that a user many not re-use any of the previous 20 passwords.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/user -s default -a histsize=20
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/user -s default -a histsize
```

The above command should yield the following output:

```
default histsize=20
```

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy histsize = 20 Medium Level policy histsize = 4 Low Level policy histsize = 4

1.1.10 /etc/security/user - maxexpired (Level 1, Scorable)

Description:

Defines the number of weeks after maxage, that a password can be reset by the user

Rationale:

In setting the maxexpired attribute, it limits the number of weeks after password expiry when it may be changed by the user.

Remediation:

In /etc/security/user, set the default user stanza maxexpired attribute to 2.

This means that a user can only reset their password up to 2 weeks after it has expired. After this an administrative user would need to reset the password.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/user -s default -a maxexpired=2
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/user -s default -a maxexpired
```

The above command should yield the following output:

```
default maxexpired=2
```

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy maxexpired = 2

Medium Level policy maxexpired = 4

Low Level policy maxexpired = 8

1.1.11 /etc/security/login.cfg - pwd_algorithm (AIX 5.3 TL-07 +) (Level 2, Scorable)

Description:

Defines the loadable password algorithm used when storing user passwords.

The management of the password encryption algorithm is not performed within the default AIX Security Expert framework. This change is managed as a customized entry in the XML files.

Rationale:

A development of AIX 6.1 was the ability to use different password algorithms as defined in /etc/security/pwdalg.cfg. This functionality has been back ported into AIX 5.3 TL-07 and above. The traditional UNIX password algorithm is crypt, which is a one-way hash function supporting only 8 character passwords. The use of brute force password guessing attacks means that crypt no longer provides an appropriate level of security and so other encryption mechanisms are recommended.

The recommendation of this benchmark is to set the password algorithm to ssha256. This algorithm supports long passwords, up to 255 characters in length and allows passphrases including the use of the extended ASCII table and the space character. Any passwords already set using crypt will remain supported, but there can only one system password algorithm active at any one time.

Remediation:

In /etc/security/login.cfg, set the usw user stanza pwd algorithm attribute to ssha256.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsec -f /etc/security/login.cfg -s usw -a pwd algorithm=ssha256

Audit:

From the command prompt, execute the following command:

lssec -f /etc/security/login.cfg -s usw -a pwd_algorithm

The above command should yield the following output:

usw pwd algorithm=ssha256

Reversion:

If there is a requirement to continue to use the crypt algorithm or the system is running on a level older than AIX 5.3 TL-07, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

Replace:

```
<AIXPertArgs>"chsec -f /etc/security/login.cfg -s usw -a
pwd_algorithm=ssha256"</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>"chsec -f /etc/security/login.cfg -s usw -a pwd_algorithm=ssha256"</AIXPertArgs> -->
```

Default Value: crypt

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.2 AIX Security Expert – Login Policy

This section provides guidance on the configuration of the system login policy. This includes login timeouts, delays and remote root access.

The recommendations in this section affect the general login policy of the system for all users. Every user should have a dedicated account, to ensure accountability and audit trailing. Any generic accounts should be disabled from direct login, where possible. All remote logons as root should also be prohibited, instead elevation to root should only be allowed once a user has authenticated locally through their individual user account.

1.2.1 /etc/security/login.cfg - logininterval (Level 1, Scorable)

Description:

Defines the time interval, in seconds, when the unsuccessful logins must occur to disable a port. This parameter is applicable to all tty connections and the system console.

Rationale:

In setting the <code>logininterval</code> attribute, a port will be disabled if the incorrect password is entered a pre-defined number of times, set via <code>logindisable</code>, within this interval.

Remediation:

In /etc/security/login.cfg, set the default stanza logininterval attribute to be less than or equal to 300.

This means that the port will be disabled if the incorrect password is typed the appropriate number of times, within a 300 second interval.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsec -f /etc/security/login.cfg -s default -a logininterval=300

Audit:

From the command prompt, execute the following command:

lssec -f /etc/security/login.cfg -s default -a logininterval

The above command should yield the following output:

default logininterval=300

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy logininterval = 300 Medium Level policy logininterval = 60 Low Level policy no effect

1.2.2 /etc/security/login.cfg - logindisable (Level 1, Scorable)

Description:

Defines the number of unsuccessful login attempts required before a port will be locked. This parameter is applicable to all tty connections and the system console.

Rationale:

In setting the logindisable attribute, a port will be disabled if the incorrect password is entered a set number of times within a specified interval, set via logininterval.

Remediation:

In /etc/security/login.cfg, set the default stanza logindisable attribute to be less than or equal to 10.

This means that the port will be disabled if the incorrect password is typed 10 times within a 300 second interval.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsec -f /etc/security/login.cfg -s default -a logindisable=10

Audit:

From the command prompt, execute the following command:

lssec -f /etc/security/login.cfg -s default -a logindisable

The above command should yield the following output:

default logindisable=10

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy logindisable = 10 Medium Level policy logindisable = 10 Low Level policy no effect

1.2.3 /etc/security/login.cfg - loginreenable (Level 1, Scorable)

Description:

Defines the number of minutes after a port is locked when it will be automatically un-locked. This parameter is applicable to all tty connections and the system console.

Rationale:

In setting the loginreenable attribute, a locked port will be automatically re-enabled once a given number of minutes have passed.

Remediation:

In /etc/security/login.cfg, set the default stanza loginreenable attribute to be greater than or equal to 360.

This means that a locked port will be automatically re-enabled 360 minutes after being locked.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsec -f /etc/security/login.cfg -s default -a loginreenable=360

Audit:

From the command prompt, execute the following command:

lssec -f /etc/security/login.cfg -s default -a loginreenable

The above command should yield the following output:

default loginreenable=360

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy loginreenable = 360 Medium Level policy loginreenable = 30 Low Level policy no effect

1.2.4 /etc/security/login.cfg - logintimeout (Level 1, Scorable)

Description:

Defines the number of seconds during which the password must be typed at login.

Rationale:

In setting the logintimeout attribute, a password must be entered within a specified time period.

Remediation:

In /etc/security/login.cfg, set the usw stanza logintimeout attribute to be less than or equal to 30.

This means that a user will have 30 seconds, from prompting, in which to type in their password.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/login.cfg -s usw -a logintimeout=30
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/login.cfg -s usw -a logintimeout
```

The above command should yield the following output:

```
usw logintimeout=30
```

Default Value: 60

Default AIX Security Expert policy values:

High Level policy | logintimeout = 30 Medium Level policy | logintimeout = 60 Low Level policy | logintimeout = 60

1.2.5 /etc/security/login.cfg - logindelay (Level 1, Scorable)

Description:

Defines the number of seconds delay between each failed login attempt. This works as a multiplier, so if the parameter is set to 10, after the first failed login it would delay for 10 seconds, after the second failed login 20 seconds etc.

Rationale:

In setting the logindelay attribute, this implements a delay multiplier in-between unsuccessful login attempts.

Remediation:

In /etc/security/login.cfg, set the default stanza logindelay attribute to be greater than or equal to 10.

This means that a user will have to wait 10 seconds before being able to re-enter their password. During subsequent attempts this delay will increase as a multiplier of (the number of failed login attempts * logindelay)

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/login.cfg -s default -a logindelay=10
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/login.cfg -s default -a logindelay
```

The above command should yield the following output:

```
default logindelay=10
```

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy logindelay = 10 Medium Level policy logindelay = 5 Low Level policy logindelay = 5

1.2.6 /etc/security/user - loginretries (Level 1, Scorable)

Description:

Defines the number of attempts a user has to login to the system before their account is disabled.

Rationale:

In setting the loginretries attribute, this ensures that a user can have a pre-defined number of attempts to get their password right, prior to locking the account.

Remediation:

In /etc/security/user, set the default stanza loginretries attribute to 3.

This means that a user will have 3 attempts to enter the correct password. This does not apply to the root user, which has its own stanza entry disabling this feature.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/user -s default -a loginretries=3
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/user -s default -a loginretries
```

The above command should yield the following output:

```
default loginretries=3
```

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy loginretries = 3 Medium Level policy loginretries = 4

Low Level policy AIX 5.3 = No effect AIX 6.1 = 5

1.2.7 /etc/security/user - rlogin (Level 1, Scorable)

Description:

Defines whether or not the root user can login remotely.

Rationale:

In setting the rlogin attribute to false, this ensures that the root user cannot remotely log into the system. All remote logins as root should be prohibited, instead elevation to root should only be allowed once a user has authenticated locally through their individual user account.

Remediation:

In /etc/security/user, set the root stanza rlogin attribute to false.

This means that the root user will not be able to log in the system directly.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/user -s root -a rlogin=false
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/user -s root -a rlogin
```

The above command should yield the following output:

```
root rlogin=false
```

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy rlogin = false Medium Level policy rlogin = false Low Level policy rlogin = true

1.2.8 /etc/security/user - sugroups (Level 1, Scorable)

Description:

Restricts access to root, via su, to members of a specific group.

Rationale:

In setting the <code>sugroups</code> attribute to <code>system</code>, this ensures that only members of the system group are able to <code>su</code> root. This makes it difficult for an attacker to use a stolen root password as the attacker first has to get access to a system user ID.

Remediation:

In /etc/security/user, set the root stanza sugroups attribute to system.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chuser su=true sugroups=system root
```

Audit:

From the command prompt, execute the following command:

```
lssec -f /etc/security/user -s root -a sugroups -a su
```

The above command should yield the following output:

root sugroups=system su=true

Default Value: N/A

Default AIX Security Expert policy values:

High Level policy N/A

1.2.9 System account lockdown (Level 2, Scorable)

Description:

This change disables direct login access for the generic system accounts i.e. daemon, bin, sys, adm, uucp, nobody and lpd.

The lockdown of the non-interactive system users is not a managed process within the default AIX Security Expert framework. This change is managed as a customized entry in the XML files.

Rationale:

This change disables direct local and remote login to the generic system accounts i.e. daemon, bin, sys, adm, uucp, nobody and lpd. It is recommended that a password is not set on these accounts to ensure that the only access is via su from the root account.

There should not be a requirement to log in as any of these users directly. All users should be given specific logon ids to ensure traceability and accountability.

Remediation:

Change the login and remote login user flags to disable access.

Please note the commands below are for information only, as the setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chuser login=false rlogin=false daemon
chuser login=false rlogin=false bin
chuser login=false rlogin=false sys
chuser login=false rlogin=false adm
chuser login=false rlogin=false uucp
chuser login=false rlogin=false nobody
chuser login=false rlogin=false lpd
```

Audit:

```
lsuser -a login rlogin <user>
```

The above command should yield the following output:

```
<user> login=false rlogin=false
```

Reversion:

If there is a requirement to enable generic account remote access, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

<AIXPertArgs>"chuser login=false rlogin=false daemon; chuser login=false
rlogin=false bin; chuser login=false rlogin=false sys; chuser login=false
rlogin=false adm; chuser login=false rlogin=false uucp; chuser login=false
rlogin=false nobody; chuser login=false rlogin=false lpd"</AIXPertArgs>

With:

<!-- <AIXPertArgs>"chuser login=false rlogin=false daemon; chuser login=false
rlogin=false bin; chuser login=false rlogin=false sys; chuser login=false
rlogin=false adm; chuser login=false rlogin=false uucp; chuser login=false
rlogin=false nobody; chuser login=false rlogin=false lpd"</AIXPertArgs> -->

Default Value: No effect

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3 AIX Security Expert – System Services Management

The objective of this section is to reduce the number of running services down to those which are core to the common functions of a UNIX server. When a superfluous service is not running, the system will not be subject to any latent vulnerability later discovered with that service and not require any subsequent remediation.

This section provides guidance on the startup of system services in /etc/inittab, /etc/rc.tcpip and /etc/inetd.conf. The majority of services within these files are disabled in AIX by default, so this section will focus on those services which are enabled, which if possible, should be disabled.

1.3.1 /etc/inittab - qdaemon (Level 2, Scorable)

Description:

This is the printing scheduling daemon that manages the submission of print jobs to piobe.

Rationale:

If there is not a requirement to support local or remote printing, remove the <code>qdaemon</code> entry from /etc/inittab.

Remediation:

In /etc/inittab, remove the qdaemon entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

rmitab qdaemon

Audit:

From the command prompt, execute the following command:

lsitab qdaemon

The above command should yield not yield output

Reversion:

If there is a requirement to implement print queues on the system, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>qdaemon: /etc/inittab : d disqdaemonhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>qdaemon: /etc/inittab : d disqdaemonhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>qdaemon: /etc/inittab : d hls disqdaemon</AIXPertArgs>

With:

<!-- <AIXPertArgs>qdaemon: /etc/inittab : d hls disqdaemon</AIXPertArgs> -->

Default Value: Uncommented

Default AIX Security Expert policy values:

High Level policy Entry removed Medium Level policy Entry removed Low Level policy No effect

1.3.2 /etc/inittab - lpd (Level 2, Scorable)

Description:

The lpd daemon accepts remote print jobs from other systems.

Rationale:

If there is not a requirement for the system to act as a remote print server for other servers, remove the lpd entry.

Remediation:

In /etc/inittab, remove the lpd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

rmitab lpd

Audit:

From the command prompt, execute the following command:

lsitab lpd

The above command should not yield output

Reversion:

If there is a requirement to allow remote print queues on the system, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>lpd: /etc/inittab : d dislpdhls </AIXPertArgs>

With:

<!-- <AIXPertArgs>lpd: /etc/inittab : d dislpdhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs> lpd: /etc/inittab : d hls dislpd</AIXPertArgs>

With:

<!-- <AIXPertArgs> lpd: /etc/inittab : d hls dislpd</AIXPertArgs> -->

Default Value: Uncommented

Default AIX Security Expert policy values:

High Level policy Entry removed Medium Level policy Entry removed Low Level policy No effect

1.3.3 /etc/inittab - piobe (Level 2, Scorable)

Description:

This daemon is the I/O back end for the printing process, handling the job scheduling and spooling.

Rationale:

If there is not a requirement for the system to support either local or remote printing, remove the piobe entry.

Remediation:

In /etc/inittab, remove the piobe entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

rmitab piobe

Audit:

From the command prompt, execute the following command:

lsitab piobe

The above command should yield not yield output

Reversion:

If there is a requirement to implement print queues on the system, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>piobe: /etc/inittab : d dispiobehls</AIXPertArgs>

With:

<!-- <AIXPertArgs>piobe: /etc/inittab : d dispiobehls</AIXPertArgs -->

AIX 6.1

Replace:

<AIXPertArgs>piobe: /etc/inittab : d hls_dispiobe</AIXPertArgs>

With:

<!-- <AIXPertArgs>piobe: /etc/inittab : d hls dispiobe</AIXPertArgs -->

Default Value: Uncommented

Default AIX Security Expert policy values:

High Level policy Entry removed Medium Level policy Entry removed Low Level policy No effect

1.3.4 /etc/inittab – dt (Level 2, Scorable)

Description:

This entry executes the CDE startup script which starts the AIX Common Desktop Environment.

Rationale:

If there is not an lft connected to the system and there are no other X11 clients that require CDE, remove the dt entry.

Remediation:

In /etc/inittab, remove the dt entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

rmitab dt

Audit:

From the command prompt, execute the following command:

lsitab dt

The above command should yield not yield output

Reversion:

No reversion is required if an lft is attached, it will not be disabled.

If there is a requirement to run CDE, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>"dt:" "/etc/inittab" ":" d discdehls</AIXPertArgs>

With:

```
<!-- <AIXPertArgs>"dt:" "/etc/inittab" ":" d discdehls</AIXPertArgs> -->
```

AIX 6.1

Replace:

```
<AIXPertArgs> >"dt:" "/etc/inittab" ":" d hls discde</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>"dt:" "/etc/inittab" ":" d hls discde</AIXPertArgs> -->
```

Default Value: Uncommented (if an lft is present)

Default AIX Security Expert policy values:

High Level policy Entry removed (if an lft is not present)
Medium Level policy Entry removed (if an lft is not present)
Low Level policy No effect

1.3.5 /etc/inittab - rcnfs (Level 2, Scorable)

Description:

The ronfs entry starts the NFS daemons during system boot.

Rationale:

NFS is a service with numerous historical vulnerabilities and should not be enabled unless there is no alternative. If NFS serving is required, then read-only exports are recommended and no filesystem or directory should be exported with root access. Unless otherwise required the NFS daemons will be disabled.

Remediation:

Use the rmitab command to remove the NFS start-up script from /etc/inittab.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

rmitab rcnfs

Audit:

From the command prompt, execute the following command:

lsitab rcnfs

The above command should yield not yield output

Reversion:

If there is a requirement to run NFS, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>d disablenfshls</AIXPertArgs>

With:

<!-- <AIXPertArgs>d disablenfshls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>d hls_disablenfs</AIXPertArgs>

With:

<!-- <AIXPertArgs>d hls disablenfs</AIXPertArgs> -->

Default Value: No effect

Default AIX Security Expert policy values:

High Level policy NFS disabled Medium Level policy No effect Low Level policy No effect

1.3.6 /etc/rc.tcpip - sendmail (Level 2, Scorable)

Description:

This entry starts the sendmail daemon on system startup. This means that the system can operate as a mail server.

Rationale:

sendmail is a service with many historical vulnerabilities and where possible should be disabled. If the system is not required to operate as a mail server i.e. sending, receiving or processing e-mail, comment out the sendmail entry.

Remediation:

In /etc/rc.tcpip, comment out the sendmail entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d sendmail

Audit:

From the command prompt, execute the following command:

```
grep "^#start[[:blank::]]/usr/lib/sendmail" /etc/rc.tcpip
```

The above command should yield the following output:

```
#start /usr/lib/sendmail "$src running" "-bd -q${qpi}"
```

Reversion:

If there is a requirement to run sendmail, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>sendmail d dismaildmnhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>sendmail d dismaildmnhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>sendmail d hls dismaildmn</AIXPertArgs>

With:

<!-- <AIXPertArgs>sendmail d hls dismaildmn</AIXPertArgs> -->

Default Value: Uncommented

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.7 /etc/rc.tcpip - snmpd (Level 2, Scorable)

Description:

This entry starts the snmpd daemon on system startup. This allows remote monitoring of network and server configuration.

Rationale:

The snmpd daemon is used by many 3rd party applications to monitor the health of the system. If snmpd is not required, it is recommended that it is disabled.

Remediation:

In /etc/rc.tcpip, comment out the snmpd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d snmpd

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/snmpd" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/snmpd "\$src running"

Reversion:

If there is a requirement to run snmpd, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>snmpd d dissnmpdmnhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>snmpd d dissnmpdmnhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>snmpd d hls dissnmpdmn</AIXPertArgs>

With:

<!-- <AIXPertArgs>snmpd d hls dissnmpdmn</AIXPertArgs> -->

Default Value: Uncommented

Default AIX Security Expert policy values:

High Level policy Commented out

Medium Level policy Commented out Low Level policy No effect

1.3.8 /etc/rc.tcpip - dhcpcd (Level 2, Scorable)

Description:

This entry starts the dhcpcd daemon on system startup. The dhcpcd deamon receives address and configuration information from the DHCP server.

Rationale:

The <code>dhcpcd</code> daemon is the DHCP client that receives address and configuration information from the DHCP server. This must be disabled if DHCP is not used to serve IP address to the local system.

Remediation:

In /etc/rc.tcpip, comment out the dhcpcd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d dhcpcd

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/dhcpcd" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/dhcpcd "\$src running"

Reversion:

If there is a requirement to run dhoped, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>dhcpcd d disdhcpclienthls</AIXPertArgs>

With:

<!-- <AIXPertArgs>dhcpcd d disdhcpclienthls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>dhcpcd d hls disdhcpclient</AIXPertArgs>

With:

<!-- <AIXPertArgs>dhcpcd d hls disdhcpclient</AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy Commented out Low Level policy No effect

1.3.9 /etc/rc.tcpip – dhcprd (Level 2, Scorable)

Description:

This entry starts the <code>dhcprd</code> daemon on system startup. The <code>dhcpcd</code> deamon receives address and configuration information from the DHCP server.

Rationale:

The dhcprd daemon is the DHCP relay deamon that forwards the DHCP and BOOTP packets in the network. You must disable this service if DHCP is not enabled in the network.

Remediation:

In /etc/rc.tcpip, comment out the dhcprd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d dhcprd

Audit:

From the command prompt, execute the following command:

```
grep "^#start[[:blank::]]/usr/sbin/dhcprd" /etc/rc.tcpip
```

The above command should yield the following output:

#start /usr/sbin/dhcprd "\$src running"

Reversion:

If there is a requirement to run dhoprd, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

With:

<!-- <AIXPertArgs>dhcprd d disdhcpagenthls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>dhcprd d hls disdhcpagent</AIXPertArgs>

With:

<!-- <AIXPertArgs>dhcprd d hls disdhcpagent</AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy Commented out Low Level policy No effect

1.3.10 /etc/rc.tcpip - dhcpsd (Level 2, Scorable)

Description:

This entry starts the <code>dhcpsd</code> daemon on system startup. The <code>dhcpsd</code> deamon is the DHCP server that serves addresses and configuration information to DHCP clients in the network.

Rationale:

The dhcpsd daemon is the DHCP server that serves addresses and configuration information to DHCP clients in the network. You must disable this service if the server is not a DHCP server.

Remediation:

In /etc/rc.tcpip, comment out the dhcpsd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d dhcpsd

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/dhcpsd" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/dhcpsd "\$src running"

Reversion:

If there is a requirement to run dhcpsd, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>dhcpsd d disdhcpservhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>dhcpsd d disdhcpservhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>dhcpsd d hls disdhcpserv</AIXPertArgs>

With:

<!-- <AIXPertArgs>dhcpsd d hls disdhcpserv</AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy Commented out Low Level policy No effect

1.3.11 /etc/rc.tcpip - autoconf6 (Level 2, Scorable)

Description:

This entry starts autoconf6 on system startup. This is to automatically configure IPv6 interfaces at boot time.

Rationale:

authoconf6 is used to automatically configure IPv6 interfaces at boot time. Running this service may allow other hosts on the same physical subnet to connect via IPv6, even when the network does not support it. You must disable this unless you utilize IPv6 on the server.

Remediation:

In /etc/rc.tcpip, comment out the autoconf6 entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d autoconf6

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/autoconf6" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/autoconf6 ""

Reversion:

If there is a requirement to run autoconf6, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>autoconf6 d disautoconf6hls</AIXPertArgs>

With:

<!-- <AIXPertArgs>autoconf6 d disautoconf6hls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>autoconf6 d hls_disautoconf6</AIXPertArgs>

With:

<!-- <AIXPertArgs>autoconf6 d hls disautoconf6</AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.12 /etc/rc.tcpip - gated (Level 2, Scorable)

Description:

This entry starts the gated daemon system startup. This daemon provides gateway routing functions for protocols such as RIP and SNMP.

Rationale:

The gated daemon provides gateway routing functions for protocols such as RIP and SNMP. It is recommended that this daemon is disabled, unless the server is functioning as a network router.

Remediation:

In /etc/rc.tcpip, comment out the gated entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d gated

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/gated" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/gated "\$src running"

Reversion:

If there is a requirement to run gated, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>gated d disgateddmnhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>gated d disgateddmnhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>gated d hls disgateddmn</AIXPertArgs>

With:

<!-- <AIXPertArgs>gated d hls disgateddmn</AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy Commented out Low Level policy Commented out

1.3.13 /etc/rc.tcpip - mrouted (Level 2, Scorable)

Description:

This entry starts the mrouted daemon at system startup. This daemon is an implementation of the multicast routing protocol.

Rationale:

The mrouted daemon is an implementation of the multicast routing protocol. It is recommended that this daemon is disabled, unless the server is functioning as a multicast router.

Remediation:

In /etc/rc.tcpip, comment out the mrouted entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d mrouted

Audit:

From the command prompt, execute the following command:

```
grep "^#start[[:blank::]]/usr/sbin/mrouted" /etc/rc.tcpip
```

The above command should yield the following output:

#start /usr/sbin/mrouted "\$src running"

Reversion:

If there is a requirement to run mrouted, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>mrouted d dismrouteddmnhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>mrouted d dismrouteddmnhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>mrouted d hls dismrouteddmn</AIXPertArgs>

With:

<!-- <AIXPertArgs>mrouted d hls dismrouteddmn</AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.14 /etc/rc.tcpip - named (Level 2, Scorable)

Description:

This entry starts the named daemon at system startup. This is the server for the DNS protocol and controls domain name resolution for its clients.

Rationale:

The named daemon is the server for the DNS protocol and controls domain name resolution for its clients. It is recommended that this daemon is disabled, unless the server is functioning as a DNS server.

Remediation:

In /etc/rc.tcpip, comment out the named entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d named

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/named" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/named "\$src running"

Reversion:

If there is a requirement to run named, edit the customized XML file prior to implementing:

AIX 5.3

Replace:

<AIXPertArgs>named d disdnsdmnhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>named d disdnsdmnhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>named d hls disdnsdmn</AIXPertArgs>

With:

<!-- <AIXPertArgs>named d hls disdnsdmn</AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.15 /etc/rc.tcpip - routed (Level 2, Scorable)

Description:

This entry starts the routed daemon at system startup. The routed daemon manages the network routing tables in the kernel.

Rationale:

The routed daemon manages the network routing tables in the kernel. It is recommended that this daemon is disabled, unless the server is functioning as a network router.

Remediation:

In /etc/rc.tcpip, comment out the routed entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d routed

Audit:

From the command prompt, execute the following command:

```
grep "^#start[[:blank::]]/usr/sbin/routed" /etc/rc.tcpip
```

The above command should yield the following output:

```
#start /usr/sbin/routed "$src running" -q
```

Reversion:

If there is a requirement to run routed, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>routed d disrtngdmnhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>routed d disrtngdmnhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>mrouted d hls dismrouteddmn</AIXPertArgs>

With:

<!-- <AIXPertArgs>mrouted d hls dismrouteddmn</AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.16 /etc/rc.tcpip - rwhod (Level 2, Scorable)

Description:

This entry starts the rwhod daemon at system startup. This is the remote WHO service.

Rationale:

The rwhod daemon is the remote WHO service, which collects and broadcasts status information to peer servers on the same network. It is recommended that this daemon is disabled, unless it is required.

Remediation:

In /etc/rc.tcpip, comment out the rwhod entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d rwhod

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/rwhod" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/rwhod "\$src running"

Reversion:

If there is a requirement to run rwhod, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>rwhod d disrwhoddmnhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>rwhod d disrwhoddmnhls</AIXPertArgs> -->

Enable the daemon:

chrctcp -a rwhod

AIX 6.1

Replace:

<AIXPertArgs>rwhod d hls_disrwhoddmn</AIXPertArgs>

With:

<!-- <AIXPertArgs>rwhod d hls disrwhoddmn</AIXPertArgs> -->

Enable the daemon:

chrctcp -a rwhod

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.17 /etc/rc.tcpip - timed (Level 2, Scorable)

Description:

This entry starts the timed daemon at system startup. This is old UNIX time service.

Rationale:

The timed daemon is the old UNIX time service. You must disable this service and use xntp, if time synchronization is required in your environment.

Remediation:

In /etc/rc.tcpip, comment out the timed entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d timed

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/timed" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/timed "\$src running"

Reversion:

If there is a requirement to run timed, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>timed d distimedmnhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>timed d distimedmnhls</AIXPertArgs> -->

Enable the daemon:

chrctcp -a timed

AIX 6.1

Replace:

<AIXPertArgs>timed d hls distimedmn</AIXPertArgs>

With:

<!-- <AIXPertArgs>timed d hls distimedmn</AIXPertArgs> -->

Enable the daemon:

chrctcp -a timed

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy Commented out Low Level policy Commented out

1.3.18 /etc/rc.tcpip - dpid2 (Level 2, Scorable)

Description:

This entry starts the <code>dpid2</code> daemon on system startup. The <code>dpid2</code> deamon acts as a protocol converter, which enables DPI (SNMP v2) sub-agents, such as <code>hostmibd</code>, to talk to a SNMP v1 agent that follows SNMP MUX protocol

Rationale:

The dpid2 deamon acts as a protocol converter, which enables DPI (SNMP v2) sub-agents, such as hostmibd, to talk to a SNMP v1 agent that follows SNMP MUX protocol. Unless the server hosts an SNMP agent, it is recommended that dpid2 is disabled.

Remediation:

In /etc/rc.tcpip, comment out the dpid2 entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d dpid2

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/dpid2" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/dpid2 "\$src running"

Reversion:

If there is a requirement to run dpid2, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>dipid2 d disdpid2dmnhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>dipid2 d disdpid2dmnhls</AIXPertArgs> -->

Enable the daemon:

chrctcp -a dpid2

AIX 6.1

Replace:

<AIXPertArgs>dpid2 d hls disdpid2dmn</AIXPertArgs>

With:

<!-- <AIXPertArgs>dpid2 d hls disdpid2dmn</AIXPertArgs> -->

Enable the daemon:

chrctcp -a dpid2

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.19 /etc/rc.tcpip - hostmibd (Level 2, Scorable)

Description:

This entry starts the hostmibd daemon on system startup. This is a dpi2 sub-agent that may be required if the server runs SNMP.

The hostmibd daemon is not managed within the default AIX Security Expert framework. This change is managed as a customized entry in the XML files.

Rationale:

The hostmibd daemon is a dpi2 sub-agent which manages a number of MIB variables. If snmpd is not required, it is recommended that it is disabled.

The specific MIB variables which are managed by hostmibd are defined by RFC 2790. Further details relating to these MIBS can be found in the URL below:

http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic=/com.ibm.aix.cmds/doc/aixcmds2/hostmibd.htm

Remediation:

In /etc/rc.tcpip, comment out the hostmibd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d hostmibd

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/hostmibd" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/hostmibd "\$src running"

Reversion:

If there is a requirement to run hostmibd, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom_aix<OS>.xml

Replace:

<AIXPertArgs>"chrctcp -d hostmibd"</AIXPertArgs>

With:

<!-- <AIXPertArgs>"chrctcp -d hostmibd"</AIXPertArgs> -->

Enable the daemon:

chrctcp -a hostmibd

Default Value: Uncommented

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.20 /etc/rc.tcpip - snmpmibd (Level 2, Scorable)

Description:

This entry starts the snmpmibd daemon on system startup. This is a dpi2 sub-agent that may be required if the server runs SNMP.

The snmpmibd daemon is not managed within the default AIX Security Expert framework. This change is managed as a customized entry in the XML files.

Rationale:

The snmpmibd daemon is a dpi2 sub-agent which manages a number of MIB variables. If snmpd is not required, it is recommended that it is disabled.

The specific MIB variables which are managed by snmpmibd are defined by numerous RFCs. Further details relating to these MIBS can be found in the URL below:

http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic=/com.ibm.aix.cmds/doc/aixcmds5/snmpmibd.htm

Remediation:

In /etc/rc.tcpip, comment out the snmpmibd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d snmpmibd

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/snmpmibd" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/snmpmibd "\$src running"

Reversion:

If there is a requirement to run snmpmibd, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

Replace:

With:

<!-- <AIXPertArgs>"chrctcp -d snmpmibd"</AIXPertArgs> -->

Enable the daemon:

chrctcp -a snmpmibd

Default Value: Uncommented

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.21 /etc/rc.tcpip – aixmibd (Level 2, Scorable)

Description:

This entry starts the aixmibd daemon on system startup. This is a dpi2 sub-agent that may be required if the server runs SNMP.

The aixmibd daemon is not a managed within the default AIX Security Expert framework. This change is managed as a customized entry in the XML files.

Rationale:

The aixmibd daemon is a dpi2 sub-agent which manages a number of MIB variables. If snmpd is not required, it is recommended that it is disabled.

The aixmibd collects data from an AIX specific MIB. Further details relating to this MIB can be found in the URL below:

http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic=/com.ibm.aix.cmds/doc/aixcmds1/aixmibd.htm

Remediation:

In /etc/rc.tcpip, comment out the aixmibd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d aixmibd

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/aixmibd" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/aixmibd "\$src running"

Reversion:

If there is a requirement to run aixmibd, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

Replace:

<AIXPertArgs>"chrctcp -d aixmibd"</AIXPertArgs>

With:

<!-- <AIXPertArgs>"chrctcp -d aixmibd"</AIXPertArgs> -->

Enable the daemon:

chrctcp -a aixmibd

Default Value: Uncommented

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.22 /etc/rc.tcpip - ndpd-host (Level 2, Scorable)

Description:

This entry starts ndpd-host on system startup. This is the Neighbor Discovery Protocol (NDP) daemon, required in IPv6.

The ndpd-host entry is not managed within the default AIX Security Expert framework. This change is managed as a customized entry in the XML files.

Rationale:

The ndpd-host is the NDP deamon for the server. Unless the server utilizes IPv6, this is not required and should be disabled.

Remediation:

In /etc/rc.tcpip, comment out the ndpd-host entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d ndpd-host

Audit:

From the command prompt, execute the following command:

```
grep "^#start[[:blank::]]/usr/sbin/ndpd-host" /etc/rc.tcpip
```

The above command should yield the following output:

```
#start /usr/sbin/ndpd-host "$src running"
```

Reversion:

If there is a requirement to run ndpd-host, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

Replace:

```
<AIXPertArgs>"chrctcp -d ndpd-host"</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>"chrctcp -d ndpd-host"</AIXPertArgs> -->
```

Enable the daemon:

```
chrctcp -a ndpd-host
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.23 /etc/rc.tcpip – ndpd-router (Level 2, Scorable)

Description:

This entry starts ndpd-router on system startup. This manages the Neighbor Discovery Protocol (NDP) for non kernel activities, required in IPv6.

The ndpd-router entry is not managed within the default AIX Security Expert framework. This change is managed as a customized entry in the XML files.

Rationale:

The ndpd-router manages NDP for non-kernel activities. Unless the server utilizes IPv6, this is not required and should be disabled.

Remediation:

In /etc/rc.tcpip, comment out the ndpd-router entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chrctcp -d ndpd-router

Audit:

From the command prompt, execute the following command:

grep "^#start[[:blank::]]/usr/sbin/ndpd-router" /etc/rc.tcpip

The above command should yield the following output:

#start /usr/sbin/ndpd-router "\$src running"

Reversion:

If there is a requirement to run ndpd-router, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

Replace:

<AIXPertArgs>"chrctcp -d ndpd-router"</AIXPertArgs>

With:

<!-- <AIXPertArgs>"chrctcp -d ndpd-router"</AIXPertArgs> -->

Enable the daemon:

chrctcp -a ndpd-router

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.24 /etc/inetd.conf - telnet (Level 2, Scorable)

Description:

This entry starts the telnetd daemon when required. This provides a protocol for command line access, from a remote machine.

Rationale:

This telnet service is used to service remote user connections. This is historically the most commonly used remote access method for UNIX servers. The username and passwords are passed over the network in clear text and therefore insecurely. Unless required the telnetd daemon will be disabled.

Many older legacy systems do not support SSH and still require telnet as a protocol for access. If this is not required, it is recommended that telnet is disabled and SSH is used as a replacement authentication mechanism.

Remediation:

In /etc/inetd.conf, comment out the telnet entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'telnet' -p 'tcp6'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#telnet[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#telnet stream tcp6 nowait root /usr/sbin/telnetd telnetd -a
```

Reversion:

If there is a requirement to run telnet, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>telnet tcp d telnethls</AIXPertArgs>

With:

```
<!-- <AIXPertArgs>telnet tcp d telnethls</AIXPertArgs> -->
```

AIX 6.1

Replace:

```
<AIXPertArgs>telnet tcp d hls telnet</AIXPertArgs>
```

With:

<!-- <AIXPertArgs>telnet tcp d hls telnet</AIXPertArgs> -->

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.25 /etc/inetd.conf - exec (Level 2, Scorable)

Description:

This entry starts the rexect daemon when required. This daemon executes a command from a remote system, once the connection has been authenticated.

Rationale:

The exec service is used to execute a command sent from a remote server. The username and passwords are passed over the network in clear text and therefore insecurely. Unless required the rexect daemon will be disabled. This function, if required, should be facilitated through SSH.

Remediation:

In /etc/inetd.conf, comment out the exec entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'exec' -p 'tcp6'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#exec[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

<pre>#exec stream tcp6 nowait root /usr/sbin/rexecd rexecd</pre>	
--	--

Reversion:

If there is a requirement to run exec, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>exec tcp d rexecdhls</AIXPertArgs>

With:

```
<!-- <AIXPertArgs>exec tcp d rexecdhls</AIXPertArgs> -->
```

AIX 6.1

Replace:

```
<AIXPertArgs>exec tcp d hls_rexecd</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>exec tcp d hls_rexecd</AIXPertArgs> -->
```

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy Commented out Low Level policy No effect

1.3.26 /etc/inetd.conf - daytime (Level 2, Scorable)

Description:

This entry starts the daytime service when required. This provides the current date and time to other servers on a network.

Rationale:

This daytime service is a defunct time service, typically used for testing purposes only. The service should be disabled as it can leave the system vulnerable to DoS ping attacks.

Remediation:

In /etc/inetd.conf, comment out the daytime entries.

Please note the commands below are for information only, as the settings will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'daytime' -p 'udp' chsubserver -r inetd -C /etc/inetd.conf -d -v 'daytime' -p 'tcp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#daytime[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

#daytime	stream	tcp	nowait	root	internal
#daytime	dgram	udp	wait	root	internal

Reversion:

If there is a requirement to run daytime, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

AIX 5.3

Replace:

```
<AIXPertArgs>daytime tcp d tcpdaytimehls</AIXPertArgs>
<AIXPertArgs>daytime udp d udpdaytimehls</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>daytime tcp d tcpdaytimehls</AIXPertArgs> --> <!-- <AIXPertArgs>daytime udp d udpdaytimehls</AIXPertArgs> -->
```

AIX 6.1

Replace:

With:

```
<!-- <AIXPertArgs>daytime tcp d hls_tcpdaytime</</AIXPertArgs> --> <!-- <AIXPertArgs>daytime udp d hls_udpdaytime</AIXPertArgs> -->
```

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.27 /etc/inetd.conf - shell (Level 2, Scorable)

Description:

This entry starts the rshd daemon when required. This daemon executes a command from a remote system.

Rationale:

This shell service is used to execute a command from a remote server. The username and passwords are passed over the network in clear text and therefore insecurely. Unless required the rshd daemon will be disabled. This function, if required, should be facilitated through SSH.

Remediation:

In /etc/inetd.conf, comment out the shell entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsubserver -r inetd -C /etc/inetd.conf -d -v 'shell' -p 'tcp6'

Audit:

From the command prompt, execute the following command:

grep "^#shell[[::blank::]]" /etc/inetd.conf

The above command should yield the following output:

#shell stream tcp6 nowait root /usr/sbin/rshd rshd

Reversion:

If there is a requirement to run shell, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>shell tcp d shellhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>shell tcp d shellhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>shell tcp d hls shell</AIXPertArgs>

With:

<!-- <AIXPertArgs>shell tcp d hls_shell</AIXPertArgs> -->

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy Commented out Low Level policy Commented out

1.3.28 /etc/inetd.conf - cmsd (Level 2, Scorable)

Description:

This entry starts the cmsd service when required. This is a calendar and appointment service.

Rationale:

The cmsd service is utilized by CDE to provide calendar functionality. If CDE is not required, this service should be disabled.

Remediation:

In /etc/inetd.conf, comment out the cmsd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'cmsd' -p 'sunrpc udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#cmsd[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

#cmsd	sunrpc_udp	udp	wait	root	/usr/dt/bin/rpc.cmsd cmsd 100068
2-5					

Reversion:

If there is a requirement to run cmsd, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>cmsd udp d cmsdhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>cmsd udp d cmsdhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>cmsd udp d hls cmsd</AIXPertArgs>

With:

```
<!-- <AIXPertArgs>cmsd udp d hls cmsd</AIXPertArgs> -->
```

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.29 /etc/inetd.conf - ttdbserver (Level 2, Scorable)

Description:

This entry starts the ttdbserver service when required. It is not a pre-requisite service for CDE, which is fully functional when it is disabled.

Rationale:

The ttdbserver service is the tool-talk database service for CDE. This service runs as root and should be disabled. Unless required the ttdbserver service will be disabled.

Remediation:

In /etc/inetd.conf, comment out the ttdbserver entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'ttdbserver' -p 'sunrpc_tcp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#ttdbserver[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#ttdbserver sunrpc_tcp tcp wait root
/usr/dt/bin/rpc.ttdbserver rpc.ttdbserver 100083 1
```

Reversion:

If there is a requirement to run ttdbserver, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>ttdbserver tcp d ttdbserverhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>ttdbserver tcp d ttdbserverhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>ttdbserver tcp d hls ttdbserver</AIXPertArgs>

With:

<!-- <AIXPertArgs>ttdbserver tcp d hls ttdbserver</AIXPertArgs> -->

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.30 /etc/inetd.conf - uucp (Level 2, Scorable)

Description:

This entry starts the uucp service when required. This service facilitates file copying between networked servers.

Rationale:

The uucp (UNIX to UNIX Copy Program), service allows users to copy files between networked machines. Unless an application or process requires UUCP this should be disabled.

Remediation:

In /etc/inetd.conf, comment out the uucp entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsubserver -r inetd -C /etc/inetd.conf -d -v 'uucp' -p 'tcp'

Audit:

From the command prompt, execute the following command:

```
grep "^#uucp[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

#uucp stream tcp nowait root /usr/sbin/uucpd uucpd

Reversion:

If there is a requirement to run uucp, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>uucp tcp d uucphls</AIXPertArgs>

With:

<!-- <AIXPertArgs>uucp tcp d uucphls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>uucp tcp d hls uucp</AIXPertArgs>

With:

<!-- <AIXPertArgs>uucp tcp d hls uucp</AIXPertArgs> -->

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.31 /etc/inetd.conf - time (Level 2, Scorable)

Description:

This entry starts the time service when required. This service can be used to synchronize system clocks.

Rationale:

The time service is an obsolete process used to synchronize system clocks at boot time. This has been superseded by NTP, which should be use if time synchronization is necessary. Unless required the time service will be disabled.

Remediation:

In /etc/inetd.conf, comment out the time entries.

Please note the commands below are for information only, as these settings will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'time' -p 'udp' chsubserver -r inetd -C /etc/inetd.conf -d -v 'time' -p 'tcp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#time[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#time stream tcp nowait root internal #time dgram udp wait root internal
```

Reversion:

If there is a requirement to run time, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

AIX 5.3

Replace:

```
<AIXPertArgs>time tcp d tcptimehls</AIXPertArgs>
<AIXPertArgs>time udp d udptimehls</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>time tcp d tcptimehls</AIXPertArgs> --> <!-- <AIXPertArgs>time udp d udptimehls</AIXPertArgs> -->
```

AIX 6.1

Replace:

```
<AIXPertArgs>time tcp d hls_tcptime</AIXPertArgs>
<AIXPertArgs>time udp d hls_udptime</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>time tcp d hls_tcptime</AIXPertArgs> --> <!-- <AIXPertArgs>time udp d hls_udptime</AIXPertArgs> -->
```

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.32 /etc/inetd.conf – login (Level 2, Scorable)

Description:

This entry starts the rlogin daemon when required. This service authenticates remote user logins.

Rationale:

This login service is used to authenticate a remote user connection when logging in via the rlogin command. The username and password are passed over the network in clear text and therefore insecurely. Unless required the rlogin daemon will be disabled. This function, if required, should be facilitated through SSH.

Remediation:

In /etc/inetd.conf, comment out the login entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'login' -p 'tcp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#login[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

#login stream tcp6 nowait root /usr/sbin/rlogind rlogind
--

Reversion:

If there is a requirement to run login, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom_aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>login tcp d rloginhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>login tcp d rloginhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>login tcp d hls rlogin</AIXPertArgs>

With:

<!-- <AIXPertArgs>login tcp d hls rlogin</AIXPertArgs> -->

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy Commented out Low Level policy No effect

1.3.33 /etc/inetd.conf - talk (Level 2, Scorable)

Description:

This entry starts the talkd daemon when required. This service establishes a two-way communication link between two users, either locally or remotely.

Rationale:

This talk service is used to establish an interactive two-way communication link between two UNIX users. It is unlikely that there would be a requirement to run this type of service on a UNIX system. Unless required the talk service will be disabled

Remediation:

In /etc/inetd.conf, comment out the talk entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'talk' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#talk[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

#talk dgram udp wait root /usr/sbin/talkd talkd

Reversion:

If there is a requirement to run talk, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>talk udp d talkhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>talk udp d talkhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>talk udp d hls talk</AIXPertArgs>

With:

<!-- <AIXPertArgs>talk udp d hls talk</AIXPertArgs> -->

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy Commented out Low Level policy Commented out

1.3.34 /etc/inetd.conf - ntalk (Level 2, Scorable)

Description:

This entry starts the talkd daemon when required. This service establishes a two-way communication link between two users, either locally or remotely.

The ntalk service is not a managed parameter within the default AIX Security Expert framework. This parameter is managed as a customized entry in the XML files.

Rationale:

This talk service is used to establish an interactive two-way communication link between two UNIX users. It is unlikely that there would be a requirement to run this type of service on a UNIX system. Unless required the ntalk service will be disabled

Remediation:

In /etc/inetd.conf, comment out the ntalk entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'ntalk' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#ntalk[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#ntalk dgram udp wait root /usr/sbin/talkd talkd
```

Reversion:

If there is a requirement to run ntalk, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'ntalk' -p 'udp'" </AIXPertArgs>
```

With:

```
<!-- "chsubserver -r inetd -C /etc/inetd.conf -d -v 'ntalk' -p 'udp'" -->
```

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.35 /etc/inetd.conf - ftp (Level 2, Scorable)

Description:

This entry starts the ftpd daemon when required. This service is used for transferring files from/to a remote machine.

Rationale:

This ftp service is used to transfer files from or to a remote machine. The username and passwords are passed over the network in clear text and therefore insecurely. Unless required the ftpd daemon will be disabled.

Many older legacy systems do not support SSH and still required ftp as a service for data copying. If this is not required it is recommended that ftp is disabled and sftp is used as a replacement file and directory copying mechanism.

Remediation:

In /etc/inetd.conf, comment out the ftp entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsubserver -r inetd -C /etc/inetd.conf -d -v 'ftp' -p 'tcp6'

Audit:

From the command prompt, execute the following command:

grep "^#ftp[[::blank::]]" /etc/inetd.conf

The above command should yield the following output:

#ftp stream tcp6 nowait root /usr/sbin/ftpd ftpd

Reversion:

If there is a requirement to run ftp, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>ftp tcp d ftphls</AIXPertArgs>

With:

<!-- <AIXPertArgs>ftp tcp d ftphls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>ftp tcp d hls ftp</AIXPertArgs>

With:

<!-- <AIXPertArgs>ftp tcp d hls_ftp</AIXPertArgs> -->

Default Value: Commented in

Default AIX Security Expert policy values:

High Level policy Commented out Medium Level policy No effect Low Level policy No effect

1.3.36 /etc/inetd.conf - chargen (Level 2, Scorable)

Description:

This entry starts the chargen service when required. This service is used to test the integrity of TCP/IP packets arriving at the destination.

Rationale:

This chargen service is a character generator service and is used for testing the integrity of TCP/IP packets arriving at the destination. An attacker may spoof packets between machines running the chargen service and thus provide an opportunity for DoS attacks. You must disable this service unless you are testing your network.

Remediation:

In /etc/inetd.conf, comment out the chargen entries.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'chargen' -p 'tcp' chsubserver -r inetd -C /etc/inetd.conf -d -v 'chargen' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#chargen[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

#chargen	stream	tcp	nowait	root	internal
#chargen	dgram	udp	wait	root	internal

Reversion:

If there is a requirement to run chargen, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'chargen' -p 'udp'" </AIXPertArgs>
```

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'chargen' -p
'tcp'" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'chargen' -p
'udp'" </AIXPertArgs> -->
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'chargen' -p
'tcp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.37 /etc/inetd.conf - discard (Level 2, Scorable)

Description:

This entry starts the discard service when required. This service is used as a debugging tool by setting up a listening socket which ignores the data it receives.

Rationale:

The discard service is used as a debugging and measurement tool. It sets up a listening socket and ignores data that it receives. This is a /dev/null service and is obsolete. This can be used in DoS attacks and therefore, must be disabled.

Remediation:

In /etc/inetd.conf, comment out the discard entries.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'discard' -p 'tcp' chsubserver -r inetd -C /etc/inetd.conf -d -v 'discard' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#discard[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

#discard	stream	tcp	nowait	root	internal
#discard	dgram	udp	wait	root	internal

Reversion:

If there is a requirement to run discard, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'discard' -p
'udp'" </AIXPertArgs>
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'discard' -p
'tcp'" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'discard' -p 'udp'" </AIXPertArgs> --> <!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'discard' -p 'tcp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.38 /etc/inetd.conf - dtspc (Level 2, Scorable)

Description:

This entry starts the $\tt dtspc$ service when required. This service is used in response to a CDE client request.

Rationale:

The <code>dtspc</code> service deals with the CDE interface of the X11 daemon. It is started automatically by the <code>inetd</code> daemon in response to a CDE client requesting a process to be started on the daemon's host. This makes it vulnerable to buffer overflow attacks, which may allow an attacker to gain root privileges on a host. This service must be disabled unless it is absolutely required.

Remediation:

In /etc/inetd.conf, comment out the dtspc entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'dtspc' -p 'tcp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#dtspc[[::blank::]]" /etc/inetd.conf
```

```
#dtspc stream tcp nowait root /usr/dt/bin/dtspcd /usr/dt/bin/dtspcd
```

Reversion:

If there is a requirement to run dtspc, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'dtspc' -p 'tcp'" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'dtspc' -p 'tcp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.39 /etc/inetd.conf - echo (Level 2, Scorable)

Description:

This entry starts the echo service when required. This service sends back data received by it on a specified port.

Rationale:

The echo service sends back data received by it on a specified port. This can be misused by an attacker to launch DoS attacks or Smurf attacks by initiating a data storm and causing network congestion. The service is used for testing purposes and therefore must be disabled if not required.

Remediation:

In /etc/inetd.conf, comment out the echo entries.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'echo' -p 'tcp' chsubserver -r inetd -C /etc/inetd.conf -d -v 'echo' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#echo[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#echo stream tcp nowait root internal
#echo dgram udp wait root internal
```

Reversion:

If there is a requirement to run discard, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'echo' -p 'udp'" </AIXPertArgs> 
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'echo' -p 'tcp'" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'echo' -p 'udp'" </AIXPertArgs> --> <!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'echo' -p 'tcp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.40 /etc/inetd.conf - pcnfs (Level 2, Scorable)

Description:

This entry starts the pcnfsd daemon when required. This service is an authentication and printing program, which uses NFS to provide file transfer services.

Rationale:

The pcnfsd service is an authentication and printing program, which uses NFS to provide file transfer services. This service is vulnerable and exploitable and permits the machine to be compromised both locally and remotely. If PC NFS clients are required within the environment, Samba is recommended as an alternative software solution. The pcnfsd daemon predates Microsoft's release of SMB specifications. This service should therefore be disabled.

Remediation:

In /etc/inetd.conf, comment out the pcnfsd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'pcnfsd' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#pcnfsd[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#pcnfsd sunrpc_udp udp wait root /usr/sbin/rpc.pcnfsd pcnfsd
150001 1-2
```

Reversion:

If there is a requirement to run pcnfsd, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'pcnfsd' -p 'udp'"
</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'pcnfsd' -p 'udp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.41 /etc/inetd.conf - rstatd (Level 2, Scorable)

Description:

This entry starts the rstatd daemon when required. This service is used to provide kernel statistics and other monitorable parameters such as CPU usage, system uptime, network usage etc

Rationale:

The rstatd service is used to provide kernel statistics and other monitorable parameters pertinent to the system such as: CPU usage, system uptime, network usage etc. An attacker may use this information in a DoS attack. This service should be disabled.

Remediation:

In /etc/inetd.conf, comment out the rstatd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'rstatd' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#rstatd[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#rstatd sunrpc_udp udp wait root /usr/sbin/rpc.rstatd rstatd
100001 1-3
```

Reversion:

If there is a requirement to run rstatd, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'rstatd' -p 'udp'" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'rstatd' -p 'udp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.42 /etc/inetd.conf - rusersd (Level 2, Scorable)

Description:

This entry starts the rsusersd daemon when required. This service provides a list of current users active on a system.

Rationale:

The rusersd service runs as root and provides a list of current users active on a system. An attacker may use this information in a DoS attack. This is not an essential service and should be disabled

Remediation:

In /etc/inetd.conf, comment out the rusersd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'rusersd' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#rusersd[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#rusersd sunrpc_udp udp wait root
/usr/lib/netsvc/rusers/rpc.rusersd rusersd 100002 1-2
```

Reversion:

If there is a requirement to run rusersd, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'rusersd' -p 'udp'" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'rusersd' -p 'udp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.43 /etc/inetd.conf - rwalld (Level 2, Scorable)

Description:

This entry starts the rwalld daemon when required. This service allows remote users to broadcast system wide messages.

Rationale:

The rwalld service allows remote users to broadcast system wide messages. The service runs as root and must be disabled unless absolutely necessary. Attackers may use this service to launch DoS attacks.

Remediation:

In /etc/inetd.conf, comment out the rwalld entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'rwalld' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#rwalld[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#rwalld sunrpc_udp udp wait root /usr/lib/netsvc/rwall/rpc.rwalld
rwalld 100008 1
```

Reversion:

If there is a requirement to run rwalld, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'rwalld' -p 'udp'"
</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'rwalld' -p 'udp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A

Medium Level policy N/A Low Level policy N/A

1.3.44 /etc/inetd.conf - sprayd (Level 2, Scorable)

Description:

This entry starts the sprayd daemon when required. This service is used as a tool to generate UDP packets for testing and diagnosing network problems.

Rationale:

The sprayd service is used as a tool to generate UDP packets for testing and diagnosing network problems. The service must be disabled if you are not running NFS, as it can be used by attackers in a Distributed Denial of Service (DDoS) attack.

Remediation:

In /etc/inetd.conf, comment out the sprayd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'sprayd' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#sprayd[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

#sprayd sunrpc_udp	udp	wait	root	/usr/lib/netsvc/spray/rpc.sprayd
sprayd 100012 1				

Reversion:

If there is a requirement to run sprayd, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'sprayd' -p 'udp'"
</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'sprayd' -p 'udp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.45 /etc/inetd.conf - klogin (Level 2, Scorable)

Description:

This entry starts the klogin service when required. This is a kerberized login service, which provides a higher degree of security over traditional rlogin and telnet.

Rationale:

The klogin service offers a higher degree of security than traditional rlogin or telnet by eliminating most clear-text password exchanges on the network. However, it is still not as secure as SSH, which encrypts all traffic. If you use klogin to login to a system, the password is not sent in clear text; however, if you su to another user, that password exchange is open to detection from network-sniffing programs. The recommendation is to utilize SSH wherever possible instead of klogin.

If the klogin service is used, you must use the latest kerberos version available and make sure that all the latest patches are installed.

Remediation:

In /etc/inetd.conf, comment out the klogin entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'klogin' -p 'tcp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#klogin[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

#klogin stream	+ an	nowait r	00±	/usr/sbin/krlogind	krlogind	
#KIOGIN Stream	rcb	HOWalt 10	001	/ usi/sbin/kilogina	KLIOGINA	

Reversion:

If there is a requirement to run klogin, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'klogin' -p 'tcp'" </AIXPertArgs>

With:

<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'klogin' -p 'tcp'" </AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.46 /etc/inetd.conf - kshell (Level 2, Scorable)

Description:

This entry starts the kshell service when required. This is a kerberized remote shell service, which provides a higher degree of security over traditional rsh.

Rationale:

The kshell service offers a higher degree of security than traditional rsh services. However, it still does not use encrypted communications. The recommendation is to utilize SSH wherever possible instead of kshell.

If the kshell service is used, you should use the latest kerberos version available and must make sure that all the latest patches are installed.

Remediation:

In /etc/inetd.conf, comment out the kshell entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'kshell' -p 'tcp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#kshell[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#kshell stream tcp nowait root /usr/sbin/krshd krshd
```

Reversion:

If there is a requirement to run klogin, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'kshell' -p 'tcp'" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'kshell' -p 'tcp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.47 /etc/inetd.conf - rquotad (Level 2, Scorable)

Description:

This entry starts the rquotad service when required. This allows NFS clients to enforce disk quotas on locally mounted filesystems.

Rationale:

The rquotad service allows NFS clients to enforce disk quotas on file systems that are mounted on the local system. This service should be disabled if it is not required.

Remediation:

In /etc/inetd.conf, comment out the rquotad entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'rquotad' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#rquotad[[::blank::]]" /etc/inetd.conf
```

The above command should yield the following output:

```
#rquotad sunrpc_udp udp wait root /usr/sbin/rpc.rquotad
rquotad 100011 1
```

Reversion:

If there is a requirement to run rquotad, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'rquotad' -p
'udp'" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'rquotad' -p 'udp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.48 /etc/inetd.conf - tftp (Level 2, Scorable)

Description:

This entry starts the tftp service when required.

Rationale:

The tftp service allows remote systems to download or upload files to the tftp server without any authentication. It is therefore a service that should not run, unless needed. One of the main reasons for requiring this service to be activated is if the host is a NIM master. However, the service can be enabled and then disabled once a NIM operation has completed, rather than left running permanently.

Remediation:

In /etc/inetd.conf, comment out the tftp entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'tftp' -p 'udp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#tftp[[::blank::]]" /etc/inetd.conf
```

#tftp dgram udp6 SRC nobody /usr/sbin/tftpd tftpd -n

Reversion:

If there is a requirement to run tftp, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

Replace:

<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'tftp' -p 'udp'" </AIXPertArgs>

With:

<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'tftp' -p 'udp'" </AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.49 /etc/inetd.conf - imap (Level 2, Scorable)

Description:

This entry starts the imap2 service when required.

Rationale:

The <code>imap2</code> service or Internet Message Access Protocol (IMAP) supports the IMAP4 remote mail access protocol. It works with <code>sendmail</code> and <code>bellmail</code>. This service should be disabled if it is not required.

Remediation:

In /etc/inetd.conf, comment out the imap2 entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'imap2' -p 'tcp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#imap2[[::blank::]]" /etc/inetd.conf
```

#imap2 stream tcp nowait root /usr/sbin/imapd imapd

Reversion:

If there is a requirement to run imap2, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

Replace:

<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'imap2' -p 'tcp'" </AIXPertArgs>

With:

<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'imap2' -p 'tcp'" </AIXPertArgs> -->

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.50 /etc/inetd.conf - pop3 (Level 2, Scorable)

Description:

This entry starts the pop3 service when required.

Rationale:

The pop3 service provides a pop3 server. It supports the pop3 remote mail access protocol. It works with sendmail and bellmail. This service should be disabled if it is not required.

Remediation:

In /etc/inetd.conf, comment out the pop3 entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsubserver -r inetd -C /etc/inetd.conf -d -v 'pop3' -p 'tcp'

Audit:

From the command prompt, execute the following command:

grep "^#pop3[[::blank::]]" /etc/inetd.conf

```
#pop3 stream tcp nowait root /usr/sbin/pop3d pop3d
```

Reversion:

If there is a requirement to run pop3, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'pop3' -p 'tcp" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'pop3' -p 'tcp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.51 /etc/inetd.conf - fingerd (Level 2, Scorable)

Description:

This entry starts the fingerd daemon when required.

Rationale:

The fingerd daemon provides the server function for the finger command. This allows users to view real-time pertinent user login information on other remote systems. This service should be disabled if it is not required.

Remediation:

In /etc/inetd.conf, comment out the fingerd entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'finger' -p 'tcp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#finger[[::blank::]]" /etc/inetd.conf
```

```
#finger stream tcp nowait nobody /usr/sbin/fingerd fingerd
```

Reversion:

If there is a requirement to run fingerd, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'finger' -p 'tcp'" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'finger' -p 'tcp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.52 /etc/inetd.conf - instsrv (Level 2, Scorable)

Description:

This entry starts the instarv service when required.

Rationale:

The instary service is part of the Network Installation Tools, used for servicing servers running AIX 3.2. This service should be disabled.

Remediation:

In /etc/inetd.conf, comment out the instsrv entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsubserver -r inetd -C /etc/inetd.conf -d -v 'instsrv' -p 'tcp'
```

Audit:

From the command prompt, execute the following command:

```
grep "^#instsrv[[::blank::]]" /etc/inetd.conf
```

```
#instsrv stream tcp nowait netinst /u/netinst/bin/instsrv instsrv -r
/tmp/netinstalllog /u/netinst/scripts
```

Reversion:

If there is a requirement to run instary, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'instsrv' -p
'tcp'" </AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chsubserver -r inetd -C /etc/inetd.conf -d -v 'instsrv' -p 'tcp'" </AIXPertArgs> -->
```

Default Value: Commented out

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.3.53 /etc/inetd.conf – permissions and ownership (Level 1, Scorable)

Description:

The recommended permissions and ownership for /etc/inetd.conf are applied.

Rationale:

The /etc/inetd.conf file contains the list of services that inetd controls and determines their current status i.e. active or disabled. This file must be protected from unauthorized access and modifications to ensure that the services disabled in this benchmark remain locked down.

Remediation:

Set the recommended permissions and ownership to /etc/inetd.conf.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chmod u=rw,go=r /etc/inetd.conf
chown root:system /etc/inetd.conf
```

Audit:

From the command prompt, execute the following command:

```
ls -1 /etc/inetd.conf | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

```
-rw-r--r- root system /etc/inetd.conf
```

If there is a requirement to leave the current ownership and permissions in place, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

Replace

```
<AIXPertArgs> "chmod 644 /etc/inetd.conf; chown root:system /etc/inetd.conf"
</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs> "chmod 644 /etc/inetd.conf; chown root:system /etc/inetd.conf" </AIXPertArgs> -->
```

Default Value: 644, root:system

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.4 AIX Security Expert – Disabling Remote Services

This section provides guidance on the local disablement of remote system services. In the previous section, recommendations were made to disable the remote services in <code>/etc/inetd.conf</code>. This stops the server from accepting connections, but the binaries to initiate remote connections from the server to another host should also be restricted along with the daemons themselves being fully disabled. There are also many known security vulnerabilities that relate to these services, they are a primary target for any DoS attack.

It is recommended that, unless otherwise required, that the following services and daemons will have their execute permissions removed:

/usr/bin/rcp /usr/bin/rlogin /usr/bin/rsh /usr/sbin/rlogind /usr/sbin/rshd

1.4.1 Remote command lockdown (Level 2, Scorable)

Description:

Removes all permissions from the remote service commands: rsh, rlogin and rcp.

Rationale:

This effectively disables the following commands, for all users:

```
/usr/bin/rcp
/usr/bin/rlogin
/usr/bin/rsh
```

These remote services send usernames and passwords in clear text and should not be used. Unless required these binaries will be disabled for all users. The SSH suite of commands should be utilized to provide equivalent functionality.

Remediation:

Use the chmod command to remove all permissions on the remote services.

Please note the commands below are for information only, as these settings will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chmod ugo= /usr/bin/rcp
chmod ugo= /usr/bin/rlogin
chmod ugo= /usr/bin/rsh
```

Audit:

From the command prompt, execute the following commands:

```
ls -l /usr/bin/rcp | awk '{print $1}'
ls -l /usr/bin/rlogin | awk '{print $1}'
ls -l /usr/bin/rsh | awk '{print $1}'
```

Each of the above commands should return with the following permissions:

Reversion:

If there is a requirement to run any of these services, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

AIX 5.3

Replace:

```
<AIXPertArgs>d disrmtcmdshls</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>d disrmtcmdshls</AIXPertArgs> -->
```

AIX 6.1

Replace:

```
<AIXPertArgs>d hls disrmtcmds</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>d hls disrmtcmds</AIXPertArgs> -->
```

If there is a requirement to just revert one or more services, implement the customized AIX Security Expert XML file and execute the relevant command/s:

```
chmod ugo=rx,u+s /usr/bin/rcp
chmod ugo=rx,u+s /usr/bin/rlogin
chmod ugo=rx,u+s /usr/bin/rsh
```

Default Value: No effect

Default AIX Security Expert policy values:

High Level policy Permissions removed Medium Level policy No effect Low Level policy No effect

1.4.2 Remote daemon lockdown (Level 2, Scorable)

Description:

Removes all permissions from the remote service daemons: rshd, and rlogind.

Rationale:

This effectively disables the following daemons, for all users:

```
/usr/sbin/rlogind
/usr/sbin/rshd
/usr/sbin/tftpd
```

These remote services both send and receive usernames and passwords in clear text and should not be used. Unless required these daemons will be disabled for all users.

Remediation:

Use the chmod command to remove all permissions on the remote daemons.

Please note the commands below are for information only, as these settings will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chmod ugo= /usr/sbin/rlogind
chmod ugo= /usr/sbin/rshd
```

chmod ugo= /usr/sbin/tftpd

Audit:

From the command prompt, execute the following commands:

```
ls -l /usr/sbin/rlogind | awk '{print $1}'
ls -l /usr/sbin/rshd | awk '{print $1}'
ls -l /usr/sbin/tftpd | awk '{print $1}'
```

Each of the above commands should return with the following permissions:

Reversion:

If there is a requirement to run any of these services, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom_aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>d disrmtdmnshls</AIXPertArgs>

With:

<!-- <AIXPertArgs>d disrmtdmnshls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>d hls_disrmtdmns</AIXPertArgs>

With:

```
<!-- <AIXPertArgs>d hls_disrmtdmns</AIXPertArgs> -->
```

If there is a requirement to just revert one or more daemons, implement the customized AIX Security Expert XML file and execute the relevant command/s:

```
chmod ug=rx,o=r /usr/sbin/rlogind
chmod ug=rx,o=r /usr/sbin/rshd
chmod ug=rx,o=r /usr/sbin/tftpd
```

Default Value: No effect

Default AIX Security Expert policy values:

High Level policy Permissions removed

Medium Level policy No effect Low Level policy No effect

1.5 AIX Security Expert – Automated Authentication

This section provides guidance on the removal of .nertrc, .rhosts files and /etc/hosts.equiv entries. The existence of these files could allow remote access to the system without user or password authentication. It is recommended, that unless otherwise required, any such files are removed from all home directories on the system.

1.5.1 Removal of .rhosts and .netrc files (Level 2, Scorable)

Description:

This process removes all instances of .rhosts and .netrc files.

Rationale:

The .rhosts and .netrc files can be used to circumvent normal login or change control procedures. The existence of such files, with the relevant entries, can allow remote user access to a system bypassing local user and password authentication. Unless required these files will be removed from all user home directories.

Remediation:

Remove the .rhosts and .netrc files from all user home directories.

Please note the commands below are for information only, as these settings will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
find / -name ".netrc" -exec rm {} \;
find / -name ".rhosts" -exec rm {} \;
```

Audit:

From the command prompt, execute the following commands:

```
find / -name ".netrc" -print
find / -name ".rhosts" -print
```

The above commands should not yield output

Reversion:

If there is a requirement to implement . nertrc and . rhosts files, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>h rmrhostsnetrchls</AIXPertArgs>

With:

```
<!-- <AIXPertArgs>h rmrhostsnetrchls</AIXPertArgs> -->
```

AIX 6.1

Replace:

```
<AIXPertArgs>h hls_rmrhostsnetrc</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>h hls rmrhostsnetrc</AIXPertArgs> -->
```

Default Value: No effect

Default AIX Security Expert policy values:

High Level policy All files removed from all home directories

Medium Level policy All files removed from all home directories

Low Level policy All files removed from root home directory only

1.5.2 Removal of entries from /etc/hosts.equiv (Level 2, Scorable)

Description:

This process removes all entries from the /etc/hosts.equiv file.

Rationale:

The /etc/hosts.equiv file can be used to circumvent normal login or change control procedures. The existence of this file, with the relevant entries, can allow remote user access to a system bypassing local user and password authentication. Unless required all entries will be removed from this file.

Remediation:

Remove all entries from the /etc/hosts.equiv file.

Please note the commands below are for information only, as these settings will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
sed '/^\s*$/d; s/^\(\s*[^#].*\)/#\1/' /etc/hosts.equiv > /etc/hosts.equiv.work
mv hosts.equiv.work hosts.equiv
chown root:system /etc/hosts.equiv
chmod 644 /etc/hosts.equiv
```

Note: the above command removes blank lines and comments out any non commented entries.

Audit:

From the command prompt, execute the following command:

grep -v "^\s*#" /etc/hosts.equiv

The above command should not yield output

Reversion:

If there is a requirement to have entries in this file, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>rmetchostsequivhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>rmetchostsequivhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>hls_rmetchostsequiv</AIXPertArgs>

With:

<!-- <AIXPertArgs>hls rmetchostsequiv</AIXPertArgs> -->

Default Value: No effect

Default AIX Security Expert policy values:

High Level policy Remove all entries from /etc/hosts.equiv
Medium Level policy Remove all entries from /etc/hosts.equiv
Low Level policy Remove all entries from /etc/hosts.equiv

1.6 AIX Security Expert - TCP/IP Hardening

This section of the benchmark will focus on the hardening of standard TCP/IP tuning parameters. This is particularly important for the security of the system as the risk of SYN, source routing and smurf attacks can all be significantly reduced or eliminated by following the recommendations in this section. It is anticipated that any firewalls will also be configured to safeguard against these types of attack.

1.6.1 TCP/IP Tuning - ipsrcrouteforward (Level 2, Scorable)

Description:

The ipsrcrouteforward parameter determines whether or not the system forwards IPV4 source-routed packets.

Rationale:

The ipsrcrouteforward will be set to 0, to prevent source-routed packets being forwarded by the system. This would prevent a hacker from using source-routed packets to bridge an external facing server to an internal LAN, possibly even through a firewall.

Remediation:

In /etc/tunables/nextboot, add the ipsrcrouteforward entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o ipsrcrouteforward=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "ipsrcrouteforward[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

ipsrcrouteforward = 0

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>ipsrcrouteforward=0 s ipsrcrouteforwardhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>ipsrcrouteforward=0 s ipsrcrouteforwardhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>ipsrcrouteforward=0 s hls ipsrcrouteforward</AIXPertArgs>

With:

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0
Medium Level policy 0
Low Level policy No effect

1.6.2 TCP/IP Tuning - ipignoreredirects (Level 2, Scorable)

Description:

The ipignoreredirects parameter determines whether or not the system will process IP redirects.

Rationale:

The <code>ipignoreredirects</code> will be set to 1, to prevent IP re-directs being processed by the system.

Remediation:

In /etc/tunables/nextboot, add the ipignoreredirects entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o ipignoreredirects=1
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "ipignoreredirects[[:space:]]=[[:space:]]1"
```

The above command should yield the following output:

```
ipignoreredirects = 1
```

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>ipignoreredirects=1 s ipignoreredirectshls</AIXPertArgs>

With:

<!-- <AIXPertArgs>ipignoreredirects=1 s ipignoreredirectshls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>ipignoreredirects=1 s hls ipignoreredirects</AIXPertArgs>

With:

<!-- <AIXPertArgs>ipignoreredirects=1 s hls ipignoreredirects</AIXPertArgs> -->

Default Value: 0

Default AIX Security Expert policy values:

High Level policy 1
Medium Level policy 0
Low Level policy No effect

1.6.3 TCP/IP Tuning - clean_partial_conns (Level 2, Scorable)

Description:

The clean_partial_conns parameter determines whether or not the system is open to SYN attacks. This parameter, when enabled, clears down connections in the SYN RECEIVED state after a set period of time. This attempts to stop DoS attacks when a hacker may flood a system with SYN flag set packets.

Rationale:

The clean_partial_conns parameter will be set to 1, to clear down pending SYN received connections after a set period of time.

Remediation:

In /etc/tunables/nextboot, add the clean partial conns entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o clean partial conns=1
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "clean partial conns[[:space:]]=[[:space:]]1"
```

```
clean_partial_conns = 1
```

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

AIX 5.3

Replace:

```
<AIXPertArgs>clean_partial_conns=1 s clean_partial_connshls</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>clean_partial_conns=1 s clean_partial_connshls </AIXPertArgs>
-->
```

AIX 6.1

Replace:

```
<AIXPertArgs>clean partial conns=1 s hls clean partial conns</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>clean_partial_conns=1 s hls_clean_partial_conns</AIXPertArgs>
-->
```

Default Value: 0

Default AIX Security Expert policy values:

High Level policy 1 Medium Level policy 1 Low Level policy 1

1.6.4 TCP/IP Tuning - ipsrcroutesend (Level 2, Scorable)

Description:

The ipsrcroutesend parameter determines whether or not the system can send source-routed packets.

Rationale:

The ipsrcroutesend parameter will be set to 0, to ensure that any local applications cannot send source routed packets.

Remediation:

In /etc/tunables/nextboot, add the ipsrcroutesend entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o ipsrcroutesend=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "ipsrcroutesend[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

ipsrcroutesend = 0

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>ipsrcroutesend=0 s ipsrcroutesendhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>ipsrcroutesend=0 s ipsrcroutesendhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>ipsrcroutesend=0 s hls ipsrcroutesend</AIXPertArgs>

With:

<!-- <AIXPertArgs>ipsrcroutesend=0 s hls ipsrcroutesend</AIXPertArgs> -->

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0 Medium Level policy 1 Low Level policy 1

1.6.5 TCP/IP Tuning - ipforwarding (Level 2, Scorable)

Description:

The ipforwarding parameter determines whether or not the system forwards TCP/IP packets.

Rationale:

The ipforwarding parameter will be set to 0, to ensure that redirected packets do not reach remote networks. This should only be enabled if the system is performing the function of an IP router. This is typically handled by a dedicated network device.

Remediation:

In /etc/tunables/nextboot, add the ipforwarding entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o ipforwarding=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "ipforwarding[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

```
ipforwarding = 0
```

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>ipforwarding=0 s ipforwardinghls</AIXPertArgs>

With:

<!-- <AIXPertArgs>ipforwarding=0 s ipforwardinghls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>ipforwarding=0 s hls ipforwarding</AIXPertArgs>

With:

<!-- <AIXPertArgs>ipforwarding=0 s hls ipforwarding</AIXPertArgs> -->

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0 Medium Level policy 1 Low Level policy 1

1.6.6 TCP/IP Tuning - ipsendredirects (Level 2, Scorable)

Description:

The ipsendredirects parameter determines whether or not the system forwards re-directed TCP/IP packets.

Rationale:

The ipsendredirects parameter will be set to 0, to ensure that redirected packets do not reach remote networks.

Remediation:

In /etc/tunables/nextboot, add the ipsendredirects entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o ipsendredirects=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "ipsendredirects[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

```
ipsendredirects = 0
```

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>ipsendredirects=0 s ipsendredirectshls</AIXPertArgs>

With:

<!-- <AIXPertArgs>ipsendredirects=0 s ipsendredirectshls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>ipsendredirects=0 s hls ipsendredirects</AIXPertArgs>

With:

<!-- <AIXPertArgs>ipsendredirects=0 s hls ipsendredirects</AIXPertArgs> -->

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0 Medium Level policy 1 Low Level policy 1

References:

1. CCE-ID TBC

1.6.7 TCP/IP Tuning - ip6srcrouteforward (Level 2, Scorable)

Description:

The ip6srcrouteforward parameter determines whether or not the system forwards IPV6 source-routed packets.

Rationale:

The ip6srcrouteforward parameter will be set to 0, to prevent source-routed packets being forwarded by the system. This would prevent a hacker from using source-routed packets to bridge an external facing server to an internal LAN, possibly even through a firewall.

Remediation:

In /etc/tunables/nextboot, add the ip6srcrouteforward entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o ip6srcrouteforward=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "ip6srcrouteforward[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

```
ip6srcrouteforward = 0
```

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>ip6srcrouteforward=0 s ip6srcrouteforwardhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>ip6srcrouteforward=0 s ip6srcrouteforwardhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>ip6srcrouteforward=0 s hls ip6srcrouteforward </AIXPertArgs>

With:

```
<!-- <AIXPertArgs>ip6srcrouteforward=0 s hls_ip6srcrouteforward</AIXPertArgs> -->
```

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0 Medium Level policy 1 Low Level policy 1

1.6.8 TCP/IP Tuning – directed_broadcast (Level 2, Scorable)

Description:

The directed_broadcast parameter determines whether or not the system allows a directed broadcast to a network gateway.

Rationale:

The directed_broadcast parameter will be set to 0, to prevent directed broadcasts being sent network gateways. This would prevent a redirected packet from reaching a remote network.

Remediation:

In /etc/tunables/nextboot, add the directed broadcast entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o directed broadcast=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "directed broadcast[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

```
directed broadcast = 0
```

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>directed broadcast=0 s directed broadcasthls</AIXPertArgs>

With:

<!-- <AIXPertArgs>directed broadcast=0 s directed broadcasthls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>directed broadcast=0 s hls directed broadcast</AIXPertArgs>

With:

```
<!-- <AIXPertArgs>directed_broadcast=0 s hls_directed_broadcast</AIXPertArgs> -- >
```

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0 Medium Level policy 0 Low Level policy 0

1.6.9 TCP/IP Tuning – tcp_pmtu_discover (Level 2, Scorable)

Description:

The top pmtu discover parameter controls whether TCP MTU discovery is enabled.

Rationale:

The tcp_pmtu_discover parameter will be set to 0. The idea of MTU discovery is to avoid packet fragmentation between remote networks. This is achieved by discovering the network route and utilizing the smallest MTU size within that path when transmitting packets. When tcp_pmtu_discover is enabled, it leaves the system vulnerable to source routing attacks.

Remediation:

In /etc/tunables/nextboot, add the tcp pmtu discover entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o tcp pmtu discover=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "tcp_pmtu_discover[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

```
tcp_pmtu_discover = 0
```

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>tcp pmtu discover=0 s tcp pmtu discoverhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>tcp pmtu discover=0 s tcp pmtu discoverhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>tcp pmtu discover=0 s hls tcp pmtu discover</AIXPertArgs>

With:

<!-- <AIXPertArgs>tcp pmtu discover=0 s hls tcp pmtu discover</AIXPertArgs> -->

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0 Medium Level policy 0 Low Level policy 0

1.6.10 TCP/IP Tuning – bcastping (Level 2, Scorable)

Description:

The bcastping parameter determines whether the system responds to ICMP echo packets sent to the broadcast address.

Rationale:

The beastping parameter will be set to 0. This means that the system will not respond to ICMP packets sent to the broadcast address. By default, when this is enabled the system is susceptible to smurf attacks, where a hacker utilizes this tool to send a small number of ICMP echo packets. These packets can generate huge numbers of ICMP echo replies and seriously affect the performance of the targeted host and network. This parameter will be disabled to ensure protection from this type of attack.

Remediation:

In /etc/tunables/nextboot, add the bcastping entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o bcastping=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "bcastping[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

```
bcastping = 0
```

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>bcastping=0 s bcastpinghls</AIXPertArgs>

With:

<!-- <AIXPertArgs>bcastping=0 s bcastpinghls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>bcastping=0 s hls bcastping</AIXPertArgs>

With:

```
<!-- <AIXPertArgs>bcastping=0 s hls bcastping</AIXPertArgs> -->
```

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0 Medium Level policy 0 Low Level policy 0

1.6.11 TCP/IP Tuning – icmpaddressmask (Level 2, Scorable)

Description:

The icmpaddressmask parameter determines whether the system responds to an ICMP address mask ping.

Rationale:

The icmpaddressmask parameter will be set to 0, This means that the system will not respond to ICMP address mask request pings. By default, when this is enabled the system is susceptible to source routing attacks. This is typically a feature performed by a device such as a network router and should not be enabled within the operating system.

Remediation:

In /etc/tunables/nextboot, add the icmpaddressmask entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o icmpaddressmask=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "icmpaddressmask[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

icmpaddressmask = 0

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>icmpaddressmask=0 s icmpaddressmaskhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>icmpaddressmask=0 s icmpaddressmaskhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>icmpaddressmask=0 s hls icmpaddressmask</AIXPertArgs>

With:

<!-- <AIXPertArgs>icmpaddressmask=0 s hls_icmpaddressmask</AIXPertArgs> -->

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0 Medium Level policy 0 Low Level policy 0

1.6.12 TCP/IP Tuning – udp_pmtu_discover (Level 2, Scorable)

Description:

The udp pmtu discover parameter controls whether MTU discovery is enabled.

Rationale:

The udp_pmtu_discover parameter will be set to 0. The idea of MTU discovery is to avoid packet fragmentation between remote networks. This is achieved by discovering the network route and utilizing the smallest MTU size within that path when transmitting packets. When udp_pmtu_discover is enabled, it leaves the system vulnerable to source routing attacks.

Remediation:

In /etc/tunables/nextboot, add the udp pmtu discover entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o udp pmtu discover=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "udp pmtu discover[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

```
udp pmtu discover = 0
```

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>udp pmtu discover=0 s udp pmtu discoverhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>udp pmtu discover=0 s udp pmtu discoverhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>udp pmtu discover=0 s hls udp pmtu discover</AIXPertArgs>

With:

<!-- <AIXPertArgs>udp pmtu discover=0 s hls udp pmtu_discover</AIXPertArgs> -->

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0 Medium Level policy 0 Low Level policy 0

1.6.13 TCP/IP Tuning – ipsrcrouterecv (Level 2, Scorable)

Description:

The ipsrcrouterecv parameter determines whether the system accepts source routed packets.

Rationale:

The ipsrcroutered parameter will be set to 0, This means that the system will not accept source routed packets. By default, when this is enabled the system is susceptible to source routing attacks.

Remediation:

In /etc/tunables/nextboot, add the ipsrcrouterecv entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o ipsrcrouterecv=0
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "ipsrcrouterecv[[:space:]]=[[:space:]]0"
```

The above command should yield the following output:

ipsrcrouterecv = 0

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>ipsrcrouterecv=0 s ipsrcrouterecvhls</AIXPertArgs>

With:

<!-- <AIXPertArgs>ipsrcrouterecv=0 s ipsrcrouterecvhls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>ipsrcrouterecv=0 s hls ipsrcrouterecv</AIXPertArgs>

With

<!-- <AIXPertArgs>ipsrcrouterecv=0 s hls ipsrcrouterecv</AIXPertArgs> -->

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0
Medium Level policy No effect
Low Level policy No effect

1.6.14 TCP/IP Tuning – nonlocsrcroute (Level 2, Scorable)

Description:

The nonlocsrcroute parameter determines whether the system allows source routed packets to be addressed to hosts outside of the LAN.

Rationale:

The nonlocsrcroute parameter will be set to 0. This means that the system will not allow source routed packets to be addressed to hosts outside of the LAN. By default, when this is enabled the system is susceptible to source routing attacks.

Remediation:

In /etc/tunables/nextboot, add the nonlocsrcroute entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

no -p -o nonlocsrcroute=0

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

no -a |grep "nonlocsrcroute[[:space:]]=[[:space:]]0"

The above command should yield the following output:

nonlocsrcroute = 0

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>nonlocsrcroute=0 s nonlocsrcroutehls</AIXPertArgs>

With:

<!-- <AIXPertArgs>nonlocsrcroute=0 s nonlocsrcroutehls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>nonlocsrcroute=0 s hls nonlocsrcroute</AIXPertArgs>

With:

<!-- <AIXPertArgs>nonlocsrcroute=0 s hls nonlocsrcroute</AIXPertArgs> -->

Default Value: 1

Default AIX Security Expert policy values:

High Level policy 0 Medium Level policy No effect

1.6.15 TCP/IP Tuning -tcp_tcpsecure (Level 2, Scorable)

Description:

The tcp_tcpsecure parameter value determines if the system is protected from three specific vulnerabilities:

Fake SYN – This is used to terminate an established connection. A tcp_tcpsecure value of 1 protects the system from this vulnerability.

Fake RST – As above, this is used to terminate an established connection. A tcp_tcpsecure value of 2 protects the system from this vulnerability.

Fake data – A hacker may inject fake data into an established connection. A tcp_tcpsecure value of 4 protects the system from this vulnerability.

The tcp_tcpsecure parameter is, by default, only managed within the AIX 6.1 Security Expert framework. The parameter will also be set for AIX 5.3 as it has been added as a customized entry in the XML file.

Rationale:

The tcp_tcpsecure parameter will be set to 7. This means that the system will be protected from any connection reset and data integrity attacks.

Remediation:

In /etc/tunables/nextboot, add the tcp_tcpsecure entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o tcp tcpsecure=7
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "tcp_tcpsecure[[:space:]]=[[:space:]]7"
```

The above command should yield the following output:

```
tcp tcpsecure = 7
```

Reversion:

If there is a requirement have this parameter set to the default, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>"no -p -o tcp tcpsecure=7"</AIXPertArgs>

With:

<!-- <AIXPertArgs>"no -p -o tcp tcpsecure=7"</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs> tcp tcpsecure=7 s hls tcp tcpsecure </AIXPertArgs>

With:

<!-- <AIXPertArgs>tcp tcpsecure=7 s hls tcp tcpsecure</AIXPertArgs> -->

Default Value: 0

Default AIX Security Expert policy values:

High Level policy 7 Medium Level policy 7 Low Level policy 5

1.6.16 TCP/IP Tuning – sockthresh (Level 2, Scorable)

Description:

The sockthresh parameter value determines what percentage of the total memory allocated to networking, set via thewall, can be used for sockets.

The sockthresh parameter is, by default, only managed within the AIX 6.1 Security Expert framework. The parameter will also be set for AIX 5.3 as it has been added as a customized entry in the XML file.

Rationale:

The sockthresh parameter will be set to 60. This means that 60% of network memory can be used to service new socket connections, the remaining 40% is reserved for existing sockets. This ensures a quality of service for existing connections.

Remediation:

In /etc/tunables/nextboot, add the sockthresh entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

no -p -o sockthresh=60

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

no -a |grep "sockthresh[[:space:]]=[[:space:]]60"

The above command should yield the following output:

sockthresh = 60

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>"no -p -o sockthresh=60"</AIXPertArgs>

With:

<!-- <AIXPertArgs>"no -p -o sockthresh=60"</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>sockthresh=60 s hls sockthresh</AIXPertArgs>

With:

<!-- <AIXPertArgs>sockthresh=60 s hls_sockthresh</AIXPertArgs> -->

Default Value: No limit

Default AIX Security Expert policy values:

High Level policy 60 Medium Level policy 70 Low Level policy 85

1.6.17 TCP/IP Tuning – rfc1323 (Level 2, Scorable)

Description:

The rfc1323 parameter determines whether the TCP window sizes (tcp_sendspace and tcp_recvspace) can be greater than 64KB.

Rationale:

The rfc1323 parameter will be set to 1. This means that the system will allow the TCP windows sizes to exceed 64KB. This is a requirement for high performance networks, particularly those which utilize large MTU sizes.

Remediation:

In /etc/tunables/nextboot, add the rfc1323 entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o rfc1323=1
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "rfc1323[[:space:]]=[[:space:]]1"
```

The above command should yield the following output:

rfc1323 = 1

Reversion:

If there is a requirement have this parameter enabled, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>rfc1323=1 s rfc1323hls</AIXPertArgs>

With:

<!-- <AIXPertArgs>rfc1323=1 s rfc1323hls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>rfc1323=1 s hls rfc1323</AIXPertArgs>

With:

<!-- <AIXPertArgs>rfc1323=1 s hls rfc1323</AIXPertArgs> -->

Default Value: 0

Default AIX Security Expert policy values:

High Level policy 1 Medium Level policy 1 Low Level policy 1

1.6.18 TCP/IP Tuning - tcp_sendspace (Level 2, Scorable)

Description:

The tcp_sendspace parameter sets the socket buffer size for sending data. This recommendation changes the default size, but many adapters have specific buffer sizes implemented within the device driver. These are typically 64KB or greater.

Rationale:

The tcp_sendspace parameter will be set to 262144. This means that the system default socket buffer size for sending data will be 262KB. This is the minimum recommendation for modern high performance networks.

Remediation:

In /etc/tunables/nextboot, add the tcp sendspace entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o tcp sendspace=262144
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "tcp_sendspace[[:space:]]=[[:space:]]262144"
```

The above command should yield the following output:

```
tcp sendspace = 262144
```

Reversion:

If there is a requirement to leave this parameter at the default value, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>tcp sendspace=262144 s tcp sendspacehls</AIXPertArgs>

With:

<!-- <AIXPertArgs>tcp_sendspace=262144 s tcp_sendspacehls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>tcp sendspace=262144 s hls tcp sendspace</AIXPertArgs>

With:

<!-- <AIXPertArgs>tcp_sendspace=262144 s hls_tcp_sendspace</AIXPertArgs> -->

Default Value: 16384

Default AIX Security Expert policy values:

High Level policy 262144 Medium Level policy 262144 Low Level policy 262144

1.6.19 TCP/IP Tuning - tcp_recvspace (Level 2, Scorable)

Description:

The tcp_recvspace parameter sets the socket buffer size for receiving data. This recommendation changes the default size, but many adapters have specific buffer sizes implemented within the device driver. These are typically 64KB or greater.

Rationale:

The tcp_recvspace parameter will be set to 262144. This means that the system default socket buffer size for receiving data will be 262KB. This is the minimum recommendation for modern high performance networks.

Remediation:

In /etc/tunables/nextboot, add the tcp recvspace entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

no -p -o tcp recvspace=262144

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "tcp_recvspace[[:space:]]=[[:space:]]262144"
```

The above command should yield the following output:

```
tcp recvspace = 262144
```

Reversion:

If there is a requirement to leave this parameter at the default value, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>tcp recvspace=262144 s tcp recvspacehls</AIXPertArgs>

With:

```
<!-- <AIXPertArgs>tcp_recvspace=262144 s tcp_recvspacehls</AIXPertArgs> -->
```

AIX 6.1

Replace:

```
<AIXPertArgs>tcp recvspace=262144 s hls tcp recvspace</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>tcp recvspace=262144 s hls tcp recvspace</AIXPertArgs> -->
```

Default Value: 16384

Default AIX Security Expert policy values:

High Level policy 262144 Medium Level policy 262144 Low Level policy 262144

1.6.20 TCP/IP Tuning - tcp_mssdflt (Level 2, Scorable)

Description:

The tcp_mssdflt parameter sets the maximum segment size for communication to a remote network. This parameter is only relevant if MTU discovery is disabled, which is recommended in this benchmark.

Rationale:

The $tcp_{mssdflt}$ parameter will be set to 1448. This value reflects the packet size minus the TCP/IP headers.

Remediation:

In /etc/tunables/nextboot, add the tcp mssdflt entry.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
no -p -o tcp mssdflt=1448
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
no -a |grep "tcp_mssdflt[[:space:]]=[[:space:]]1448"
```

The above command should yield the following output:

```
tcp mssdflt = 1448
```

Reversion:

If there is a requirement to leave this parameter at the default value, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom aix<OS>.xml
```

AIX 5.3

Replace:

<AIXPertArgs>tcp mssdflt=1448 s tcp mssdflthls</AIXPertArgs>

With:

<!-- <AIXPertArgs>tcp mssdflt=1448 s tcp mssdflthls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>tcp_mssdflt=1448 s hls_tcp_mssdflt</AIXPertArgs>

With:

<!-- <AIXPertArgs>tcp mssdflt=1448 s hls tcp mssdflt</AIXPertArgs> -->

Default Value: 1460

Default AIX Security Expert policy values:

High Level policy 1448 Medium Level policy 1448 Low Level policy 1448

1.6.21 TCP/IP Tuning – nfs_use_reserved_ports (Level 2, Scorable)

Description:

The portcheck and nfs_use_reserved_ports parameters force the NFS server process on the local system to ignore NFS client requests that do not originate from the privileged ports range (ports less than 1024).

Rationale:

The portcheck and nfs_use_reserved_ports parameters will both be set to 1. This value means that NFS client requests that do not originate from the privileged ports range (ports less than 1024) will be ignored by the local system.

Remediation:

In /etc/tunables/nextboot, add the portcheck and nfs use reserved ports entries.

Please note the command below is for information only, as this setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
nfso -p -o portcheck=1
nfso -p -o nfs_use_reserved_ports=1
```

This makes the change permanent by adding the entry into /etc/tunables/nextboot

Audit:

```
nfso -a |egrep "(portcheck|nfs_use_reserved_ports)[[:space:]]=[[::space::]]1"
```

The above command should yield the following output:

```
portcheck = 1
nfs_use_reserved_ports = 1
```

Reversion:

If there is a requirement to leave this parameter at the default value, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs>"nfso -p -o portcheck=1; nfso -p -o
nfs use reserved ports=1"</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>"nfso -p -o portcheck=1; nfso -p -o nfs_use_reserved_ports=1"<AIXPertArgs> -->
```

Default Value: 0

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.7 AIX Security Expert – Miscellaneous Enhancements

This section will detail some of the more generic changes made during the implementation of the customized XML file i.e. those which may not warrant a dedicated section.

These recommendations are the final automated AIX Security Expert changes in this benchmark.

1.7.1 Miscellaneous Enhancements – crontab access (Level 2, Scorable)

Description:

This change creates a cron.allow file with a root user entry and removes the cron.deny file, if it exists.

Rationale:

This ensures that only the root user has the ability to create a crontab. A hacker may exploit use of the crontab to execute programs or processes automatically. Limiting access to the root account only reduces this risk.

NOTE: The adm user may also be added, particularly if system accounting is to be implemented.

Remediation:

Create the /var/adm/cron/cron.allow file

Please note the command below is for information only, as the setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
print "root\nadm" >> /var/adm/cron/cron.allow
```

Audit:

egrep "root|adm" /var/adm/cron/cron.allow

The above command should yield the following output:

root adm

Reversion:

If there is a requirement to leave cron access at the default level, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom_aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>h limitsysacchls</AIXPertArgs>

With:

<!-- <AIXPertArgs>h limitsysacchls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>h hls limitsysacc</AIXPertArgs>

With:

<!-- <AIXPertArgs>h hls_limitsysacc</AIXPertArgs> -->

Default Value: No effect

Default AIX Security Expert policy values:

High Level policy File created Medium Level policy No effect Low Level policy No effect

1.7.2 Miscellaneous Enhancements – at access (Level 2, Scorable)

Description:

This change creates an at.allow file with a root user entry and removes the at.deny file, if it exists.

Controlling at access is not a managed process within the default AIX Security Expert framework. This change is managed as a customized entry in the XML files.

Rationale:

This ensures that only the root user has the ability to schedule jobs through the at command. A hacker may exploit use of at to execute programs or processes automatically. Limiting access to the root account only reduces this risk.

Remediation:

Create the /var/adm/cron/at.allow file

Please note the command below is for information only, as the setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

echo "root" > /var/adm/cron/at.allow

Audit:

grep "root" /var/adm/cron/at.allow

The above command should yield the following output:

root

Reversion:

If there is a requirement to leave at access at the default level, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

Replace:

<AIXPertArgs>"echo root > /var/adm/cron/at.allow; rm
/var/adm/cron/at.deny"</AIXPertArgs>

With:

<!-- <AIXPertArgs>"echo root > /var/adm/cron/at.allow; rm /var/adm/cron/at.deny"</AIXPertArgs> -->

Default Value: No effect

Default AIX Security Expert policy values:

High Level policy N/A Medium Level policy N/A Low Level policy N/A

1.7.3 Miscellaneous Enhancements - /etc/ftpusers (Level 1, Scorable)

Description:

This change adds the root user to the /etc/ftpusers file, which disables ftp for root.

Rationale:

This change ensures that direct root ftp access is disabled. As detailed previously, ftp as a service should be disabled. If the service has to be enabled then this change must be implemented to ensure that remote root file transfer access is not enabled.

Remediation:

Add root to the /etc/ftpusers file

Please note the command below is for information only, as the setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

echo "root" >> /etc/ftpusers

Audit:

grep "root" /etc/ftpusers

The above command should yield the following output:

root

Default Value: No effect

Default AIX Security Expert policy values:

High Level policy Entry added Medium Level policy Entry added Low Level policy No effect

1.7.4 Miscellaneous Enhancements – login herald (Level 1, Scorable)

Description:

This change adds a default herald to /etc/security/login.cfg.

Rationale:

This change puts into place a suggested login herald to replace the default entry. As the herald is presented to a user prior to logon, it should not provide any information about the operating system or version. Instead, it should detail a company standard acceptable use policy. This herald can be subsequently tailored to reflect a corporate standard policy.

Remediation:

Add a default login herald to /etc/security/login.cfg

Please note the command below is for information only, as the setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsec -f /etc/security/login.cfg -s default -a herald="Unauthorized use of this system is prohibited.\nlogin:"

Audit:

```
lssec -f /etc/security/login.cfg -s default -a herald |grep
'^default[[::space::]]herald="Unauthorized use of this system is prohibited.'
```

The above command should yield the following output:

default herald="Unauthorized use of this system is prohibited.\nlogin:"

Default AIX Security Expert policy values:

High Level policy Herald configured Medium Level policy Herald configured Low Level policy Herald configured

1.7.5 Miscellaneous Enhancements – guest account removal (Level 1, Scorable)

Description:

This change removes the guest user and home directory from the system.

Rationale:

This change removes the guest user. If a user logs in with a generic username, audit trails are of limited value as it is not necessarily possible to identify who has accessed an account. The quest account should be removed and all users should be given specific logon ids to ensure traceability and accountability.

Remediation:

Remove the guest user

Please note the commands below are for information only, as these settings will be automatically applied when the customized AIX Security Expert XML file is implemented.

rmuser -p guest rm -r /home/guest

Audit:

lsuser quest

The above command should yield the following output:

3004-687 User "quest" does not exist.

Default Value: Account exists

Default AIX Security Expert policy values:

High Level policy Account removed Medium Level policy Account removed Low Level policy Account removed

1.7.6 Miscellaneous Enhancements – crontab permissions (Level 1, Scorable)

Description:

This script checks the permissions of all the root crontab entries, to ensure that they are owned and writable by the root user only.

Rationale:

All root crontab entries must be owned and writable by the root user only. If a script had group or world writable access, it could be replaced or edited with malicious content, which would then subsequently run on the system with root authority.

Remediation:

Ensure that all root crontab entries are owned and writable by root only.

Please note the commands below are for information only, as these settings will be automatically applied when the customized AIX Security Expert XML file is implemented.

The script below traverses up each individual directory path, ensuring that all directories are not group/world writable and that they are owned by the root or bin user:

```
crontab -1 |awk '{print $6}' |grep "^/" |sort -u | while read DIR
do
DIR=${DIR:-$(pwd)}
print "Checking ${DIR}"
while [[ -a ${DIR} ]]
do
[[ "$(ls -ld ${DIR})" = @(???????w? *) ]] && print " WARNING ${DIR} is world wr
itable"
[[ "$(ls -ld ${DIR})" = @(?????w???? *) ]] && print " WARNING ${DIR} is group wr
itable"
[[ "$(ls -ld ${DIR}) " = @(?????w???? *) ]] && print " WARNING ${DIR} is group wr
itable"
[[ "$(ls -ld ${DIR}) |awk '{print $3}')" != @(root|bin) ]] && print " WARNING ${DIR} is not owned by root or bin"
DIR=${DIR*/*}
done
done
```

NOTE: Review the output and manually change the directories, if possible. Directories which are group and/or world writable or not owned by root are marked with "WARNING"

To manually change permissions on the files or directories:

To remove group writable access:

```
chmod g-w <name>
```

To remove world writable access:

```
chmod o-w <name>
```

To remove both group and world writable access:

```
chmod go-w <name>
```

To change the owner of a file or directory:

```
chown <new user> <name>
```

Audit:

Execute the following code:

```
crontab -l |awk '{print $6}' |grep "^/" |sort -u | while read DIR
do
DIR=${DIR:-$(pwd)}
while [[ -a ${DIR} ]]
do
[[ "$(ls -ld ${DIR})" = @(???????w? *) ]] && print " WARNING ${DIR} is world wr
itable"
[[ "$(ls -ld ${DIR})" = @(?????w???? *) ]] && print " WARNING ${DIR} is group wr
itable"
[[ "$(ls -ld ${DIR}) | = @(?????w???? *) ]] && print " WARNING ${DIR} is group wr
itable"
[[ "$(ls -ld ${DIR} |awk '{print $3}')" != @(root|bin) ]] && print " WARNING ${DIR} is not owned by root or bin"
DIR=${DIR%/*}
done
done
```

Default Value: No effect

Default AIX Security Expert policy values:

High Level policy Permissions checked Medium Level policy Permissions checked Low Level policy Permissions checked

1.7.7 Miscellaneous Enhancements – default umask (Level 2, Scorable)

Description:

This changes the default user umask in /etc/security/user.

Rationale:

The default user umask will be set to 027. This means that the default file creation permissions give read and write access to the user, read access to the group and no access to other. The default directory creation permissions give read, write and execute access to the user, read and

execute to the group and no access to other. This is the recommended <code>umask</code> setting, as world access should be explicitly defined and not added during default creation. Where possible, access to files and directories should be managed via group membership and ACL's, rather than opening up directory structures for world access. In particular, world write access should be avoided.

Consideration should be given to further securing the default user <code>umask</code> by implementing 077. This means that only the user has read/write access to the files and directories they create. Group and/or world access would need to be explicitly defined.

As part of this change all explicitly defined umask user settings are removed.

Remediation:

Add the umask attribute to the default user stanza in /etc/security/user.

Please note the command below is for information only, as the setting will be automatically applied when the customized AIX Security Expert XML file is implemented.

chsec -f /etc/security/user -s default -a umask=027

If a umask of 077 is required, reflect the following changes in the AIX Security Expert XML files:

AIX 5.3

Replace:

<AIXPertArgs>umask=27 ALL umaskmls</AIXPertArgs>

With:

<AIXPertArgs>umask=77 ALL umaskmls</AIXPertArgs>

AIX 6.1

Replace:

<AIXPertArgs> umask=27 ALL hls umask</AIXPertArgs>

With:

<AIXPertArgs> umask=77 ALL hls umask</AIXPertArgs>

Audit:

From the command prompt, execute the following command:

lssec -f /etc/security/user -s default -a umask

The above command should yield the following output:

default umask=27

Reversion:

If there is a requirement to not change the default umask value, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>umask=27 ALL umaskmls</AIXPertArgs>

With:

<!-- <AIXPertArgs>umask=27 ALL umaskmls</AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs> umask=27 ALL hls umask</AIXPertArgs>

With:

<!-- <AIXPertArgs> umask=27 ALL hls umask</AIXPertArgs> -->

Default Value: 022

Default AIX Security Expert policy values:

High Level policy 077 Medium Level policy 027 Low Level policy 022

1.7.8 Miscellaneous Enhancements – disabling core dumps (Level 2, Scorable)

Description:

This change disables core dumps in the default user stanza of /etc/security/limits and also ensures the fullcore kernel parameter is set to false.

Disabling core dumps is not a managed process within the default AIX Security Expert framework. This change is managed as a customized entry in the XML files.

Rationale:

The creation of core dumps can reveal pertinent system information, potentially even passwords, within the core file. The ability to create a core dump is also a vulnerability to be exploited by a hacker.

The commands below disable core dumps by default, but they may be specifically enabled for a particular user in /etc/security/limits.

Remediation:

Change the default user stanza attributes core and core_hard in /etc/security/limits and the set the fullcore kernel parameter to false.

Please note the commands below are for information only, as the settings will be automatically applied when the customized AIX Security Expert XML file is implemented.

```
chsec -f /etc/security/limits -s default -a core=0 -a core_hard=0
chdev -l sys0 -a fullcore=false
```

Audit:

From the command prompt, execute the following command to validate the /etc/security/limits changes:

```
lssec -f /etc/security/limits -s default -a core -a core_hard
```

The above command should yield the following output:

```
default core=0 core_hard=0
```

Ensure that the fullcore kernel parameter has been set to false:

```
lsattr -El sys0 -a fullcore
```

The above command should yield the following output:

```
fullcore false Enable full CORE dump True
```

Reversion:

If there is a requirement to enable core dumps, edit the customized XML file prior to implementing:

```
vi /etc/security/aixpert/custom/custom_aix<OS>.xml
```

Replace:

```
<AIXPertArgs>"chsec -f /etc/security/limits -s default -a core=0 -a core_hard=0;
chdev -l sys0 -a fullcore=false"</AIXPertArgs>
```

With:

```
<!-- <AIXPertArgs>"chsec -f /etc/security/limits -s default -a core=0 -a core_hard=0; chdev -l sys0 -a fullcore=false"</AIXPertArgs> -->
```

Default Value: Core dumps enabled

Default AIX Security Expert policy values:

```
High Level policy N/A
Medium Level policy N/A
Low Level policy N/A
```

1.7.9 Miscellaneous Enhancements – AIX Auditing (Level 2, Scorable)

Description:

This change configures AIX auditing in bin mode. If auditing is already configured, this enhancement is not implemented.

Rationale:

AIX auditing provides a framework within which to capture pertinent system and security related information, such as failed login attempts, cron usage etc. It is recommended that auditing is enabled as part of a group of measures designed to provide enhanced logging of system and security changes.

Further information regarding the setup and management of accounting and auditing can be found in the "Accounting and Auditing for AIX 5L Redbook":

http://www.redbooks.ibm.com/redbooks/pdfs/sg246396.pdf

Remediation:

Configure AIX auditing in-line with the High Level AIX Security Expert policy.

Please note the commands below are for information only, as the commands will be automatically executed when the customized AIX Security Expert XML file is implemented.

Create a /audit filesystem, at least 100 MB in size. The script always creates a standard jfs filesystem. If the /audit filesystem exists, this step is skipped:

```
mklv -y <LV name> -t jfs -u 1 -c 1 rootvg 1 hdisk0
crfs -v jfs -d auditlv -m /audit -A yes -t no
mount /audit
```

Reflect the following configuration in the /etc/security/audit/config file:

```
vi /etc/security/audit/config
```

Add in:

```
start:
    binmode = on
    streammode = off
bin:
    trail = /audit/trail
    bin1 = /audit/bin1
    bin2 = /audit/bin2
    binsize = 10240
    cmds = /etc/security/audit/bincmds
```

Add the auditing entries for root and all other users below the pre-defined audit classes:

Update the /usr/lib/security/mkuser.default auditclasses entry to ensure that auditing is set up for any newly created users:

```
chsec -f /usr/lib/security/mkuser.default -s user -a
auditclasses=general, SRC, cron, tcpip
```

A cron job is implemented to monitor the free space in /audit, running hourly, to ensure that /audit does not fill up. If /audit is greater than 90% used, /audit/trail is moved to /audit/trailOneLevelBack:

```
crontab -e
```

Add in:

```
0 * * * /etc/security/aixpert/bin/cronaudit
```

NOTE: The implementation of a script to suit internal security policy is recommended to further enhance the log rotation process.

Add the audit startup command into /etc/inittab:

```
mkitab "audit:2:boot:audit start > /dev/console 2>&1 # Start audit"
```

Audit:

Ensure that the /audit filesystem has been created and mounted:

```
df -k /audit
```

The above command should yield the following output:

```
/dev/auditlv 262144 261776 1% 4 1% /audit
```

Validate the configuration in the /etc/security/audit/config file, this should match the changes made in the remediation section:

```
cat /etc/security/audit/config
```

Ensure that the /usr/lib/security/mkuser.default auditclasses entry has been updated:

lssec -f /usr/lib/security/mkuser.default -s user -a
auditclasses

The above command should yield the following output:

user auditclasses=general, SRC, cron, tcpip

Ensure that the cron audit rotation script has been implemented:

crontab -l |grep "cronaudit"

The above command should yield the following output:

0 * * * * /etc/security/aixpert/bin/cronaudit

Ensure that the audit startup line has been added into /etc/inittab:

lsitab audit

This should echo:

audit:2:boot:audit start > /dev/console 2>&1 # Start audit

Reversion:

If there is a requirement to not implement auditing, edit the customized XML file prior to implementing:

vi /etc/security/aixpert/custom/custom aix<OS>.xml

AIX 5.3

Replace:

<AIXPertArgs>h hls binaudit</AIXPertArgs>

With:

<!-- <AIXPertArgs>h hls binaudit/AIXPertArgs> -->

AIX 6.1

Replace:

<AIXPertArgs>h binaudithls</AIXPertArgs>

With:

<!-- <AIXPertArgs>h binaudithls</AIXPertArgs> -->

Default Value: Auditing not configured

Default AIX Security Expert policy values:

High Level policy Auditing configured Medium Level policy Auditing configured Low Level policy Auditing configured

2. Non AIX Security Expert Managed Recommendations

This section of the benchmark will focus on the recommendations which are not automatically applied during the implementation of the AIX Security Expert customized XML file. A number of these recommendations are not scorable, in that the implementation needs to be tailored to suit the needs of a given environment, which also makes compliance checking impossible.

The following recommendations are detailed in this section:

- Configuring syslog
- Secure remote access
- Configuring sendmail
- Configuring CDE
- Configuring NFS
- Configuring SNMP
- > TCP Wrappers
- File and directory permissions and ownership
- Privileged command management Enhanced RBAC and sudo
- Encrypted Filesystem (EFS)
- > Trusted Execution
- > General Permissions Management

2.1 Configuring syslog

This section will detail the recommendations regarding the configuration of <code>syslog</code>. By default the information sent to <code>syslogd</code> is not logged and important and pertinent information, such as failed switch user and login attempts are not recorded. The type of data which can be captured through this mechanism can be used for real-time and retrospective analysis, and is particularly useful for monitoring access to the system.

Logging data, via syslogd, may also provide unequivocal evidence against any individual or organization that successfully breach, or attempt to circumvent the security access controls surrounding a system.

2.1.1 Configuring syslog - local logging (Level 2, Scorable)

Description:

This recommendation implements a local syslog configuration.

Rationale:

Establishing a logging process via syslog provides system and security administrators with pertinent information relating to: login, mail, daemon, user and kernel activity. The recommendation is to enable local syslog logging, with a weekly rotation policy in a four weekly cycle. The log rotation isolates historical data which can be reviewed retrospectively if an issue is uncovered at a later date.

Remediation:

Explicitly define a log file for the auth.info output in /etc/syslog.conf:

```
printf "auth.info\t\t/var/adm/authlog rotate time 1w files 4\n" >>
/etc/syslog.conf
```

NOTE: This ensures that remote login, sudo or su attempts are logged separately

Create the authlog file and make it readable by root only:

```
touch /var/adm/authlog chown root:system /var/adm/authlog chmod u=rw,go= /var/adm/authlog
```

Create an entry in /etc/syslog.conf to capture all other output of level info or higher, excluding authentication information, as this is to be captured within /var/adm/authlog:

```
printf "*.info;auth.none\t/var/adm/syslog rotate time 1w files 4\n" >>
/etc/syslog.conf
```

Create the syslog file:

```
touch /var/adm/syslog chmod u=rw,g=r,o= /var/adm/syslog
```

Refresh syslogd to force the daemon to read the edited /etc/syslog.conf:

```
refresh -s syslogd
```

Audit:

Ensure that the log entries have been added successfully:

```
tail -2 /etc/syslog.conf
```

The above command should yield the following output:

```
auth.info /var/adm/authlog rotate time 1w files 4 *.info;auth.none /var/adm/syslog rotate time 1w files 4
```

Check that the authlog and syslog files have been created:

```
ls -l /var/adm/authlog /var/adm/syslog
```

Reversion:

Edit the /etc/syslog.conf and the remove the authlog and syslog entries:

```
vi /etc/syslog.conf
```

Remove:

auth.info	/var/adm/authlog rotate time 1w files 4	
*.info;auth.none	/var/adm/syslog rotate time 1w files 4	

Refresh syslogd to force the daemon to read the edited /etc/syslog.conf:

```
refresh -s syslogd
```

Delete the authlog and syslog files:

```
rm /var/adm/authlog /var/adm/syslog
```

Default Value: Not Configured

2.1.2 Configuring syslog – remote logging (Level 2, Scorable)

Description:

This recommendation implements a remote syslog configuration.

Rationale:

To further enhance the local syslog logging process, it is recommended that syslog information, in particular that generated by the auth facility, is logged remotely. This recommendation assumes that a remote and secure syslog server is available on the network. If this is not the case, please skip to the next recommendation.

The primary reason for logging remotely is to provide an un-editable audit trail of system access. If a hacker were to access a system and gain super user authority it would be easy to edit local files and remove all traces of access, providing the system administrator with no way of identifying the individual or group responsible. If the log data is sent remotely at the point of access, these remote logs can then be reconciled with local data to identify tampered and altered files. The logs can also be used as evidence in any subsequent prosecution.

Remediation:

Explicitly define a remote host for auth.info data in /etc/syslog.conf (enter the remote host IP address in the example below):

```
printf "auth.info\t\t@<IP address of remote syslog server>\n" >> \
/etc/syslog.conf
```

NOTE: This ensures that remote login, sudo or su attempts are logged separately

Create a remote host entry in /etc/syslog.conf to capture all other output of level info or higher:

```
printf "*.info;auth.none\t@<IP address of remote syslog server>\n" >> \
/etc/syslog.conf
```

Refresh syslogd to force the daemon to read the edited /etc/syslog.conf:

```
refresh -s syslogd
```

Audit:

Ensure that the log entries have been added successfully:

```
tail -2 /etc/syslog.conf
```

The above command should yield the following output:

Reversion:

Edit the /etc/syslog.conf and the remove the remote syslog entries:

```
vi /etc/syslog.conf
```

Remove:

Refresh syslogd to force the daemon to read the edited /etc/syslog.conf:

```
refresh -s syslogd
```

Default Value: Not Configured

2.1.3 Configuring syslog - remote messages (Level 2, Scorable)

Description:

This recommendation prevents the local syslogd daemon from accepting messages from other hosts on the network.

Rationale:

Apart from a central <code>syslog</code> server, all other hosts should not accept remote <code>syslog</code> messages. By default the <code>syslogd</code> daemon accepts all remote <code>syslog</code> messages as no authentication is required. This means that a hacker could flood a server with <code>syslog</code> messages and potentially fill up the <code>/var</code> filesystem.

Remediation:

If the server does not act as a central syslog server, suppress the logging of messages originating from remote servers:

```
chssys -s syslogd -a "-r"
```

Re-cycle syslogd to activate the configuration change:

```
stopsrc -s syslogd
startsrc -s syslogd
```

Audit:

Ensure that daemon is running with the newly updated configuration:

```
ps -ef |grep "syslogd"
```

The above command should yield the following output:

```
root 57758 70094 0 10:22:08 - 0:00 /usr/sbin/syslogd -r
```

NOTE: The -r flag should be present at the end out of the output.

Reversion:

Remove the suppression of remote syslog messages:

```
chssys -s syslogd -a ""
```

Re-cycle syslogd to activate the configuration change:

```
stopsrc -s syslogd startsrc -s syslogd
```

Default Value: Not Configured

2.2 Secure Remote Access

The use of SSH provides a secure and encrypted mechanism for connecting to a UNIX server. The recommendations in this benchmark disable clear text password access methods, such as telnet and rlogin. There are many legacy scenarios where telnet and ftp may still be required, but SSH should not be ignored in these situations and used where ever possible

alongside the non-encrypted services. The preferred scenario is that SSH is the only available remote access service.

One of the historical issues relating to the use of OpenSSH was the lack of vendor support for the software. This has now been addressed as it has the full support, and is in fact packaged, by IBM for AIX based on the Open source libraries.

This section of the benchmark will focus on the installation and configuration of SSH. Some of the parameters specified in this section are actually the default values, but explicit declaration is preferred, to ensure that these recommendations remain constant over time.

2.2.1 Configuring SSH – installation (Level 2, Scorable)

Description:

The recommendation is to install OpenSSH and OpenSSL libraries from the expansion pack media, or the IBM supported packages downloaded from the internet.

Rationale:

This is the preferred mechanism for remote client access as it provides socket level encryption, via OpenSSL. If any clear text password service is required for legacy connections the two services may sit side by side, with SSH utilized wherever possible. Ideally, SSH should be the only available remote access mechanism.

If the software is not available from the expansion pack media, download from the following locations.

OpenSSH:

http://sourceforge.net/projects/openssh-aix/

OpenSSL:

https://www14.software.ibm.com/webapp/iwm/web/preLogin.do?source=aixbp

NOTE: A login is required to download OpenSSL.

Remediation:

Place the OpenSSH and OpenSSL software into a convenient location, such as / tmp and install via:

```
/usr/lib/instl/sm_inst installp_cmd -a -Q -d /tmp -f openssl,openssh.license,openssh.base,openssh.man.en_US,openssh.msg.en_US -c -N - g -X -G -Y
```

NOTE: If the software is not located in /tmp, reflect the actual location in the command above.

Audit:

Validate the installation of the software:

```
lslpp -L |egrep "openssh|ssl"
```

The above command should yield the following output:

openssh.base.client	4.3.0.5300	С	F	Open Secure Shell Commands
openssh.base.server	4.3.0.5300	С	F	Open Secure Shell Server
openssh.license	4.3.0.5300	С	F	Open Secure Shell License
openssh.msg.en_US	4.3.0.5300	С	F	Open Secure Shell Messages
openssl.base	0.9.8.601	С	F	Open Secure Socket Layer
openssl.license	0.9.8.601	С	F	Open Secure Socket License
openssl.man.en_US	0.9.8.601	С	F	Open Secure Socket Layer
openssl	0.9.7g-1	С	R	Secure Sockets Layer and

NOTE: The version numbers may differ based on the source of the software

Ensure that the SSH daemon is set to automatically start during system IPL:

```
ls -l /etc/rc.d/rc2.d/Ssshd | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

```
-r-xr-xr-x root system Ssshd
```

Reversion:

De-install the OpenSSL and OpenSSH software:

```
installp -u openssh* openssl
```

Default Value: Not Installed

2.2.2 Configuring SSH – disabling direct root access (Level 1, Scorable)

Description:

The recommendation is to edit the /etc/ssh/sshd_config file to disable direct root login. By default direct root login via SSH is enabled.

Rationale:

All root access should be facilitated through a local logon with a unique and identifiable user ID and then via the su command once locally authenticated. Direct root login is extremely insecure and offers little in the way of audit trailing for accountability.

Remediation:

Edit the /etc/ssh/sshd config file and disable direct root login for SSH:

```
vi /etc/ssh/sshd_config
```

Replace:

#PermitRootLogin yes

With:

PermitRootLogin no

Re-cycle the sshd daemon to pick up the configuration changes:

stopsrc -s sshd
startsrc -s sshd

Audit:

Ensure that the PermitRootLogin parameter has been changed:

```
grep "^PermitRootLogin[[::blank::]]" /etc/ssh/sshd config
```

The above command should yield the following output:

PermitRootLogin no

Default Value: PermitRootLogin yes

References:

1. CCE-ID TBC

2.2.3 Configuring SSH – server protocol 2 (Level 1, Scorable)

Description:

The recommendation is to edit the /etc/ssh/sshd_config file and allow the SSH2 protocol only. By default the SSH1 protocol is also available. This is the SSH server configuration file.

Rationale:

There are publicly known vulnerabilities in SSH1 protocol, because of which the SSH1 protocol was deprecated in early 2001. SSH2 is a complete re-write of SSH1 with additional security features. All SSH connections should communicate over the SSH2 protocol. There are numerous benefits of utilizing SSH2 over SSH1, these include: an enhanced and stronger crypto integrity check and support for RSA and DSA keys, rather than just RSA key support in SSH1. The recommendation is to edit the /etc/ssh/sshd_config file and allow the SSH2 protocol only.

Remediation:

Edit the /etc/ssh/sshd config file and explicitly define the SSH2 protocol:

vi /etc/ssh/sshd_config

Replace:

#Protocol 2,1

With:

Protocol 2

Re-cycle the sshd daemon to pick up the configuration changes:

stopsrc -s sshd
startsrc -s sshd

Audit:

Ensure that the Protocol parameter has been changed:

```
grep "^Protocol[[::blank::]]" /etc/ssh/sshd config
```

The above command should yield the following output:

Protocol 2

Default Value: Both SSH2 and SSH1 protocols are available

2.2.4 Configuring SSH – client protocol 2 (Level 1, Scorable)

Description:

The recommendation is to edit the /etc/ssh/ssh_config file and allow the SSH2 protocol only. By default the SSH1 protocol is also available. This is the SSH client configuration file.

Rationale:

There are publicly known vulnerabilities in SSH1 protocol, because of which the SSH1 protocol was deprecated in early 2001. SSH2 is a complete re-write of SSH1 with additional security features. All SSH connections should communicate over the SSH2 protocol. There are numerous benefits of utilizing SSH2 over SSH1, these include: an enhanced and stronger crypto integrity check and support for RSA and DSA keys, rather than just RSA key support in SSH1. The recommendation is to edit the /etc/ssh/ssh_config file and allow the SSH2 protocol only.

Remediation:

Edit the /etc/ssh/ssh config file and explicitly define the SSH2 protocol:

vi /etc/ssh/ssh_config

Replace:

Protocol 2,1

With:

Protocol 2

Re-cycle the sshd daemon to pick up the configuration changes:

stopsrc -s sshd
startsrc -s sshd

Audit:

Ensure that the Protocol parameter has been changed:

```
grep "^Protocol[[::blank::]]" /etc/ssh/ssh config
```

The above command should yield the following output:

Protocol 2

Default Value: Both SSH2 and SSH1 protocols are available

2.2.5 Configuring SSH – banner configuration (Level 1, Scorable)

Description:

The recommendation is to edit the /etc/ssh/sshd_config file and configure a path to a login herald message.

Rationale:

The login herald configured previously is not displayed during the initiation of a new SSH connection. Prior to a password being entered the user should accept the terms and conditions of the corporate acceptable usage policy.

Remediation:

Create an SSH banner file:

printf "Unauthorized use of this system is prohibited.\n" > /etc/ssh/ssh banner

NOTE: The content of the banner file can reflect any internal acceptable usage policy standards

Edit the /etc/ssh/sshd config file and customize the Banner parameter:

vi /etc/ssh/sshd config

Replace:

#Banner /some/path

With:

Banner /etc/ssh/ssh banner

Re-cycle the sshd daemon to pick up the configuration changes:

stopsrc -s sshd
startsrc -s sshd

Audit:

Ensure that the Banner parameter has been changed:

grep "^Banner[[::blank::]" /etc/ssh/sshd config

The above command should yield the following output:

Banner /etc/ssh/ssh banner

Default Value: No banner is configured

2.2.6 Configuring SSH – ignore .shosts and .rhosts (Level 1, Scorable)

Description:

The recommendation is to edit the /etc/ssh/sshd_config file and set the IgnoreRhosts parameter to ignore .shosts and .rhosts files

Rationale:

A user can logon to a remote system without authenticating themselves if .rhosts or .shosts files exist in the remote home directory and if the client machine name and user name are present in these files. This method is fundamentally insecure as the local system can be exploited by IP, DNS (Domain Name Server) and routing spoofing attacks. Additionally, this authentication method relies on the integrity of the client machine. These weaknesses have been known and exploited for a long time. Since this authentication method is not secure, it must be disabled.

Remediation:

Edit the /etc/ssh/sshd_config file to disable the .shosts and .rhosts authentication parameter:

vi /etc/ssh/sshd config

Replace:

#IgnoreRhosts yes

With:

IgnoreRhosts yes

Re-cycle the sshd daemon to pick up the configuration changes:

stopsrc -s sshd
startsrc -s sshd

Audit:

Ensure that the IgnoreRhosts parameter has been changed:

grep "^IgnoreRhosts[[::blank::]]" /etc/ssh/sshd config

The above command should yield the following output:

IgnoreRhosts yes

Default Value: IgnoreRhosts yes

2.2.7 Configuring SSH – disable null passwords (Level 1, Scorable)

Description:

The recommendation is to edit the /etc/ssh/sshd_config file to ensure that the SSH daemon does not authenticate users with a null password.

Rationale:

If password authentication is used and an account has an empty password, the SSH server must be configured to disallow access to the account. Permitting empty passwords could create an easy path of access for hackers to enter the system.

Remediation:

Edit the /etc/ssh/sshd config file to disable the acceptance null passwords:

vi /etc/ssh/sshd config

Replace:

#PermitEmptyPasswords no

With:

PermitEmptyPasswords no

Re-cycle the sshd daemon to pick up the configuration changes:

stopsrc -s sshd
startsrc -s sshd

Audit:

Ensure that the PermitEmptyPasswords parameter has been changed:

```
grep "^PermitEmptyPasswords[[::blank::]]" /etc/ssh/sshd config
```

The above command should yield the following output:

PermitEmptyPasswords no

Default Value: PermitEmptyPasswords no

2.2.8 Configuring SSH – disallow host based authentication (Level 2, Scorable)

Description:

The recommendation is to edit the /etc/ssh/sshd_config file to ensure that host-based authentication is disallowed.

Rationale:

Using host-based authentication, any user on a trusted host can log into another host on which this feature is enabled. Since this feature depends only on system authentication and not on user authentication, it must be disabled.

Remediation:

Edit the /etc/ssh/sshd config file to ensure that host based authentication is disallowed:

vi /etc/ssh/sshd config

Replace:

#HostbasedAuthentication no

With:

HostbasedAuthentication no

Re-cycle the sshd daemon to pick up the configuration changes:

stopsrc -s sshd
startsrc -s sshd

Audit:

Ensure that the HostbasedAuthentication parameter has been changed:

grep "^HostbasedAuthentication[[::blank::]]" /etc/ssh/sshd_config

The above command should yield the following output:

HostbasedAuthentication no

Reversion:

Revert to the default setting for the HostBasedAuthentication parameter:

vi /etc/ssh/sshd config

Replace:

HostbasedAuthentication no

With:

HostbasedAuthentication no

Re-cycle the sshd daemon to pick up the configuration changes:

stopsrc -s sshd
startsrc -s sshd

Default Value: HostbasedAuthentication no

2.2.9 Configuring SSH – set privilege separation (Level 1, Scorable)

Description:

The recommendation is to edit the /etc/ssh/sshd_config file to ensure that privilege separation is enabled.

Rationale:

Setting privilege separation helps to secure remote ssh access. Once a user is authenticated the sshd daemon creates a child process which has the privileges of the authenticated user and this then handles incoming network traffic. The aim of this is to prevent privilege escalation through the initial root process.

Remediation:

Edit the /etc/ssh/sshd config file to ensure that privilege separation is enabled:

vi /etc/ssh/sshd config

Replace:

#UsePrivilegeSeparation yes

With:

UsePrivilegeSeparation yes

Re-cycle the sshd daemon to pick up the configuration changes:

stopsrc -s sshd startsrc -s sshd

Audit:

Ensure that the UsePrivilegeSeparation parameter has been changed:

grep "^UsePrivilegeSeparation[[::blank::]]" /etc/ssh/sshd config

The above command should yield the following output:

UsePrivilegeSeparation yes

Default Value: UsePrivilegeSeparation yes

2.2.10 Configuring SSH – sshd_config permissions lockdown (Level 1, Scorable)

Description:

 $The \ / \verb|etc/ssh/sshd_config| file \ defines \ SSH \ server \ behavior.$

Rationale:

The SSH daemon reads the configuration information from this file and includes the authentication mode and cryptographic levels to use during SSH communication. The recommended value is not to provide any access rights for any user, other than the owner of the file.

Remediation:

Change the permissions of the /etc/ssh/sshd_config file to ensure that only the owner can read and write to the file:

chmod u=rw,go= /etc/ssh/sshd_config

Audit:

Ensure that the /etc/ssh/sshd_config permissions have been successfully changed:

ls -l /etc/ssh/sshd_config | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

-rw---- root system /etc/ssh/sshd_config

Default Value: 640

2.2.11 Configuring SSH – ssh_config permissions lockdown (Level 1, Scorable)

Description:

The /etc/ssh/ssh config file defines SSH client behavior.

Rationale:

The /etc/ssh/ssh_config file is the system-wide client configuration file for OpenSSH, which allows you to set options that modify the operation of the client programs. The recommended value is not to provide any writable access rights for any user, other than the owner of the file.

Remediation:

Change the permissions of the /etc/ssh/ssh_config file to ensure that only the owner can read and write to the file:

chmod u=rw,go=r /etc/ssh/ssh config

Audit:

Ensure that the /etc/ssh/ssh config permissions have been successfully changed:

ls -l /etc/ssh/ssh_config | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

-rw-r--r- root system /etc/ssh/ssh config

Default Value: 640

2.2.12 Configuring SSH – removal of .shosts files (Level 2, Scorable)

Description:

The recommendation is to remove any existing .shosts files from all user home directories.

Rationale:

The existence of .shosts files in a user home directory, combined with the correct SSH parameter can allow passwordless authentication between servers. As previous recommendations in this section disable this authentication method, these files, if they exist, should be removed.

Remediation:

List out all of the existing .shost files:

find / -name ".shosts" -print

Review the list of . shost files and remove them individually, or all at once:

Individually:

rm (full pathname)

All at once:

find / -name ".shosts" -exec rm {} \;

Audit:

Ensure that the all of the .shost files have been successfully removed:

find / -name ".shosts" -print

The above command should yield no output.

Reversion:

Any deleted files would need to be restored from a backup.

Default Value: N/A

2.2.13 Configuring SSH – removal of /etc/shosts.equiv (Level 2, Scorable)

Description:

The recommendation is to remove the /etc/shosts.equiv file.

Rationale:

The existence of a /etc/shosts.equiv file, combined with the correct SSH parameter can allow passwordless authentication between servers. As previous recommendations in this section disable this authentication method these files, if they exist, should be removed.

Remediation:

Review the content of the etc/shosts.equiv file:

cat /etc/shosts.equiv

If the file exists:

rm /etc/shosts.equiv

Audit:

Ensure that the /etc/shosts.equiv file has been successfully removed:

ls /etc/shosts.equiv

The above command should yield no output.

Reversion:

The /etc/shosts.equiv file would need to be restored from a backup.

Default Value: N/A

2.3 Sendmail Configuration

During the implementation of the default customized aixpert XML file the <code>sendmail</code> daemon will have been disabled. However, if the <code>sendmail</code> service is active and required in the environment, the recommendations in this section should be applied.

2.3.1 /etc/mail/sendmail.cf - SmtpGreetingMessage (Level 1, Scorable)

Description:

The recommendation is to change the default sendmail greeting string to not display the sendmail version and other related information.

Rationale:

The sendmail deamon has a history of being associated with security vulnerabilities. The recommendation is to change the default sendmail greeting string so as not to display the sendmail version and other related information, which can be used by an attacker for fingerprinting purposes.

Remediation:

Create a backup copy of /etc/mail/sendmail.cf:

cp -p /etc/mail/sendmail.cf /etc/mail/sendmail.cf.pre cis

Edit:

vi /etc/mail/sendmail.cf

Change:

O SmtpGreetingMessage=\$j Sendmail \$b

To:

O SmtpGreetingMessage=mailerready

Audit:

Validate the installation of the software:

grep "SmtpGreetingMessage=mailerready" /etc/mail/sendmail.cf

The above command should yield the following output:

O SmtpGreetingMessage=mailerready

Reversion:

Copy back the original /etc/sendmail.cf file:

cp -p /etc/mail/sendmail.cf.pre cis /etc/mail/sendmail.cf

Default Value: SmtpGreetingMessage=\$j Sendmail \$b

2.3.2 /etc/mail/sendmail.cf – permissions and ownership (Level 1, Scorable)

Description:

The recommended permissions and ownership for /etc/mail/sendmail.cf are applied.

Rationale:

The /etc/mail/sendmail.cf file is used by the sendmail daemon to determine its default configuration. This file must be protected from unauthorized access and modifications.

Remediation:

Set the recommended permissions and ownership to /etc/mail/sendmail.cf:

chmod u=rw,g=r,o= /etc/mail/sendmail.cf
chown root /etc/mail/sendmail.cf

Audit:

From the command prompt, execute the following command:

ls -1 /etc/mail/sendmail.cf | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

-rw-r--- root system sendmail.cf

Default Value: 644, root:system

2.3.3 /var/spool/mqueue – permissions and ownership (Level 1, Scorable)

Description:

The recommended permissions and ownership for the <code>/var/spool/mqueue</code> directory are applied.

Rationale:

The sendmail daemon generally stores its queued mail in the /var/spool/mqueue directory. Queued messages are the messages that have not yet reached their final destination. To ensure the integrity of the messages during storage, the mail queue directory must be secured from unauthorized access.

NOTE: It is possible to specify an alternate spool directory in the /etc/mail/sendmail.cf file via the QueueDirectory parameter.

Remediation:

Set the recommended permissions and ownership to /var/spool/mqueue:

```
chmod u=rwx,go= /var/spool/mqueue
chown root /var/spool/mqueue
```

Audit:

From the command prompt, execute the following command:

```
ls -ld /var/spool/mqueue | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

drwx---- root system /var/spool/mqueue

Default Value: 770, root:system

2.4 Common Desktop Environment (CDE)

During the implementation of the default customized aixpert XML file, CDE will have been disabled as the /etc/rc.dt startup file will have been removed from /etc/inittab.

CDE has a history of security problems and should remain disabled. However, if the server has a graphics adapter and CDE is used then the recommendations in this section should be followed to enhance security. If CDE is not required and the filesets are installed, is recommended that the filesets are de-installed to avoid exposure to potential security vulnerabilities.

2.4.1 CDE – de-installing CDE (Level 2, Scorable)

Description:

The recommendation is to de-install CDE from the system, assuming that it is not required and is already installed.

Rationale:

The CDE has a history of security problems and should be disabled.

NOTE: If CDE is required, it is vital to patch the software and consider TCP Wrappers to further enhance security.

Remediation:

Identity if CDE is already installed:

lslpp -L |grep -i CDE

If there are CDE filesets installed – de-install them if CDE is not required.

For each fileset preview the de-installation:

```
installp -up <fileset name>
```

Review the fileset removal preview output, paying particular attention to the other prerequisites that will also be removed. Typically only x11. Dt filesets should be de-installed as pre-requisites.

Once reviewed, de-install the fileset and pre-requisites:

```
installp -ug <fileset name>
```

NOTE: Repeat until all CDE filesets are de-installed

Audit:

Validate the de-installation of the software:

```
lslpp -L |grep -i CDE
```

The above command should yield no output.

Reversion:

Re-install the CDE software from the AIX media.

Default Value: N/A

2.4.2 CDE – disabling dtlogin (Level 2, Scorable)

Description:

Do not start CDE automatically on system boot.

Rationale:

The implementation of the customized aixpert XML file disables CDE if there is not a graphical console attached to the system. If there is a graphical console consider disabling CDE anyway.

Remediation:

Disable CDE start up:

/usr/dt/bin/dtconfig -d

NOTE: If CDE is not installed the command will not be found

Audit:

Validate the de-installation of the software:

```
lsitab dt
```

The above command should yield no output.

Reversion:

To re-configure the auto-start of the CDE software:

```
/usr/dt/bin/dtconfig -e
```

Default Value: N/A

2.4.3 CDE – sgid/suid binary lockdown (Level 1, Scorable)

Description:

CDE buffer overflow vulnerabilities may be exploited by a local user to obtain root privilege via suid/sgid programs owned by root:bin or root:sys.

Rationale:

CDE has been associated with major security risks, most of which are buffer overflow vulnerabilities. These vulnerabilities may be exploited by a local user to obtain root privilege via suid/sgid programs owned by root:bin or root:sys. It is recommended that the CDE binaries have the suid/sgid removed.

Remediation:

Remove the suid/sgid from the following CDE binaries:

```
chmod ug-s /usr/dt/bin/dtaction
chmod ug-s /usr/dt/bin/dtappgather
chmod ug-s /usr/dt/bin/dtprintinfo
chmod ug-s /usr/dt/bin/dtsession
```

Audit:

Validate the permissions of the binaries:

```
ls -l /usr/dt/bin/dtaction | awk '{print $1 " " $3 " " $4 " " $9}'
ls -l /usr/dt/bin/dtappgather | awk '{print $1 " " $3 " " $4 " " $9}'
ls -l /usr/dt/bin/dtprintinfo | awk '{print $1 " " $3 " " $4 " " $9}'
ls -l /usr/dt/bin/dtsession | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

-r-xr-xr-x	root	sys	/usr/dt/bin/dtaction
-r-xr-xr-x	root	bin	/usr/dt/bin/dtappgather
-r-xr-xr-x	root	bin	/usr/dt/bin/dtprintinfo
-r-xr-xr-x	root	bin	/usr/dt/bin/dtsession

Default Value: N/A

2.4.4 CDE – remote GUI login disabled (Level 2, Scorable)

Description:

The XDMCP service allows remote systems to start local X login sessions.

Rationale:

The XDMCP service should be disabled unless there is a requirement to allow remote X servers to start login sessions. If the ability to host remote X servers is not required, disable the service

Remediation:

Copy /usr/dt/config/Xconfig to /etc/dt/config if it does not already exist:

ls -l /etc/dt/config/Xconfig

If the file does not exist, create it:

mkdir -p /etc/dt/config
cp /usr/dt/config/Xconfig /etc/dt/config

Disable remote X sessions from being started:

vi /etc/dt/config/Xconfig

Replace:

Dtlogin.requestPort: (

With:

Dtlogin.requestPort: 0

Audit:

Validate the change:

grep "^Dtlogin.requestPort:[[::space::]]" /etc/dt/config/Xconfig

The command above should yield the following output:

Dtlogin.requestPort:

Reversion:

Comment out the option:

vi /etc/dt/config/Xconfig

Reflect:

```
# Dtlogin.requestPort: 0
```

Default Value: Enabled

2.4.5 CDE – screensaver lock (Level 1, Scorable)

Description:

The default timeout is 30 minutes of keyboard and mouse inactivity before a password protected screensaver is invoked by the CDE session manager.

Rationale:

The default timeout of 30 minutes prior to a password protected screensaver being invoked is too long. The recommendation is to set this to 10 minutes to protect from unauthorized access on unattended systems.

Individual users are able to over ride this default setting.

Remediation:

Set the default timeout parameters dtsession*saverTimeout: and dtsession*lockTimeout:

```
for file in /usr/dt/config/*/sys.resources; do
   dir=`dirname $file | sed -e s/usr/etc/`
   mkdir -p $dir
   echo 'dtsession*saverTimeout: 10' >> $dir/sys.resources
   echo 'dtsession*lockTimeout: 10' >> $dir/sys.resources
done
```

Audit:

Validate the changes to the sys.resources files:

```
egrep "dtsession\*saverTimeout:|dtsession\*lockTimeout:"
/etc/dt/config/*/sys.resources
```

The above command should yield a similar output to the following:

```
/etc/dt/config/en_US/sys.resources:dtsession*saverTimeout: 10
/etc/dt/config/en_US/sys.resources:dtsession*lockTimeout: 10
```

Default Value: N/A

2.4.6 CDE – /etc/dt/config/Xconfig permissions and ownership (Level 1, Scorable)

Description:

The /etc/dt/config/Xconfig file is used to customize CDE DT login attributes.

Rationale:

The /etc/dt/config/Xconfig file can be used to customize CDE DT login attributes. The default file, /usr/dt/config/Xconfig, is unconditionally overwritten upon subsequent installation. It is recommended that the appropriate permissions and ownership are applied to secure the file.

Remediation:

Check to see if the /etc/dt/config/Xconfig exists:

```
ls -l /etc/dt/config/Xconfig
```

Apply the appropriate ownership and permissions to /etc/dt/config/Xconfig:

```
chown root:bin /etc/dt/config/Xconfig
chmod ugo=r /etc/dt/config/Xconfig
```

Audit:

Validate the ownership and permissions:

```
ls -l /etc/dt/config/Xconfig | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

```
-r--r-- root bin /etc/dt/config/Xconfig
```

Default Value: N/A

2.4.7 CDE – /etc/dt/config/Xservers permissions and ownership (Level 1, Scorable)

Description:

The /etc/dt/config/Xservers contains entries to start the Xserver on the local display.

Rationale:

The /etc/dt/config/Xservers contains entries to start the Xserver on the local display. The default file, /usr/dt/config/Xservers, is unconditionally overwritten upon subsequent installation. It is recommended that the appropriate permissions and ownership are applied to secure the file.

Remediation:

Check to see if the /etc/dt/config/Xservers exists:

```
ls -l /etc/dt/config/Xservers
```

If it exists ensure that it is explicitly defined in /etc/dt/config/Xconfig:

vi /etc/dt/config/Xconfig

Replace:

Dtlogin.servers: Xservers

With:

Dtlogin*servers: /etc/dt/config/Xservers

Apply the appropriate ownership and permissions to /etc/dt/config/Xservers:

chown root:bin /etc/dt/config/Xservers
chmod ugo=r /etc/dt/config/Xservers

Audit:

Validate the ownership and permissions:

ls -l /etc/dt/config/Xservers | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

-r--r-- root bin /etc/dt/config/Xservers

Default Value: N/A

2.4.8 CDE – login screen hostname masking (Level 1, Scorable)

Description:

The Dtlogin*greeting.labelString parameter is the message displayed in the first dialogue box on the CDE login screen. This is where the username is entered.

The Dtlogin*greeting.persLabelString is the message displayed in the second dialogue box on the CDE login screen. This is where the password is entered.

Rationale:

Potential hackers may gain access to valuable information such as the hostname and the version of the operating system from the default AIX login screen. This information would assist hackers in choosing the exploitation methods to break into the system. For security reasons, change the login screen default messages.

Remediation:

Copy the files from /usr/dt/config/*/Xresources to /etc/dt/config/*/Xresources and add the Dtlogin*greeting.labelString and Dtlogin*greeting.persLabelString parameters to all copied Xresources files:

```
for file in /usr/dt/config/*/Xresources; do
   dir=`dirname $file | sed s/usr/etc/`
   mkdir -p $dir
   if [ ! -f $dir/Xresources ]; then
   cp $file $dir/Xresources
   fi
   WARN="Authorized uses only. All activity may be monitored and
   reported."
   echo "Dtlogin*greeting.labelString: $WARN" >>$dir/Xresources
   echo "Dtlogin*greeting.persLabelString: $WARN" >>$dir/Xresources
   done
```

Audit:

Validate the changes to the Xresources files:

```
egrep "Dtlogin\*greeting.labelString|Dtlogin\*greeting.persLabelString:"
/etc/dt/config/*/Xresources
```

The above command should yield a similar output to the following:

```
/usr/dt/config/en_US/Xresources:!! Dtlogin*greeting.labelString: Authorized uses only. All activity may be monitored and reported.
/usr/dt/config/en_US/Xresources:!! Dtlogin*greeting.persLabelString: Authorized uses only. All activity may be monitored and reported.
```

Default Value: N/A

2.4.9 CDE – /etc/dt/config/*/Xresources permissions and ownership (Level 1, Scorable)

Description:

The /etc/dt/config/*/Xresources file contains appearance and behavior resources for the Dtlogin login screen.

Rationale:

The /etc/dt/config/*/Xresources file defines the customization of the Dtlogin screen. The default file, /usr/dt/config/*/Xresources, is unconditionally overwritten upon subsequent installation. It is recommended that the appropriate permissions and ownership are applied to secure the file.

Remediation:

Set the appropriate permissions and ownership on all xresources files:

```
chown root:sys /etc/dt/config/*/Xresources
chmod u=rw,go=r /etc/dt/config/*/Xresources
```

Audit:

Validate the ownership and permissions:

```
ls -l /etc/dt/config/*/Xresources | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield a similar output to the following:

-rrr	root	sys	/etc/dt/config/en_GB/Xresources
-rrr	root	sys	/etc/dt/config/en_US/Xresources

Default Value: N/A

2.5 NFS

During the implementation of the default customized aixpert XML file, NFS services will have been disabled as the /etc/rc.nfs startup file will have been removed from /etc/inittab.

The first recommendation in this section is to de-install NFS to complete the lockdown of this service. However, if the server acts as either an NFS server or NFS client there are further security recommendations to implement.

2.5.1 NFS – de-install NFS (Level 2, Scorable)

Description:

Remove /etc/exports and de-install NFS.

Rationale:

NFS is frequently exploited to gain unauthorized access to file and directories. Unless the server needs to act as an NFS server or client, the filesets should be de-installed.

Remediation:

Ensure that there are no current NFS client mounts:

```
mount |grep "nfs"
cat /etc/filesystems |grep "nfs"
```

The above commands should yield no output.

De-install the NFS client software:

```
installp -u bos.net.nfs.client
```

Ensure that there are no current NFS exports:

```
cat /etc/exports
```

The above command should yield no output. Or the file should not exist.

De-install the NFS sever software:

installp -u bos.net.nfs.server

If there was an empty /etc/exports file, remove it:

rm /etc/exports

Audit:

Ensure that the software has been successfully de-installed:

lslpp -L |grep -i nfs

The above command should yield no output.

Reversion:

Re-install the software from the product DVD's

Default Value: N/A

2.5.2 NFS – nosuid on NFS client mounts (Level 1, Scorable)

Description:

Disable suid/sgid program execution within any mounted NFS filesystem.

Rationale:

Setting the nosuid option means that on the NFS server the root user cannot make an suid-root program within an exported filesystem. Then log onto an NFS client as a standard user and use the suid-root program to effectively become root on that client.

Remediation:

For each NFS mount, disable suid programs.

List the current NFS mounts:

mount |grep "nfs"

For each NFS filesystem add the nosuid option, this change should be made via an edit to the /etc/filesystems file.

Create a copy of /etc/filesystems:

cp -p /etc/filesystems /etc/filesystems.pre cis

For each NFS mount edit the options line to reflect the nosuid option:

vi /etc/filesystems

Reflect in each NFS options line:

```
options = rw,bg,hard,intr,nosuid,sec=sys
```

NOTE: The above options line is an example, the nosuid should be added to the existing options

The NFS mount needs to be re-mounted to reflect this change

Audit:

For each NFS filesystem, ensure that the options have been changed to reflect the nosuid option:

```
mount |grep "nfs" |wc -l mount |grep "nfs" |grep "nosuid" |wc -l
```

Both commands should yield the same output.

Default Value: N/A

2.5.3 NFS – localhost removal (Level 1, Scorable)

Description:

Remove any reference to localhost or localhost aliases from /etc/exports.

Rationale:

If the RPC portmapper has proxy forwarding enabled, which is a default setting in many vendor versions. You must not export your local filesytems back to the localhost, either by name or to the alias localhost, and you must not export to any netgroups of which your host is a member. If proxy forwarding is enabled, an attacker may carefully craft NFS packets and send them to the portmapper, which in turn, forwards them to the NFS server. As the packets come from the portmapper process, which runs as root, they appear to be coming from a trusted system. This configuration may allow anyone to alter and delete files at will.

Remediation:

Remove any reference to localhost or localhost aliases in /etc/exports:

Review the content of /etc/exports and check for localhost or localhost aliases:

```
cat /etc/exports
```

NOTE: If instances of localhost or localhost aliases are found, edit the file and remove them.

Create a copy of /etc/exports:

```
cp -p /etc/exports /etc/exports.pre_cis
```

Edit the file:

vi /etc/exports

Edit the relevant NFS exports to remove the localhost access, for example:

/nfsexport sec=sys,rw,access=localhost:testserver

If /etc/exports is updated, as localhost references have been removed, update the current NFS export options:

exportfs -a

Audit:

Re-review /etc/exports if the file was updated, to validate the changes:

cat /etc/exports

Default Value: N/A

2.5.4 NFS – restrict NFS access (Level 2, Scorable)

Description:

Only allow explicitly defined host access to NFS exported filesystems and directories.

Rationale:

The NFS server should be configured to only allow explicitly defined hosts to mount filesystems from the server. If an unauthorized host is denied the permission to mount a filesystem, then the unauthorized users on that host will not be able to access the server's files.

The default value of access allows any machine to mount any exported filesystems/directories.

Remediation:

Ensure that all exports defined in /etc/exports have explicit client access options which clearly define the host or hosts allowed access:

Review the content of /etc/exports and that all exports have explicit access lists:

cat /etc/exports

Ensure that each NFS export has an explicit access line, for example:

/usr/spool/mail -access=symmachine

If the file is updated, to reflect client access changes, update the current NFS export options:

exportfs -a

Audit:

Re-review /etc/exports if the file was updated, to validate the changes:

cat /etc/exports

Reversion:

Copy back the original /etc/exports:

cp -p /etc/exports.pre cis /etc/exports

Default Value: N/A

2.5.5 NFS – no_root_squash option (Level 1, Scorable)

Description:

For each NFS export, ensure that the root squash option is set to -2 or -1.

Rationale:

Each NFS export on the server should have the <code>anon=-2</code> option set. Without this, an NFS export could be at risk, where the remote root user effectively has root access on the NFS mount. By setting the export option <code>anon=-2</code>, when the client attempts to access (read, write, or delete) the NFS mount, the server substitutes the UID to the server's nobody account, which is <code>-2</code>. This means that the root user on the client cannot access or change files that only root on the server can access or change. It is therefore recommended that <code>root_squash</code> is set on all exported filesystems.

The default value of any exported filesystem or directory is -2, another value has to be explicitly set.

As a more secure option you can set the option to anon=-1, which disables anonymous access. By default, secure NFS accepts non-secure requests as anonymous.

NOTE: The root user on the client can still use su to become any other user and access and change that users files, assuming that the same user exists on the NFS server and owns files and/or directories in the NFS export.

Remediation:

Use smitty to change/validate this value for all NFS exported filesystems:

smitty chnfsexp

For each filesystem, as defined in the F4 list, set the following option:

Anonymous UID [-2]

NOTE: Press enter to accept the change

Once all exported filesystems have been successfully validated or changed, re-export the filesystems and directories to activate the new options:

```
exportfs -a
```

Audit:

As -2 is the default NFS export value, ensure that there are no explicit anon= options set in /etc/exports:

```
grep "anon=" /etc/exports
```

The above should command should yield no output.

Default Value: -2

2.5.6 NFS – secure NFS (Level 2, Scorable)

Description:

For each NFS export, ensure that the secure option is selected.

Rationale:

Secure NFS uses DES encryption or Kerberos to authenticate hosts involved in RPC transactions. RPC is a protocol used by NFS to communicate requests between hosts. Secure NFS mitigates attempts by an attacker to spoof RPC requests by encrypting the time stamp in the RPC requests. A receiver successfully decrypts the time stamp and confirms that it is correct. This serves as a confirmation that the RPC request came from a trusted host.

Remediation:

Use smitty to change/validate this value for all NFS exported filesystems:

```
smitty chnfsexp
```

For each filesystem, as defined in the F4 list. There are five security methods which can be used to define different security access methods for different clients:

The security method options are:

```
sys - UNIX authentication
dh - DES authentication
none - Use the anonymous ID if it has a value other than -1
krb5 - Kerberos. Authentication only
krb5i - Kerberos. Authentication and integrity
krb5p - Authentication, integrity, and privacy
```

Once all exported filesystems have been successfully validated or changed, re-export the filesystems and directories to activate the new options:

```
exportfs -a
```

Audit:

Ensure that the relevant sec= options set in /etc/exports:

```
grep "sec=" /etc/exports
```

The above should command should return each export and the security mode of the export.

Reversion:

Copy back the original /etc/exports:

```
cp -p /etc/exports.pre_cis /etc/exports
```

Default Value: N/A

2.6 NIS

Network Information Service (NIS) or Yellow Pages (YP), is a client/server directory service protocol used for distributing system configuration data, such as: users, groups, passwords and hosts between computers in a network. This is typically done in larger environments to centralize the management of this data. If the NIS software is installed but not configured, an attacker can cripple a machine by starting NIS. In environments where NIS is utilized, tools like <code>ypsnarf</code> allow an attacker to grab the contents of your NIS maps, providing large amounts of information about your site.

The first recommendation in this section is to de-install NIS, if it is installed, to lockdown this service. However, if NIS is used in the environment it is recommended that NIS+ is used instead. NIS+ is structured differently from NIS and supports secure and encrypted RPC, which resolves many of the security issues.

The configuration of NIS+ is not within the scope of this benchmark; however the links below can be used for initial reference:

AIX 5.3:

NIS+ transition

AIX 6.1:

NIS+ transition

2.6.1 NIS – disable NIS client (Level 2, Scorable)

Description:

If NIS is not used in the environment, disable the NIS client and de-install the software.

Rationale:

As NIS is extremely insecure, the NIS client packages must be removed from the system unless absolutely needed.

Remediation:

Ensure that all of the NIS daemons are inactive:

stopsrc -g yp

De-install the NIS client software:

installp -u bos.net.nis.client

Audit:

Ensure that the software has been successfully de-installed:

lslpp -L |grep "bos.net.nis.client"

The above should command should yield no output.

Reversion:

Re-install the software from the product DVD's:

Default Value: N/A

2.6.2 NIS – disable NIS server (Level 2, Scorable)

Description:

If NIS is not used in the environment, disable the NIS server and de-install the software.

Rationale:

As NIS is extremely insecure, the NIS server packages must be removed from the system unless absolutely needed.

Remediation:

Ensure that all of the NIS daemons are inactive:

stopsrc -g yp

De-install the NIS server software:

```
installp -u bos.net.nis.server
```

Audit:

Ensure that the software has been successfully de-installed:

```
lslpp -L |grep "bos.net.nis.server"
```

The above should command should yield no output.

Reversion:

Re-install the software from the product DVD's:

Default Value: N/A

2.6.3 NIS – remove NIS markers from password and group files (Level 2, Scorable)

Description:

If NIS has been de-installed in the environment, or has historically been used, ensure the + markers are removed from /etc/passwd and /etc/group.

Rationale:

The + entries in /etc/passwd and /etc/group were used as markers to insert data from a NIS map. These entries may provide an avenue for attackers to gain privileged access on the system. The + entries must be deleted if they still exist.

Remediation:

Examine the /etc/passwd and /etc/group files:

```
grep "^+" /etc/passwd /etc/group
```

If the above command yields output, delete the + line:

```
vi /etc/passwd
vi /etc/group
```

Audit:

Re-run the command:

```
grep "^+" /etc/passwd /etc/group
```

The command above should yield no output.

Reversion:

Add the + line back to the same point in the file/s:

```
vi /etc/passwd
vi /etc/group
```

Default Value: N/A

2.6.4 NIS – restrict NIS server communication (Level 2, Scorable)

Description:

If NIS must be used in the environment, limit access to the NIS data to specific subnets.

Rationale:

By default the NIS server will authenticate all IP addresses if the <code>/var/yp/securenets</code> file does not exist, or exists without any subnets defined. The <code>/var/yp/securenets</code> file contains a list of subnets that are considered trusted and are allowed to access NIS data using the <code>ypserv</code> and <code>ypxfrd</code> daemons. This is a user-created file that resides on a NIS master server and any slave servers. Without configuring this file, anyone with knowledge of the NIS server address and the domain name, can obtain NIS served data, including the contents of the <code>/etc/passwd</code> file. Hence, it is recommended that the <code>/var/yp/securenets</code> file is configured to restrict access.

Remediation:

Create and secure the /var/yp/securenets file (if it does not already exist):

```
touch /var/yp/securenets
chmod u=rw,go= /var/yp/securenets
```

Edit the file:

```
vi /var/yp/securenets
```

Add the allowed subnets:

```
255.255.255.0 128.311.10.0
```

NOTE: The format of the file is netmask netaddr as shown in the example above. Explicitly define all valid network subnets (one entry per line).

Stop and start NIS to implement the configuration changes:

```
stopsrc -g yp
startsrc -g yp
```

Audit:

Review the content of the /var/yp/securenets file:

```
cat /var/yp/securenets
```

NOTE: A test should be performed from an allowed client and non-allowed subnet to validate the securenets configuration

Reversion:

Remove the /var/yp/securenets file:

rm /var/yp/securenets

Default Value: N/A

2.7 SNMP

During the implementation of the default customized aixpert XML file, the snmpd daemon will have been disabled. However, if SNMP is active and required in the environment, the recommendations in this section should be applied.

The Simple Network Management Protocol (SNMP) is a commonly used service that provides network management and monitoring capabilities. SNMP offers the capability to poll networked devices and monitor data such as utilization and errors from various subsystems on the host. SNMP is also capable of changing the configurations on the host, allowing remote management of the system. The protocol uses a community string for authentication from the SNMP client to the SNMP agent on the managed device.

In AIX, two SNMP community names, private and system, are enabled with read/write privileges, but only allow access from localhost connections. Nevertheless, a local user may install an SNMP client and modify sensitive variables. If SNMP is required, the community strings must be greater than six characters and include a combination of letters, numbers, and special characters to avoid a brute force attack.

2.7.1 SNMP – disable private community string (Level 2, Scorable)

Description:

If snmpd is required within the environment, disable the private community string.

Rationale:

In AIX, two SNMP community names, private and system, are enabled with read/write privileges, but are allowed access only from localhost connections. As these SNMP names are the default, they must not be used. Any SNMP community name should be a combination of letters, numbers and special characters to enhance security.

Remediation:

Create a backup of /etc/snmpd.conf:

cp -p /etc/snmpd.conf /etc/snmpd.conf.pre_cis

Edit the file:

vi /etc/snmpd.conf

Comment out the private entry:

#community private 127.0.0.1 255.255.255.255 readWrite

Audit:

Ensure the private entry has been commented out from /etc/snmpd.conf:

grep "^#community[[:space:]]*private" /etc/snmpd.conf

The above command should yield the following output:

#community private 127.0.0.1 255.255.255 readWrite

Reversion:

Copy back the original /etc/snmpd.conf file:

cp -p /etc/snmpd.conf.pre cis /etc/snmpd.conf

Default Value: Commented in

2.7.2 SNMP – disable system community string (Level 2, Scorable)

Description:

If snmpd is required within the environment, disable the system community string.

Rationale:

In AIX, two SNMP community names, private and system, are enabled with read/write privileges, but are allowed access only from localhost connections. As these SNMP names are the default, they must not be used. Any SNMP community name should be a combination of letters, numbers and special characters to enhance security.

Remediation:

Edit the file:

vi /etc/snmpd.conf

Comment out the system entry:

#community system 127.0.0.1 255.255.255 readWrite 1.17.2

Audit:

Ensure the system entry has been commented out from /etc/snmpd.conf:

```
grep "^#community[[:space:]]*system" /etc/snmpd.conf
```

The above command should yield the following output:

```
#community system 127.0.0.1 255.255.255 readWrite 1.17.2
```

Reversion:

Copy back the original /etc/snmpd.conf file:

```
cp -p /etc/snmpd.conf.pre cis /etc/snmpd.conf
```

Default Value: Commented in

2.7.3 SNMP – disable public community string (Level 2, Scorable)

Description:

If snmpd is required within the environment, disable or change the public community string.

Rationale:

The public community string can be polled by remote SNMP devices and pertinent information can be read or changed on the host. The public community string should but commented out, or if SNMP is a required service the public community name should be changed to be a combination of letters, numbers and special characters to enhance security.

Remediation:

Edit the file:

```
vi /etc/snmpd.conf
```

Comment out the public entry:

```
#community public
```

Audit:

Ensure the public entry has been commented out from /etc/snmpd.conf:

```
grep "^#community[[:space:]]*public" /etc/snmpd.conf
```

The above command should yield the following output:

```
#community public
```

Reversion:

Copy back the original /etc/snmpd.conf file:

```
cp -p /etc/snmpd.conf.pre_cis /etc/snmpd.conf
```

Default Value: Commented in

2.7.4 SNMP – restrict community access (Level 2, Scorable)

Description:

If snmpd is required within the environment, implement IP access restrictions on the available community strings.

Rationale:

If SNMP is required, IP access restrictions should be put into place to limit which hosts or networks subnets are able to remotely poll the server.

Remediation:

Identify if there are any currently configured community strings:

```
grep "^community[[::space::]]" /etc/snmpd.conf
```

If there are active community strings, edit the configuration file:

```
vi /etc/snmpd.conf
```

Implement IP access restrictions to ALL of the available community names:

```
community public 192.132.10.0 255.255.255.0 readOnly
```

The format of each line should reflect:

```
community <community name> <IP addresses> <netmask> [ <permissions> <view>]
```

Audit:

Review the available community strings IP access control configuration:

```
grep "^community[[::space::]]" /etc/snmpd.conf
```

NOTE: validate the allowed IP address and netmasks

Reversion:

Copy back the original /etc/snmpd.conf file:

```
cp -p /etc/snmpd.conf.pre_cis /etc/snmpd.conf
```

Default Value: N/A

2.7.5 SNMP – disable Readwrite community access (Level 2, Scorable)

Description:

If snmpd is required within the environment, disable readWrite permissions for all active community strings.

Rationale:

If SNMP is required, none of the available community strings should have global readWrite permissions defined. This would allow any remote client to query and to set system configuration parameters. SNMP readWrite communities must be disabled unless absolutely necessary. If a readWrite community is enabled, then access must be granted to only trusted machines in your network. As SNMP uses community names as part of authentication, you must ensure that all community names are greater than six characters and is a mix of characters, numbers, and special characters.

Remediation:

Identify if there are any currently configured community strings:

```
grep "^community[[::space::]]" /etc/snmpd.conf
```

If there are active community strings, edit the configuration file:

```
vi /etc/snmpd.conf
```

Replace all instances of:

```
community <community name> <IP addresses> <netmask> [ readWrite <view>]
```

With:

```
community <community name> <IP addresses> <netmask> [ readOnly <view>]
```

Audit:

Review the community lines in /etc/snmpd.conf:

```
grep "^community[[::space::]]" /etc/snmpd.conf.
```

NOTE: ensure that there is no readWrite access.

Reversion:

Copy back the original /etc/snmpd.conf file:

```
cp -p /etc/snmpd.conf.pre_cis /etc/snmpd.conf
```

Default Value: N/A

2.8 Securing inetd

During the implementation of the default customized aixpert XML file, the services within /etc/inetd.conf will have been disabled. If all services have been disabled and are not required, the inetd daemon itself can be disabled to further enhance security.

2.8.1 inetd - disabling inetd (Level 2, Scorable)

Description:

If all of services run and managed by inetd are disabled, disable the inetd daemon itself.

Rationale:

If all inetd services are disabled, then there is no need to start the daemon at boot time. An administrator can manually start the inetd service post-IPL, if any of the inetd controlled services are required.

Remediation:

Review any active inetd services:

```
refresh -s inetd lssrc -ls inetd
```

NOTE: If there are active services and the services are required, do not disable inetd. Skip to the next section and consider the implementation of TCP Wrappers to secure access to these active services. If the active services are not required disable them via the chsubserver command.

Disable inetd if there are no active services:

```
chrctcp -d inetd stopsrc -s inetd
```

Audit:

Ensure that inetd startup has been commented out of /etc/rc.tcpip:

```
grep "^#start[[::space::]]/usr/sbin/inetd" /etc/rc.tcpip
```

The above command should yield the following output:

```
#start /usr/sbin/inetd "$src_running"
```

Reversion:

Comment in inetd startup in /etc/rc.tcpip:

```
chrctcp -a inetd
```

Default Value: Commented in

2.9 Portmap Lockdown

The portmap deamon is required for the RPC service. It converts the RPC program numbers into Internet port numbers. The daemon may be disabled if the server is not:

- An NFS client or server
- A NIS (YP) or NIS+ client or server
- Running the CDE GUI
- Running a third-party software application, which is dependent on RPC support

2.9.1 /etc/rc.tcpip - portmap (Level 2, Scorable)

Description:

If all RPC services are disabled, disable the portmap daemon itself.

Rationale:

If all RPC services are disabled, then there is no need to start the portmap daemon at boot time. An administrator can manually start portmap post-IPL, if any of the RPC services are required.

Remediation:

Review any active RPC services:

```
rpcinfo -p localhost
```

NOTE: If there are active RPC services and the services are required, do not disable portmap.

Disable portmap if there are no active RPC services:

```
chrctcp -d portmap stopsrc -s portmap
```

Audit:

Ensure that portmap startup has been commented out of /etc/rc.tcpip:

```
grep "^#start[[::space::]]/usr/sbin/portmap" /etc/rc.tcpip
```

The above command should yield the following output:

```
#start /usr/sbin/portmap "$src_running"
```

Reversion:

Comment in portmap startup in /etc/rc.tcpip:

```
chrctcp -a portmap
```

Default Value: Commented in

2.10 TCP Wrappers

During the implementation of the default customized aixpert XML file, the services within <code>/etc/inetd.conf</code> will have been disabled. However, if some of the services are required, then it is recommended that TCP Wrappers are installed and configured to limit access to any active TCP and UDP services.

TCP Wrappers allow the administrator to control who has access to various inetd network services via source IP address controls. TCP Wrappers also provide logging information via syslog about both successful and unsuccessful connections.

TCP Wrappers are generally triggered via /etc/inetd.conf, but other options exist for "wrappering" non-inetd based software.

The configuration of TCP Wrappers to suit a particular environment is outside the scope of this benchmark; however the following links will provide the necessary documentation to plan an appropriate implementation:

TCP Wrappers Home Page

The website contains source code for both IPv4 and IPv6 versions.

2.10.1 TCP Wrappers – installing TCP Wrappers (Level 2, Scorable)

Description:

The recommendation is to install and configure TCP Wrappers if there are active inetd controlled services on the system.

Rationale:

TCP Wrappers is a freely available IP packet filtering facility. It provides for greater and more specific control over local network services and the hosts that are allowed to access them. It also makes use of the standard syslog facility to track local network use.

Remediation:

Identity any active inetd services:

```
refresh -s inetd lssrc -ls inetd
```

If there are any active TCP or UDP services, download and install the TCP Wrappers software:

TCP Wrappers is bundled on the AIX media expansion cdrom.

Alternatively, the source code may be downloaded and compiled from:

TCP Wrappers Source Code

NOTE: Ensure that the latest version is downloaded.

The installation example below assumes that the AIX media expansion pack cdrom has been used as the source of the software.

Place the TCP Wrappers software into a convenient location, such as /tmp and install via:

```
/usr/lib/instl/sm_inst installp_cmd -a -Q -d /tmp -f netsec.options.tcpwrapper,netsec.options.idprotocol -c -N -g -X -G -Y
```

NOTE: If the software is not located in /tmp, reflect the actual location in the command above.

Audit:

Validate the installation of the software:

```
lslpp -L |grep "netsec.options"
```

The above command should yield the following output:

```
netsec.options.idprotocol 1.1.0.0 C F Authentication daemon(RFC1413)
netsec.options.tcpwrapper.base
netsec.options.tcpwrapper.license
netsec.options.tcpwrapper.man.en_US
netsec.options.tcpwrapper.msg.en_US
```

NOTE: The version numbers may differ based on the source of the software

Reversion:

De-install the TCP Wrappers software:

```
installp -u netsec.options*
```

Default Value: N/A

2.10.2 TCP Wrappers – creating a hosts.deny file (Level 1, Scorable)

Description:

Once TCP Wrappers are installed a /etc/hosts.deny file should be created and be configured.

Rationale:

The /etc/hosts.deny file describes the names of the hosts which are not allowed to access the local inetd services, as decided by the /usr/sbin/tcpd server. All access should be denied by default unless explicitly authorized.

Access is granted when a (daemon,client) pair matches an entry in the /etc/hosts.allow file. Access is denied when a (daemon,client) pair matches an entry in the /etc/hosts.deny file. However, access is granted if matching entry does not exist in both the files. This is why, by default, all access must be denied.

Remediation:

Create a /etc/hosts.deny file:

```
touch /etc/hosts.deny
chown root:system /etc/hosts.deny
chmod u=rw,go= /etc/hosts.deny
```

Deny all traffic by default, explicit access will be defined in the /etc/hosts.allow file:

```
vi /etc/hosts.deny
```

Add:

```
ALL: ALL
```

Audit:

Validate the content of the /etc/hosts.deny file:

```
cat /etc/hosts.deny
```

The above command should yield the following output:

```
ALL: ALL
```

Default Value: N/A

2.10.3 TCP Wrappers - creating a hosts.allow file (Level 1, Scorable)

Description:

Once TCP Wrappers are installed a /etc/hosts.allow file should be created and be configured.

Rationale:

This file describes the names of the hosts which are allowed to access the local inetd services as decided by the /usr/sbin/tcpd server. Access is granted when a (daemon,client) pair matches an entry in the /etc/hosts.allow file. Access is denied when a (daemon,client) pair matches an entry in the /etc/hosts.deny file. However, access is granted if matching entry does not exist in both the files.

Remediation:

Create a /etc/hosts.allow file:

```
touch /etc/hosts.allow
chown root:system /etc/hosts.allow
chmod u=rw,go= /etc/hosts.allow
```

Define explicit access to the local inetd services:

vi /etc/hosts.allow

An example configuration:

```
ALL: LOCAL @some_netgroup
ALL: .foobar.edu EXCEPT terminalserver.foobar.edu
```

Audit:

Validate the content of the /etc/hosts.allow file:

```
cat /etc/hosts.allow
```

The above command should reflect the defined configuration file.

NOTE:- Since the /etc/hosts.allow file is processed before /etc/hosts.deny, ensure that there are no entries in /etc/hosts.allow that may accidentally grant access to a system which are then subsequently denied in /etc/hosts.deny.

Default Value: N/A

2.10.4 TCP Wrappers – wrapping inetd services (Level 2, Scorable)

Description:

If TCP Wrappers have been installed because there are active inetd services, these services must utilize TCP Wrappers to restrict host access.

Rationale:

By limiting access to the server, you reduce your exposure to threats from attackers on remote systems. Therefore any active inetd controlled service which cannot be disabled should be restricted so that it can only be used by trusted hosts.

Remediation:

Prior to implementing this recommendation it is important that hosts.deny and hosts.allow files have been created.

For each active TCP and UDP inetd service, change the entry in /etc/inetd.conf, so that tcpd is executed.

Copy the current /etc/inetd.conf file for reversion purposes:

```
cp -p /etc/inetd.conf /etc/inetd.conf.pre_tcp_wrappers
```

For example, to utilize TCP Wrappers on the telnet service:

Edit:

vi /etc/inetd.conf

Change:

telnet stream tcp6 nowait root /usr/sbin/telnetd telnetd

To:

telnet stream tcp nowait root /usr/sbin/tcpd telnetd

Repeat the change for other services.

Audit:

Ensure that the amended service line reflects the topd path:

grep "^<service name>[[:blank::]]" /etc/inetd.conf |grep "tcpd"

The above command should yield output.

Reversion:

Copy back the original /etc/inetd.conf file:

cp -p /etc/inetd.conf.pre tcp wrappers /etc/inetd.conf

Default Value: N/A

2.11 Permissions and Ownership

This section will of the benchmark will focus on locking down access to specific key configuration files, log files and directories. If these critical files and directories have incorrect ownership and permissions, they can provide an attacker with a method of attack, or with pertinent system information.

Some of the files and directories changed in this section may not exist on your system. In this instance the recommendation can be ignored.

2.11.1 Permissions and Ownership – /etc/security (Level 1, Scorable)

Description:

This /etc/security directory contains the user and group configuration files and the encrypted passwords.

Rationale:

The /etc/security directory contains sensitive files such as /etc/security/passwd, /etc/security/group. It must be secured from unauthorized access and modifications.

Remediation:

Remove world read, write and execute access and group write access from /etc/security:

```
chown -R root:security /etc/security
chmod u=rwx,g=rx,o= /etc/security
chmod -R go-w,o-rx /etc/security
```

Audit:

Validate the permissions of /etc/security:

```
ls -ld /etc/security | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

```
drwxr-x--- root security /etc/security
```

Default Value: N/A

2.11.2 Permissions and Ownership – /etc/group (Level 1, Scorable)

Description:

The /etc/group file contains a list of the groups defined within the system.

Rationale:

The /etc/group file defines basic group attributes. Since the file contains sensitive information, it must be properly secured.

Remediation:

Ensure correct ownership and permissions are in place for /etc/group:

```
chown root:security /etc/group
chmod u=rw,go=r /etc/group
```

Audit:

Validate the permissions of /etc/group:

```
ls -l /etc/group | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:



Default Value: 644

2.11.3 Permissions and Ownership – /etc/passwd (Level 1, Scorable)

Description:

The /etc/passwd file contains a list of the users defined within the system.

Rationale:

The /etc/passwd file defines all users within the system. Since the file contains sensitive information, it must be properly secured.

Remediation:

Ensure correct ownership and permissions are in place for /etc/passwd:

```
chown root:security /etc/passwd
chmod u=rw,go=r /etc/passwd
```

Audit:

Validate the permissions of /etc/passwd:

```
ls -l /etc/passwd | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

```
-rw-r--r- root security /etc/passwd
```

Default Value: 644

2.11.4 Permissions and Ownership – /etc/security/audit (Level 1, Scorable)

Description:

The /etc/security/audit directory contains the system audit configuration files.

Rationale:

The /etc/security/audit directory stores the audit configuration files. This directory must have adequate access controls to prevent unauthorized access.

Remediation:

Ensure correct ownership and permissions are in place for /etc/security/audit:

```
chown -R root:audit /etc/security/audit
chmod u=rwx,g=rx,o= /etc/security/audit
chmod -R u=rw,g=r,o= /etc/security/audit/*
```

Audit:

Validate the permissions of /etc/security/audit:

```
ls -ld /etc/security/audit | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

Default Value: N/A

2.11.5 Permissions and Ownership – /audit (Level 1, Scorable)

Description:

The /audit directory holds the output produced from the audit subsystem.

Rationale:

The /audit directory stores the audit output files. This directory must have adequate access controls to prevent unauthorized access.

Remediation:

Ensure correct ownership and permissions are in place for /audit:

```
chown root:audit /audit
chmod u=rwx,g=rx,o= /audit
chmod -R u=rw,g=r,o= /audit/*
```

Audit:

Validate the permissions of /audit:

```
ls -ld /audit | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

```
drwxr-x--- root audit /audit
```

Default Value: N/A

2.11.6 Permissions and Ownership – /smit.log (Level 1, Scorable)

Description:

The/smit.log file maintains a history of all smit commands run as root.

Rationale:

The /smit.log file may contain sensitive information regarding system configuration, which may be of interest to an attacker. This log file must be secured from unauthorized access and modifications.

Remediation:

Remove world read and write access to /smit.log:

```
chmod o-rw /smit.log
```

Audit:

Validate the permissions of /smit.log:

```
ls -1 /smit.log | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

-rw-r--- root system /smit.log

Default Value: 644

2.11.7 Permissions and Ownership – /var/adm/cron/log (Level 1, Scorable)

Description:

The /var/adm/cron file contains a log of all cron jobs run on the system.

Rationale:

The /var/adm/cron/log, records all cron jobs run on the system. The file permissions must ensure that it is accessible only to its owner and group.

Remediation:

Remove world read and write access to /var/adm/cron/log:

chmod o-rw /var/adm/cron/log

Audit:

Validate the permissions of /var/adm/cron/log:

ls -l /var/adm/cron/log | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

-rw-rw--- root cron /var/adm/cron/log

Default Value: 664

2.11.8 Permissions and Ownership – /var/spool/cron/crontabs (Level 1, Scorable)

Description:

The /var/spool/cron/crontabs directory contains all of the crontabs for the users on the system.

Rationale:

The /var/spool/cron/crontabs directory contains all of the crontabs for the users on the system. Crontab files present a security problem because they are run by the cron daemon, which runs with super user rights. Allowing other users to have read/write permissions on these files may allow them to escalate their privileges. To negate this risk, the directory and all the files that it contains must be secured.

Remediation:

Apply the appropriate permissions to /var/spool/cron/crontabs:

chmod -R o= /var/spool/cron/crontabs
chmod ug=rwx,o= /var/spool/cron/crontabs
chgrp -R cron /var/spool/cron/crontabs

Audit:

Validate the permissions of /var/spool/cron/crontabs:

ls -ld /var/spool/cron/crontabs | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

drwxrwx--- root cron /var/spool/cron/crontabs

Default Value: N/A

2.11.9 Permissions and Ownership – /var/adm/cron/at.allow (Level 1, Scorable)

Description:

The /var/adm/cron/at.allow file contains a list of users who can schedule jobs via the at command.

Rationale:

The /var/adm/cron/at.allow file controls which users can schedule jobs via the at command. Only the root user should have permissions to create, edit, or delete this file.

Remediation:

Apply the appropriate permissions to /var/adm/cron/at.allow:

chown root:sys /var/adm/cron/at.allow
chmod u=r,go= /var/adm/cron/at.allow

Audit:

Validate the permissions of /var/adm/cron/at.allow:

ls -1 /var/adm/cron/at.allow | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

-r---- root sys /var/adm/cron/at.allow

Default Value: N/A

2.11.10 Permissions and Ownership – /var/adm/cron/cron.allow (Level 1, Scorable)

Description:

The /var/adm/cron/cron.allow file contains a list of users who can schedule jobs via the cron command.

Rationale:

The /var/adm/cron/cron.allow file controls which users can schedule jobs via cron. Only the root user should have permissions to create, edit, or delete this file.

Remediation:

Apply the appropriate permissions to /var/adm/cron/cron.allow:

```
chown root:sys /var/adm/cron/cron.allow
chmod u=r,go= /var/adm/cron/cron.allow
```

Audit:

Validate the permissions of /var/adm/cron/cron.allow:

```
ls -1 /var/adm/cron/cron.allow | awk '{print $1 " " $3 " " $4 " " $9}' theone
```

The above command should yield the following output:

```
-r---- root sys /var/adm/cron/cron.allow
```

Default Value: N/A

2.11.11 Permissions and Ownership – /etc/motd (Level 1, Scorable)

Description:

The /etc/motd file contains the message of the day, shown after successful initial login.

Rationale:

The /etc/motd file contains the message of the day, shown after successful initial login. The file should only be editable by its owner.

Remediation:

Apply the appropriate permissions to /etc/motd:

```
chown bin:bin /etc/motd
chmod u=rw,go=r /etc/motd
```

Audit:

Validate the permissions of /etc/motd:

```
ls -l /etc/motd | awk '{print $1 " " $3 " " $4 " " $9}'
```

The above command should yield the following output:

-rw-rr b	oin bin	/etc/motd
----------	---------	-----------

Reversion:

Revert to the previous permissions

Default Value: 644

2.11.12 Permissions and Ownership – /var/adm/ras (Level 1, Scorable)

Description:

The /var/adm/ras directory contains log files which contain sensitive information such as login times and IP addresses.

Rationale:

The log files in the /var/adm/ras directory can contain sensitive information such as login times and IP addresses, which may be altered by an attacker when removing traces of system access. All files in this directory must be secured from unauthorized access and modifications.

Remediation:

Remove world read and write access from all files in /var/adm/ras:

chmod o-rw /var/adm/ras/*

Audit:

Validate the permissions of the files in /var/adm/ras:

ls -l /var/adm/ras | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

NOTE: The output from the command above will contain numerous files. No files should have read or write permission for other

Default Value: N/A

2.11.13 Permissions and Ownership – /var/ct/RMstart.log (Level 1, Scorable)

Description:

The /var/ct/RMstart.log is the logfile used by RMC and can contain sensitive data that must be secured.

Rationale:

RMC provides a single monitoring and management infrastructure for both RSCT peer domains and management domains. Its generalized framework is used by cluster management tools to monitor, query, modify, and control cluster resources, /var/ct/RMstart.log is the logfile used by RMC and can contain sensitive data that must be secured.

Remediation:

Remove world read and write from /var/ct/RMstart.log:

chmod o-rw /var/ct/RMstart.log

Audit:

Validate the permissions of /var/ct/RMstart.log:

ls -l /var/ct/RMstart.log | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

-rw-r---- root system /var/ct/RMstart.log

Default Value: 644

2.11.14 Permissions and Ownership – /var/tmp/dpid2.log (Level 1, Scorable)

Description:

The /var/tmp/dpid2.log is the logfile used by dpid2 daemon, and contains SNMP information.

Rationale:

The /var/tmp/dpid2.log logfile is used by the dpid2 daemon and can contain sensitive SNMP information. This file must be secured from unauthorized access and modifications.

As part of the default implementation of the customized XML file, dpid2 will have been disabled.

Remediation:

Remove world read and write from /var/tmp/dpid2.log:

chmod o-rw /var/tmp/dpid2.log

Audit:

Validate the permissions of /var/tmp/dpid2.log:

ls -l /var/tmp/dpid2.log | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

-rw-r--- root system /var/tmp/dpid2.log

Default Value: 644

2.11.15 Permissions and Ownership – /var/tmp/hostmibd.log (Level 1, Scorable)

Description:

The /var/tmp/hostmibd.log is the logfile used by hostmibd daemon, and contains network and machine related information.

Rationale:

The /var/tmp/hostmibd.log logfile can contain network and machine related statistics logged by the daemon. This file must be secured from unauthorized access and modifications.

As part of the default implementation of the customized XML file, hostmibd will have been disabled.

Remediation:

Remove world read and write from /var/tmp/hostmibd.log:

chmod o-rw /var/tmp/hostmibd.log

Audit:

Validate the permissions of /var/tmp/hostmibd.log:

ls -l /var/tmp/hostmibd.log | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

-rw-r--- root system /var/tmp/hostmibd.log

Default Value: 644

2.11.16 Permissions and Ownership –/var/tmp/snmpd.log (Level 1, Scorable)

Description:

The /var/tmp/snmpd.log is the logfile used by snmpd daemon, and contains network and machine related information.

Rationale:

The /var/tmp/snmpd.log logfile contains sensitive information through which an attacker can find out about the SNMP deployment architecture in your network. This log file must be secured from unauthorized access.

As part of the default implementation of the customized XML file, snmpd will have been disabled.

Remediation:

Remove world read and write from /var/tmp/snmpd.log:

chmod o-rw /var/tmp/snmpd.log

Audit:

Validate the permissions of /var/tmp/snmpd.log:

ls -1 /var/tmp/snmpd.log | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

-rw-r--- root system /var/tmp/snmpd.log

Default Value: 644

2.11.17 Permissions and Ownership –/var/adm/sa (Level 1, Scorable)

Description:

The /var/adm/sa directory holds the performance data produced by the sar utility.

Rationale:

The /var/adm/sa directory contains the report files produced by the sar utility. This directory must be secured from unauthorized access.

Remediation:

Set the recommended ownership and permissions on /var/adm/sa:

chown adm:adm /var/adm/sa chmod u=rwx,go=rx /var/adm/sa

Audit:

Validate the permissions of /var/adm/sa:

ls -ld /var/adm/sa | awk '{print \$1 " " \$3 " " \$4 " " \$9}'

The above command should yield the following output:

rwxr-xr-x adm adm /var/adm/sa

Default Value: N/A

2.11.18 Permissions and Ownership – world/group writable directory in root PATH (Level 1, Scorable)

Description:

To secure the root users executable PATH, all directories must not be group and world writable.

Rationale:

There should not be group or world writable directories in the root user's executable path. This may allow an attacker to gain super user access by forcing an administrator operating as root to execute a Trojan horse program.

Remediation:

Search and report on group or world writable directories in root's PATH. The command must be run as the root user. The script below traverses up each individual directory PATH,

ensuring that all directories are not group/world writable and that they are owned by root or the bin user:

```
su - root -c "echo /:${PATH}" | tr ':' '\n' | while read DIR
do
DIR=${DIR:-$(pwd)}
print "Checking ${DIR}"
while [[ -d ${DIR} ]]
do
[[ "$(ls -ld ${DIR})" = @(d??????w? *) ]] && print " WARNING ${DIR} is world wr
itable" || print " ${DIR} is not world writable"
[[ "$(ls -ld ${DIR}))" = @(d????w???? *) ]] && print " WARNING ${DIR} is group wr
itable" || print " ${DIR} is not group writable"
[[ "$(ls -ld ${DIR}) | awk '{print $3}')" != @(root|bin) ]] && print " WARNING ${DIR} is not owned by root or bin"
DIR=${DIR%/*}
done
done
```

NOTE: Review the output and manually change the directories, if possible. Directories which are group and/or world writable are marked with "WARNING"

To manually change permissions on the directories:

To remove group writable access:

```
chmod g-w <dir name>
```

To remove world writable access:

```
chmod o-w <dir name>
```

To remove both group and world writable access:

```
chmod go-w <dir name>
```

To change the owner of a directory:

```
chown <owner> <dir name>
```

To fully automate the PATH directory permission changes:

```
su - root -c "echo /:${PATH}" | tr ':' '\n' | while read DIR
do
DIR=${DIR:-$(pwd)}
while [[ -d ${DIR} ]]
do
[[ "$(ls -ld ${DIR})" = @(d??????w? *) ]] && chmod o-w ${DIR} && print "Removin"
```

```
g world write from ${DIR}"
[[ "$(ls -ld ${DIR})" = @(d????w???? *) ]] && chmod g-w ${DIR} && print "Removin
g group write from ${DIR}"
DIR=${DIR*/*}
done
done
```

Audit:

Execute the following code:

```
su - root -c "echo /:${PATH}" | tr ':' '\n' | while read DIR
do
DIR=${DIR:-$(pwd)}
while [[ -d ${DIR} ]]
do
[[ "$(ls -ld ${DIR})" = @(d??????w? *) ]] && print " WARNING ${DIR} is world wr
itable"
[[ "$(ls -ld ${DIR})" = @(d????w???? *) ]] && print " WARNING ${DIR} is group wr
itable"
[[ "$(ls -ld ${DIR}) | awk '{print $3}')" != @(root|bin) ]] && print " WARNING ${DIR} is group wr
DIR=${DIR}/*}
done
done
```

The above command should yield no output

Default Value: N/A

2.11.19 Permissions and Ownership – home directory configuration files (Level 1, Scorable)

Description:

The user configuration files in each home directory e.g. \$HOME/.profile, must not be group or world writable.

Rationale:

Group or world-writable user configuration files may enable malicious users to steal or modify other user's data, or to gain elevated privileges.

Remediation:

Search and remediate any user configuration files which have group or world writable access:

```
lsuser -a home ALL |cut -f2 -d= | while read HOMEDIR; do
echo "Examining $HOMEDIR"
if [ -d $HOMEDIR ]; then
ls -a $HOMEDIR | grep -Ev "^.$|^..$" | \
while read FILE; do
if [ -f $FILE ]; then
ls -l $FILE
```

```
chmod go-w $FILE
fi
done
else
echo "No home dir for $HOMEDIR"
fi
done
```

NOTE: The permission change is automatically applied

Audit:

Re-execute the remediation script and all listed files in each user directory, should not have group or world writable permissions.

Default Value: N/A

2.11.20 Permissions and Ownership – home directory permissions (Level 1, Scorable)

Description:

All user home directories must not have group write or world writable access.

Rationale:

Group or world-writable user home directories may enable malicious users to steal or modify data, or to gain other user's system privileges. Disabling read and execute access for users, who are not members of the same group, allows for appropriate use of discretionary access control by each user.

Remediation:

Change any home directories which have group or world writable access:

```
NEW_PERMS=750
lsuser -c ALL | grep -v ^#name | cut -f1 -d: | while read NAME; do
if [ `lsuser -f $NAME | grep id | cut -f2 -d=` -ge 200 ]; then
HOME=`lsuser -a home $NAME | cut -f 2 -d =`
echo "Changing $NAME homedir $HOME"
chmod $NEW_PERMS $HOME
fi
done
```

NOTE: The permission change is automatically applied to all user directories with a user ID over 200.

Modify /usr/lib/security/mkuser.sys to ensure that all new user home directories will be created with a default permission of 750:

```
vi /usr/lib/security/mkuser.sys
```

Replace:

mkdir \$1

With:

```
mkdir $1 && chmod u=rwx,g=rx,g= $1
```

Audit:

Validate the permissions of all of the directories changed:

```
lsuser -c ALL | grep -v ^#name | cut -f1 -d: | while read NAME; do
if [ `lsuser -f $NAME | grep id | cut -f2 -d=` -ge 200 ]; then
HOME=`lsuser -a home $NAME | cut -f 2 -d =`
ls -ld $HOME
fi
done
```

NOTE: All listed directories should have drwxr-x--- permissions

Ensure that the change has been made to /usr/lib/security/mkuser.sys to reflect permissions setting:

```
grep -c 'mkdir $1 && chmod u=rwx,g=rx,g= $1' /usr/lib/security/mkuser.sys
```

NOTE: The output from the command above should be 1

Default Value: N/A

2.12 Miscellaneous Configuration Changes

This section of the benchmark will focus on miscellaneous configuration changes. These are general changes which do not warrant a dedicated section.

2.12.1 Miscellaneous Config – serial port restriction (Level 2, Scorable)

Description:

The recommendation is to disable the login capability of all connected tty devices.

Rationale:

It is recommended that the login capability for all serial ports is disabled, so that unauthorized users cannot attach modems or remote access devices to these ports and bypass any network access control.

If the environment utilizes tty devices to facilitate user connections. This recommendation may be ignored.

Remediation:

Create a list of active tty ports:

lsitab -a |grep "on:/usr/sbin/getty"

If any tty devices are returned from the previous output, lock down each one via:

chitab "tty2:2:off:/usr/sbin/getty /dev/tty2"

NOTE: Replace tty2 with the relevant port

Audit:

Ensure that all tty devices are now disabled:

lsitab -a |grep "on:/usr/sbin/getty"

The above command should yield no output:

Reversion:

Re-enable login for the tty port/s:

chitab "tty2:2:on:/usr/sbin/getty /dev/tty2"

NOTE: Replace tty2 with the relevant port

Default Value: N/A

2.12.2 Miscellaneous Config – disable i4ls (Level 2, Scorable)

Description:

The recommendation is to disable the i41s license manager. This is typically used for C and Cobol license management.

Rationale:

It is recommended that the i4ls license manager is disabled. The license manager is needed for C and Cobol compilers etc. If the environment supports NCS and a license server is required, a node locked license server should be used instead.

Remediation:

Identify if i41s is enabled:

lsitab i4ls

If the command above yields output, remove via:

rmitab i4ls

Audit:

Ensure that i41s is now disabled:

lsitab i4ls

The above command should yield no output.

Reversion:

Re-add the i41s startup line to /etc/inittab:

mkitab "i4ls:2:wait:/etc/i4ls.rc > /dev/null 2>&1 # Start i4ls"

Default Value: N/A

2.12.3 Miscellaneous Config – disable NCS (Level 2, Scorable)

Description:

The recommendation is to disable Network Computing System (NCS). It provide tools for designing, implementing, and supporting applications requiring distributed data and distributed computing.

Rationale:

NCS is an implementation of the Network Computing Architecture developed to provide tools for designing, implementing, and supporting applications requiring distributed data and distributed computing. It is recommended that NCS is disabled, unless it is required within the environment.

Remediation:

Identify if NCS is enabled:

lsitab -a |grep "/etc/rc.ncs" | cut -f1 -d:

If the command above yields output, remove via:

rmitab rcncs

NOTE: If the output from the lsitab command was not rongs, substitute that above.

Audit:

Ensure that NCS is now disabled:

lsitab rcncs

NOTE: If the output from the lsitab command was not rcncs, substitute that above.

The above command should yield no output.

Reversion:

Re-add the NCS startup line to /etc/inittab:

mkitab "rcncs:2:wait:/etc/rc.ncs > /dev/console 2>&1 #Start NCS"

Default Value: N/A

2.12.4 Miscellaneous Config – disable httpdlite (Level 2, Scorable)

Description:

The recommendation is to disable httpdlite. This is a web server which provides on-line documentation.

Rationale:

httpdlite is the Lite NetQuestion Web server software for online documentation. It is recommended that this software is disabled, unless it is required in the environment.

NOTE: The man command does not need this to work correctly.

Remediation:

Identify if httpdlite is enabled:

lsitab httpdlite

If the command above yields output, remove via:

rmitab httpdlite

Audit:

Ensure that httpdlite is now disabled:

lsitab httpdlite

The above command should yield no output.

Reversion:

Re-add the httpdlite startup line to /etc/inittab:

mkitab "httpdlite:2:once:/usr/IMNSearch/httpdlite/httpdlite -r
/etc/IMNSearch/httpdlite/httpdlite.conf & >/dev/console 2>&1"

Default Value: N/A

2.12.5 Miscellaneous Config – disable pmd (Level 2, Scorable)

Description:

The recommendation is to disable pmd. This is the power management service that turns the machine off if it has been idle for a specific amount of time.

Rationale:

pmd is the power management service that turns the machine off if it has been idle for a specific amount of time. This recommendation is to disable this service.

Remediation:

Identify if pmd is enabled:

lsitab pmd

If the command above yields output, remove via:

rmitab pmd

Audit:

Ensure that pmd is now disabled:

lsitab pmd

The above command should yield no output.

Reversion:

Readd the pmd startup line to /etc/inittab:

mkitab "pmd:2:wait:/usr/bin/pmd > /dev/console 2>&1 # Start PM daemon"

Default Value: N/A

2.12.6 Miscellaneous Config – disable writesrv (Level 2, Scorable)

Description:

The recommendation is to disable writesrv. This allows users to chat using the system write facility on a terminal.

Rationale:

writesrv allows users to chat using the system write facility on a terminal. The recommendation is that this service must be disabled.

Remediation:

Identify if writesrv is enabled:

lsitab writesrv

If the command above yields output, remove via:

rmitab writesrv

Audit:

Ensure that writesry is now disabled:

```
lsitab writesrv
```

The above command should yield no output.

Reversion:

Readd the writesrv startup line to /etc/inittab:

```
mkitab "writesrv:2:wait:/usr/bin/startsrc -swritesrv"
```

Default Value: N/A

2.12.7 Miscellaneous Config – block talk/write (Level 2, Scorable)

Description:

The recommendation is to block talk and write. This allows connected users to chat within terminal sessions.

Rationale:

The recommendation is to block attempts to use the write or talk commands. This improves the security of the tty device.

However, there are two exceptions:

- 1) The super user can write to anyone
- 2) If you are logged in as the same user who has turned the messages off, you can write to the super user

Remediation:

Disable talk and write for ALL shells:

```
echo "mesg n" >> /etc/profile echo "mesg n" >> /etc/csh.login
```

Audit:

Ensure that talk and write have been disabled:

```
grep -c "mesg n" /etc/profile
grep -c "mesg n" /etc/csh.login
```

NOTE: Both commands should return a value of 1

Reversion:

Remove the mesg entries from /etc/profile and /etc/csh.login:

```
vi /etc/profile
```

Default Value: N/A

2.12.8 Miscellaneous Config – enable sar accounting (Level 2, Scorable)

Description:

The recommendation is to enable sar performance accounting. This will provide a normal performance baseline which will help identify unusual performance patterns, created through potential attacks via a password cracking program being executed or through a DoS attack etc.

Rationale:

System accounting gathers periodic baseline system data, such as CPU utilization and disk I/O. Once a normal baseline for the system has been established, unauthorized activities, such as a password cracking being executed and activity outside of normal usage hours may be detected due to departure from the normal system performance baseline. It is recommended that the collection script is run on an hourly basis, every day, to help to detect any anomalies. It is also important to generate and review the system activity report on a daily basis.

There may be 3rd party tools, or in-house written scripts in place which perform a similar function. In this instance this recommendation can be ignored.

Remediation:

Prior to configuring sar reporting, ensure that the bos.acct fileset is installed:

```
lslpp -L bos.acct
```

NOTE: The bos.acct fileset should be listed, along with the currently installed version

If the software is not installed, install from the relevant AIX media pack:

```
/usr/lib/instl/sm_inst installp_cmd -a -Q -d /tmp -f bos.acct -c -N -g -X -G -Y
```

NOTE: If the software is not located in /tmp, reflect the actual location in the command above.

Edit the adm user crontab:

```
vi /var/spool/cron/crontabs/adm
```

NOTE: There are commented out example system activity report lines. Review and tailor to the needs of the environment:

NOTE: Change and uncomment the lines where appropriate. Refer to the sar documentation for further guidance

Create the reporting directory structure and apply the appropriate permissions:

```
mkdir -p /var/adm/sa
chown adm:adm /var/adm/sa
chmod u=rwx,go=rx /var/adm/sa
```

Audit:

Review the adm user crontab:

```
cat /var/spool/cron/crontabs/adm
```

The above command should yield output which reflects the changes made in the remediation section.

Reversion:

Comment out the entries in the adm user crontab:

```
vi /var/spool/cron/crontabs/adm
```

Default Value: N/A

2.12.9 Miscellaneous Config – /etc/ftpusers (Level 2, Scorable)

Description:

The /etc/ftpusers is a configuration file used by ftp daemon. It contains a list of users who are not allowed to access the system via ftp.

Rationale:

The /etc/ftpusers file contains a list of users who are not allowed to access the system via ftp. All users with a UID less than 200 should be added into the file.

As part of the default implementation of the customized XML file the /etc/ftpusers file will have already been created with a root user entry. It also disables the ftp service.

Remediation:

List all users with a UID less than 200 to the /etc/ftpusers file:

```
lsuser -c ALL | grep -v ^#name |grep -v root | cut -f1 -d: | while read NAME; do
if [ `lsuser -f $NAME | grep id | cut -f2 -d=` -lt 200 ] > /dev/null 2>&1; then
```

```
echo "Would add $NAME to /etc/ftpusers" fi done
```

NOTE: Review the list of users

Add all users with a UID of less that 200 to the /etc/ftpusers file:

```
lsuser -c ALL | grep -v ^#name |grep -v root | cut -f1 -d: | while read NAME; do
if [ `lsuser -f $NAME | grep id | cut -f2 -d=` -lt 200 ] > /dev/null 2>&1; then
echo $NAME >> /etc/ftpusers
fi
done
```

Audit:

Review the content /etc/ftpusers, ensure there are no duplicate entries:

```
cat /etc/ftpusers
```

Reversion:

Edit /etc/ftpusers and leave only the root entry:

```
vi /etc/ftpusers
```

Default Value: N/A

2.12.10 Miscellaneous Config - ftp umask (Level 1, Scorable)

Description:

The umask of the ftp service should be set to at least 027 in order to prevent the FTP daemon process from creating world-writable files by default.

Rationale:

The umask of the ftp service should be set to at least 027 in order to prevent the FTP daemon process from creating world-writable files by default. These files could then be transferred over the network which could result in compromise of the critical information.

During the implementation of the default customized aixpert XML file the ftp daemon will have been disabled. However, if ftp is active and required in the environment, the recommendations in this section should be applied.

Remediation:

Set the default umask of the ftp daemon:

```
[[ $(grep -c "^ftp[[:blank:]]" /etc/inetd.conf) -gt 0 ]] && chsubserver -c -v ftp -p tcp "ftpd -l -u077" && refresh -s inetd || RC=0
```

NOTE: The umask above restricts read/write permissions for both group and other

Audit:

Validate the umask setting:

The above command should yield the following output (only if the ftp daemon is not disabled):

```
/usr/sbin/ftpd ftpd -l -u077
```

Default Value: N/A

2.12.11 Miscellaneous Config – ftp banner (Level 1, Scorable)

Description:

Set an ftp login banner which displays the acceptable usage policy.

Rationale:

The message in banner.msg is displayed for FTP logins. Banners display necessary warnings to users trying to gain unauthorized access to the system and are required for legal purposes. The recommendation is to set the banner as:

"Authorized uses only. All activity will be monitored and reported".

The content may be changed to reflect any corporate AUP.

During the implementation of the default customized aixpert XML file the ftp daemon will have been disabled. However, if ftp is active and required in the environment, the recommendations in this section should be applied.

Remediation:

Ensure that the bos.msg.en US.net.tcp.client fileset installed:

```
lslpp -L "bos.msg.en_US.net.tcp.client"
```

NOTE: If the fileset is not installed, install it from the AIX media or another software repository. The fileset should reflect the language used on the server.

Once installed set the ftp AUP banner:

```
dspcat -g /usr/lib/nls/msg/en_US/ftpd.cat > /tmp/ftpd.tmp
sed "s/\"\%s FTP server (\%s) ready.\"/\"\%s Authorized uses only. All activity
may be monitored and reported\"/" /tmp/ftpd.tmp > /tmp/ftpd.msg
gencat /usr/lib/nls/msg/en_US/ftpd.cat /tmp/ftpd.msg
rm /tmp/ftpd.tmp /tmp/ftpd.msg
```

Audit:

Open a session to the localhost and validate the banner:

```
dspcat -g /usr/lib/nls/msg/en_US/ftpd.cat | grep "^9[[:blank:]]"
```

The above command should yield the following output:

```
9 "%s Authorized uses only. All activity may be monitored and reported"
```

Default Value: N/A

2.12.12 Miscellaneous Config - /etc/motd (Level 1, Scorable)

Description:

Create a /etc/motd file which displays, post initial logon, a statutory warning message.

Rationale:

The creation of a /etc/motd file which contains a statutory warning message could aid in the prosecution of offenders guilty of unauthorized system access. The /etc/motd is displayed after successful logins from the console, SSH and other system access protocols.

Remediation:

Create a /etc/motd file:

```
touch /etc/motd
chmod u=rw,go=r /etc/motd
chown bin:bin /etc/motd
```

Below is a sample banner:

NOTICE TO USERS This computer system is the private property of its owner, whether individual, corporate or government. It is for authorized use only. Users (authorized or unauthorized) have no explicit or implicit expectation of privacy. Any or all uses of this system and all files on this system may be intercepted, monitored, recorded, copied, audited, inspected, and disclosed to your employer, to authorized site, government, and law enforcement personnel, as well as authorized officials of government agencies, both domestic and foreign. By using this system, the user consents to such interception, monitoring, recording, copying, auditing, inspection, and disclosure at the discretion of such personnel or officials. Unauthorized or improper use of this system may result in civil and criminal penalties and administrative or disciplinary action, as appropriate. By continuing to use this system you indicate your awareness of and consent to these terms and conditions of use. LOG OFF IMMEDIATELY if you do not agree to the conditions stated in this warning.

NOTE: Replace "its owner" with the relevant company name

Audit:

Log back into the system via SSH:

ssh localhost

NOTE: The /etc/motd file will now be displayed

Default Value: N/A

2.12.13 Miscellaneous Config – authorized users in at.allow (Level 1, Scorable)

Description:

The /var/adm/cron/at.allow file defines which users on the system are able to schedule jobs via at.

Rationale:

The /var/adm/cron/at.allow file defines which users are able to schedule jobs via at. Review the current at files and add any relevant users to the /var/adm/cron/at.allow file.

As part of the default implementation of the customized XML file the /var/adm/cron/at.allow file will have been created with a root user entry.

Remediation:

Review the current at files:

```
ls -l /var/spool/cron/atjobs cat /var/spool/cron/atjobs/*
```

NOTE: Review the list of at schedules and remove any files which should not be there, or have no content

Add the recommended system users to the at.allow list:

```
echo sys >> /var/adm/cron/at.allow
echo adm >> /var/adm/cron/at.allow
```

Add any other users who require permissions to use the at scheduler:

```
echo <user> >> /var/adm/cron/at.allow
```

NOTE: Where <user> is the username

Audit:

Review the content /var/adm/cron/at.allow, ensure that the content reflects the changes made:

cat /var/adm/cron/at.allow

Default Value: N/A

2.12.14 Miscellaneous Config – authorized users in cron.allow (Level 1, Scorable)

Description:

The /var/adm/cron/cron.allow file defines which users on the system are able to schedule jobs via cron.

Rationale:

The /var/adm/cron/cron.allow file defines which users are able to schedule jobs via cron. Review the current cron files and add any relevant users to the /var/adm/cron/cron.allow file.

As part of the default implementation of the customized XML file the /var/adm/cron/at.allow file will have been created with a root user entry.

Remediation:

Review the current cron files:

```
ls -l /var/spool/cron/crontabs
cat /var/spool/cron/crontabs/*
```

NOTE: Review the list of cron schedules and remove any files which should not be there, or have no content

Add the recommended system users to the cron.allow list:

```
echo sys >> /var/adm/cron/cron.allow
echo adm >> /var/adm/cron/cron.allow
```

Add any other users who require permissions to use the cron scheduler:

```
echo <user> >> /var/adm/cron/cron.allow
```

NOTE: Where <user> is the username

Audit:

Review the content /var/adm/cron/cron.allow, ensure that the content reflects the changes made:

```
cat /var/adm/cron/cron.allow
```

Default Value: N/A

2.12.15 Miscellaneous Config – all unlocked accounts must have a password (Level 1, Scorable)

Description:

All unlocked accounts on the server must have a password.

Rationale:

An account password is a secret code word that must be entered to gain access to the account. If an account exists that has a blank password, multiple users may access the account without authentication and leave a weak audit trail. An attacker may gain unauthorized system access or perform malicious actions, which then cannot be attributed to any specific individual.

Remediation:

Check for empty passwords:

pwdck -n ALL

If the command above yields output, set up a password on the account:

passwd <username>

Audit:

Re-run the command:

pwdck -n ALL

The command should not yield output

Default Value: N/A

2.12.16 Miscellaneous Config – all user id must be unique (Level 1, Scorable)

Description:

All users should have a unique UID. In particular the only user on the system to have a UID of 0 should be the root user.

Rationale:

The only user with a UID of 0 on the system must be the root user. Any account with a UID of 0 has super user privileges on the system and is effectively root. All access to the root account should be via su or sudo to provide an audit trail. All other users must also have a unique UID to ensure that file and directory security is not compromised.

Remediation:

Examine the user IDs of all configured users:

cut -d: -f 3 /etc/passwd |sort -n |uniq -d

If a number, or numbers are returned from the command above, these are UID which are not unique within the /etc/passwd file. Determine the effected username/s:

```
cut -f "1 3" -d : /etc/passwd |grep ":<UID>$"
```

NOTE: Any user names returned should either be deleted or have the UID changed

To remove:

```
rmuser <username>
```

To change the UID:

```
chuser id=<id> <username>
```

Audit:

Re-run the command:

```
cut -d: -f 3 /etc/passwd |sort -n |uniq -d
```

The command above should not yield output

Default Value: N/A

2.12.17 Miscellaneous Config – all group id must be unique (Level 1, Scorable)

Description:

All groups should have a unique GID on the system.

Rationale:

All groups should have an individual and unique GID. If GID numbers are shared this could lead to undesirable file and directory access.

Remediation:

Ensure that all group IDs are unique:

```
cut -d: -f 3 /etc/group |sort -n | uniq -d
```

If a number, or numbers are returned from the command above, these are GID which are not unique within the /etc/group file. Determine the effected group names:

```
cut -f "1 3" -d : /etc/group |grep ":<GID>$"
```

NOTE: Any group names returned should either be deleted or have the UID changed

To remove:

rmgroup <groupname>

To change the UID:

```
chgroup id=<id> <groupname>
```

Audit:

Re-run the command:

```
cut -d: -f 3 /etc/group |sort -n |uniq -d
```

The command above should not yield output

Default Value: N/A

2.12.18 Miscellaneous Config – unnecessary user and group removal (Level 2, Scorable)

Description:

Remove unnecessary administrative user accounts to further enhance security.

Rationale:

Remove unnecessary administrative user accounts and groups, if possible. Generic administrative user accounts are targeted by hackers in an attempt to gain unauthorized access to a server.

Remediation:

Remove the uucp, nuucp, lpd, and printg user accounts and respective groups, if possible:

```
# Remove users
LIST="uucp nuucp lpd printq"
for USERS in $LIST; do
rmuser -p $USERS
rmgroup $USERS
done

# Remove groups
LIST="uucp printq"
for USERS in $LIST; do
rmgroup $USERS
done
```

NOTE:- Other users and groups can be added to the list if required

Audit:

Ensure that the user accounts have been removed:

```
egrep "uucp|nuucp|lpd|printq" /etc/passwd
```

The command should not yield output

Ensure that the groups have been removed:

```
egrep "uucp|printq" /etc/group
```

The command should not yield output

Reversion:

Re-create the user accounts.

Default Value: N/A

2.12.19 Miscellaneous Config - removing current working directory from root's PATH (Level 1, Scorable)

Description:

This change removes any "." or "::" entries from the root PATH. If a "." or "::" is present the current working directory is included in the search path.

Rationale:

Any "." and "::" will be removed from the root PATH. This means that any harmful programs placed in common PATH locations, would never be automatically executed. All directories must be explicitly defined within the PATH variable.

Remediation:

Examine root's PATH to see if it contains any "." or "::" entries:

```
su - root -c "echo ${PATH}" |awk '/((:[ \t]*:)|(:[ \t]*$)|(^[ \t]*:)|(^.:)|(:.$)|(:.:))/'
```

If the command above yields output, remove the "." and "::" entries from the relevant initialization files. The files to examine are dependant on the root users shell definition in <code>/etc/passwd</code>. Once the file or files have been identified remove the "." and "::" from the PATH variable

```
vi <filename>
```

Audit:

```
su - root -c "echo ${PATH}" |awk '/((:[ \t]*:)|(:[ \t]*$)|(^[ \t]*:)|(^.:))|(:.$)|(:.:))/'
```

The above command should yield no output.

Default Value: dot not present

2.12.20 Miscellaneous Config – removing current working directory from default /etc/environment PATH (Level 1, Scorable)

Description:

This change removes any "." or "::" entries from /etc/environment. If a "." or "::" is present the current working directory is included in the default search path.

Rationale:

Any "." and "::" will be removed from /etc/environment. This means that any harmful programs placed in common PATH locations, would never be automatically executed. All directories must be explicitly defined within the PATH variable.

Remediation:

Examine PATH in /etc/environment to see if it contains any "." or "::" entries:

```
grep "^PATH=" /etc/environment |awk '/((:[ \t]*:)|(:[ \t]*$)|(^[
\t]*:)|(^.:)|(:.$)|(:.:))/'
```

If the command above yields output, remove the "." and "::" entries from /etc/environment

```
vi /etc/environment
```

Audit:

```
grep "^PATH=" /etc/environment |awk '/((:[ \t]*:)|(:[ \t]*$)|(^[
\t]*:)|(^.:)|(:.$)|(:.:))/'
```

The above command should yield no output.

2.13 Privileged Command Management

One of the primary causes of system outages is inadvertent or accidental command usage when a user has root privileges. Many users seemingly forget that they are logged in as root, or use inappropriate command arguments. The carte blanche use of the root account should be limited to those individuals who administer the operating system. Users such as database administrators, application support teams and troubleshooters can be given privileged access to the commands they need via tools such as sudo or enhanced RBAC. These tools require careful planning and implementation, but ultimately can eradicate the need for the root password.

This section of the benchmark will detail the recommended methods of managing privileged command access.

2.13.1 PCM - sudo (Level 2, Scorable)

Description:

The recommendation is to install and configure sudo, to reflect the privileged command access requirements of all users of the system.

Rationale:

Privileged command access should be limited to and defined by a user's individual needs. Access to a root command prompt should limited, wherever possible, to minimize the risk of inadvertent or deliberate misuse of the account.

If the system is AIX 5.3 based, enhanced RBAC is not an available option. If the system is AIX 6.1 based, the choice between sudo and enhanced RBAC revolves around whether or not the environment is heterogeneous in nature, running different flavors of UNIX, or perhaps different versions of AIX. It may be that sudo is the standard tool of choice for managing privileged command access across an entire UNIX estate. However, if the environment is AIX 6.1 only, it is recommended that enhanced RBAC is used as the tool of choice. Some implementations however may benefit from a combined approach, utilizing both sudo and enhanced RBAC.

The sudo software is packaged as an RPM by IBM and is available on the AIX Toolbox for LINUX media, or via download from the following location:

http://www-03.ibm.com/systems/power/software/aix/linux/toolbox/download.html

Remediation:

Place the sudo software into a convenient location, such as /tmp and install via:

```
/usr/lib/instl/sm inst installp cmd -a -Q -d /tmp -f sudo -c -N -g -X -G -Y
```

NOTE: If the software is not located in /tmp, reflect the actual location in the command above.

Once installed refer to the sudo man page for information regarding the creation of a custom <code>/etc/sudoers</code> file. It is recommended that, to reduce rule complexity, privileges are assigned at a group level wherever possible:

http://www.gratisoft.us/sudo/man/sudo.html

NOTE: The configuration of sudo is completely dependant on the unique requirements of a given environment.

All editing of the /etc/sudoers file must be performed by the following command:

visudo

Once the /etc/sudoers file has been successfully created, validate the syntax of the file:

visudo -c

Audit:

Validate the sudo installation:

rpm -q sudo

The above command should yield the following output:

sudo-1.6.9p15-2noldap

NOTE: The version reflected above may differ from the one installed.

Reversion:

De-install the sudo software:

rpm -e sudo

Default Value: Not Installed

2.13.2 PCM – enhanced RBAC (AIX 6.1 only) (Level 2, Not Scorable)

Description:

The recommendation is to configure RBAC to reflect the privileged command access requirements for all users of the system. RBAC is a default component of AIX 6.1.

Rationale:

Privileged command access should be limited to and defined by a user's individual needs. Access to a root command prompt should limited, wherever possible, to minimize the risk of inadvertent or deliberate misuse of the account.

If the system is AIX 6.1 based, the choice between sudo and enhanced RBAC revolves around whether or not the environment is heterogeneous in nature, running different flavors of UNIX, or perhaps different versions of AIX. It may be that sudo is the standard tool of choice for managing privileged command access across an entire UNIX estate. However, if the environment is AIX 6.1 only, it is recommended that enhanced RBAC is used as the tool of choice. Some implementations however may benefit from a combined approach, utilizing both sudo and enhanced RBAC.

Remediation:

Enhanced RBAC improves on its legacy implementation by allowing greater flexibility around command lists and authorization definitions, which can be customized. The definitions are also saved to a kernel table rather than in flat files, which improves security.

The implementation of RBAC is role based, allowing users to be specifically granted access to the privileged commands they need to perform their day to day tasks. The tool can be used to replace sudo in many instances, or indeed to work alongside it.

A successful implementation may also allow the root account to be deprecated.

The RBAC definition files:

/etc/security/privcmds
/etc/security/privfiles
/etc/security/privdevs

The command used to list the active RBAC definitions, i.e. those loaded into the kernel:

lskst

The command used to update RBAC definitions in the kernel table:

setkst

Further details regarding planning and implementation of RBAC can be found within the IBM AIX 6.1 Infocentre:

http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic=/com.ibm.aix.security/doc/security/rbac.htm

NOTE: The configuration of enhanced RBAC is completely dependant on the unique requirements of a given environment.

Audit:

N/A

Default Value: N/A

2.14 Encrypted Filesystems (EFS) (AIX 6.1 only)

Another enhancement of AIX 6.1 is the introduction of Encrypted Filesystems. This enables an individual user, via keystore files, to encrypt their own data within a jfs2 filesystem. After creating EFS enabled filesystems, individual files can be encrypted or inheritance can be set at the filesystem or directory level. The standard AIX data and user management commands have been modified to work with encryption.

There are a number of reasons for encrypting data in this manner, perhaps to send backups of data off site, or to encrypt sensitive or confidential information such as payroll details.

2.14.1 EFS - implementation (AIX 6.1 only) (Level 2, Scorable)

Description:

The recommendation, if there is a requirement for file based encryption, is to utilize EFS.

Rationale:

The use of EFS further enhances the file and directory security within AIX. If there are sensitive or confidential files, encryption provides that extra level of security in the event of an accidental chmod which may allow read or write access to other users.

The encryption operates at the filesystem level and each file is encrypted with a separate key. From a user perspective the encryption is transparent as the key can be automatically loaded during login.

Remediation:

There are two pre-requisite requirements for EFS, it requires RBAC and the installation of the CLiC cryptographic fileset. The fileset is located on the expansion pack, shipped with the AIX media.

Place the CLiC software into a convenient location, such as /tmp and install via:

```
/usr/lib/instl/sm_inst installp_cmd -a -Q -d /tmp -f clic.rte -c -N -g -X -G -Y
```

NOTE: If the software is not located in /tmp, reflect the actual location in the command above.

Load the CLiC kernel extension:

```
/usr/lib/methods/loadkclic
```

As the EFS administrator, create the initial keystore. This is typically the root user:

```
efsenable -a
```

An EFS enabled filesystem can be created with the following command:

```
chfs -v jfs2 -q <vq name> -m </filesystem> -a size=<size> -a efs=yes
```

To enable EFS for an existing filesystem:

```
chfs -a efs=yes </filesystem>
```

To encrypt a file, load your keystore via:

```
efskeymgr -o ksh
```

Then encrypt via:

```
efsmgr -c AES 192 ECB -e <filename>
```

To decrypt:

```
efsmgr -d <filename>
```

Further details regarding planning and implementation of EFS can be found within the IBM AIX 6.1 Infocentre:

http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic=/com.ibm.aix.security/doc/security/efs efs.htm

NOTE: The configuration of EFS is completely dependant on the unique requirements of a given environment.

Audit:

Validate the installation of the CLiC software:

```
lslpp -L |grep "clic"
```

The above command should yield the following output:

clic.rte.includes	4.3.0.0	С	F	_	toLite for C Library lude File
clic.rte.kernext	4.3.0.0		С	F	CrytpLite for C Kernel
clic.rte.lib	4.3.0.0		С	F	CyrptoLite for C Library
clic.rte.pkcs11	4.3.0.0		С	F	PKCS11 Software Token
Support					

NOTE: The version numbers may differ based on the source of the software

Validate that the CLiC kernel extension has loaded:

```
genkex |grep crypt
```

The above command should yield the following output:

```
438b000 39000 /usr/lib/drivers/crypto/clickext
```

Reversion:

De-install the CLiC fileset:

```
installp -u clic.rte
```

Decrypt all files:

```
efsmgr -d <filename>
```

Default Value: N/A

2.15 Trusted Execution (TE) (AIX 6.1 only)

This is a further development of the Trusted Computing Base (TCB) packaged with previous versions of AIX. Unlike TCB, Trusted Execution is not an install time only option and it can be enabled on previously installed systems. Its primary purpose is to protect from Trojan horse style attacks, by only allowing the execution of certain executables and kernel extensions.

TE has two modes of operation, online and offline. The online mode provides the most comprehensive security, as a check is made every time a file is loaded into memory. If the integrity checks fail, the file will not be loaded into memory. The offline mode checks file integrity at a specified time, via either the command line or via crontab.

2.15.1 TE - implementation (AIX 6.1 only) (Level 2, Scorable)

Description:

The recommendation is to implement TE to protect the system from Trojan horse style attacks. TE provides a robust system integrity checking process.

Rationale:

One of the common ways a hacker infiltrates a system is through file tampering or the use of a Trojan horse. The implementation of TE can provide a number of integrity checks prior to loading a program into memory, any deviations can also be highlighted when programs and files are validated offline. This ensures that the programs executed are those which are intended to be and not malicious code masquerading as a true program.

When a discrepancy is identified it is classified as either minor or major. A minor discrepancy is automatically reset to the value defined in the TSD. In the event of a major discrepancy the file access permissions are changed to make the file inaccessible.

There is a pre-requisite requirement to install CLiC and SSL software.

Remediation:

It is recommended that TE is configured in online mode. This provides real time protection against Trojan horse attacks.

The tsd.dat file contains the important security attributes relating to all of the managed files:

```
cat /etc/security/tsd/tsd.dat
```

NOTE: The trustchk command is used to manage the entries in this file.

To enable TE, firstly enable online checking of executables and shell scripts:

```
trustchk -p CHKEXEC=ON
trustchk -p CHKSCRIPT=ON
```

Stop the execution or loading of binaries and files into memory when the integrity checks fail:

trustchk -p STOP ON CHKFAIL=ON

Enable online TE based on the policy selections above:

trustchk -p TE=ON

To set a Trusted Execution Path or TEP:

trustchk -p TEP=<PATH variable>

Enable the TEP:

trustchk -p TEP=ON

NOTE: Commands will not be executed if they reside outside of the TEP.

Further details regarding planning and implementation of TE can be found within the IBM AIX 6.1 Infocentre:

http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic=/com.ibm.aix.security/doc/security/bos trusted execution.htm&tocNode=toc:front/front.cmb/0/0/11/0/0/1/

NOTE: The configuration of TE is dependant on the unique requirements of a given environment.

Audit:

Ensure that TE is enabled:

trustchk -p TE

The above command should yield the following output:

TE=ON

Ensure that TEP is enabled:

trustchk -p TEP

The above command should yield the following output:

TEP=ON

Reversion:

Disable TE:

trustchk -p TE=off

Disable TEP:

trustchk -p TEP=off

Default Value: Not enabled

2.16 General Permissions Management

2.16.1 General Permissions Management - suid and sgid files and programs (Level 2, Scorable)

Description:

The system is audited for both suid and sgid files and programs.

Rationale:

An audit should be performed on the system to search for the presence of both suid and sgid files and programs. In order to prevent these files from being potentially exploited the suid and sgid permissions should be removed wherever possible.

Remediation:

Review the currently mounted filesystems:

mount

Un-mount all non-local filesystems and cdrom media:

```
unmount <mount point>
```

If there are non-local filesystems which cannot be un-mounted, use the following to find all suid and sgid files on local JFS/JFS2 filesystems only:

```
find / \( -fstype jfs -o -fstype jfs2 \) \( -perm -04000 -o -perm -02000 \) -type f -ls
```

If all non-local filesystems have been un-mounted:

```
find / \( -perm -04000 -o -perm -02000 \) -type f -ls
```

Review the files and where possible, use the chmod command to remove the appropriate suid or sgid bits:

```
chmod u-s <file>
chmod g-s <file>
```

Audit:

Re-execute the appropriate find command and review the output. This should reflect the changes made in the remediation section.

If there are non-local filesystems which cannot be un-mounted, use the following to find all suid and sgid files on local JFS/JFS2 filesystems only:

```
find / \( -fstype jfs -o -fstype jfs2 \) \( -perm -04000 -o -perm -02000 \) -type f -ls
```

If all non-local filesystems are un-mounted:

```
find / \( -perm -04000 -o -perm -02000 \) -type f -ls
```

Reversion:

Use the chmod command to re-instate the suid and sgid bits to the relevant files:

```
chmod u+s <file>
chmod g+s <file>
```

Default Value: N/A

2.16.2 General Permissions Management - un-owned files and directories (Level 2, Scorable)

Description:

The system is audited for un-owned files and directories.

Rationale:

An audit should be performed on the system to search for the presence of un-owned files and directories. All files and directories should have a valid owner and group.

Remediation:

Review the currently mounted filesystems:

```
mount
```

Un-mount all non-local filesystems and cdrom media:

```
unmount <mount point>
```

If there are non-local filesystems which cannot be un-mounted, use the following to find all unowned files and directories on local JFS/JFS2 filesystems only:

```
find / \( -fstype jfs -o -fstype jfs2 \) \( -type d -o -type f \) \( -nouser -o -nogroup \) -ls
```

If all non-local filesystems have been un-mounted:

```
find / \( -type d -o -type f \) \( -nouser -o -nogroup \) -ls
```

NOTE: An un-owned file or directory is referred to via the GID or UID as it cannot be translated to a user or group name in /etc/group or /etc/passwd. This is typically caused by removing users or groups from the system.

Remediate the un-owned file and directory list:

```
chown <owner> <file>
chgrp <group> <file>
```

Audit:

Re-execute the appropriate find command.

If there are non-local filesystems which cannot be un-mounted, use the following to find all unowned files and directories on local JFS/JFS2 filesystems only:

```
find / \( -fstype jfs -o -fstype jfs2 \) \( -type d -o -type f \) \( -nouser -o -nogroup \) -ls
```

If all non-local filesystems have been un-mounted:

```
find / \( -type d -o -type f \) \( -nouser -o -nogroup \) -ls
```

The find command should yield not yield output

Reversion: N/A

Default Value: N/A

2.16.3 General Permissions Management - world writable files and directories (Level 2, Scorable)

Description:

The system is audited for world writable files and directories.

Rationale:

An audit should be performed on the system to search for the presence of world writable files and directories. Files and directories should only be world writable when absolutely necessary.

Remediation:

Review the currently mounted filesystems:

mount

Un-mount all non-local filesystems and cdrom media:

unmount <mount point>

If there are non-local filesystems which cannot be un-mounted, use the following to find all world writable files and directories on local JFS/JFS2 filesystems only:

find / \(-fstype jfs -o -fstype jfs2 \) \(-type d -o -type f \) -perm -o+w -ls

If all non-local filesystems have been un-mounted:

find / \(-type d -o -type f \) -perm -o+w -ls

Review the world writable files and directories and where possible, if the application configuration allows, remove access via:

chmod o-w <dir or file>

If a directory must retain world writable access, ensure that sticky bit is set so that users can only remove the files they create:

chmod o+t <dir>

NOTE: This will retain world writable permissions, but add a sticky bit to the directory.

Audit:

Re-execute the appropriate find command.

If there are non-local filesystems which cannot be un-mounted, use the following to find all world writable files and directories on local JFS/JFS2 filesystems only:

find / \(-fstype jfs -o -fstype jfs2 \) \(-type d -o -type f \) -perm -o+w -ls

If all non-local filesystems have been un-mounted:

find / \(-type d -o -type f \) -perm -o+w -ls

NOTE: Review the output based on the performed remediation

Reversion:

To reinstate world writable permission:

chmod o+w <dir or file>

Default Value: N/A

3. Final Steps

3.1 System Reboot and Backup

Once all of the customization has been successfully performed, reboot the server to initialize all of the new security settings:

shutdown -Fr 0

When the system has been successfully rebooted, create a mksysb system backup to reflect the new server configuration:

If writing to tape:

mksysb -i /dev/rmt<x>

If writing to a file:

mksysb -i /<pathname to file>

NOTE: The mksysb can subsequently be used as a source to install new systems, which ensures compliance to this benchmark. If this is intended, it is recommended that a bosinst_data resource is created within NIM and that the following parameter is defined:

RECOVER DEVICES = no

NOTE: This ensures that no device information stored in the current systems ODM will be recovered on a target system during installation.

Appendix A: References

Resource (date webpage)	Location
IBM AIX Operating System Service Strategy Details and Best Practices Dec 2008 (As of Dec 28th 2008)	http://www14.software.ibm.com/webapp/set2/sas/f/best/home. html
AIX Security Expert Password Policy (AIX 5.3 and AIX 6.1 Infocenter Jan 2009)	AIX 5.3: http://publib.boulder.ibm.com/infocenter/pseries/v5r3/index.jsp?topic=/com.ibm.aix.security/doc/security/aix sec expert pwd policy settings.htm
	AIX 6.1: http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic =/com.ibm.aix.security/doc/security/aix sec expert pwd policy se ttings.htm
AIX Security Expert Login Policy (AIX 5.3 and AIX 6.1 Infocenter Jan 2009)	AIX 5.3: http://publib.boulder.ibm.com/infocenter/pseries/v5r3/index.jsp? topic=/com.ibm.aix.security/doc/security/aix sec expert login poli cy settings.htm
	AIX 6.1: http://publib.boulder.ibm.com/infocenter/systems/topic/com.ibm.aix.security/doc/security/aix sec expert login policy settings.htm?tocNode=toc:front/front.cmb/0/0/11/2/10/
AIX Security Expert /etc/inittab Settings (AIX 5.3 and AIX 6.1 Infocenter Jan 2009)	AIX 5.3: http://publib.boulder.ibm.com/infocenter/pseries/v5r3/index.jsp?topic=/com.ibm.aix.security/doc/security/aix sec expert etcinittab_entries.htm
	AIX 6.1: http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic =/com.ibm.aix.security/doc/security/aix sec expert etcinittab entr ies.htm&tocNode=toc:front/front.cmb/0/0/11/2/12/
AIX Security Expert /etc/rc.tcpip Settings (AIX 5.3 and	AIX 5.3: http://publib.boulder.ibm.com/infocenter/pseries/v5r3/index.jsp? topic=/com.ibm.aix.security/doc/security/aix sec expert etcrctcpi

AIX 6.1 Infocenter Jan 2009)	<u>p services settings.htm</u>
	AIX 6.1:
	http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic
	=/com.ibm.aix.security/doc/security/aix sec expert etcrctcpip ser
	vices settings.htm&tocNode=toc:front/front.cmb/0/0/11/2/13/
AIX Security Expert	AIX 5.3:
/etc/inetd.conf	http://publib.boulder.ibm.com/infocenter/pseries/v5r3/index.jsp?
Setting (AIX 5.3 and	topic=/com.ibm.aix.security/doc/security/aix sec expert etcinetdc
AIX 6.1 Infocenter Feb 09)	onf settings.htm
	AIX 6.1:
	http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic
	=/com.ibm.aix.security/doc/security/aix sec expert etcinetdconf s
	ettings.htm&tocNode=toc:front/front.cmb/0/0/11/2/14/
AIX Security Expert	AIX 5.3:
Disabling Remote	http://publib.boulder.ibm.com/infocenter/pseries/v5r3/index.jsp?
Services (AIX 5.3 and	topic=/com.ibm.aix.security/doc/security/aix sec expert remov u
AIX 6.1 Infocenter Feb 09)	nnec services.htm
1600)	AIX 6.1:
	http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic
	=/com.ibm.aix.security/doc/security/aix sec expert remov unnec
	services.htm&tocNode=toc:front/front.cmb/0/0/11/2/16/
AIX Security Expert	AIX 5.3:
Automated	http://publib.boulder.ibm.com/infocenter/pseries/v5r3/index.jsp?
Authentication (AIX	topic=/com.ibm.aix.security/doc/security/aix sec expert removal
5.3 and AIX 6.1 Infocenter Feb 09)	nonauth access.htm
infocenter rep 09)	AIX 6.1:
	http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic
	=/com.ibm.aix.security/doc/security/aix sec expert removal nona
	uth access.htm&tocNode=toc:front/front.cmb/0/0/11/2/17/
AIX Security Expert	AIX 5.3:
TCP/IP Hardening	http://publib.boulder.ibm.com/infocenter/pseries/v5r3/index.jsp?
(AIX 5.3 and AIX 6.1	topic=/com.ibm.aix.security/doc/security/aix sec expert tuning n
Infocenter Mar 09)	etwork opts.htm
	AIX 6.1:
	http://publib.boulder.ibm.com/infocenter/systems/index.jsp?topic
	=/com.ibm.aix.security/doc/security/aix sec expert tuning networ
	k opts.htm&tocNode=toc:front/front.cmb/0/0/11/2/18/

AIX Security Expert Misc Changes (AIX 5.3 and AIX 6.1 Infocentre Mar 09)	AIX 5.3: http://publib.boulder.ibm.com/infocenter/pseries/v5r3/index.jsp? topic=/com.ibm.aix.security/doc/security/aix sec expert misc.htm AIX 6.1:

Appendix B: Change History

Date	Version	Changes for this version
December 21st, 2010	1.0.0	Initial Release
September 28th, 2012	1.1.0	 Added 2.7.3 SNMP Community String - <u>Ticket #2</u>
		• 2.13.2 set not Not Scored - <u>Ticket #4</u>
		• 2.2.12 updated to allow world read on ssh_config - <u>Ticket #9</u>
		 1.1.6 Updated rationale statement - <u>Ticket #11</u>
		• 1.7.1 Updated audit procedure - <u>Ticket #15</u>
		• 2.16.1 Updated audit procedure - <u>Ticket #16</u>
		• 2.12.11 Updated audit procedure - <u>Ticket #12</u>
		• 2.12.10 Updated audit/remediation procedures - <u>Ticket #13</u>
		• 2.10.2 Scoped to UDP and TCP services - <u>Ticket #14</u>
		• 2.11.18 Updated audit procedure - <u>Ticket #18</u>
		• 1.1.3 Updated requirement to be >0 && <= 13 - <u>Ticket #20</u>