EVNDISP Manual IACT event analysis and display v4.00

Gernot Maier (DESY)

.

SVN Rev:660

SVN Date: 2012 - 03 - 2112: 31: 20 + 0100(Wed, 21Mar 2012)

 ${\bf SVN}\ Author: maierg$

Contents

1	Doc	Documentation 1					
2	Intr	roduction	3				
3	Inst	tallation and auxiliary data files	4				
	3.1	Auxiliary data files	4				
		3.1.1 Detector description	4				
		3.1.2 Analysis parameters files	4				
4	evei	ntdisplay - calibration, image analysis and stereo reconstruction	5				
	4.1	Trace integration	5				
	4.2	Calibration	5				
		4.2.1 Low gain calibration	5				
	4.3	Image analysis	6				
		4.3.1 Log-likelihood fitting of images	6				
	4.4	Image cleaning	6				
5	$\mathbf{Dis}_{\mathbf{I}}$	playing events	7				
6	msc	cw_energy - using lookup tables	8				
	6.1	Energy reconstruction	8				
7	Gar	mma/hadron separation	9				
	7.1	Cut parameters	9				
8	mak	keEffectiveArea - instrument response functions	11				
9	CT	A analysis	13				
	9.1	General concept	13				
	9.2	Analysis steps for CTA IRF and sensitivity calculation	13				
		9.2.1 Step 1: Converter	13				
		9.2.2 Step 2: Display (event-by-event)	14				
		9.2.3 Step 3, Eventdisplay: Calibration, image analysis and stereo recon-					
		struction	15				
		9.2.4 Step 1 & 3 combined [USE]	15				
		9.2.5 Step 4: mscw_energy	15				
		0.2.6 Stop 5: Optimize cuts or train MVA	15				

ii CONTENTS

	9.2.7	Step 6: Effective Areas		 				. 16	j
	9.2.8	Step 7: Sensitivity curves & WP-Phys files $$.		 				. 17	,
10 Iı	nput data	a format						18	j
10	0.1 VBF -	- VERITAS Bank Format		 				. 18	,
10	0.2 DST -	- data summary tree		 				. 18	,
	10.2.1	Limitations		 	•			. 18	,
11 D	etector S	Setup						19)
1	1.1 Telesco	cope types		 				. 19)
12 T	ools for	VERITAS analysis						20)
1:	2.1 Expos	sure maps and run lists for any point in the sky		 				. 20)
1:	2.2 Radios	sonde Atmospheric Data		 	•			. 21	
13 L	ight curv	ve analysis						23	į
13	3.1 Code o	organization		 				. 23)
13	3.2 Light	curve plotting		 				. 23	j
13	3.3 Lomb	Scargle analysis		 				. 24	č
1:	3.4 ZDCF	Autocorrelation analysis		 				. 25	,

Documentation

EVNDISP is work-in-progress and the documentation is not in the state it is supposed to be. Apart from the information in this manual, other sources for help are:

README files

INSTALL: information on installation the analysis package, dependencies, environmental variables

README.CTA: short description of a typical CTA analysis

README.VTS: description of a typical VERITAS analysis

AUTHORS: author description

Description and command line options for the different software parts:

README.EVNDISP:

README.MSCW_ENERGY:

README.ANASUM:

README.EFFECTIVEAREA:

README.ANALYSISLIBRARY:

README.SCRIPTS:

README.MACROS:

WIKI pages

The EVNDISP manual for VERITAS users:

http://veritas.sao.arizona.edu/wiki/index.php/Eventdisplay_Manual

Introduction

eventdisplay is a complete package for VERITAS and CTA analysis (whatever 'complete' means...) The package consists of several analysis steps and tools:

- 1. evndisp (calibrate and parametrize images, event reconstruction, stereo analysis)
- 2. mscw_energy (use lookup tables to produce msw, msl, and energies)
- 3. anasum (produce maps and calculate analysis results)
- 4. shared library tools and macros (produce the energy spectrum and integral fluxes, plot maps, plot sensitivities, etc.)
- 5. makeEffectiveArea (calculate effective areas)
- 6. trainTMVAforGammaHadronSeparation (tools to train MVA and optimize cuts)
- 7. ...

This is a very incomplete manual, started in September 2011. Please help updating it. The original developers are Gernot Maier (DESY) and Jamie Holder (University of Delaware). A large number of people contributed, among others: ..

Installation and auxiliary data files

The installation, compilation, and needed or useful environmental variables are described in detail in the file README/INSTALL in the EVNDISP source code.

3.1 Auxiliary data files

The auxiliary data files contain information needed for the analysis. This might be files describing the detector geometry, lookup tables, effective areas file, etc. We assume in the following that these files are located in the directory $OBS_EVNDISP_ANA_DIR$ where OBS is your observatory (i.e. VERITAS or CTA).

3.1.1 Detector description

VERITAS

The detector description is read from a configuration file in GrIsu style. There are examples for the different detector configurations (e.g. pre or post-upgrade) in the tar ball with all the analysis files. Check the files in $$OBS_EVNDISP_ANA_DIR/*.efg$.

CTA

No detector description is needed, since the telescope and array description is read directly from the DST file (telescoping tree). The converter from hessio to EVNDISP DST format needs a subarray file, a simple list of telescopes to be selected from the corresponding hyper array. The subarray files for prod1 can be found in \$OBS_EVNDISP_ANA_DIR/DetectorGeometry/*.lis.

3.1.2 Analysis parameters files

Detailed description of these files can be found in the corresponding chapters of the different analysis stages.

eventdisplay - calibration, image analysis and stereo reconstruction

4.1 Trace integration

4.2 Calibration

4.2.1 Low gain calibration

VERITAS only

For the calibration of the low-gain chain two values are important: the low-gain pedestal and the ratio between low and high-gain channel (usually between 5 and 6).

Low-gain pedestal calibration

Pedestal values of the low-gain chain are not sensitive to changes in the NSB as the high-gain chain. Therefore new calibration is only necessary after changes in the electronics, e.g. the after swapping a FADC board. For a list of good low-gain calibration runs and the valid time ranges look the VERITAS wiki page *Low gain calibration*. There is a list of documents linked to this page, valuable for background information.

Low-gain calibration runs are taken by raising the HV in part of the cameras - therefore a pair of flasher runs is needed for the calibration (exception is the first run, 36862). The calculation of the low-gain pedestal values consists of two steps: i) the calculation of the pedestal values and ii) merging these files into single pedestal files.

Step 1 (script is in \$EVNDISPSYS/scripts/VTS)

Results are written into the calibration directory in $VERITAS_EVNDISP_ANA_DIR$, files with suffixes .lped and .lped.root.

Step 2: merge files into a single low-gain pedestal file Use the EVNDISP shared library and the class *VPedestalCombineLowGainFiles*:

```
root [0] .L $EVNDISPSYS/lib/libVAnaSum.so
root [1] VPedestalCombineLowGainFiles a;
root [2] a.combineLowGainPedestalFileForAllTelescopes( unsigned int iNTel, \\
string iCalibrationDirectory, \\
string iRun1, string iRun2, string iOutRun);
```

The list of run numbers and the corresponding valid ranges are listen in the file *calibrationlist.LowGain.dat* in the calibration direction in \$VERITAS_EVNDISP_ANA_DIR:

```
LOWGAINPED <TELESCOPE> <RUNSTART> <RUNSTOP> <LOW GAIN PEDESTAL RUN NUMBER> (all comparisons are >= and <=)

RUNS 55975 and 55978 (128 samples)

* LOWGAINPED -1 46642 60000 5597578
....
```

Low-gain multiplicator

4.3 Image analysis

4.3.1 Log-likelihood fitting of images

The status of the covariance matrix is returned and saved to the image parameter tree tpars in the variable Fitstat. No fitting has been applied to images with Fitstat = -1

4.4 Image cleaning

Displaying events

eventdisplay can be used to display events. Camera images of integrated charges, timing and calibration values, image cleaning and parameterization, core and direction reconstruction results can be displayed. There are example scripts for display files, see

- for CTA: \$EVNDISP/scripts/CTA/CTA.EVNDISP.display
- for VERITAS: \$EVNDISP/scripts/VTS.EVNDISP.display

Note that the display can be a bit slow for arrays with a large number of telescopes.

mscw_energy - using lookup tables

6.1 Energy reconstruction

Gamma/hadron separation

7.1 Cut parameters

Option	Number of parameters	Allowed value(s)	Default value(s)	Description
cutselection	2			type of gamma/hadron and direction cut
	Parameter #1	?	0	gamma/hadron cut id
	Parameter #2	0-5	0	direction cut id: fixed Θ^2 cut (0, needs parameter theta2cut), energy dependent Θ^2 from a function read from a IRF file (1, needs parameter theta2file), from a IRF graph (2, needs parameter theta2file and option IRF), all other values: experimental (3-5,
angres	1]0,100]	0	TMVA) containment probability for energy dependent Θ^2 cut (in %)

Table 7.1: Parameter definition and range for gamma/hadron cut files. This is used for example in the effective area calculation or for data analysis.

Table 7.2: Gamma/hadron cut selector values. They consist of two digits: ID1+ID2*10

gamma/hadron cut	Description
selector	
ID2	
0	apply gamma/hadron cuts on parameters in given data tree
1	apply gamma/hadron cuts on probabilities given by a friend to the
	data tree (e.g. random forest analysis)
2	same as 2
3	apply cuts on probabilities given by a friend to the data tree already
	at the level of the event quality level (e.g. of use for analysis of certain
	binary phases only)
4	TMVA gamma/hadron separation
ID1	
0	apply cuts on MSCW/MSCL (mean reduced scaled width/length)
1	apply cuts on mean width/length (no lookup tables necessary)
2	no cut applied (always passed)
3	apply cuts on MWR/MLR (mean scaled width/length)
Example:	
0	apply MSCW/MSCL cuts (default)
22	apply event probability cuts
10	apply cuts from a tree AND apply MSCW/MSCL cuts
40	use TMVA AND apply MSCW/MSCL cuts

makeEffectiveArea - instrument response functions

Instrument response functions (IRF), i.e. effective areas and angular, core and energy resolution and bias curve can be calculated using makeEffectiveArea.

Option	Number of parameters	Allowed value(s)	Default value(s)	Description
FILLINGMODE	1	0,1,2,3	0	filling of IRFs: fill all IRFs (0), resolution plots only (1), angu- lar resolution plot only (2), effective areas only (3)
ENERGYRECONSTRUCTIONMETHOD	1	0,1	0	energy reconstruction method (see 6.1)
ENERGYAXISBINS	1	> 0	60	number of bins on \log_{10} energy axis
ENERGYRECONSTRUCTIONQUALITY	1	0,1	0	
AZIMUTHBINS	1	0,1	1	define azimuth bins and calculate IRFs in each azimuth bin. Bins are hardwired with a bin width of 22.5° (16 bins), bin 17 contains the full azimuth range
ISOTROPICARRIVALDIRECTIONS	1	0,1	0	input MC are simulated with random direction (wobble) offsets (use for gamma rays only)
TELESCOPETYPECUTS	1	0,1	0	apply telescope type dependent cuts CHECK! STILL USEFUL?
FILLMONTECARLOHISTOS	1	0,1	0	fill histograms with MC spectra only (no IRF calculation)

ENERGYSPECTRUMINDEX	3			reweight events to this set of spectral indexes
	#1	> 0	1	number of different spectral indexes
	#2	> 0.	2.0	lower value
	#3	> 0.	0.1	step size
CUTFILE	1			cut file (full path, see
				7.1)
SIMULATIONFILE_DATA	1			simulation data file
				(mscw file)
SIMULATIONFILE_MCHISTO	1			data file with thrown
				events. This can be
				either a full mscw file
				(slow) or a file with the
				filled MC histograms

Table 8.1: Parameters in the run parameter file for the IRF calculation.

CTA analysis

9.1 General concept

To use Eventdisplay for CTA analyses, the *simtel.gz* files have first to be converted into ROOT format (called in the following DST format). This must be done for each subarray separately. The following list shows the binaries and macros needed to produce CTA sensitivity files:

CTA.convert_hessio_to_VDST convert simtel.gz files into ROOT format

eventdisplay image cleaning & calculation of telescope parameters & reconstruction of the direction and core; display

 ${\bf mscw_energy}$ train and use lookup tables to estimate the energy and mean scaled parameters

trainTMVAforGammaHadronSeparation optimize cuts or train MVA

makeEffectiveArea make effective areas

\$EVNDISPSYS/macros/sensitivity.C calculate and plot sensitivity curves

writeCTAWPPhysSensitivityFiles write sensitivity files (WP-Phys style root file)

There are scripts to simplify these steps in the \$EVNDISP/scripts/CTA directory. It is easy with their help to analyze many simtel.gz files for several subarrays, offsets, and so on. The scripts expect several environmental variables to be set (see 3). Most of the scripts work fine on the DESY batch system, they might need some adjustment for other computing environments.

9.2 Analysis steps for CTA IRF and sensitivity calculation

9.2.1 Step 1: Converter

In this step a simulation data file in hessio format is converted to the EVNDISP DST format (see 10.2). These are the possible options to run the converter:

14 CTA analysis

```
$EVNDISPSYS/bin/CTA.convert_hessio_to_VDST
c_DST: A program to convert hessio data to EVNDISP DST files (v.4.00)
Syntax: ./bin/CTA.convert_hessio_to_VDST [ options ] [ - | input_fname ... ]
Options:
                     (More verbose output)
   -v
  -q
                     (Much more quiet output)
   -s
                     (Show data explained)
                     (Show data explained, including raw data)
    -history (-h)
                     (Show contents of history data block)
  — i
                     (Ignore unknown data block types)
                     (Skip remaining data after so many triggered events.)
   --max-events n
  -a subarray file
                     (list of telescopes to read with FOV.)
  -o dst filename
                     (name of dst output file)
  -f \text{ on}=1/\text{of}f=0
                     (write FADC samples to DST file; default=0)
  -r on=1/off=0
                     (apply camera place scaling for DC telescopes; default=1)
```

The following options are necessary: -a and -o. Note the limitations of the DST format (10.2.1).

Many of the CTA simulation files contain data for a so called hyper array. To select the actual array, the corresponding subarray has to be specified in a ASCII text file (called *subarray* file in the following). The following example file selects an array consisting of telescopes 63, 19, 67, and 33, each telescope with a field of view of 8 degrees (the FOV can be reduced compared to the simulated FOV by setting the corresponding pixels dead):

```
63 8
19 8
67 8
33 8
```

Subarray files for most of the typical arrays used in the CTA sensitivities studies are part of the analysis file package (see 3.1). Note that a subarray file is always needed, even if all telescopes from the hessio file are read out and analyzed.

For a typical run, the following command line should be used:

```
./CTA.convert_hessio_to_VDST -a subArray.list -o dstfile.dst.root \
gamma_run12241.simhess.gz
```

For FADC analysis, add the option -f 1. Note again the limitations of the DST format (10.2.1).

9.2.2 Step 2: Display (event-by-event)

It is always useful to look at events in the display. To do this, it is best to select a small subarray with the *-teltoana* option in evndisp. The display might otherwise be quite slow in responding to your input due to the large number of objects to be drawn.

A typical command line to look at events might be:

```
$EVNDISPSYS/bin/evndisp -display=1 \
-reconstructionparameter ./EVNDISP.reconstruction.runparameter \
-l2setspecialchannels nofile \
-sourcefile tt.v2.root
```

9.2.3 Step 3, Eventdisplay: Calibration, image analysis and stereo reconstruction

9.2.4 Step 1 & 3 combined [USE]

Run the converter and Eventdisplay for a specific subarray: use script (in \$EVNDISP-SYS/scripts/CTA)

```
./CTA.EVNDISP.sub_convert_and_analyse_MC_VDST.sh

<sub array list> text file with list of subarray IDs

list of simtelarray files>

cparticle> gamma_onSource , gamma_cone10 , proton , ...

<data set> e.g. cta-ultra3 , ISDC3700m , ...
```

NOTE: The image cleaning thresholds can be specified in the file $\$OBS_EVNDISP_ANA_DIR/ParameterFiles/EVNDISP.reconstruction.runparameter$ file either for all telescopes to the same values or for each telescope type seperately (see section XXXX).

9.2.5 Step 4: mscw_energy

If you use standard configurations maybe some lookup tables already exist (ask Gernot or Heike where you could find them). If not, you have to create them from gamma-ray simulations yourself with \$EVNDISPSYS/scripts/CTA/CTA.MSCW_ENERGY.sub_make_tables.sh Copy or move the created tables to your directory \$CTA_EVNDISP_ANA_DIR/Tables/Now you have to run mscw_energy for estimating the energy of each event: \$EVNDISPSYS/scripts/CTA/CTA.MSCW_ENERGY.sub_analyse_MC.sh For all different particle types, use \$EVNDISPSYS/scripts/CTA/CTA.subAllParticles_analyse_MC.sh

9.2.6 Step 5: Optimize cuts or train MVA

Gamma-hadron separation is based on TMVA and needs to be trained for each subarray due to their different layouts. Here an example how to do this for Boosted Decicion Trees (BDT):

```
$EVNDISPSYS/scripts/CTA/CTA.TMVA.sub_train.sh subArray.list \
TMVA.BDT.runparameter BDT.20120321 BDT onSource ISDC3700m
```

16 CTA analysis

9.2.7 Step 6: Effective Areas

For using TMVA based gamma-hadron cuts, you have to run through several steps now. The reason for this is that the cuts on the MVA variable is optimized 'on the fly', depending on the energy spectrum of the source, the source strength and the observation time. First the typical angular resolution for the given array is calculated, then the signal and background rates after quality cuts, and finally, the optimal MVA cut value.

All scripts needed can be found in

\$EVNDISPSYS/scripts/CTA/CTA.EFFAREA.sub_analyse.sh

Angular resolution:

Calculate the angular resolution from gamma-ray simulations

```
$EVNDISPSYS/scripts/CTA/CTA.EFFAREA.subAllParticles_analyse.sh \
subArray.list $CTA_EVNDISP_ANA_DIR/ParameterFiles \
ANASUM.GammaHadron.TMVAFixedSignal.gamma.dat \
$CTA_USER_DATA_DIR/analysis/EffectiveArea/<DataSet>/AngularResolution \
<DataSet> 2
```

Quality cuts:

Apply quality cuts and calculate the particle numbers using a root macro.

```
$EVNDISPSYS/scripts/CTA/CTA.EFFAREA.subAllParticles_analyse.sh \
subArray.list $CTA_EVNDISP_ANA_DIR/ParameterFiles \
ANASUM.GammaHadron.QC \
$CTA_USER_DATA_DIR/analysis/EffectiveArea/<DataSet>/QualityCuts \
<DataSet>
```

```
% cd $CTA_USER_DATA_DIR/analysis/EffectiveArea/<DataSet>/QualityCuts
% root
root [0] .L $EVNDISPSYS/lib/libVAnaSum.so
root [1] .L $EVNDISPSYS/macros/sensitivity.C
root [2] writeAllParticleNumberFiles("subArray.list", 0);
// or for several (e.g. 8) offsets:
root [2] writeAllParticleNumberFiles("subArray.list", 8);
```

Make effective areas:

Make effective area while applying the TMVA-based gamma-hadron cuts trained before.

```
$EVNDISPSYS/scripts/CTA/CTA.EFFAREA.subAllParticles_analyse.sh \
subArray.list $CTA_EVNDISP_ANA_DIR/ParameterFiles \
ANASUM.GammaHadron.TMVA \
$CTA_USER_DATA_DIR/analysis/EffectiveArea/<DataSet>/IMVA/BDT.20120321 \
<DataSet>
```

Plotting the effective areas and instrument response functions using the shared library from evndisplay:

```
% root
root [0] .L $EVNDISPSYS/lib/libVAnaSum.so
root [1] VPlotInstrumentResponseFunction a;
root [2] a.addInstrumentResponseData("gamma_onSource.E_ID0.eff-0.root")
root [3] a.plotEffectiveArea()
root [4] a.plotAngularResolution()
root [5] a.plot...
```

9.2.8 Step 7: Sensitivity curves & WP-Phys files

Writing the IRF and sensitivity curves in the agreed WP-Phys format

```
\VNDISPSYS/scripts/CTA/CTA.WPPhysWriter.sh <sub array list> \ <directory with effective areas> <observation time [h]> \ <output file name> <offset=0/1>
```

This can then be used as well to plot all the sensitivities using the root macro \$EVNDISP-SYS/macros/sensitivity.C

Input data format

10.1 VBF - VERITAS Bank Format

10.2 DST - data summary tree

The DST format is a simple ROOT tree containing standard C++ variables only (no class data).

10.2.1 Limitations

The implementation requires the hardwiring of the maximum number of telescopes, channels, etc. These values can be found in inc/VGlobalRunParameter, for example:

```
// HARDWIRED MAXIMUM NUMBER OF TELESCOPES AND CHANNELS, etc.
// maximum number of telescopes
#define VDST MAXTELESCOPES 100

// maximum number of channels per telescopes
#define VDST MAXCHANNELS 12000

// maximum number of summation windows

// (=maximum number of samples per FADC trace)
#define VDST MAXSUMWINDOW 64

// maximum number of time slices for pedestal calculation
#define VDST PEDTIMESLICES 5000

// maximum number of arrayreconstruction method
#define VDST MAXRECMETHODS 100

// maximum number of timing levels
#define VDST MAXTIMINGLEVELS 10
```

NOTE: These numbers determine the memory requirements of *evndisp* and *CTA.convert_hessio_to_VDST*. **NOTE:** *evndisp* must be compiled with the same settings as the writing program.

Detector Setup

11.1 Telescope types

Different telescope types (e.g. mid-size and small-size telescopes, telescopes with different FOV, etc) are assigned a telescope type number in the code, this number is as well written to the data trees. The telescope type contains the mirror shape (DC, Parabolic, SC), the mirror area (m²), the field of view ([deg]) and the pixel size ([deg]). For VERITAS, the telescope type correspond simply to the different telescope numbers (and are therefore 0,1,2,3). For clarification, this is the corresponding code bit from src/CTA.convert_hessio_to_VDST.cpp:

```
fTelescope_type = TMath::Nint(pix_size*100.);
fTelescope_type += TMath::Nint(fFOV*10.)*100;
fTelescope_type += TMath::Nint(fMirrorArea)*100*10*100;

// all large telescopes are parabolic, all others are Davies-Cotton (hardwired)

if(fMirrorArea > fParabolic_mirrorArea) fTelescope_type += 100000000;

// Schwarzschild-Couder: check number of mirrors

else if(fNMirrors == fSC_number_of_mirrors) fTelescope_type += 200000000;
```

Note: There is currently no way to determine the mirror/telescope shape (parabolic, Davies-Cotton, etc) from the hessio file. This is why the mirror area and the number of mirrors is used. The parabolic shape is assigned to all telescopes with a mirror area $> 400 \text{ m}^2$. Schwarzschild-Couder Design are all telescopes with 2 mirrors only.

Tools for VERITAS analysis

12.1 Exposure maps and run lists for any point in the sky

This small tools allows you to

- plot exposure maps in Galactic coordinates for VERITAS (with and without radial acceptance)
- get a list of data runs for a given direction in the sky
- get a list of data runs for objects from a catalogue
- print a LaTex-style table for the selected list of objects with exposure, zenith angles, observing angle, etc.

Usage example:

```
// load shared library
.L lib/libVAnaSum.so
VExposure f;
// read VERITAS db for a given period
// (only necessary if no root file with
// exposures is available)
f.setTimeRange("20070901", "20071231");
f.readFromDB();
// the results can be saved to a root file (fast access)
f.writeRootFile("myrootfile.root");
// and later retrieved with
f.readRootFile("myrootfile.root");
// for radial acceptance correction an acceptance curve is needed
f.readAcceptanceCurveFromFile("myacceptance.root");
// fill maps: (this may take a while)
f.fillExposureMap();
// plot the maps for a given l, b range
f.plot(-10., 10., 60, 100., "");
// plot the maps with some objects from a catalogue:
// (there are some examples of catalogues in the directory
// with the auxiliary files:
```

```
// AstroData/Catalogues/: tevcat.dat, ...
f.plot(-10., 10., 60, 100., "mycatalogue.dat");
// print list of runs of data taken e.g. around the Galactic centre (5 deg circle)
f.printListOfRuns( 0., 0., 5. );
// print list of runs around the objects in the given catalogue
f.printListOfRuns( "mycatalogue.dat");
```

12.2 Radiosonde Atmospheric Data

Download radiosonde balloon data from Tucson airport using a wget script and create a root file of the data.

Use the download script, for example get data for the entire year of 2010:

```
cd $EVNDISPSYS/scripts/VTS/
./VTS.downloadSoundingDatafromUWYO.sh 2010
```

Combine the monthly data into one file and create a list of files (in this case just the total file):

```
cat sounding_2010* > all_2010.dat
ls all_2010.dat > list_2010.dat
```

Use a root file of radiosonde data and plot results

```
root -l
.L ../../../sharedLib/libVAnaSum.so
VAtmosphereSoundings a;
a.readSoundingsFromTextFile("list_2010.dat");
a.writeRootFile("all_2010.root");
.q
```

Use the VAtmosphereSoundings class to plot the data:

```
root -l
gROOT->SetStyle("Plain");
gStyle->SetCanvasBorderMode(0);
gStyle->SetPadBorderMode(0);
gStyle->SetPalette(1);
.L ../../../sharedLib/libVAnaSum.so
VAtmosphereSoundings a("all_2010.root");
a.plotAverages(2010,1,2010,12);
a.plot2DProfiles(2010,1,2010,12);
```

• please read through \$EVNDISPSYS/src/VAtmosphereSoundings.cpp for full analysis details

- for a detailed overview of the results please see: Atmosphere
- radiosonde data is from http://weather.uwyo.edu/upperair/sounding.html

There is a root macro in EVNDISPSYS/macros/VTS/atmosphericSounding. C to plot monthly/yearly average and compare with atmospheric profiles from simulations.

Light curve analysis

Several methods for light curve analysis are currently under development. We describe in the following the existing tools, for further details please check the different sections in the code. Light curve data can be read from evndisplay result files (anasum files) or from ascii files.

13.1 Code organization

- VLightCurveData: data class (contains a single point of the light curve)
- VLightCurveUtilities: basic functions to read ascii files, print light curves, and get light curve properties (e.g. mean, variance)
- VLightCurve: light curve reader and plotter for ascii and evndisplay result files (anasum files)
- *VLombScargle*: discrete Fourier transform for unevenly spaced data after Lomb and Scargle
- VZDCF: plotting class for Z-transformed discrete correlation functions

13.2 Light curve plotting

Example for plotting light curves using an evndisplay result files (anasum file:

```
iLightCurve->fill(0.5);
// plot light curve
iLightCurve->plotLightCurve();
```

Text file example (observation date (MJD), length of observation (in days), flux and flux error):

54857.173780	0.074748	1.27275	0.17745	
54858.178508	0.074864	1.27704	0.17042	
54859.139628	0.101489	1.30742	0.18451	
54860.154963	0.105847	1.31362	0.17415	
54867.274058	0.262490	1.09824	0.15957	

Note the first two columns can be as well: begin and end of observations in MJD. Example for plotting light curves using a simple text file:

```
.L $EVNDISPSYS/lib/libVAnaSum.so

VLightCurve b;

// plot 95\% upper flux limits for points with

// significances $<2 \sigma$:
b.setSignificanceParameters( 2., -9999., 0.95 );

// set spectral parameters assumed in the flux calculation:
b.setSpectralParameters( 0., 1., -2.5 );
b.initializeXRTLightCurve("mylightcurve.txt");
b.setPlottingStyle( 2, 1, 1., 20, 1. );
b.setLightCurveAxis( 0., 2., "counting_rate" );
b.plotLightCurve();
```

Additionally to the described functions, there are several functions to fill gaps in light curves. This is work in progress and should be used only after carefully reading of the code. VLightCurve and VLightCurveUtillities provide several methods to print details of the calcu-

13.3 Lomb Scargle analysis

lations to the screen and fill Latex and Wiki tables.

The discrete Fourier transform for unevenly spaced data after Lomb and Scargle is implemented in the *VLombScargle* class [Scargle(1982)]. The basic light curve reader classes can be used to read in a light curve from a text or eventdisplay result file.

There are two different implementations for the calculation of the significances of the peaks:

- 1. the calculation provided by Lomb & Scargle taking into account the number of independent frequencies scanned and Poissonian errors
- 2. a toy MC based method: the light curve is randomly shuffled N times with the flux points changed randomly according to their errors. For each of the resulting light curve the periodigram is calculated. The probability/significance is derived from the distribution of powers at each frequency bin (note: a large number of toy light curves have to be produced for larger values of significance).

Example:

```
.L $EVNDISPSYS/lib/libVAnaSum.so
VLombScargle g;
g.readASCIIFile("mylightcurve.txt");
// scan 1000 frequencies between 50. and 1000. days
g.setFrequencyRange(1000., 1./1000., 1./50.);
g.plotPeriodigram();
// plot a line at the give frequency
g.plotFrequencyLine(1./315.);
// plot probability levels using the Lomb & Scargle calculation
g.plotProbabilityLevels();
// plot probability levels using a toy MC with 500 MC light curve realisations
g.plotProbabilityLevelsFromToyMC(500);
```

13.4 ZDCF Autocorrelation analysis

No autocorrelation analysis is implemented yet. We used until now the Z-transformed discrete correlation functions and the code provided by the authors of ZDCF¹.

There is a small class in eventdisplay provided to plot the ZDCF results, see the following example:

```
.L $EVNDISPSYS/lib/libVAnaSum.so
VZDCF a;
a.readZDCF( "XRT20120216.dcf");
a.setMLinterval( 315., 315.+6., 315.-3.86 ); // error provided by plike
a.plotZDCFoverError( 0, 45., 405., 12. );
a.plotZDCF( 0, 45., 405. );
```

¹http://www.weizmann.ac.il/weizsites/tal/research/software/

Bibliography

 $[Scargle(1982)] \ Scargle, \, J. \ 1982, \, ApJ \ 263, \, 835$