


VaultSpeed Studio

SCD2 dimension on a BRIDGE



USE CASE FOR THIS TEMPLATE

This document describes how a user can configure a template in the VaultSpeed Studio to generate an SCD Type 2 dimension based on an insert-only RDV by using a bridge table with multiple HUB's. In the setup there is the possibility to limit the fields which should show up in the dimension. The generated query will also remove unnecessary records (no changes in the combination of selected fields).

Before you explore and use this example template, ensure that you understand the example SQL attached to understand what the template does and that it covers your needs.

This template is designed for:

- DIMENSION creation based on a BRIDGE
- The BRIDGE represents 1 hierarchy in a dimension with 2 levels (eg product → product type)
- Slowly Changing Type 2 Dimension
- · Versions in the dimension will be compressed
- PIT tables must exist on EACH entry table on the BRIDGE
- MAIN_HUB must be assigned
- Dimension_hkey will be calculated based on the BK's of the MAIN_HUB in combination with the date
- Only the change date of the main hub will be taken into account for the SCD2 time slices

Example

The example that is used in this document is based on a customer and its address information. In the Raw Data Vault model this is a HUB_CUSTOMER with a Link to the HUB_ADDRESSES.

Components of the implementation

- Standard business vault BRIDGE table
- PIT table on all HUB and LNK objects that exist in the BRIDGE
- · Signature objects
- Assign Signature objects to the correct tables
- · Create Signature attribute type and assigned in the requested fields
- Create the Template
- Create Target definition
- Fill in the Dependency

Implement a Standard business vault BRIDGE table

In the open release of the Business Vault, create the bridge table. For use within the template, this bridge doesn't need to have the hash key created or the Business keys of the HUBs added.



PIT table is created on all HUB and LNK objects that exist in the BRIDGE.

The Dimension is a SCD2 type dimension, for this we need to have a detailed PIT implementation on all HUBs and LNKs that exist in the BRIDGE that has been created.

The PIT setup is like the following:




After that, the PIT is applied on the HUBs and LNKs of the example:

☐ HUB_ADDRESSES
☐ HUB_CUSTOMERS
☐ LNK_CUSTOMERS_ADDRESSES

Create Signature objects

In order for the template to know which tables to use for which purpose we need to create some specific Signature Objects.



Signature objects are assigned

MAIN_HUB Indicate the driving table of the dimension. Meaning the lowest level of your

multi-level dimension setup

Object Name	Object Type	Signature Object	
Filter	Filter	Filter ▼ MAIN_HUB	
HUB_CUSTOMERS	Hubs	HUB, MAIN_HUB	

PIT_DETAIL_TRANS

Indicating which PIT tables must be used in the setup of the date ranges

Object Name	Object Type	Signature Object
Filter	Filter	Filter ▼ PIT_DETAIL_TRANS
PIT_DETAIL_TRANS_ADDRESSES	Point in Time table	PIT, PIT_DETAIL_TRANS
PIT_DETAIL_TRANS_CUSTOMERS	Point in Time table	PIT, PIT_DETAIL_TRANS, SNAP_DATE_PIT
PIT_DETAIL_TRANS_CUSTOMERS_ADI	Point in Time table	PIT, PIT_DETAIL_TRANS
SNAP_DATE_PIT	Indicating which PIT table is the PIT on	the MAIN_HUB that must be used
Object Name	Object Type	Signature Object
Filter	Filter	Filter ▼ SNAP_DATE_PIT


PIT, PIT_DETAIL_TRANS, SNAP_DATE_PIT

Create Signature attribute type and flag the usage in the requested fields

Point in Time table


Management	
Search	
Signature Attribute	
DIM_ATTRIBUTE	

PIT_DETAIL_TRANS_CUSTOMERS



Create the template

Template definition, according to the standard that you want to use. Important element here is the Signature Object naming. That name comes back in the .dvt file that contains the definition of the dimension template. If you have multiple implementations, you might want to go for a different name. But then you will need to adapt the template file accordingly and replace all the DIMB references with your chosen name.



Ensure you have this use case's latest version from the following location: https://github.com/Vaultspeed/studio-templates.

Each of our templates has its folder where the code resides.

Take the dim_etl_template.dvt file and upload it for the ETL template of this view.

Fill in the Target Definition

The target definition is very specific to the template:

Existing Attributes		
New Attributes	Search	
Overview	Signature Object	Signature Attribute
	SAT	DIM_ATTRIBUTE
	PIT	SNAPSHOT_TIMESTAMP
	BRIDGE	OBJECT_H_KEY
	BRIDGE	BUSINESS_KEY

Add new attribute for the calculated snapshot and end snapshot. Attention, to avoid overlap with the existing snapshot_timestamp there is a double $_!$

Unique Name	Prefix	Suffix	Signature Object	Signature Attribute	Data Type
snapshot_timestamp					TIMESTAMP_TZ
end_snapshot_timesta	mp				TIMESTAMP_TZ

Fill in the Dependency

Def	ine on whi	ch BRIDGE table this template must be implemented.
		Object Name (Linked)
		BRIDGE_BRG_CUSTOMER_ADDRESS (BRIDGE)