


VaultSpeed Studio

Fact on Bridge with SCD2 Dimension



USE CASE FOR THIS TEMPLATE

This document describes how a user can configure a template in the VaultSpeed Studio to generate a view that represents a FACT based on a bridge table with multiple HUBs. The dimensions that are included in the dimension is based on the correct tagging of multiple SCD Type 2 dimensions. The selection of the correct dimension record is based on the invoice date (EOD) from the invoice.

Before you explore and use this example template, ensure that you understand the example SQL attached to understand what the template does and that it covers your needs.

This template is designed for:

- FACT creation based on a BRIDGE
- SCD Type 2 Dimension
- Hard Join with dimension, no check for existence, a not existing version will lead to record loss at loading time
- No aggregation in the template
- the date used for the FACT must be tagged using a Signature Attribute
- all attributes with SA OTHER_ATTR, BUSINESS_SRC_KEY and FOREIGN_KEY from the selected SAT will be loaded in the FACT
- The dimensions are dimensions created with the SCD2_DIM_HUB template

Example

The example that is used in this document is based on an invoice, the customer and his address.


In the Raw Data Vault model this is a HUB_INVOICE with a Link to the HUB_CUSTOMER and HUB_ADDRESSES.

Components of the implementation

- Standard business vault BRIDGE table
- Ensure there are SCD Type 2 dimensions for each HUB
- Signature objects
- Assign Signature objects to the correct tables
- Create Signature attribute type and assigned in the requested fields
- Create the Template
- Create Target definition
- Fill in the Dependency

Implement a Standard business vault BRIDGE table

In the open release of the Business Vault, create the bridge table. For use within the template, this bridge doesn't need to have the hash key created or the Business keys of the HUBs added.



Create Signature objects

In order for the template to know which tables to use for which purpose, we need to create some specific Signature Objects.

Signature Object

FACT_ON_BRIDGE_SCD2_DIM_SELECTION

FACT_ON_BRIDGE_SCD2_SAT_SELECTION

FACT_ON_BRIDGE_SCD2_DIM_SELECTION: From the Bridge, not all HUBs should become dimensions. The template expects the user that configures this fact uses the SO to flag those HUBs for which the dimension must be visible in the fact.

FACT_ON_BRIDGE_SCD2_SAT_SELECTION: From which SAT the template will select all OTHER_ATTR fields has to be configured. The template expects the user that configures this fact uses the SO to flag those SATs from which the values must be visible in the fact.

Signature objects are assigned

FACT_ON_BRIDGE_SCD2_DIM_SELECTION

HUB_ADDRESSES	Hubs	HUB, FACT_ON_BRIDGE_SCD2_DIM_SELECTION
HUB_CUSTOMERS	Hubs	HUB, MAIN_HUB, FACT_ON_BRIDGE_SCD2_DIM_SELECTION

FACT_ON_BRIDGE_SCD2_SAT_SELECTION

SAT_SLS_INVOICES	Satellites on Hubs	SAT, FACT_ON_BRIDGE_SCD2_SAT_SELECTION

Create Signature attribute type and flag the usage in the requested fields

In order to identify the field in the SAT which is used to select the correct version of the dimension

	FACT_ON_BRIDGE_S	SCD2_TIME_FIELD			
^	SAT_SLS_INVOICES	Satellites on Hubs			
			INVOICE_ID	BUSINESS_SRC_KEY	VAI
			CUSTOMER_INVOICE_ID	FOREIGN_KEY	NUN
			INVOICE_DATE	OTHER_ATTR, FACT_ON_BRIDGE_SCD2_TI	TIM
			AMOUNT	OTHER ALLIK	NUN


Create the template

Template definition, according to the standard that you want to use. Important element here is the Signature Object naming. That name comes back in the .dvt file that contains the definition of the dimension template. If you have multiple implementations, you might want to go for a different name. But then you will need to adapt the template file accordingly and replace all the references to the Signature Object of your choice with your chosen name.

Take the fact_view_on_bridge_etl.dvt file and upload it for the ETL template of this view.

Fill in the Target Definition

The target definition is very specific to the template:



Fill in the Dependency

Define on which BRIDGE table this template must be implemented.

Object Name (Linked)
BRIDGE_BRG_CUSTOMER_ADDRESS (BRIDGE)