

Packet Tracer - Configure Named Standard IPv4 ACLs

Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	F0/0	192.168.100.1	255.255.255.0	N/A
	F0/1	192.168.200.1	255.255.255.0	
	E0/0/0	192.168.10.1	255.255.255.0	
	E0/1/0	192.168.20.1	255.255.255.0	
File Server	NIC	192.168.200.100	255.255.255.0	192.168.200.1
Web Server	NIC	192.168.100.100	255.255.255.0	192.168.100.1
PC0	NIC	192.168.20.3	255.255.255.0	192.168.20.1
PC1	NIC	192.168.20.4	255.255.255.0	192.168.20.1
PC2	NIC	192.168.10.3	255.255.255.0	192.168.10.1

Objectives

Part 1: Configure and Apply a Named Standard ACL

Part 2: Verify the ACL Implementation

Background / Scenario

The senior network administrator has asked you to create a standard named ACL to prevent access to a file server. The file server contains the data base for the web applications. Only the Web Manager workstation PC1 and the Web Server need to access the File Server. All other traffic to the File Server should be denied.

Instructions

Part 1: Configure and Apply a Named Standard ACL

Step 1: Verify connectivity before the ACL is configured and applied.

All three workstations should be able to ping both the **Web Server** and **File Server**.

Step 2: Configure a named standard ACL.

- Configure the following named ACL on R1.

```
R1(config)# ip access-list standard File_Server_Restrictions
R1(config-std-nacl)# permit host 192.168.20.4
R1(config-std-nacl)# permit host 192.168.100.100
R1(config-std-nacl)# deny any
```

Note: For scoring purposes, the ACL name is case-sensitive, and the statements must be in the same order as shown.

Note: Deny any command was included only to highlight the existence of the implicit deny that automatically exists at the end of every ACL. If you try it without it, you will get the same results.

-
- b. Use the **show access-lists** command to verify the contents of the access list before applying it to an interface. Make sure you have not mistyped any IP addresses and that the statements are in the correct order.

```
R1# show access-lists
Standard IP access list File_Server_Restrictions
10 permit host 192.168.20.4
20 permit host 192.168.100.100
30 deny any
```

Step 3: Apply the named ACL.

- a. Apply the ACL outbound on the Fast Ethernet 0/1 interface.

Note: In an actual operational network, applying an access list to an active interface is not a good practice and should be avoided if possible.

```
R1(config-if)# ip access-group File_Server_Restrictions out
```

- b. Save the configuration.

Part 2: Verify the ACL Implementation

Step 1: Verify the ACL configuration and application to the interface.

Use the **show access-lists** command to verify the ACL configuration. Use the **show run** or **show ip interface fastethernet 0/1** command to verify that the ACL is applied correctly to the interface.

Step 2: Verify that the ACL is working properly.

All three workstations should be able to ping the **Web Server**, but only **PC1** and the **Web Server** should be able to ping the **File Server**. Repeat the **show access-lists** command to see the number of packets that matched each statement.