Communication and Synchronisation

Files

Signals (UNIX)

Events, exceptions (Windows)

Pipes

Message Queues (UNIX)


Mailslots (Windows)

Sockets – in NDS course


Shared memory

Semaphores, Locks, Monitors


Types of Process Interaction



Require mutually exclusive access to prevent interference



P1 informs P2 that some event has happened. P2 waits for it



P1 sends P2 data. P1 blocks when buffer is full, P2 blocks when buffer is empty.

Mutual Exclusion, Synchronisation and Communication are closely related.

UNIX Signals

Inter-Process Communication (IPC) mechanism
Signal delivery similar to delivery of hardware interrupts
Used to notify processes when an event occurs
A process can send a signal to another process if it has permission

- "the real or effective user ID of the receiving process must match that of the sending process or the user must have appropriate privileges (such as given by a set-user-ID program or the user is the super-user)." (man page)
- The kernel can send signals to any process

When Are Signals Generated?

When an exception occurs

e.g., division by zero => SIGFPE,segment violation => SIGSEGV

When the kernel wants to notify the process of an event

e.g., if process writes to a closed pipe => SIGPIPE

When certain key combinations are typed in a terminal

e.g., Ctrl-C => SIGINT

Explicitly using the kill() system call

UNIX Signals – Examples

SIGINT	Interrupt from keyboard
SIGABRT	Abort signal from abort
SIGFPE	Floating point exception
SIGKILL	Kill signal
SIGSEGV	Invalid memory reference
SIGPIPE	Broken pipe: write to pipe with no readers
SIGALRM	Timer signal from alarm
SIGTERM	Termination signal

UNIX Signals

The default action for most signals is to terminate the process

But the receiving process may choose to

- Ignore it
- Handle it by installing a signal handler
- Two signals cannot be ignored/handled: SIGKILL and SIGSTOP

```
signal(SIGINT, my_handler);

void my_handler(int sig) {
    printf("Received SIGINT. Ignoring...")
}
```

Signal Handlers – Example

```
#include <signal.h>
#include <stdio.h>

void my_handler(int sig) {
    fprintf(stderr, "SIGINT caught!");
}

int main(int argc, char *argv[])


{
    signal(SIGINT, my_handler);
```

while (1) {}

UNIX Pipes

A pipe is a method of connecting the standard output of one process to the standard input of another

Allows for one-way communication between processes



Widely-used on the command line and in shell scripts

- ls | less
- cat file.txt | grep hello | wc -l

Two types of pipes

- unnamed
- named

pipe()

```
int pipe(int fd[2])
```

Returns two file descriptors in fd:

- fd[0] the read end of the pipe
- fd[1] the write end of the pipe

The sender should close the read end

The receiver should close the write end

If the receiver reads from an empty pipe, it blocks until data is written at the other end

If the sender attempts to write to a full pipe, it blocks until data is read at the other end

Processes must have child-parent relationship

pipe() example

```
int main(int argc, char *argv[]) {
  int fd[2]; char buf;
                                             $ ./a.out abc
 assert(argc == 2);
  if (pipe(fd) == -1) exit(1);
                                             abc
  if (fork() != 0) {
    close(fd[0]); /* Parent = writer, so close read */
   write(fd[1], argv[1], strlen(argv[1]));
    close(fd[1]);
   waitpid(-1, NULL, 0);
  } else {
    close(fd[1]); /* Child = reader, so close write */
    while (read(fd[0], \&buf, 1) > 0)
     printf("%c", buf);
   printf("\n");
    close(fd[0]);
```

UNIX Named Pipes (FIFOs)

Persistent pipes that outlive the process which created them

Stored on the file system

Any process can open it like a regular file

Why use named pipes instead of files?

```
$ mkfifo /tmp/abc
$ echo ABC >/tmp/abc
```

\$ cat /tmp/abc ABC

Sockets

Allow bidirectional communication

Can be used to exchange information both locally and across a network

Unlike pipes which are identified by machine specific file descriptors

Two types of sockets:

- TCP (stream sockets)
- UDP (datagram sockets)


Covered in Networks and Distributed Systems course

Shared Memory

Processes can set up shared memory areas

Implicitly or explicitly mapped to files on disk

After shared memory is established, no need for kernel involvement



Shared Memory – System V API

shmget	Allocates a shared memory segment
shmat	Attaches a shared memory segment to the address space of a process
shmctl	Changes the properties associate with a shared memory segment
shmdt	Detaches a shared memory segment from a process

Synchronisation

Process Synchronization

How do processes synchronize their operation to perform a task?

Key concepts:

- Critical sections
- Mutual exclusion
- Atomic operations
- Race conditions
- Synchronization mechanisms
 - → Locks, semaphores, monitors, etc.
- Deadlock
- Starvation

Concepts relevant to both processes and threads

Shared Data Example

Account #1234: £10,000



Extract £1000 from account 1234



Extract £1000 from account 1234 17

Shared Data Example

```
void Extract(int acc_no, int sum)
{
   int B = Acc[acc_no];
   Acc[acc_no] = B - sum;
}
```

Acc[1234]

10,000



```
B = 10,000
Acc[1234] = 9000
```

B = 9,000 Acc[1234] = 8000



Extract(1234, 1000)

Extract(1234, 1000)

Shared Data Example


```
Extract(int acc no, int sum)
void
  int B = Acc[acc_no];
  Acc[acc no] = B - sum;
                                        Critical section!
                                        Need mutual exclusion
```

10,000 Acc[1234]

$$B = 10,000$$



$$Acc[1234] = 9000$$





$$Acc[1234] = 9000$$

Extract(1234, 1000)

Extract(1234, 1000)

Critical Sections and Mutual Exclusion

Critical section/region: section of code in which processes access a shared resource – executed by only one process at a time.

A code section is critical if it:

- 1. Reads a memory location which is shared with another process
- 2. Updates a shared memory location with a value which depends on what it read

Mutual exclusion ensures that if a process is executing its critical section, no other process can be executing it


Processes must request *permission* to enter critical sections

A **synchronisation mechanism** is required at the entry and exit of the critical section

Requirements for Mutual Exclusion

- No two processes may be simultaneously inside a critical section
- No process running outside the critical section may prevent other processes from entering the critical section
 - When no process is inside a critical section, any process requesting permission to enter must be allowed to do so immediately
- No process requiring access to its critical section can be delayed forever
- No assumptions are made about relative the speed of processes

Critical Sections and Mutual Exclusion



Disabling Interrupts

```
void Extract(int acc_no, int sum)
{
   CLI();
   int B = Acc[acc_no];
   Acc[acc_no] = B - sum;
   STI();
}
```

Works only on single-processor systems, but not with user level threads.

Misbehaving/buggy processes may never release CPU

Mechanism usually only used by kernel code

Software Solution – Strict Alternation

What happens if P_0 takes a long time in its non-critical section?

 Remember: No process running outside its critical section may prevent other processes from entering the critical section

Can we have P_1 execute its loop twice in a row (w/o P_0 executing in-between)?

Busy Waiting

Strict alternation solution requires continuously testing the value of a variable

Called **busy waiting**

- Wastes CPU time
- Should only be used when the wait is expected to be short

Atomic Operations

Does this work?

Not atomic!

Atomic operation: a sequence of one or more statements that is/appears to be indivisible

Lock Variables

```
L= 0 lock open/free
L=1 locked
```

```
void Extract(int acc_no, int sum)
{
  lock(L);
  int B = Acc[acc_no];
  Acc[acc_no] = B - sum;
  unlock(L);
}
```

Does this work?

```
void unlock(int L)
{
   L = 0;
}
```

TSL (Test and Set Lock) Instruction

Atomic instruction provided by most CPUs

TSL (LOCK)

 Atomically sets memory location LOCK to 1 and returns old value

Pseudocode

```
void lock(int L)
{
    while (TSL(L) != 0)
    /* wait */;
}
```

Assembler

```
TSL L Read L and set
condition code if L=0
BNZ jumps if Z is not set.
MOV #n,L sets L to constant n
```

```
LOCK: TSL L
BNZ LOCK
```

UNLOCK: MOV #0, L

Spin Locks

Locks using busy waiting are called spin locks Waste CPU

Should only be used when the wait is expected to be short
 May run into priority inversion problem

Priority Inversion Problem and Spin Locks

Two processes:

- H with high priority
- L with low priority
- H should always be scheduled if runnable

Assume the following scenario:

- H is waiting for I/O
- L acquires lock A and enters critical section
- I/O arrives and H is scheduled
- H tries to acquire lock A that L is holding

What happens?

Lock Granularity

```
void Extract(int acc_no, int sum)
{
   lock(L);
   int B = Acc[acc_no];
   Acc[acc_no] = B - sum;
   unlock(L);
}
```

```
T1: Extract(1, 40);
```

What happens if there are concurrent accesses to different accounts?

Lock Granularity

```
void Extract(int acc_no, int sum)
{
   lock(L[acc_no]);
   int B = Acc[acc_no];
   Acc[acc_no] = B - sum;
   unlock(L[acc_no]);
}
```

```
T1: Extract(1, 40);
```

```
T2: Extract(2, 40);
```

Lock granularity: the amount of data a lock is protecting

Is finer granularity always better?

Lock Overhead and Lock Contention

Lock overhead: a measure of the cost associated with using locks

- Memory space
- Initialization
- Time required to acquire and release locks

Lock contention: a measure of the number of processes waiting for a lock

More contention, less parallelism

Coarser granularity:

- Lower overhead
- More contention
- Lower complexity

Finer granularity:

- Higher lock overhead
- Less contention
- Higher complexity

Minimizing Lock Contention/Maximizing Concurrency

Choose finer lock granularity

But understand tradeoffs

Release a lock as soon as it is not needed

Make critical sections small!

```
void AddAccount(int acc_no, int balance)
{
    lock(L_Acc);
    CreateAccount(acc_no);
    lock(L[acc_no]);
    Acc[acc_no] = balance;
    unlock(L[acc_no]);
    unlock(L_Acc);
}
```

Read/Write Locks

```
void ViewHistory(int acc_no)
{
   print_transactions(acc_no);
}

P1: ViewHistory(1234);

P2: ViewHistory(1234);

P3: ViewHistory(1234);
```

Any locks needed?

Race Condition

Occurs when multiple threads or processes read and write **shared data** and the final result depends on the relative timing of their execution

i.e. on the exact process or thread interleaving

E.g., the Extract example → final value of account 8,000 or 9,000

Thread Interleavings

a = 1	a = 1	a = 1	b = 2	b = 2	b = 2
b = 1	b = 2	b = 2	a = 2	a = 1	a = 1
b = 2	b = 1	a = 2	a = 1	a = 2	b = 1
a = 2	a = 2	b = 1	b = 1	b = 1	a = 2
(2, 2)	(2, 1)	(2, 1)	(1, 1)	(2, 1)	(2, 1)

Semaphores

Blocking synchronization mechanism invented by Dijkstra in 1965

Idea: Processes will cooperate by means of *signals*

- A process will block, waiting for a specific signal
- A process will continue if it has received a specific signal

Semaphores are *special variables*, accessible via the following *atomic* operations:


- down (s): receive a signal via semaphore s
- up (s): transmit a signal via semaphore s
- init(s, i): initialise semaphore s with value i

down() also called P() (probeer te verlagen)
up() also called V() (verhogen)

Semaphores

Semaphores have two private components:

- A counter (non-negative integer)
- A queue of processes currently waiting for that semaphore Queue is typically first in first out (FIFO)



Semaphore Data Structure

Queue of processes waiting on Semaphore

Semaphore Operations

```
init(s, i) ::= counter(s) = i
          queue(s) = {}
```

Semaphores for Mutual Exclusion

Binary semaphore: counter is initialized to 1 Similar to a lock/mutex


```
process A
                               process B
  down(s)
                                  down(s)
    critical section
                                    critical section
  up(s)
                                 up(s)
                               end
end
main() {
  var s:Semaphore
  init(s, 1) /* initialise semaphore */
    start processes A and B in random order
```

Note: for binary semaphore if s = 1, up (s) leaves s = 1

General Semaphores

The initial value of a semaphore counter indicates how many processes can access shared data at the same time counter(s) >= 0: how many processes can execute down without being blocked

Producer / Consumer



There can be multiple producers and consumers

Producer / Consumer

Buffer constraints:

Buffer can hold between 0 and N items

Producer constraints:

- Items can only be deposited in buffer if there is space (items in buffer < N)
- Items can only be deposited in buffer if mutual exclusion is ensured

Consumer constraints:

- Items can only be fetched from buffer if it is not empty (items in buffer > 0)
- Items can only be fetched from buffer if mutual exclusion is ensured

Producer/Consumer?

```
var item, space, mutex: semaphore
init (item, 0) /* Semaphore to ensure buffer is not empty */
init (space, N) /* Semaphore to ensure buffer is not full */
init (mutex, 1) /* Semaphore to ensure mutual exclusion */
process Producer
                             process Consumer
 loop
                              loop
   produce item
                                down (mutex)
   down (mutex)
                               down (item)
   down (space)
                                fetch item
   deposit item
                               up (space)
   up(item)
                               up (mutex)
   up (mutex)
                                consume item
 end loop
                              end loop
end Producer
                             end Producer
```


What is wrong with this?

Producer/Consumer

```
var item, space, mutex: semaphore
init (item, 0) /* Semaphore to ensure buffer is not empty */
init (space, N) /* Semaphore to ensure buffer is not full */
init (mutex, 1) /* Semaphore to ensure mutual exclusion */
process Producer
                             process Consumer
 loop
                              loop
   produce item
                               down (item)
   down (space)
                               down (mutex)
   down (mutex)
                               fetch item
   deposit item
                               up (mutex)
   up (mutex)
                               up (space)
   up(item)
                                consume item
 end loop
                              end loop
end Producer
                             end Producer
```

Works for multiple producers & consumers What happens when space = 0 or items = 0?

Readers/Writers



- items can only be written if no other process is writing;
- items can only be written if no other process is reading.
- Readers constraints:
 - items can only be read if no other process is writing;
 - items can be read if there are other processes reading.
- File can hold an arbitrary number of items.

Readers/Writers With Semaphores

```
semaphore mutex, wrt;
                               process reader()
int read cnt = 0;
                                 loop
init(mutex, 1);
                                    down (mutex)
init(wrt, 1);
                                    read cnt += 1;
                                    if(read cnt == 1)
                                        down (wrt) ;
process writer()
                                    up (mutex);
  loop
                                    read item
   produce item
                                    down (mutex) ;
   down (wrt) ;
                                    read cnt -= 1
    write item
                                    If (read cnt == 0)
   up(wrt);
                                       up(wrt);
                                    up (mutex);
  end loop
                                    consume item
end writer
                                 end loop
                               end reader
```

Is this fair?

Monitors

Higher-level synchronization primitive Introduced by Hansen (1973) and Hoare (1974) Refined by Lampson (1980)

Monitors

Ensure mutual exclusion for shared resource (data) Entry procedures

Can be called from outside the monitor

Internal procedures

Can be called only from monitor procedures

An (implicit) monitor lock

One or more condition variables

Processes can only call entry procedures

cannot directly access internal data

Only one process can be in the monitor at one time

Condition Variables

Associated with high-level conditions

- "some space has become available in the buffer"
- "some data has arrived in the buffer"

Operations:

- wait(c): releases monitor lock and waits for c to be signalled
- signal(c): wakes up one process waiting for c
- broadcast(c): wakes up all processes waiting for c

Signals do not accumulate i.e c is not a counter.

 If a condition variable is signalled with no one waiting for it, the signal is lost

What happens on signal?

[Hoare] A process waiting for signal is immediately scheduled

- + Easy to reason about
- Inefficient: the process that signals is switched out, even if it has not finished yet with the monitor
- Places extra constraints on the scheduler

[Lampson] Sending signal and waking up from a wait are not atomic

- More difficult to understand, need to take extra care when waking up from a wait()
- + More efficient, no constraints on the scheduler
- + More tolerant of errors: if the condition being notified is wrong, it is simply discarded when rechecked (see next slides)

Usually [Lampson] is used

Hoare Monitor Implementation Using Semaphores

Variables

```
semaphore mutex; // (initially = 1)
semaphore next; // (initially = 0)
int next_count = 0;

Each procedure F will be replaced by
    wait(mutex);
    ...
    body of F;
    ...
    if (next_count > 0)
        up(next)
    else
```

Mutual exclusion within a monitor is ensured

up (mutex);

Monitor Implementation – Condition Variables

```
For each condition variable c, we have:
       semaphore c sem; // (initially = 0)
       int c count = 0;
The operation wait (c) can be implemented as:
         c count++;
          if (next count > 0) up(next);
         else up(mutex);
         down(c sem);
         c count--;
The operation signal (c) can be implemented as:
         if (c count > 0) {
            next count++; up(c sem);
            down(next); next count--;
```

Producer/Consumer with Monitors

```
monitor ProducerConsumer
    condition not full, not empty;
    integer count = 0;
    entry procedure insert(item)
       if (count == N) wait(not full);
       insert item(item); count++;
       signal(not empty);
                                     Does this work?
    entry procedure remove(item)
       if (count == 0) wait(not empty);
       remove item(item); count--;
       signal(not full);
end monitor
```

Producer/Consumer with Lampson Monitors

```
monitor ProducerConsumer
    condition not full, not empty;
    integer count = 0;
    entry procedure insert(item)
       while (count == N) wait(not full);
       insert item(item); count++;
       signal(not empty);
    entry procedure remove(item)
       while (count == 0) wait(not empty);
       remove item(item); count--;
       signal(not full);
end monitor
```

Readers/Writers Revisited

Correctness Constraints:

- Readers can access file when no writers
- Writers can access file when no readers or writers
- Only one thread manipulates state variables at a time

Basic structure of a solution:

```
    Reader()
    Wait until no writers
    Access file
    Check out – wake up a waiting writer
```

Writer()
 Wait until no active readers or writers
 Access file
 Check out – wake up waiting readers or writer

Readers/Writers: Fairness?

Problem statement clarification

- Suppose that a writer is active and a mixture of readers and writers now shows up. Who should get in next?
- If a writer is waiting and an endless of stream of readers keeps showing up. Is it fair for them to become active?

Alternation is a possible fair solution:

- Once a reader is waiting, readers will get in next.
- If a writer is waiting, one writer will get in next.

State variables needed (Protected by a lock called "lock"):

- int NReaders: Number of active readers; initially = 0
- int WaitReaders: Number of waiting readers; initially = 0
- int NWriters: Number of active writers; initially = 0
- int WaitWriters: Number of waiting writers; initially = 0
- Condition CanRead = NIL, CanWrite = NIL

Readers/Writers with Monitors

```
monitor ReadersNWriters
  integer WaitWriters, WaitReaders,
            NReaders, NWriters;
  condition CanRead, CanWrite;
  entry procedure StartRead()
    if (NWriters == 1 or WaitWriters > 0)
      ++WaitReaders; Wait(CanRead); --WaitReaders;
    ++Nreaders;
    Signal (CanRead) ;
  end StartRead
  entry procedure EndRead()
    If(--Nreaders == 0) Signal(CanWrite);
  end EndRead
```

Reader/Writer contd

```
entry procedure StartWrite()
    if(NWriters == 1 or NReaders > 0)
      ++WaitWriters; wait(CanWrite); --WaitWriters;
    NWriters = 1;
  end StartWrite;
  entry procedure EndWrite()
    NWriters = 0;
    if (WaitReaders > 0) Signal (CanRead);
      else Signal(CanWrite);
  end EndWrite;
end monitor
```

Monitors

Monitors are a language construct Not supported by C

Java

- synchronized methods
- no condition variables
 - + wait() and notify()

Bohr and Heisen bugs

Bohrbugs:

- Deterministic, reproducible bugs
- Behave similar to Bohr's atom model where electrons deterministically orbit the nucleus

Heisenbugs

- Non-deterministic, hard to reproduce bugs
 - → Often caused by race conditions
- Suffer from the observer effect (Heisenberg Uncertainty Principle): attempts to observe them (i.e., printfs) make them disappear!

Which bug would you rather have?

- During development/testing:
- During deployment: _____

Communication & Synchronization Summary

Signals: really interaction with kernel, to wake a waiting process or indicate a problem.

Pipes: simple read, write type communication

Shared memory: requires synchronisation to prevent corruption

Critical section: code in which process accesses shared resource

Mutual exclusion: only 1 process at a time within CS

Disabling interrupts: may not be effective

Locks: low level, busy wait, very difficult to program correctly

Semaphores: blocks waiting program, but difficult to program

Monitors: easier to program, but signal semantics can be tricky