

# Lab – CLI Automation with Python using netmiko

#### **Objectives**

Part 1: Install the netmiko Python module

Part 2: Connect to IOS XE's SSH service using netmiko

Part 3: Use netmiko to gather information from the device

Part 4: Use netmiko to alter configuration on the device

#### Background / Scenario

For simple network automation using a remote telnet or ssh based command line, network administrators have been using various screen scraping techniques for a long period of time. Initially the "expect" based scripts we utilized to automate entering commands when a specific expected string appeared on the command line. With the evolution of the Python language, the netmiko Python module has emerged as an open source project hosted and maintained on GitHub.com that provides a simple network automation interface using similar techniques like the "expect" based scripts.

In this lab activity, you will identify the potential but also the limitations of using netmiko to transport CLI commands for network automation.

#### **Required Resources**

- Access to a router with the IOS XE operating system version 16.6 or higher.
- · Access to the Internet
- Python 3.x environment

#### Instructions

# Part 1: Install the netmiko Python module

In this part, you will install netmike module into your Python environment. Netmike is a python module that simplifies ssh CLI connection to network devices. It has built in functionality to identify to execute "exec mode" commands, as well as apply new commands in the running configuration.

Explore the netmiko module on the project GitHub repository: https://github.com/ktbyers/netmiko

# Step 1: Use pip to install netmiko.

- a. Start a new Windows command prompt (cmd).
- b. Install netmiko using pip in the Windows command prompt:

```
pip install netmiko
```

c. Verify that netmiko has been successfully installed. Start Python IDLE and in the interactive shell try to import the netmiko module:

```
import netmiko
```

## Part 2: Connect to IOS XE's SSH service using netmiko

#### Connect to IOS XE's SSH service using netmiko.

The netmiko module provides a "ConnectHandler ()" function to setup the remote ssh connection. After a successful connection, the returned object represents the ssh cli connection to the remote device.

- a. In Python IDLE, create a new Python script file:
- b. In the new Python script file editor, import the "ConnectHandler ()" function from the netmiko module:

```
from netmiko import ConnectHandler
```

c. Setup a sshCli connection object using the ConnectHandler() function to the IOS XE device.

```
sshCli = ConnectHandler(
    device_type='cisco_ios',
    host='192.168.56.101',
    port=22,
    username='cisco',
    password='cisco123!'
)
```

The parameters of the ConnectHandler () function are:

- device\_type identifies the remote device type
- host the address (host or IP) of the remote device (adjust the IP address "192.168.56.101" to match your router's current address)
- port the remote port of the ssh service
- username remote ssh username (in this lab "cisco" for that was setup in the IOS XE VM)
- password remote ssh password (in this lab "cisco123!" for that was setup in the IOS XE VM)

# Part 3: Use netmiko to gather information from the device

## Send show commands and display the output

a. Using the sshCli object, returned by the ConnectHandler() function that represents the ssh cli remote session, send some "show" command and print the output. Use the send\_command() function of the sshCli object with a string parameter that represents the command you wish to execute in the exec mode:

```
output = sshCli.send_command("show ip int brief")
print("show ip int brief:\n{}\n".format(output))
```

b. Execute the Python script file to see the results.

If you have not saved the script file yet, you will be prompted to save it before it is executed.

c. Verify the results:

```
RESTART: O:\tmp\Ch2_Files\Python Files with Solutions\lab 2.2 - CLI Automation with Python using netmiko - sol.py
Sending 'sh ip int brief'.
IP interface status and configuration:
Interface IP-Address OK? Method Status Protocol GigabitEthernet1 192.168.56.101 YES DHCP up up
```

d. Verify the data type of the "output" variable. How would you extract the IP address and the Interface Name into variables? What if there were multiple interfaces?

## Part 4: Use netmiko to alter configuration on the device

In the following steps, you will alter the configuration of the device by creating new loopback interfaces.

#### Create a new loopback interface

Using the sshCli object, returned by the ConnectHandler() function that represents the ssh cli remote session, send some configuration command and print the output. Use the send\_config\_set() function of the sshCli object with a list parameter including the configuration commands as strings you wish to execute in the exec mode:

Execute the Python script file and verify the results

Why does the output from "show ip int brief" not include the "loopback1" interface?

How to execute and display the output from the "show ip int brief" command after the loopback interfaces was created?

## Lab - CLI Automation with Python using netmiko

Add code to	create a	new lo	opback	interface	(loopback2)	with	the same	IP a	address	as on	the	existing	loopba	ack
interface, on	ly with a	differe	nt descri	ption.								_	-	

Execute the Python script file and verify the results.

Was the new loopback2 interface successfully created?

Was the new configuration change accepted, partially accepted or rejected?