厦門大學

信息学院软件工程系

《计算机网络》实验报告

题　　目 实验五 CISCO IOS 路由器基本配置

班　　级 软件工程 2018 级 1 班

姓　　名 詹世彬

学　　号 24320182203321

实验时间 2020 年 4 月 8 日

2020 年 4 月 19 日

1 实验目的

1、理解路由协议的分类。

2、掌握路由器的基本配置以及静态路由、动态路由和交换机端口 VLAN 的配置方法。

2 实验环境

Windows 10，Router eSIM v1.0，CCNA Network Visualizer 6.0

3 实验结果

1、使用 Router eSIM v1.0 模拟器来模拟路由器的基本配置

```
Router>enable
Router#config t
Enter configuration commands, one per line.  End with END.
Router(config)#hostname lab_A
lab_A(config)#banner motd #
Enter TEXT message.  End with the character '#'.
Accounting Department
You have entered a secured system
Authorized access only' #
lab_A(config)#ip host lab_A 192.5.5.1 205.7.5.1 201.100.11.1
lab_A(config)#ip host lab_B 219.17.100.1 199.6.13.1 201.100.11.2
lab_A(config)#ip host lab_c 223.8.151.1 204.204.7.1 199.6.13.2
lab_A(config)#ip host lab_D 210.93.105.1 204.204.7.2
lab_A(config)#ip host lab_E 210.93.105.2
lab_A(config)#ip host lab_C 223.8.151.1 204.204.7.1 201.100.11.2
lab_A(config)#int eth 0
lab_A(config-if)#ip address 192.5.5.1 255.255.255.0
lab_A(config-if)#int eth 1
lab_A(config-if)#ip address 205.7.5.1 255.255.255.0
lab_A(config-if)#int serial 0
lab_A(config-if)#ip address 201.100.11.1 255.255.255.0
```

```
lab_A#config t
Enter configuration commands, one per line.  End with END.
lab_A(config)#interface serial 0
lab_A(config-if)#clock rate 56000
```

```
lab_A#show interface serial 0
Serial0 is administratively down, line protocol is down
   Internet address is 201.100.11.1/24
   Hardware is HD64570
   MTU 1500 bytes, BW 1544 Kbit, DLY 20000 usec,
      reliability 255/255, txload 1/255, rxload 1/255
   Encapsulation HDLC, loopback not set
   Keepalive set (10 sec)
   Last input never, output never, output hang never
   Last clearing of "show interface" counters never
   Input queue: 0/75/0 (size/max/drops); Total output drops: 0
   Queueing strategy: weighted fair
   Output queue: 0/1000/64/0 (size/max total/threshold/drops)
      Conversations  0/0/256 (active/max active/max total)
      Reserved Conversations 0/0 (allocated/max allocated)
   5 minute input rate 0 bits/sec, 0 packets/sec
   5 minute output rate 0 bits/sec, 0 packets/sec
      0 packets input, 0 bytes, 0 no buffer
      Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
      0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
      0 packets output, 0 bytes, 0 underruns
      0 output errors, 0 collisions, 1 interface resets
      0 output buffer failures, 0 output buffers swapped out
```

2、静态路由配置

（1）对整个界面进行布局



（2）对 Router A 进行配置：

```
Router>enable
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z
Router(config)#hostname RouterA
RouterA(config)#int f0/0
RouterA(config-if)#ip address 192.5.5.1 255.255.255.0
RouterA(config-if)#no shutdown
10:07:35 %LINK-3-UPDOWN:  Interface FastEthernet0/0, changed state to up
10:07:35 %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

RouterA(config-if)#int f0/1
RouterA(config-if)#ip address 205.7.5.1 255.255.255.0
RouterA(config-if)#no shutdown
10:08:13 %LINK-3-UPDOWN:  Interface FastEthernet0/1, changed state to up
10:08:13 %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

RouterA(config-if)#int s0/0
RouterA(config-if)#ip address 201.100.11.1 255.255.255.0
RouterA(config-if)#clock rate 56000
%Error: This command applies only to DCE interfaces
RouterA(config-if)#no shutdown
10:09:19 %LINK-3-UPDOWN:  Interface Serial0/0, changed state to up
10:09:19 %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up

RouterA(config-if)#exit
RouterA(config)#exit
RouterA#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, * - candidate default
       U - per-user static route, o - ODR, P - periodic downloaded static route
       T - traffic engineered route

Gateway of last resort is not set
C     201.100.11.0/24 is directly connected, Serial0/0
C     205.7.5.0/24 is directly connected, FastEthernet0/1
C     192.5.5.0/24 is directly connected, FastEthernet0/0
RouterA#
```

（3）对 Router B 进行配置：

```
Router>enable
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z
Router(config)#hostname RouterB
RouterB(config)#int f0/0
RouterB(config-if)#ip address 199.6.13.1 255.255.255.0
RouterB(config-if)#no shutdown
11:57:38 %LINK-3-UPDOWN:  Interface FastEthernet0/0, changed state to up
11:57:38 %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

RouterB(config-if)#int s0/0
RouterB(config-if)#ip address 201.100.11.2 255.255.255.0
RouterB(config-if)#no shutdown
11:58:44 %LINK-3-UPDOWN:  Interface Serial0/0, changed state to up
11:58:44 %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up

RouterB(config-if)#exit
RouterB(config)#exit
RouterB#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, * - candidate default
       U - per-user static route, o - ODR, P - periodic downloaded static route
       T - traffic engineered route

Gateway of last resort is not set
C     201.100.11.0/24 is directly connected, Serial0/0
C     199.6.13.0/24 is directly connected, FastEthernet0/0
RouterB#
```

（4）在 Router A 上，通过 ping 命令测试到路由器 Router B 的直连网络地址 199.6.13.1 是否连通：

```
RouterA>ping 199.6.13.1

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 199.6.13.1, timeout is 2 seconds:
.....
Success rate is 0 percent (0/5), round-trip min/avg/max = 0/0/0 ms
RouterA>
```

（5）配置静态路由

```
RouterA>enable
RouterA#config t
Enter configuration commands, one per line.  End with CNTL/Z
RouterA(config)#ip route 199.6.13.1 255.255.255.0 201.100.11.2
RouterA(config)#exit
RouterA#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, * - candidate default
       U - per-user static route, o - ODR, P - periodic downloaded static route
       T - traffic engineered route

Gateway of last resort is not set
C     192.5.5.0/24 is directly connected, FastEthernet0/0
C     205.7.5.0/24 is directly connected, FastEthernet0/1
S     199.6.13.1 [1/0] via 201.100.11.2
C     201.100.11.0/24 is directly connected, Serial0/0
```

（6）检验连通性

```
RouterA#ping 199.6.13.1

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 199.6.13.1, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 4/4/4 ms
```

3、动态路由 RIP 协议的配置

```
RouterA(config)#router rip

RouterA(config-router)#network 199.6.13.1
```

```
RouterA#show ip protocols
Routing Protocol is "rip"
  Sending updates every 30 seconds, next due in 12 seconds
  Invalid after 180 seconds, hold down 180, flushed after 240
  Outgoing update filter list for all interfaces is not set
  Incoming update filter list for all interfaces is not set
  Redistributing: rip
  Default version control: send version 1, receive any version
    Interface             Send  Recv  Triggered RIP  Key-chain
    Serial0/0             1     1 2
    FastEthernet0/1       1     1 2
    FastEthernet0/0       1     1 2
  Automatic network summarization is in effect
  Maximum path: 4
  Routing for networks:
    199.6.13.0
  Routing information sources:
    Gateway         Distance      Last Update
  Distance: <default is 120>
```

4、VLAN 的配置



（1）设置 VTP 域

```
switch>en
switch#config t
Enter configuration commands, one per line.  End with CNTL/Z
switch(config)#hostname 3550A
3550A(config)#vpt domain Cisco
               ^
% Invalid input detected at '^' marker.
3550A(config)#vtp domain Cisco
Changing VTP domain name from NULL to Cisco
3550A(config)#exit
3550A#show vtp status
VTP Version                     : 2
Configuration Revision          : 1
Maximum VLANs supported locally : 64
Number of existing VLANs        : 5
VTP Operating Mode              : Server
VTP Domain Name                 : Cisco
VTP Pruning Mode                : Disabled
VTP V2 Mode                     : Disabled
VTP Traps Generation            : Disabled
MD5 digest                      : 0x70 0x01 0xF2 0x72 0x97 0xA1 0x35 0xEB
Configuration last modified by: 0.0.0.0 at 11-29-93 20:39:24
Local updater ID is 0.0.0.0 on interface Vl1 (lowest numbered VLAN interface
found)
3550A#
```

```
switch>en
switch#conf t
Enter configuration commands, one per line.  End with CNTL/Z
switch(config)#hostname 2950A
2950A(config)#vtp domain Cisco
Changing VTP domain name from NULL to Cisco
2950A(config)#vtp mode ?
  client       Set the device to client mode.
  server       Set the device to server mode.
  transparent  Set the device to transparent mode.

2950A(config)#vtp mode client
Setting device to VTP CLIENT mode.
2950A(config)#exit
2950A#show vtp status
VTP Version                     : 2
Configuration Revision          : 0
Maximum VLANs supported locally : 64
Number of existing VLANs        : 4
VTP Operating Mode              : Client
VTP Domain Name                 : Cisco
VTP Pruning Mode                : Disabled
VTP V2 Mode                     : Disabled
VTP Traps Generation            : Disabled
MD5 digest                      : 0x70 0x01 0xF2 0x72 0x97 0xA1 0x35 0xEB
Configuration last modified by: 0.0.0.0 at 11-29-93 20:39:24
Local updater ID is 0.0.0.0 on interface Vl1 (lowest numbered VLAN interface
found)
```

```
switch>en
switch#conf t
Enter configuration commands, one per line.  End with CNTL/Z
switch(config)#hostname 2950B
2950B(config)#vtp domain Cisco
Changing VTP domain name from NULL to Cisco
2950B(config)#vtp mode client
Setting device to VTP CLIENT mode.
2950B(config)#exit
```

（2）设置 Trunk

```
3550A>en
3550A#config t
Enter configuration commands, one per line.  End with CNTL/Z
3550A(config)#interface fa0/1
3550A(config-if)#switchport trunk encapsulation ?
  dotlq      Interface uses only 802.1q trunking encapsulation when trunking
  isl        Interface uses only ISL trunking encapsulation when trunking
  negotiate  Device will negotiate trunking encapsulation with peer on
             interface

3550A(config-if)#switchport trunk encapsulation dotlq
                                                ^
% Invalid input detected at '^' marker.
3550A(config-if)#switchport trunk encapsulation dotlq
13:09:32: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state
to down
13:09:32: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
3550A(config-if)#switchport mode trunk
3550A(config-if)#interface fa0/3
3550A(config-if)#switch trunk encapsulation dotlq
13:10:20: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/3, changed state
to down
13:10:20: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/3, changed state to up
3550A(config-if)#switchport mode trunk
```

```
2950A>en
2950A#config t
Enter configuration commands, one per line.  End with CNTL/Z
2950A(config)#interface fa0/11
2950A(config-if)#switchport mode trunk
```

```
2950B>en
2950B#config t
Enter configuration commands, one per line.  End with CNTL/Z
2950B(config)#interface fa0/11
2950B(config-if)#switchport mode trunk
```

（3）创建 VLAN

```
3550A>en
3550A#config t
Enter configuration commands, one per line.  End with CNTL/Z
3550A(config)#vlan 10
3550A(config-vlan)#vlan 20
3550A(config-vlan)#exit
3550A(config)#exit
3550A#show vlan

VLAN Name                              Status    Ports
---- --------------------------------- --------- -------------------------------
1    default                           active    Fa0/2, Fa0/3, Fa0/4, Fa0/5
                                                 Fa0/6, Fa0/7, Fa0/8, Fa0/9
                                                 Fa0/10
10   VLAN0010                          active
20   VLAN0020                          active
1002 fddi-default                      active
1003 token-ring-default                active
1004 fddinet-default                   active
1005 trnet-default                     active

VLAN Type  SAID       MTU   Parent RingNo BridgeNo Stp  BrdgMode Trans1 Trans2
---- ----- ---------- ----- ------ ------ -------- ---- -------- ------ ------
1    enet  100001     1500  -      -      -        -    -        0      0
10   enet  100010     1500  -      -      -        -    -        0      0
20   enet  100020     1500  -      -      -        -    -        0      0
1002 fddi  101002     1500  -      -      -        -    -        0      0
1003 tr    101003     1500  -      -      -        -    -        0      0
1004 fdnet 101004     1500  -      -      -        ieee -        0      0
1005 trnet 101005     1500  -      -      -        ibm  -        0      0
--More--
3550A#
```

（4）分配交换机端口加入 VLAN

```
2950A>en
2950A#config t
Enter configuration commands, one per line.  End with CNTL/Z
2950A(config)#interface fa0/2
2950A(config-if)#switchport access vlan 10
```

```
2950B>en
2950B#config t
Enter configuration commands, one per line.  End with CNTL/Z
2950B(config)#interface fa0/2
2950B(config-if)#switchport access vlan 20
```

（5）配置第三层交换机

```
3550A>en
3550A#config t
Enter configuration commands, one per line.  End with CNTL/Z
3550A(config)#int vlan 10
3550A(config-if)#ip address 10.10.10.1 255.255.255.0
3550A(config-if)#int vlan 20
3550A(config-if)#ip address 20.20.20.1 255.255.255.0
3550A(config-if)#no shut
3550A(config-if)#exit
3550A(config)#ip routing
3550A(config)#int vlan 1
3550A(config-if)#ip address 192.168.10.1 255.255.255.0
3550A(config-if)#no shut
```

```
2950A>en
2950A#config t
Enter configuration commands, one per line.  End with CNTL/Z
2950A(config)#int vlan 1
2950A(config-if)#ip address 192.168.10.2 255.255.255.0
2950A(config-if)#no shutdown
```

```
2950B>en
2950B#config t
Enter configuration commands, one per line.  End with CNTL/Z
2950B(config)#int vlan 1
2950B(config-if)#ip address 192.168.10.3 255.255.255.0
2950B(config-if)#no shutdown
```

（6）配置主机并进行测试





```
3550A>en
3550A#ping 192.168.10.2

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.168.10.2, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 4/4/4 ms
3550A#ping 192.168.10.3

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.168.10.3, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 4/4/4 ms
```

```
C:\>ping 20.20.20.2

Pinging 20.20.20.2 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping Statistics for 20.20.20.2:
    Packets Sent = 4, Received = 0, Lost = 4 (100% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
```

4 实验总结

通过这次实验，对路由协议的分类以及 IP 地址的分配有了更深的了解，掌握了路由器的基本配置以及静态路由、动态路由和交换机端口 VLAN 的配置方法，通过对所学知识加以应用，让所学的知识印象深刻。