# Thermodynamics

# Problem Set 3

Thermodynamic Potentials and Methods

Xin, Wenkang January 22, 2024

## More Practice

## **A.1**

(a) The entropy change of the water is:

$$\Delta S_w = \int_{T_1}^{T_2} \frac{C}{T} dT = C \ln \frac{T_2}{T_1}$$
 (1)

The entropy change of the 100 °C reservoir is:

$$\Delta S_r = \frac{Q}{T_2} = C \frac{T_1 - T_2}{T_2} \tag{2}$$

The total entropy change is:

$$\Delta S_{uni} = \Delta S_w + \Delta S_r \tag{3}$$

(b) The entropy change of the water is unchanged while the entropy change of the reservoirs is:

$$\Delta S_r = C \frac{T_3 - T_1}{T_3} + C \frac{T_2 - T_3}{T_2} \tag{4}$$

The total entropy change is:

$$\Delta S_{uni} = \Delta S_w + \Delta S_r \tag{5}$$

(c) For a reversible process, the total entropy change is zero. The water obtains a heat  $Q = C(T_2 - T_1)$  from the reservoir. The entropy change of the reservoir is:

$$\Delta S_r = -\frac{Q}{T_2} = -C \frac{T_2 - T_1}{T_2} \tag{6}$$

and to have a total entropy change of zero, the entropy change of the water must be:

$$\Delta S_w = -\Delta S_r = C \frac{T_2 - T_1}{T_2} \tag{7}$$

1

#### **A.2**

Assume without loss of generality that  $T_2 > T_1$ . Let  $Q_2$  be the heat drawn from the hot reservoir and  $Q_1$  be the heat released to the cold reservoir. The work done by the engine is  $W = Q_2 - Q_1$ . At final common temperature  $T_f$ , the changes of internal energy of the two reservoirs are:

$$\Delta U_1 = C_p(T_f - T_1)$$

$$\Delta U_2 = C_p(T_f - T_2)$$
(8)

By first law, we have  $Q_1 = \Delta U_1$  and  $Q_2 = -\Delta U_2$ . The work done by the engine is:

$$W = Q_2 - Q_1 = -\Delta U_2 - \Delta U_1 = C_p(T_1 + T_2 - 2T_f)$$
(9)

The efficiency of the engine is:

$$\eta = \frac{W}{Q_2} = \frac{T_1 + T_2 - 2T_f}{T_2 - T_f} \tag{10}$$

Maximising the efficiency with respect to  $T_f$ , we need:

$$\frac{(T_2 - T_f)(-2) - (T_1 + T_2 - 2T_f)(-1)}{(T_2 - T_f)^2} = 0$$
(11)

#### **A.3**

The combustion heat of the fuel is given by:

$$\Delta Q = \rho V H_c \tag{12}$$

The total input heat has the additional potential energy term:

$$Q_{in} = \Delta Q + U_0 \tag{13}$$

By first law, the work done by the engine is:

$$W = Q_{in} - Q_{out} = \Delta Q + U_0 - U_f = \rho V [H_c + c_p (T_0 - T_f)]$$
(14)

Using a specific heat capacity  $c_p = 2.22 \times 10^3 \, \mathrm{J \, kg^{-1} \, K^{-1}}$  for air, we have  $W = 3.96 \times 10^6 \, \mathrm{J}$ . The maximum height is thus:

$$h = \frac{W}{mg} = 40.3 \,\mathrm{m} \tag{15}$$

**A.4** 

The heat input happens during the isobaric expansion:

$$Q_{in} = C_p(T_3 - T_2) = \frac{1}{\gamma - 1} P_2(V_3 - V_2)$$
(16)

The heat output happens during the isochroic compression:

$$Q_{out} = C_v(T_4 - T_1) = \frac{\gamma}{\gamma - 1} V_1(p_4 - p_1)$$
(17)

The efficiency of the engine is:

$$\eta = 1 - \frac{Q_{out}}{Q_{in}} = 1 - \frac{C_v(T_4 - T_1)}{C_p(T_3 - T_2)} = 1 - \frac{\gamma}{\gamma - 1} \frac{V_1(p_4 - p_1)}{p_2(V_3 - V_2)}$$
(18)

Since the pairs  $(p_1, V_1)$ ,  $(p_2, V_2)$  and  $(p_2, V_3)$ ,  $(p_4, V_1)$  are on the same reversible adiabat, we have:

$$\frac{p_1}{p_2} = \left(\frac{V_2}{V_1}\right)^{\gamma} 
\frac{p_4}{p_2} = \left(\frac{V_3}{V_1}\right)^{\gamma}$$
(19)

Therefore, we can write:

$$\eta = 1 - \frac{\gamma}{\gamma - 1} \frac{(V_3/V_1)^{\gamma} - (V_2/V_1)^{\gamma}}{V_3/V_1 - V_2/V_1} \tag{20}$$

## Potentials and Maxwell Relations

#### **B.1**

We know from Gibbs-Duhem equation that  $SdT - Vdp + nd\mu = 0$ . Given that dT is zero, we have:

$$n = V \frac{\mathrm{d}p}{\mathrm{d}\mu} = \frac{V}{\mathrm{d}\mu/\mathrm{d}p} = \frac{pV}{k_B T} \tag{21}$$

#### B.2

The change in internal energy is just  $\Delta U = W$ . Since the process is reversible and adiabatic, we have Q = 0 and  $\Delta S = 0$ . We will be able to know the change in enthalpy as dH = TdS + Vdp and dS is zero so the change in enthalpy is:

$$\Delta H = \int_{p_1}^{p_2} V dp = p_2 V_2 - p_1 V_1 - \int_{V_1}^{V_2} p dV = p_2 V_2 - p_1 V_1 + W$$
(22)

We cannot tell the change in F or G since we do not know the temperature. If we do know that the temperature is kept constant, we will have  $\Delta F = W$  and  $\Delta G = \Delta H$ .

•

#### **B.3**

Consider the equation dU = TdS - pdV. We have  $T = (\partial U/\partial S)_V$  and  $p = -(\partial U/\partial V)_S$ . Therefore, we can write:

$$\left(\frac{\partial T}{\partial V}\right)_S = -\left(\frac{\partial p}{\partial S}\right)_V \tag{23}$$

Next consider dH = TdS + Vdp. We have  $T = (\partial H/\partial S)_p$  and  $V = (\partial H/\partial p)_S$ . Therefore:

$$\left(\frac{\partial T}{\partial p}\right)_S = \left(\frac{\partial V}{\partial S}\right)_p \tag{24}$$

Then consider dF = -SdT - pdV. We have  $S = -(\partial F/\partial T)_V$  and  $p = -(\partial F/\partial V)_T$  and:


$$\left(\frac{\partial S}{\partial V}\right)_T = \left(\frac{\partial p}{\partial T}\right)_V \tag{25}$$

Finally consider dG = -SdT + Vdp. We have  $S = -(\partial G/\partial T)_p$  and  $V = (\partial G/\partial p)_T$ . Thus:

$$\left(\frac{\partial S}{\partial p}\right)_T = -\left(\frac{\partial V}{\partial T}\right)_p \tag{26}$$

•

## **B.4**



For an isotherm, p = T/V where T is constant. For an adiabat,  $p = C/V^{\gamma}$  where C is constant. The two curves intersect at some  $(p_0, V_0)$ . The area under graph for the isotherm is apparently larger than that for the adiabat. The extra work done comes from the heat transfer from the hot reservoir.

•

#### **B.5**

A chemical reaction that happens slowly and exposed to the atmosphere (e.g. rusting) is isobaric and isothermal. Since dG = V dp - S dT, we have dG = 0 and the Gibbs free energy is constant for this process.

•

#### **B.6**

(i) Consider the ordinary internal energy dU = TdS - pdV. There is extra work done by the external force f on the rubber so that we modify the equation to:

$$dU = TdS - pdV + fdL \tag{27}$$

where the sign for f is positive as the external force is doing positive work.

(ii) Consider dU - d(fL), which we define as dX:

$$dX = TdS - pdV - Ldf (28)$$

Next, consider dX + d(pV), which we define as dY:

$$dY = TdS + Vdp - Ldf \tag{29}$$

(ii) Let us further define dZ = dU - d(TS) + d(pV):

$$dZ = -SdT + Vdp + fdL \tag{30}$$

Since dZ is an exact differential, we must have  $Z_{T,L} = Z_{L,T}$ . Noting this, we have:

$$\left(\frac{\partial S}{\partial L}\right)_{T,p} = -\frac{\partial}{\partial L} \left(\frac{\partial Z}{\partial T}\right) 
= -\frac{\partial}{\partial T} \left(\frac{\partial Z}{\partial L}\right) 
= -\left(\frac{\partial f}{\partial T}\right)_{p,L}$$
(31)

## Applications (Rod, Surface, Magnetization, Solid)

## C.1

For an elastic rod, we have the expression for the internal energy:

$$dU = TdS + fdL \tag{32}$$

The heat capacity at constant length is defined as:

$$C_L = T \left( \frac{\partial S}{\partial T} \right)_L \tag{33}$$

Let us define the 'Helmholtz free energy' as  $d\tilde{F} = -SdT + fdL$ . We have the Maxwell relation:

$$\left(\frac{\partial S}{\partial L}\right)_T = -\left(\frac{\partial f}{\partial T}\right)_L \tag{34}$$

This implies:

$$\left(\frac{\partial C_L}{\partial L}\right)_T = T \left(\frac{\partial^2 S}{\partial L \partial T}\right)_L 
= -T \left(\frac{\partial^2 f}{\partial T^2}\right)_L$$
(35)

#### C.2

For a liquid, we have:

$$dU = TdS + \sigma dA \tag{36}$$

where  $\sigma$  is surface tension as a function of temperature.

Consider the quantity:

$$dX = TdS - Ad\sigma \tag{37}$$

where  $d\sigma/dT = -1.28\sigma_0(1 - T/T_c)^{0.28}/T_0$