
Kepler's law:

$$T^2 = \frac{4\pi^2 a^3}{GM}$$

$$E_{tot} = -\frac{GMm}{2a}$$


Angular Momentum Conservation:



$$mv_1r_1=mv_2r_2=\mathcal{L}$$

$$rac{L^2}{2m^2} = rac{GM}{\left(rac{1}{r_1} + rac{1}{r_2}
ight)} = rac{GMb^2}{2a}$$

Shape parameters: a: semi-major axis, b: semi-minor axis, c: linear eccentricity, p: semi-latus rectum



# Orbital and escape velocity. Different orbits:

The orbit shape will depend on the choices of  $r_0$  and  $v_0$ . The escape speed of an object at a radius r from the center of Earth is

$$v_{esc} = \sqrt{\frac{2GM}{r}}.$$

If

$$v > \sqrt{\frac{2GM}{r}},$$

the object will have a hyperbolic escape trajectory.

If

$$v=\sqrt{\frac{GM}{r}},$$

the object will have a circular orbit.

If

$$\sqrt{\frac{2GM}{r}}>v>\sqrt{\frac{GM}{r}},$$

the object has an elliptical orbit starting closest to Earth.

If

$$\sqrt{\frac{GM}{r}} > v > 0,$$

the object has an elliptical orbit starting furthest from Earth.

**Problem 2.** Masses of two stars forming a binary star are  $m_1$  and  $m_2$ . They rotate around each other (more accurately, around their center of mass), at distance l. Determine the period of their rotation.

**Solution:** The center of mass is at distances  $l_1 = \frac{m_2 l}{m_1 + m_2}$  and  $l_2 = \frac{m_1 l}{m_1 + m_2}$  from the two stars, respectively. This comes from  $l_1 + l_2 = l$  and  $m_1 l_1 = m_2 l_2$ . The centripetal force is the gravity, so if their angular velocity is  $\omega$ 

$$m_1 l_1 \omega^2 = G \frac{m_1 m_2}{l^2}.$$

Therefore,

$$T = \frac{2\pi}{\omega} = 2\pi \sqrt{\frac{l^3}{G(m_1 + m_2)}}.$$

Elastic collision: u is velocity before collision; v is after.

$$v_1 = rac{m_1 - m_2}{m_1 + m_2} u_1 + rac{2m_2}{m_1 + m_2} u_2$$

$$v_2 = rac{2m_1}{m_1+m_2}u_1 + rac{m_2-m_1}{m_1+m_2}u_2$$

$$v_1 + u_1 = u_2 + v_2$$



$$v_y = v_0 - gt$$

$$y = v_0 t - \frac{gt^2}{2}$$

$$y = v_0 t - \frac{gt^2}{2} \qquad v_y^2 = v_0^2 - 2gy$$

General projectile motion with  $v_0$  and  $\theta$  (+ is up)

$$v_x = \text{const} = v_0 \cos \theta$$

$$x = v_x t = v_0 t \cos \theta$$

$$v_y = v_0 \sin \theta - gt$$

$$v_y = v_0 \sin \theta - gt$$

$$y = v_0 t \sin \theta - \frac{gt^2}{2}$$

$$v_y^2 = v_0^2 \sin^2 \theta - 2gy$$

$$v_y^2 = v_0^2 \sin^2 \theta - 2gy$$

$$y(x) = x \tan \theta - \frac{g}{2v_0^2 \cos^2 \theta} x^2$$
  $v^2 = v_x^2 + v_y^2$ 

$$v^2 = v_x^2 + v_y^2$$

Time in air: 
$$T = \frac{2v_0 \sin \theta}{g}$$
 Horiz.range:  $R_x = \frac{v_0^2 \sin 2\theta}{g}$  Vert.range:  $R_y = \frac{v_0^2 \sin^2 \theta}{2g}$ 

$$R_x = \frac{v_0^2 \sin 2\theta}{q}$$

$$R_y = \frac{v_0^2 \sin^2 \theta}{2q}$$

List of moment of inertia:

https://en.wikipedia.org/wiki/List\_of\_moments\_of\_inertia

# Bernoulli's principle

A common form of Bernoulli's equation is:

$$\frac{v^2}{2} + gz + \frac{p}{\rho} = \text{constant}$$

# Torricelli's law

Article Talk

From Wikipedia, the free encyclopedia

Torricelli's law, also known as Torricelli's theorem, is a theorem in fluid dynamics relating the speed of fluid flowing from an orifice to the height of fluid above the opening. The law states that the speed v of efflux of a fluid through a sharp-edged hole at the bottom of the tank filled to a depth h is the same as the speed that a body would acquire in falling freely from a height h, i.e.  $v=\sqrt{2gh}$ , where g is the acceleration due to gravity. This expression comes from equating the kinetic energy gained,  $\frac{1}{2}mv^2$ , with the potential energy lost, mgh, and solving for v. The law was discovered (though not in this form) by the Italian scientist Evangelista Torricelli, in 1643. It was later shown to be a particular case of Bernoulli's principle.

# **Venturi Effect**

The **Venturi effect** is the reduction in fluid pressure that results when a fluid flows through a constricted section (or choke) of a pipe. The Venturi effect is named after its discoverer, the 18th-century Italian physicist Giovanni Battista Venturi.

4

$$p_1-p_2=rac{
ho}{2}(v_2^2-v_1^2)$$

### Rotation from ramp:

**Problem 3.** We are given an object that can roll down a slope and has a moment of inertia  $I = cmr^2$ . For example,

- a hollow cylinder with mass m and radius r has c = 1
- a solid cylinder with mass m and radius r has c = 1/2
- a hollow sphere with mass m and radius r has c = 2/3
- a solid ball with mass m and radius r has c = 2/5

The object rolls without slipping down a slope with angle  $\theta$  to the horizon. Determine its acceleration. Note: If the object did not roll, i.e., if it was just sliding down the slope, the acceleration would be  $a = g \sin \theta$ .

Solution: One way to obtain this result is to write the equation for energies before the object starts rolling and when it traveled distance s along the slope,

$$E_p = E_k^{lin} + E_k^{rot} \quad \Rightarrow \quad mgh = \frac{mv^2}{2} + \frac{I\omega^2}{2}$$

There is no slipping so  $v = \omega r$ . Also,  $h = s \sin \theta$  and we know  $I = cmr^2$ , so

$$2gs\sin\theta = v^2 + cv^2$$
  $\Rightarrow$   $v^2 = \frac{2gs\sin\theta}{1+c}$ .

Combining this with 
$$v^2 = 2as$$
 we get  $a = \frac{v^2}{2s} = \frac{g\sin\theta}{1+c}$ .

Problem 4. Using the result of the previous problem, discuss the factors that influence how fast an object will reach the bottom of a slope: radius, mass, density, shape, then order the following objects from fastest to slowest down the slope: (a) small hollow sphere made of light wood, (b) small hollow sphere made of lead, (c) large hollow sphere made of lead, (d) small solid ball made of copper, (e) large solid ball made of copper, (f) large hollow cylinder made of copper, (g) large solid cylinder made of copper.

Solution: From  $a = \frac{g \sin \theta}{1+c}$  we see that only the shape and of the object determines how fast it will get to the bottom of the slope, nothing else. Mass, density, radius, none of that matters. Therefore, they will arrive in the order of increasing values of parameter c:

- solid balls (small and large)
- solid cylinder
- hollow spheres (two small and one large)
- hollow cylinder

Condition for rolling without slip from a ramp:

Because slipping does not occur,  $f_{
m S} \leq \mu_{
m S} N$ . Solving for the friction force,

$$f_{\rm S} = I_{\rm CM} \tfrac{\alpha}{r} = I_{\rm CM} \tfrac{(a_{\rm CM})}{r^2} = \tfrac{I_{\rm CM}}{r^2} (\tfrac{mg\sin\theta}{m + (I_{\rm CM}/r^2)}) = \tfrac{mgI_{\rm CM}\sin\theta}{mr^2 + I_{\rm CM}}.$$

Substituting this expression into the condition for no slipping, and noting that  $N=mg\cos heta$  , we have

$$rac{mgI_{ ext{CM}}\sin heta}{mr^2+I_{ ext{CM}}} \leq \mu_{ ext{S}}mg\cos heta$$

or

$$\mu_{
m S} \geq rac{ an heta}{1+(mr^2/I_{
m CM})}.$$

Period of pendulum with large angle: grows with theta and converges to a finite number

$$T = 2\pi \sqrt{\frac{L}{g}} \left[ 1 + \frac{1}{16} \theta_0^2 + \frac{11}{3072} \theta_0^4 + \dots \right]$$

# Damped simple harmonic motion:

- ullet The mechanical energy E in a real oscillating system decreases during the oscillations because external forces, such as a drag force, inhibit the oscillations and transfer mechanical energy to thermal energy. The real oscillator and its motion are then said to be damped.
- ullet If the damping force is given by  $\vec{F}_d = -b \vec{v}$ , where  $\vec{v}$  is the velocity of the oscillator and b is a damping constant, then the displacement of the oscillator is given by

$$x(t) = x_m e^{-bt/2m} \cos(\omega' t + \phi),$$

where  $\omega'$ , the angular frequency of the damped oscillator, is given by

$$\omega' = \sqrt{\frac{k}{m} - \frac{b^2}{4m^2}}.$$

• If the damping constant is small  $(b \ll \sqrt{km})$ , then  $\omega' \approx \omega$ , where  $\omega$  is the angular frequency of the undamped oscillator. For small b, the mechanical energy E of the oscillator is given by


$$E(t) \approx \frac{1}{2}kx_m^2 e^{-bt/m}.$$

Angular frequency for small oscillation around equilibrium point:  $\pmb{\omega} = \sqrt{rac{V''(x_0)}{m}}$ 

Where V is the potential, x0 is the equilibrium point

# **Physical Pendulum**

Hanging objects may be made to oscillate in a manner similar to a simple pendulum. The motion can be described by "Newton's 2nd law for rotation":



$$\tau = I_{\text{support}} \alpha$$

where the torque is

$$\tau = -mgL_{cm}\sin\theta$$

and the relevant moment of inertia is that about the point of suspension. The resulting equation of motion is:

$$\alpha \approx \frac{mgL_{cm}}{I_{\text{support}}}\theta$$

for small angles where  $\sin\theta \approx \theta$  Show


This is identical in form to the equation for the simple pendulum and yields a period:

$$T = 2\pi \sqrt{\frac{I_{\text{support}}}{mgL_{cm}}}$$

Speed of wave in a string:

$$v = \sqrt{\frac{T}{\mu}} = \sqrt{\frac{T}{M/L}}$$
 , where  $\mu$  is mass per unit length.

Tension in a circular string: restoring force F =  $2\pi T$ , where T is the tension.



# **Euler-Lagrange Equation:**

$$\frac{d}{dt}\left(\frac{\partial L}{\partial \dot{q}_k}\right) = \frac{\partial L}{\partial q_k} \ \text{, where L = T - V}$$

 $\frac{d}{dt}\left(\frac{\partial L}{\partial \dot{q}_k}\right) = \frac{\partial L}{\partial q_k} = 0 \qquad \Longrightarrow \qquad \frac{\partial L}{\partial \dot{q}_k} = C,$  If L does not depend on a certain coordinate  $q_k$ , then

We say that is a cyclic coordinate, and  $\partial L/\partial \dot{q}_k$  is a conserved quantity , if Cartesian coordinates are used then  $\partial L/\partial \dot{x}_k$  is simply the momentum,

$$E = \left(\sum_{i=1}^{N} \frac{\partial L}{\partial \dot{q}_i} \dot{q}_i\right) - L$$

**Energy:** 

$$\frac{dE}{dt} = -\frac{\partial L}{\partial t}$$

 $\frac{dE}{dt}=-\frac{\partial L}{\partial t}$  , so if L does not have depend on t explicitly (which is usually the case), the E is conserved.

8

 $2018 \ F = ma \ Exam \ A$ 

- 25. Alice and Bob are working on a lab report. Alice measures the period of a pendulum to be 1.013±0.008 s, while Bob independently measures the period to be 0.997 ± 0.016 s. Alice and Bob can combine their measurements in several ways.
  - 1: Keep Alice's result and ignore Bob's
  - 2: Average Alice's and Bob's results
  - 3: Perform a weighted average of Alice's and Bob's results, with Alice's result weighted 4 times more than Bob's

How are the uncertainties of these results related?

- (A) Method 1 has the lowest uncertainty, and method 2 has the highest
- (B) Method 3 has the lowest uncertainty, and method 2 has the highest ← CORRECT
- (C) Method 2 has the lowest uncertainty, and method 1 has the highest
- (D) Method 3 has the lowest uncertainty, and method 1 has the highest
- (E) Method 1 has the lowest uncertainty, and method 3 has the highest

## Solution

Let Alice's measurement have uncertainty  $\Delta x$ , so Bob's has uncertainty  $2\Delta x$ . The uncertainty obeys the following rules, which can be derived by identifying the uncertainty with the standard deviation:

- (A) Scaling: if x has uncertainty  $\Delta x$ , then cx has uncertainty  $c\Delta x$ .
- (B) Addition in quadrature: if x has uncertainty  $\Delta x$  and an independent measurement y has uncertainty  $\Delta y$ , then x + y has uncertainty  $\sqrt{(\Delta x)^2 + (\Delta y)^2}$ .

Then the uncertainties of the three possibilities are:

- 1: Δx
- 2:  $\sqrt{(\Delta x)^2 + (2\Delta x)^2}/2 = (\sqrt{5}/2)\Delta x$
- 3:  $\sqrt{(4\Delta x)^2 + (2\Delta x)^2}/5 = (2/\sqrt{5})\Delta x$

The lowest uncertainty is from method 3 (which is in fact optimal); the highest is from method 2.

## 21.6 DC Circuits Containing Resistors and Capacitors

- An RC circuit is one that has both a resistor and a capacitor.
- The time constant  $\tau$  for an RC circuit is  $\tau = RC$ .
- When an initially uncharged (V<sub>0</sub> = 0 at t = 0) capacitor in series with a resistor is charged by a DC voltage source, the
  voltage rises, asymptotically approaching the emf of the voltage source; as a function of time,

$$V = \text{emf}(1 - e^{-t/RC})$$
(charging).

- Within the span of each time constant τ, the voltage rises by 0.632 of the remaining value, approaching the final voltage asymptotically.
- If a capacitor with an initial voltage  $V_0$  is discharged through a resistor starting at t=0, then its voltage decreases exponentially as given by

$$V = V_0 e^{-t/RC}$$
 (discharging).

• In each time constant  $\tau$ , the voltage falls by 0.368 of its remaining initial value, approaching zero asymptotically.

### 22.3 Magnetic Fields and Magnetic Field Lines

- · Magnetic fields can be pictorially represented by magnetic field lines, the properties of which are as follows:
- 1. The field is tangent to the magnetic field line.
- 2. Field strength is proportional to the line density.
- 3. Field lines cannot cross.
- 4. Field lines are continuous loops.

### 22.4 Magnetic Field Strength: Force on a Moving Charge in a Magnetic Field

Magnetic fields exert a force on a moving charge q, the magnitude of which is

$$F = qvB \sin \theta$$
,

where  $\theta$  is the angle between the directions of  $\nu$  and B .

. The SI unit for magnetic field strength B is the tesla (T), which is related to other units by

$$1 T = \frac{1 N}{C \cdot m/s} = \frac{1 N}{A \cdot m}.$$

- The direction of the force on a moving charge is given by right hand rule 1 (RHR-1): Point the thumb of the right hand in the
  direction of v, the fingers in the direction of B, and a perpendicular to the palm points in the direction of F.
- The force is perpendicular to the plane formed by v and B. Since the force is zero if v is parallel to B, charged particles often follow magnetic field lines rather than cross them.

# 22.5 Force on a Moving Charge in a Magnetic Field: Examples and Applications

· Magnetic force can supply centripetal force and cause a charged particle to move in a circular path of radius

$$r = \frac{mv}{aB}$$

where  $\nu$  is the component of the velocity perpendicular to B for a charged particle with mass m and charge q.

#### 22.6 The Hall Effect

- The Hall effect is the creation of voltage ε, known as the Hall emf, across a current-carrying conductor by a magnetic field.
- · The Hall emf is given by

$$\varepsilon = Blv (B, v, and l, mutually perpendicular)$$

for a conductor of width  $\,l\,$  through which charges move at a speed  $\,v\,$ .

### 22.7 Magnetic Force on a Current-Carrying Conductor

· The magnetic force on current-carrying conductors is given by

$$F = IlB \sin \theta$$
,

where I is the current, l is the length of a straight conductor in a uniform magnetic field B, and  $\theta$  is the angle between I and B. The force follows RHR-1 with the thumb in the direction of I.

#### 22.8 Torque on a Current Loop: Motors and Meters

• The torque au on a current-carrying loop of any shape in a uniform magnetic field. is

$$\tau = NIAB \sin \theta$$
,

where N is the number of turns, I is the current, A is the area of the loop, B is the magnetic field strength, and  $\theta$  is the angle between the perpendicular to the loop and the magnetic field.

## 22.9 Magnetic Fields Produced by Currents: Ampere's Law

· The strength of the magnetic field created by current in a long straight wire is given by

$$B = \frac{\mu_0 I}{2\pi r}$$
 (long straight wire),

I is the current, r is the shortest distance to the wire, and the constant  $\mu_0 = 4\pi \times 10^{-7} \text{ T} \cdot \text{m/A}$  is the permeability of

- The direction of the magnetic field created by a long straight wire is given by right hand rule 2 (RHR-2): Point the thumb of the right hand in the direction of current, and the fingers curl in the direction of the magnetic field loops created by it.
- The magnetic field created by current following any path is the sum (or integral) of the fields due to segments along the path (magnitude and direction as for a straight wire), resulting in a general relationship between current and field known as
- · The magnetic field strength at the center of a circular loop is given by

$$B = \frac{\mu_0 I}{2R}$$
 (at center of loop),

R is the radius of the loop. This equation becomes  $B = \mu_0 nI/(2R)$  for a flat coil of N loops. RHR-2 gives the direction of the field about the loop. A long coil is called a solenoid.

The magnetic field strength inside a solenoid is

$$B = \mu_0 nI$$
 (inside a solenoid),

where n is the number of loops per unit length of the solenoid. The field inside is very uniform in magnitude and direction.

#### 22.10 Magnetic Force between Two Parallel Conductors

• The force between two parallel currents  $I_1$  and  $I_2$ , separated by a distance r, has a magnitude per unit length given by

$$\frac{F}{l} = \frac{\mu_0 I_1 I_2}{2\pi r}$$

 $\frac{F}{l} = \frac{\mu_0 \, I_1 I_2}{2\pi r}.$ • The force is attractive if the currents are in the same direction, repulsive if they are in opposite directions.

### 22.11 More Applications of Magnetism

· Crossed (perpendicular) electric and magnetic fields act as a velocity filter, giving equal and opposite forces on any charge with velocity perpendicular to the fields and of magnitude

$$v = \frac{E}{R}$$
.

#### 23.1 Induced Emf and Magnetic Flux

- The crucial quantity in induction is magnetic flux Φ, defined to be Φ = BA cos θ, where B is the magnetic field strength over an area A at an angle θ with the perpendicular to the area.
- Units of magnetic flux Φ are T · m<sup>2</sup>.
- Any change in magnetic flux Φ induces an emf—the process is defined to be electromagnetic induction.

#### 23.2 Faraday's Law of Induction: Lenz's Law

· Faraday's law of induction states that the emfinduced by a change in magnetic flux is

$$emf = -N \frac{\Delta \Phi}{\Delta t}$$

when flux changes by  $\Delta \Phi$  in a time  $\Delta t$  .

- If emf is induced in a coil, N is its number of turns.
- The minus sign means that the emf creates a current I and magnetic field B that oppose the change in flux ΔΦ —this opposition is known as Lenz's law.

#### 23.3 Motional Emf

An emf induced by motion relative to a magnetic field B is called a motional emf and is given by

emf = 
$$B\ell\nu$$
 (B,  $\ell$ , and  $\nu$  perpendicular),

where  $\ell$  is the length of the object moving at speed  $\nu$  relative to the field.

#### 23.4 Eddy Currents and Magnetic Damping

- Current loops induced in moving conductors are called eddy currents.
- · They can create significant drag, called magnetic damping.

#### 23.5 Electric Generators

· An electric generator rotates a coil in a magnetic field, inducing an emfgiven as a function of time by

$$emf = NAB\omega \sin \omega t$$
,

where A is the area of an N -turn coil rotated at a constant angular velocity  $\omega$  in a uniform magnetic field B.

· The peak emf emf<sub>0</sub> of a generator is

$$emf_0 = NAB\omega$$
.

#### 23.6 Back Emf

Any rotating coil will have an induced emf—in motors, this is called back emf, since it opposes the emf input to the motor.

# 23.7 Transformers

- · Transformers use induction to transform voltages from one value to another.
- For a transformer, the voltages across the primary and secondary coils are related by

$$\frac{V_{\rm S}}{V_{\rm p}} = \frac{N_{\rm S}}{N_{\rm p}},$$

where  $V_{
m p}$  and  $V_{
m S}$  are the voltages across primary and secondary coils having  $N_{
m p}$  and  $N_{
m S}$  turns.

- The currents  $I_{\rm p}$  and  $I_{\rm s}$  in the primary and secondary coils are related by  $\frac{I_{\rm s}}{I_{\rm p}} = \frac{N_{\rm p}}{N_{\rm s}}$ .
- A step-up transformer increases voltage and decreases current, whereas a step-down transformer decreases voltage and increases current.

#### 23.9 Inductance

- · Inductance is the property of a device that tells how effectively it induces an emf in another device.
- · Mutual inductance is the effect of two devices in inducing emfs in each other.
- A change in current ΔI<sub>1</sub>/Δt in one induces an emf emf<sub>2</sub> in the second:

$$\operatorname{emf}_2 = -M \frac{\Delta I_1}{\Delta t}$$

where M is defined to be the mutual inductance between the two devices, and the minus sign is due to Lenz's law.

Symmetrically, a change in current ΔI<sub>2</sub>/Δt through the second device induces an emf emf<sub>1</sub> in the first:

$$\operatorname{emf}_1 = -M \frac{\Delta I_2}{\Delta t},$$

where M is the same mutual inductance as in the reverse process

- Current changes in a device induce an emf in the device itself.
- · Self-inductance is the effect of the device inducing emf in itself.
- The device is called an inductor, and the emf induced in it by a change in current through it is

$$\operatorname{emf} = -L \frac{\Delta I}{\Delta t}$$

where L is the self-inductance of the inductor, and  $\Delta I/\Delta t$  is the rate of change of current through it. The minus sign indicates that emf opposes the change in current, as required by Lenz's law.

- The unit of self- and mutual inductance is the henry (H), where  $1~H=1~\Omega\cdot s$  .
- The self-inductance L of an inductor is proportional to how much flux changes with current. For an N-turn inductor,

$$L = N \frac{\Delta \Phi}{\Delta I}$$
.

· The self-inductance of a solenoid is

$$L = \frac{\mu_0 N^2 A}{\ell} \text{(solenoid)},$$

where N is its number of turns in the solenoid, A is its cross-sectional area,  $\ell$  is its length, and  $\mu_0 = 4\pi \times 10^{-7} \text{ T} \cdot \text{m/A}$  is the permeability of free space.

• The energy stored in an inductor  $E_{\mathrm{ind}}$  is

$$E_{\text{ind}} = \frac{1}{2}LI^2.$$

#### 23.10 RL Circuits

When a series connection of a resistor and an inductor—an RL circuit—is connected to a voltage source, the time variation
of the current is

$$I = I_0(1 - e^{-t/\tau})$$
 (turning on).

where  $I_0 = V/R$  is the final current.

- The characteristic time constant au is  $au=rac{L}{R}$  , where L is the inductance and R is the resistance.
- In the first time constant τ, the current rises from zero to 0.632I<sub>0</sub>, and 0.632 of the remainder in every subsequent time interval τ.
- · When the inductor is shorted through a resistor, current decreases as

$$I = I_0 e^{-t/\tau}$$
 (turning off)

Here  $I_0$  is the initial current.

Current falls to 0.368I<sub>0</sub> in the first time interval τ, and 0.368 of the remainder toward zero in each subsequent time τ.

### 23.11 Reactance, Inductive and Capacitive

- For inductors in AC circuits, we find that when a sinusoidal voltage is applied to an inductor, the voltage leads the current by one-fourth of a cycle, or by a 90° phase angle.
- The opposition of an inductor to a change in current is expressed as a type of AC resistance.
- · Ohm's law for an inductor is

$$I = \frac{V}{X_I}$$

where  $\,V\,$  is the rms voltage across the inductor.

. X<sub>L</sub> is defined to be the inductive reactance, given by

$$X_L = 2\pi f L$$

with f the frequency of the AC voltage source in hertz.

- Inductive reactance X<sub>L</sub> has units of ohms and is greatest at high frequencies.
- For capacitors, we find that when a sinusoidal voltage is applied to a capacitor, the voltage follows the current by one-fourth
  of a cycle, or by a 90° phase angle.
- Since a capacitor can stop current when fully charged, it limits current and offers another form of AC resistance; Ohm's law for a capacitor is

$$I = \frac{V}{X_C}$$

where  $\,V\,$  is the rms voltage across the capacitor.

X<sub>C</sub> is defined to be the capacitive reactance, given by

$$X_C = \frac{1}{2\pi fC}.$$

X<sub>C</sub> has units of ohms and is greatest at low frequencies.

#### 23.12 RLC Series AC Circuits

 The AC analogy to resistance is impedance Z, the combined effect of resistors, inductors, and capacitors, defined by the AC version of Ohm's law:

$$I_0 = \frac{V_0}{Z}$$
 or  $I_{\text{rms}} = \frac{V_{\text{rms}}}{Z}$ 

where  $I_0$  is the peak current and  $V_0$  is the peak source voltage

- Impedance has units of ohms and is given by  $Z = \sqrt{R^2 + (X_L X_C)^2}$  .
- The resonant frequency  $f_0$ , at which  $X_L = X_C$ , is

$$f_0 = \frac{1}{2\pi\sqrt{IC}}$$

• In an AC circuit, there is a phase angle  $\phi$  between source voltage V and the current I , which can be found from

$$\cos \phi = \frac{R}{Z}$$

- $\phi=0^{\rm o}$  for a purely resistive circuit or an *RLC* circuit at resonance.
- . The average power delivered to an RLC circuit is affected by the phase angle and is given by

$$P_{\text{ave}} = I_{\text{rms}} V_{\text{rms}} \cos \phi,$$

 $\cos\phi$  is called the power factor, which ranges from 0 to 1.

Electromagnetic wave:

$$c = \frac{1}{\sqrt{\mu_0 \, \varepsilon_0}}, \qquad \frac{E}{B} = c, \quad c = f \lambda,$$

### 24.4 Energy in Electromagnetic Waves

The energy carried by any wave is proportional to its amplitude squared. For electromagnetic waves, this means intensity
can be expressed as

$$I_{\text{ave}} = \frac{c\varepsilon_0 E_0^2}{2}$$

where  $I_{\rm ave}$  is the average intensity in  $\,W/m^2$ , and  $\,E_0\,$  is the maximum electric field strength of a continuous sinusoidal wave

- This can also be expressed in terms of the maximum magnetic field strength  $\,B_0\,$  as

$$I_{\text{ave}} = \frac{cB_0^2}{2\mu_0}$$

and in terms of both electric and magnetic fields as

$$I_{\text{ave}} = \frac{E_0 B_0}{2\mu_0}.$$

• The three expressions for  $I_{
m ave}$  are all equivalent.

Peak energy intensity: Io = 2 Iave

# Maxwell's equations

$$\begin{split} & \nabla \cdot \mathbf{E} &= \frac{\rho}{\varepsilon_0} \\ & \nabla \cdot \mathbf{B} &= 0 \\ & \nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t} \\ & \nabla \times \mathbf{B} = \mu_0 \left( \mathbf{J} + \varepsilon_0 \frac{\partial \mathbf{E}}{\partial t} \right) \end{split}$$

# Integral form:

$$\Phi_E = \oint \vec{E} \cdot d\vec{A} = \frac{q_{\rm enc}}{\varepsilon_0} \quad \text{(Gauss' law for electric fields)}$$

$$\Phi_{\!B} = \oint \vec{B} \cdot d\vec{A} = 0 \quad \text{(Gauss' law for magnetic fields)}.$$

$$\oint \vec{E} \cdot d\vec{s} = -\frac{d\Phi_B}{dt} \quad \text{(Faraday's law of induction)}.$$

$$\oint \vec{B} \cdot d\vec{s} = \mu_0 \varepsilon_0 \frac{d\Phi_E}{dt} + \mu_0 i_{\text{enc}} \quad \text{(Ampere-Maxwell law)}.$$

## Heat by radiation:

#### 14.7 Radiation

- · Radiation is the rate of heat transfer through the emission or absorption of electromagnetic waves.
- · The rate of heat transfer depends on the surface area and the fourth power of the absolute temperature:

$$\frac{Q}{t} = \sigma e A T^4$$
,

where  $\sigma=5.67\times10^{-8}~\mathrm{J/s\cdot m^2\cdot K^4}$  is the Stefan-Boltzmann constant and e is the emissivity of the body. For a black body, e=1 whereas a shiny white or perfect reflector has e=0, with real objects having values of e between 1 and 0. The net rate of heat transfer by radiation is

$$\frac{Q_{\text{net}}}{t} = \sigma e A \left( T_2^4 - T_1^4 \right)$$

where  $T_1$  is the temperature of an object surrounded by an environment with uniform temperature  $T_2$  and e is the emissivity of the *object*.

Change of internal energy equals heat transferred into the system, minus work done by the system to outside:

$$\Delta U = Q - W$$
.

Table 15.1 Summary of Terms for the First Law of Thermodynamics,  $\Delta U = Q - W$ 

Term	Definition
U	Internal energy—the sum of the kinetic and potential energies of a system's atoms and molecules. Can be divided into many subcategories, such as thermal and chemical energy. Depends only on the state of a system (such as its $P$ , $V$ , and $T$ ), not on how the energy entered the system. Change in internal energy is path independent.
Q	Heat—energy transferred because of a temperature difference. Characterized by random molecular motion. Highly dependent on path. $\mathcal Q$ entering a system is positive.
W	Work—energy transferred by a force moving through a distance. An organized, orderly process. Path dependent. $W$ done by a system (either against an external force or to increase the volume of the system) is positive.

# Table 15.2 Summary of Simple Thermodynamic Processes

Isobaric	Constant pressure $W = P\Delta V$
Isochoric	Constant volume $W=0$
Isothermal	Constant temperature $Q = W$
Adiabatic	No heat transfer $\mathcal{Q}=0$

$$\frac{1}{2}m\bar{v}^2 = \frac{3}{2}kT$$

Kinetic energy of the an atom of monatomic ideal gas is:

The kinetic energy is the only form of internal energy for monatomic ideal gas, so it's total internal

energy is: 
$$U = N\frac{1}{2}m\bar{v}^2 = \frac{3}{2}NkT$$
, (monatomic ideal gas)

And for monatomic gas, the molar (1 mole) heat capacity at constant volume is  $\frac{3}{2}R$ , where  $R=N_Ak$  is the gas constant.

The molar (1 mole) heat capacity at constant pressure is  $\frac{5}{2}R$ . (Extra heat is needed to do work to the environment as volume expands)

- In a cyclical process, such as a heat engine, the net work done by the system equals the net heat transfer into the system, or  $W = Q_h Q_c$ , where  $Q_h$  is the heat transfer from the hot object (hot reservoir), and  $Q_c$  is the heat transfer into the cold object (cold reservoir).
- Efficiency can be expressed as  $\mathit{Eff} = \frac{\mathit{W}}{\mathit{Q}_{\mathit{h}}}$ , the ratio of work output divided by the amount of energy input.




Figure 15.23 PV diagram for a Carnot cycle, employing only reversible isothermal and adiabatic processes. Heat transfer  $Q_{\rm h}$  occurs into the working substance during the isothermal path AB, which takes place at constant temperature  $T_{\rm h}$ . Heat transfer  $Q_{\rm c}$  occurs out of the working substance during the isothermal path CD, which takes place at constant temperature  $T_{\rm c}$ . The net work output W equals the area inside the path ABCDA. Also shown is a schematic of a Carnot engine operating between hot and cold reservoirs at temperatures  $T_{\rm h}$  and  $T_{\rm c}$ . Any heat engine using reversible processes and operating between these two temperatures will have the same maximum efficiency as the Carnot engine.

Carnot Efficiency:  $Eff_{\rm C} = 1 - \frac{T_{\rm c}}{T_{\rm h}}.$ 

 $COP_{\mathrm{hp}} = \frac{Q_{\mathrm{h}}}{W} = 1 / \mathit{Eff}$  Heat pump coefficient of performance:

Air conditioner and refrigerator performance:  $COP_{ref} = \frac{Q_c}{W} = COP_{hp} - 1$ 

 $\frac{Q_{\rm c}}{T_{\rm c}} = \frac{Q_{\rm h}}{T_{\rm h}}$  Carnot cycle:

Change in entropy: 
$$\Delta S = \left(\frac{Q}{T}\right)_{\text{rev}}$$

Entropy is constant for a reversible process; and it increases for an irreversible process.

Entropy is also the loss of energy available to do work.

The entropy of a system in a given state (a macrostate) can be written as

$$S = k \ln W$$
,

where  $k=1.38\times 10^{-23}~{\rm J/K}$  is Boltzmann's constant, and  ${\rm ln}W$  is the natural logarithm of the number of microstates W corresponding to the given macrostate.

# Wave:

#### 16.10 Superposition and Interference

- Superposition is the combination of two waves at the same location.
- · Constructive interference occurs when two identical waves are superimposed in phase.
- · Destructive interference occurs when two identical waves are superimposed exactly out of phase.
- A standing wave is one in which two waves superimpose to produce a wave that varies in amplitude but does not propagate.
- · Nodes are points of no motion in standing waves.
- · An antinode is the location of maximum amplitude of a standing wave.
- Waves on a string are resonant standing waves with a fundamental frequency and can occur at higher multiples of the fundamental, called overtones or harmonics.
- Beats occur when waves of similar frequencies  $f_1$  and  $f_2$  are superimposed. The resulting amplitude oscillates with a beat frequency given by

$$f_{\rm B} = |f_1 - f_2|$$
.

$$x = X \cos(2\pi f_1 t) + X \cos(2\pi f_2 t) = 2X \cos(\pi f_B t)\cos(2\pi f_{ave} t)$$

Standing wave:  $\lambda = 2L/n$ , where n=1,2,3,.... The longest wavelength for standing wave is 2L.

# **Relativity:**

Time dilation:

Observers moving at a relative velocity v do not measure the same elapsed time for an event. Proper time  $\Delta t_0$  is the time measured by an observer at rest relative to the event being observed. Proper time is related to the time  $\Delta t$  measured by an Earth-bound observer by the equation

$$\Delta t = \frac{\Delta t_0}{\sqrt{1 - \frac{v^2}{c^2}}} = \gamma \Delta t_0,$$

Length contraction:

Length contraction L is the shortening of the measured length of an object moving relative to the observer's frame:

$$L=L_0\sqrt{1-\frac{v^2}{c^2}}=\frac{L_0}{\gamma}$$
.

$$u = \frac{v + u'}{1 + \frac{vu'}{c^2}}$$

Addition of velocities:

$$\lambda_{\text{obs}} = \lambda_s \sqrt{\frac{1 + \frac{u}{c}}{1 - \frac{u}{c}}}$$

Relativistic Doppler effects:

 $\lambda_{\rm obs}$  is the observed wavelength,  $\lambda_{\it s}$  is the source wavelength, and  $\it u$  is the relative velocity of the source to the Where observer.

Momentum:  $p = \gamma mu$ 

Energy: 
$$E = \gamma mc^2$$

Relativistic kinetic energy is  ${
m KE}_{
m rel} = (\gamma - 1) mc^2$ 

$$E^2 = (pc)^2 + (mc^2)^2$$

# **Lorentz transformation**

$$x' = \gamma(x - vt),$$
  
 $y' = y,$   
 $z' = z,$   
 $t' = \gamma(t - vx/c^2)$  (Lorentz transformation equations; valid at all physically possible speeds).