

12. Introduction & Assembly (x86)

Seongil Wi



HW2: Web Hacking Competition

- Hacking practice: Capture the Flag (CTF)
- Challenge open (competition start): 4/14 (Mon)
- Due date (writeup report): 5/2 (Fri)



Introduction to Software Security

Secure Software?



Can we say a program is secure if it considers the CIA properties?

Where there is engineering, there is a security problem

Why?



Software Security is About Software Bugs

- Find software bugs
- Exploit software bugs
- Patch software bugs

8

Software Bug

*

 Software bug is an error/fault/mistake in the code that produces an unexpected result



Thinking like an adversary is important for security


Software Bugs is the Key

 Root cause of many security problems including malware, hacking incidents, phishing, privacy leakage, etc.



Not Every Bug is Security Critical

- Bug is an error in program that makes it malfunction
 - Ex) Compute wrong outputs for corner case inputs
- Vulnerability is a bug that causes security issues



- Stealing private data
- Executing arbitrary commands

Example #1



- Consider the python code below for bank application
 - Takes in the amount of money you want to transfer
 - Your balance and the recipient's balance will be updated

```
my_balance = 1000
def send(recipient):
    print("How much do you want to send?")
    val = read_int()
    if (val <= my_balance):
        my_balance = my_balance - val
        ... # Increase the balance of recipient</pre>
```

Input : **100**



my balance: $1000 \rightarrow 900$

Example #2



- Next, consider the following C code
 - Reads in a string input and prints it back

```
int main(void) {
    char buf[32];
    printf("Input your name: ");
    scanf("%s", buf);
    printf("Your name: %s\n", buf);
    return 0;
}
```

Input: "Seongil"



Printed output: "Your name: Seongil"

What can go wrong with this code?

Example #2

- *
- Next, consider the following C code
 - Reads in a string input and prints it back

```
int main(void) {
    char buf[32];
    printf("Input your name: ");
    scanf("%s", buf);
    printf("Your name: %s\n", buf);
    return 0;
}
```




Input: "AAAA...A"

(long string)

This is infamous buffer overflow vulnerability

1

Buffer Overflow & Memory Corruption



- C has no automatic check on array index and boundary
 - Allows writing past the end of an array
 - This is call buffer overflow, or BOF in short
 - Such write will corrupt other variables and data in the memory



Q. How can a hacker do bad things (e.g., code execution, privilege escalation) with this?

Our Goal in Software Security

• Find out whether a program is secure or not

• To do so, we need to see how the *binary code* (= executable code) executes on a machine!

Assembly

Compilation



 Converting a <u>high-level language</u> into a <u>machine language</u> that the computer can understand


```
int test (int a){
    return 32;
}
```

High-level language




010001010100100101 010010001000001010 111000110101010100 101010101010101110

Machine language



code



Source



Intermediate code




Assembly code




Binary code

test.ll



test.s



```
test: # @test
# %bb.0:
push ebp
mov ebp, esp
mov eax, dword ptr [ebp + 8]
mov eax, 32
pop ebp
ret
```



Source



Intermediate code



Assembly code



Binary code

test.ll

```
define dso_local i32 @test(i32) #0
{
    %2 = alloca i32, align 4
    store i32 %0, i32* %2, align 4
    ret i32 32
}
```


Intel syntax

test.s

```
$11c --x86-asm-syntax=intel
test.11
```

```
test: # @test
# %bb.0:
push ebp
mov ebp, esp
mov eax, dword ptr [ebp + 8]
mov eax, 32
pop ebp
ret
```

The last human-readable format



test.s

```
test: # @test
# %bb.0:
push ebp
mov ebp, esp
mov eax, dword ptr [ebp + 8]
mov eax, 32
pop ebp
ret
```

test.o

\$as -o test.o test.s


24

GNU AS (Assembler)

```
$as -o test.o test.s
$1s test.o
              .intel_syntax noprefix
              mov eax, ebx
```

25


Compilation Process



Binary code

Our goal:
Understanding binary

Disassembling Binary Code



Binary code

Disassembly!

Disassembler:

- Objdump
- IDA
- B2R2

- ..

GNU objdump

- One of the GNU Binutils
- Perform disassembly on the file

2

GNU objdump



Source code



Intermediate code



Assembly code



Binary code

00000000 <test>:

0: 55 push ebp

1: 89 e5 mov ebp,esp

3: 8b 45 08 mov eax, DWORD PTR [ebp+0x8]

6: b8 20 00 00 00 mov eax,0x20

b: 5d pop ebp

c: c3 ret



\$ objdump -M intel -d test.o

test.o

GNU objdump

Address

Binary code

Disassembled assembly code

Source code



Intermediate code



Assembly code



Binary code

```
00 000000 <test>:
```

```
0: 55
```

1: 89 e5

3: 8b 45 08

6: b8 20 00 00 00

b: 5d

c: c3

```
push ebp
```

mov ebp, esp

mov eax,DWORD PTR [ebp+0x8]

mov eax, 0x20

pop ebp


ret



\$ objdump -M intel -d test.o

test.o

Linking



Executable binary code (= Executable)

Linking







Text section (.text)

Read-only data (.rodata)

. . .

Data section (.data)

.bss

. . .

Show information about segments


Code segment

Each segment maps to one or more virtual memory areas (VMAs)

Data segment

Executable binary

Executable Binary (=Executable, Binary)



34

Segmentation Fault

• a.k.a., SegFault or Access violation

Happens when we reference an unmapped memory address

VMA

VMA

Virtual memory

x86 (IA-32) Architecture

36

x86 Instruction Set Architecture

- Developed by Intel in 1985
- CISC (Complex Instruction Set Computer) architecture
- 32-bit address space
- One of the most common architecture




History of x86 ISA




- (8086) 16-bit address space (in 1978)
- (x86 or IA-32) 32-bit address space (in 1985)
- (x86-64 or x64 or AMD64) 64-bit address space (in 2003)


Memory Layout and CPU Registers



Memory Layout and CPU Registers




File system



EBP

•••

Memory Layout and CPU Registers



Registers in x86

- *
- Program counter (instruction pointer)
 - **-EIP:** points to the instruction to execute
- Stack pointers
 - **-ESP:** points to the top of the stack
 - -EBP: points to the base of the current stack frame
- Status register (FLAGS register)
 - -EFLAGS: contains the current condition flags
- Other general purpose registers
 - -EAX, EBX, ECX, EDX, ESI, EDI

All of them have a size of a *double word* (=32 bit)

Size of Registers





- x86 registers are 32-bit
- A word is the natural unit of data used by a processor
 - Typically, a word size is 32 bits on a 32-bit machine

However, Intel defines a word is 16 bits on x86 (32-bit machine)

History of Intel/AMD Processors

- 1978: 8086
- 1982: 80286
- 1985: 80386
- 1989: 80486
- •
- 2003: Opteron
- 2005: Prescott
- 2006: Core 2
- 2008: Core i7

•

```
16-bit processor, Registers (SP, BP, IP, ...)
```

32-bit processor, Registers (ESP, EBP, EIP, ...)

64-bit processor, Registers (RSP, RBP, RIP, ...)


x86 Convention




- Word = 16 bits
- Double Word (DWORD) = 32 bits

• Linear address space = $0 \sim 2^{32}$ bits


















x86 Memory Access = Byte Addressing




x86 Assembly Basics

Basic Formats

51


- Three formats of Instructions
 - -2 operands
 - -1 operands
 - -0 operands

Basic Format #1: Instructions with 2 Operands




Basic Format #2: Instructions with 1 Operand 63





Basic Format #3: Instructions with 0 Operand 69





Intel vs AT&T Format



There are two ways to represent x86 assembly code

T&TA

mov %eax, %ebx

Intel

mov ebx, eax

We will use the Intel syntax

Recap: Compilation Process

Source code



Intermediate code



Assembly code



Binary code

test.II

```
define dso_local i32 @test(i32) #0
{
    %2 = alloca i32, align 4
    store i32 %0, i32* %2, align 4
    ret i32 32
}
```

Intel syntax

test.s

```
$11c --x86-asm-syntax=intel
test.11
```

```
test: # @test

# %bb.0:

push ebp

mov ebp, esp

mov eax, dword ptr [ebp + 8]

mov eax, 32

pop ebp


ret
```

The last human-readable format

Recap: GNU objdump









Intermediate code



Assembly code



Binary code

00000000 <test>:

0: 55 push ebp

1: 89 e5 mov ebp,esp

3: 8b 45 08 mov eax, DWORD PTR [ebp+0x8]

6: b8 20 00 00 00 mov eax,0x20

b: 5d pop ebp

c: c3 ret



\$ objdump -M intel -d test.o

test.o

Intel syntax

Opcode Decides Semantics

mov eax, ebx

sub esp, 0x8

inc eax


eax ← ebx

esp ← esp – 0x8

 $eax \leftarrow eax + 1$


Operand Types





mov eax, [ebx]

Register



Registers


eax

ebx

0x00000004








mov eax, [ebx]

Register



Registers


eax


0x273faace

ebx

0x00000004

Operand Types






Operand Types







Pointer Directive

```
*
```

```
mov [esi], al ; ok
mov [esi], 1 ; error
```

Error: ambiguous operand size for 'mov'

Because it could be any of the followings

- mov BYTE PTR [esi], 1
- mov WORD PTR [esi], 1
- mov DWORD PTR [esi], 1
- mov QWORD PTR [esi], 1

Therefore, we need pointer directive ©

Moving Data Around (mov)

```
mov eax, ebxmov al, blRegister to Register
• mov [eax], ebx } Register to Memory
• mov eax, [ebx]

    mov eax, [ebx + edx * 4]
    mov al, BYTE PTR [esi]

mov eax, 42
mov BYTE PTR [eax], 42
Constant to Memory/Register
```

Example: Storing a DWORD in Memory

mov [eax], 0xdeadbeef; eax = 0x1000

• • •	• • •
0x1000	0xdfaa2312
0xFF8	0x273faace
0xFF0	0xbffa0220


Example: Storing a DWORD in Memory

mov [eax], 0xdeadbeef; eax = 0x1000

• • •	• • •
0x1000	0xdeadbeef
0xFF8	0x273faace
0xFF0	0xbffa0220

Example: Storing a DWORD in Memory





Endianness



- The order in which a sequence of bytes are stored in memory
- Big Endian = The MSB goes to the lowest address
- Little Endian = The LSB goes to the lowest address

x86 uses Little Endian


Exercise





mov cl, BYTE ptr [eax]

Pointer directive



Registers

eax 0x00000009

ecx 0x13ef0c2e

What value will be after the instruction?

Addressing Modes





Specify how a memory operand is interpreted to derive an effective address

register

```
√mov eax, [eax]
```

• register + register

```
✓mov eax, [eax + ebx]
```

displacement

```
✓mov eax, [0x1000]
```

register + register × scale + displacement


```
✓ mov eax, [eax + ebx * 4 + 0x1000]
```

Addressing Modes



*

Specify how a memory operand is interpreted to derive an effective address



Loading Address (lea)

```
lea eax, [ebx]
lea eax, [ebp-0x8]

Memory address to Register
```

What is the Difference?

```
mov eax, [ebp + 0x10]
vs.
lea eax, [ebp + 0x10]
```

```
eax ← *(ebp + 0x10)
vs.
eax ← (ebp + 0x10)
```


Stack Memory






 Stack stores data in a LIFO (Last-In-First-Out) fashion. When a function is invoked, a new stack frame is allocated at the top of the stack memory

Stack Operations











Stack Operations - Push and Pop






Stack Operations – Push and Pop





Stack Operations - Push and Pop





Stack Operations (push)

push eax Pus

Push register on the stack

push 0x42

Push constant on the stack


push [eax]

Push a value at the memory address on the stack


push x
mov [esp], x

Stack Operations – Push and Pop






Stack Operations – Push and Pop



83

Stack Operations – Push and Pop



Stack Operations (pop)



pop eax

pop [eax]

Pop the top element of the stack into register

Pop the top element of the stack into the memory address


```
pop x mov x, [esp] add esp, 4
```


Stack Operations (leave)

leave mov esp, ebp
pop ebp

Function Call (call)








Function Call (call)







••• call foo nextret: push nextret nop jmp foo nop foo: nop nop



Function Call (call)








Function Return (ret)

90

ret **=** pop eip




Function Return (ret)



ret **=** pop eip

eip nextret



Arithmetic and Logical Operations

92

- add eax, [ebx]
- sub esp, 0x40
- •inc ecx
- dec edx
- and [eax + ecx], ebx
- •xor edx, ebx
- •shl eax, 1
- •

Control Flows





```
if ( x ) {
   /* A */
}
   while (x) {
   else {
     /* B */
}
```

```
for (i = 0; i < n; i++) {
}</pre>
```

How to represent in assembly?

Control Flows in Assembly (1)


There are only "if" and "goto" (no "else")

```
How assembly looks like ...
                         if (!x) goto F;
if ( x ) {
                        /* A */
  /* A */
                        goto DONE;
else {
                         /* B */
  /* B */
                       DONE:
```

Control Flows in Assembly (2)

There are only "if" and "goto" (no "else")

```
while (x) {
   /* body */
}
```



```
How assembly looks like...
WHILE:
   if (!x) goto DONE;
   /* body */
   goto WHILE;
```

DONE:

Control Flows in Assembly (3)

There are only "if" and "goto" (no "else")

```
for (i = 0; i < n; i++) {
   /* body */
}</pre>
```



DONE:


```
How assembly looks like...
i = 0;
LOOP:
if (i >= n) goto DONE;
/* body */
i++;
goto LOOP;
```

Control Flows in Assembly (Example)



Test if x is zero

if (!x) goto F;



cmp x, 0

If x=zero then goto F

If i >= n then goto F

Control Flows in Assembly (Example)

Control Flows in Assembly (Example)

Where do we store the result of comparison (cmp)?

EFLAGS: Storing the Processor State



 EFLAGS is a status register used in x86, which is essentially a collection of status flag bits

• There are approximately 20 different flag bits used in x86, but we are mainly interested in 6 condition flags:

- OF: Overflow flag


-SF: Sign flag

-ZF: Zero flag

- AF: Auxiliary carry flag

-PF: Parity flag

- CF: Carry flag



cmp Only Affects EFLAGS



 cmp is the same as sub, except that it only affects EFLAGS, but not the destination operand. For example, cmp eax, ebx will not change the eax register

Branch Instructions



Assume that a comparison instruction (cmp) precedes the branch instruction

Branch Instruction	Condition	Description
ja	CF = 0 and ZF = 0	Jump if above
jb	CF = 1	Jump if below
je	ZF = 1	Jump if equal
jl	SF ≠ F	Jump if less
jle	$ZF = 1 \text{ or } SF \neq F$	Jump if less or equal
jna	CF = 1 or ZF = 1	Jump if not above
jnb	CF = 0	Jump if not below
jz	ZF = 1	Jump if zero
(many more)		

Summary So Far

- *
- We learned how to move around data
 - mov, lea, push, pop, etc.
- We learned how to perform arithmetic and logical operations
 - add, sub, and, or, etc.
- We also learned how to control program flows
 - cmp, jmp, ja, jz, etc.

Already Turing Complete!

x86 Execution Model

Recap: Stack Frame



*

 When a function is invoked, a new stack frame is allocated at the top of the stack memory

Also, called as <u>procedure frame</u> or <u>activation record</u>

Our Example

```
int purple(int a1, int a2) {
    return 2 + a1 - a2;
int blue(int a1) {
    return 1 + purple(a1, b);
int red(int a1) {
    return blue(a1 - 42);
```

Our Example – Stack





```
int purple(int a1, int a2) {
    return 2 + a1 - a2;
int blue(int a1) {
    return 1 + purple(a1, b);
                       Start
int red(int a1) {
    return blue(a1 - 42);
```

Higher Memory Address

Frame for function red

Recap: Registers in x86

109

- Program counter (instruction pointer)
 - -EIP: points to the instruction to execute
- Stack pointers
 - **-ESP:** points to the top of the stack
 - -EBP: points to the base of the current stack frame
- Status register (FLAGS register)
 - -EFLAGS: contains the current condition flags
- Other general purpose registers
 - -EAX, EBX, ECX, EDX, ESI, EDI

Our Example – Stack

```
*
```

```
int purple(int a1, int a2) {
    return 2 + a1 - a2;
int blue(int a1) {
    return 1 + purple(a1, b);
int red(int a1)
    return blue(a1 - 42);
```

Higher Memory Address

Frame for function red

Frame for function blue esp

Our Example – Stack

```
*
```

```
int purple(int a1, int a2) {
    return 2 + a1 - a2;
int blue(int a1) {
    return 1 + purple(a1, b);
int red(int a1) {
    return blue(a1 - 42);
```

Higher Memory Address

Frame for function red

Frame for function blue


Frame for function purple

ebp

lesr

Questions






- How do we pass function parameters?
- When a function returns, how do we restore the register values of the caller
- Where do we store local variables?

We can easily get the answer by compiling the example program and disassembling the resulting binary

Disassembled Code (x86)

```
<red>:
                                                   32:
                                                                   DWORD PTR [esp+0x4], eax
                                                         mov
   0:
               ebp
       push
                                                                   eax, DWORD PTR [ebp+0x8]
                                                   36:
                                                         mov
   1:
               ebp,esp
       mov
                                                                   DWORD PTR [esp], eax
                                                   39:
                                                         mov
   3:
       sub
               esp,0x28
                                                         call
                                                                   purple
                                                   3c:
   6:
               DWORD PTR [ebp-0xc],0x0
       mov
                                                   41:
                                                                   edx, DWORD PTR [ebp-0xc]
                                                         mov
               eax,DWORD PTR [ebp+0x8]
   d:
       mov
                                                   44:
                                                         add
                                                                   eax, edx
  10:
       sub
               eax,0x2a
                                                   46:
                                                         leave
  13:
               DWORD PTR [esp],eax
       mov
                                                   47:
                                                         ret
               Blue
  16:
       call
                                                <purple>:
  1b:
               edx, DWORD PTR [ebp-0xc]
       mov
                                                   48:
                                                         push
                                                                   ebp
       add
               eax,edx
  1e:
                                                   49:
  20:
       leave
                                                         mov
                                                                   ebp,esp
  21:
       ret
                                                   4b:
                                                         sub
                                                                   esp,0x10
                                                                   DWORD PTR [ebp -0x4],0x2
                                                   4e:
                                                         mov
<blue>:
                                                   55:
                                                                   eax, DWORD PTR [ebp+0x8]
                                                         mov
  22:
               ebp
       push
                                                                   eax, DWORD PTR [ebp-0x4]
                                                   58:
                                                         mov
  23:
               ebp,esp
       mov
                                                   5b:
                                                         add
                                                                   eax,edx
  25:
       sub
               esp,0x28
                                                   5d:
                                                                   eax,DWORD PTR [ebp+0xc]
                                                         sub
               DWORD PTR [ebp-0xc],0x1
  28:
       mov
                                                   60:
                                                         leave
  2f:
               eax, DWORD PTR [ebp-0xc]
       mov
                                                   61:
                                                         ret
```



ret

Currently executed instruction

ebp

ebp, esp

esp,0x28

eax,0x2a

push

mov

sub

mov

mov

sub

mov

DWORD PTR [ebp-0xc],0x0

eax,DWORD PTR [ebp+0x8]

DWORD PTR [esp],eax

```
0xbfff0008
   0x100
return address
                   0xbfff0000
                    Points to instruction
                      to be executed
                   eip: 0x1
```

3: 6: d: 10: 13: 16: call ebp: 0xbfff0008 esp: 0xbfff0000

<red>:

blue edx, DWORD PTR [ebp-0xc] 1b: mov eax,edx 1e: add 20: leave 21: ret <blue>: 22: push ebp 23: ebp, esp mov 46: leave 47: ret

Execution context Virtual memory

Save the base address of the previous function's stack frame



```
0xbfff0008
   0x100
return address
0xbfff0008
                0xbffefffc
                 eip: 0x1
                 ebp: 0xbfff0008
                 esp: 0xbffefffc
```

```
<red>:
             ebp
      push
             ebp, esp
      mov
   3:
      sub
             esp,0x28
             DWORD PTR [ebp-0xc],0x0
   6:
      mov
             eax,DWORD PTR [ebp+0x8]
   d:
      mov
  10:
      sub
             eax,0x2a
             DWORD PTR [esp],eax
  13:
      mov
  16:
      call
             blue
  1b:
             edx, DWORD PTR [ebp-0xc]
      mov
             eax,edx
  1e:
      add
  20:
      leave
  21: ret
<blue>:
  22: push
              ebp
  23:
              ebp, esp
      mov
 46:
       leave
  47:
       ret
```

Virtual memory

Execution context


DWORD PTR [ebp-0xc],0x0

eax,DWORD PTR [ebp+0x8]

edx,DWORD PTR [ebp-0xc]

DWORD PTR [esp],eax

Execution Example



Virtual memory

eax,edx 1e: add 20: leave 21: ret <blue>: 22: push ebp 23: ebp, esp mov 46: leave **Execution context** 47: ret

0:

3:

6:

d:

10:

13:

16:

1b:

push

mov

sub

mov

mov

sub

mov

call

mov

ebp

ebp, esp

esp,0x28

eax,0x2a

blue

Now, ebp points to the base of the current stack frame

118

0x100

return address

0xbfff0008

0xbfff0008

0xbffefffc

eip: 0x3

ebp: 0xbffefffc

esp: 0xbffefffc

Execution context

```
Tred>:
              ebp
       push
              ebp, esp
       mov
       sub
              esp,0x28
              DWORD PTR [ebp-0xc],0x0
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax,0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16:
       call
              blue
  1b:
              edx, DWORD PTR [ebp-0xc]
       mov
              eax,edx
  1e:
       add
  20:
       leave
  21: ret
```

ebp

ebp, esp

Virtual memory

46: leave

22: push

mov

<blue>:

23:

47: ret

Execution Example

0x100

return address

0xbfff0008

0xbffefffc

eip: 0x6

ebp: 0xbffefffc

esp: 0xbffefffc

Execution context


```
*:
   0:
              ebp
       push
              ebp, esp
       mov
              esp,0x28
       sub
              DWORD PTR [ebp-0xc],0x0
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax,0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16:
       call
              blue
              edx, DWORD PTR [ebp-0xc]
  1b:
       mov
              eax,edx
  1e:
       add
  20:
       leave
  21: ret
<blue>:
  22: push
              ebp
  23:
              ebp, esp
       mov
```


46:

47:


leave


ret















```
0x100
                    8x0
return address
0xbfff0008
                 0xbffefffc
    0x0
                  eip: 0x10
                  ebp: 0xbffefffc
                  esp: 0xbffeffd4
                       0x100
                  eax:
                   Execution context
 Virtual memory
```


```
int red(int a1) {
    return blue(a1 - 42);
<red>:
   0:
             ebp
      push
             ebp, esp
      mov
             esp,0x28
   3:
      sub
             DWORD PTR [ebp-0xc],0x0
   6:
      mov
             eax,DWORD PTR [ebp+0x8]
   d:
      mov
  10:
      sub
             eax,0x2a
             DWORD PTR [esp],eax
  13:
      mov
  16:
      call
             blue
             edx,DWORD PTR [ebp-0xc]
  1b:
      mov
             eax,edx
  1e:
      add
  20:
      leave
  21: ret
<blue>:
 22: push
              ebp
  23:
              ebp, esp
      mov
 46:
       leave
  47:
       ret
```

```
0:
                                                         ebp
                                                  push
                                                         ebp, esp
                                                  mov
   0x100
                                                         esp,0x28
                                               3:
                                                  sub
                                                         DWORD PTR [ebp-0xc],0x0
                                               6:
return address
                                                  mov
                                                         eax,DWORD PTR [ebp+0x8]
                                               d:
                                                  mov
 0xbfff0008
                                              10:
                                                  sub
                                                         eax, 0x2a
                   0xbffefffc
                                                         DWORD PTR [esp],eax
                                              13:
                                                  mov
                                              16:
                                                  call
                                                         blue
                                                         edx, DWORD PTR [ebp-0xc]
                                              1b:
                                                  mov
     0x0
                                                         eax,edx
                                                  add
                                              1e:
                                              20:
                                                  leave
                    eip: 0x13
                                              21: ret
                    ebp: 0xbffefffc
                                            <blue>:
                    esp: 0xbffeffd4
                                              22: push
                                                         ebp
                                              23:
                                                         ebp, esp
                                                  mov
                    eax: 0x100
                                              46:
                                                   leave
                     Execution context
 Virtual memory
                                              47:
                                                   ret
```

```
Execution Example
   0x100
return address
0xbfff0008
                0xbffefffc
    0x0
                eip: 0x13
                 ebp: 0xbffefffc
                 esp: 0xbffeffd4
                eax: 0xd6
                  Execution context
 Virtual memory
```

```
int red(int a1) {
    return blue(a1 - 42);
<red>:
   0:
             ebp
      push
             ebp, esp
      mov
             esp,0x28
   3:
      sub
             DWORD PTR [ebp-0xc],0x0
   6:
      mov
             eax,DWORD PTR [ebp+0x8]
   d:
      mov
  10:
      sub
             eax, 0x2a
             DWORD PTR [esp],eax
  13:
      mov
  16:
      call
             blue
             edx,DWORD PTR [ebp-0xc]
  1b:
      mov
             eax,edx
  1e:
      add
  20:
      leave
  21: ret
<blue>:
 22: push
              ebp
  23:
              ebp, esp
      mov
 46:
       leave
  47:
       ret
```





```
?red>:
                                               0:
                                                         ebp
                                                  push
                                                         ebp, esp
                                                  mov
   0x100
                     push retaddress
                                                         esp,0x28
                                               3:
                                                  sub
                     jmp blue
                                                         DWORD PTR [ebp-0xc],0x0
                                               6:
return address
                                                  mov
                                                         eax,DWORD PTR [ebp+0x8]
                                               d:
                                                  mov
 0xbfff0008
                                              10:
                                                  sub
                                                         eax,0x2a
                   0xbffefffc
                                                         DWORD PTR [esp],eax
                                              13:
                                                  mov
                                              16:
                                                  call
                                                         blue
                                                         edx,DWORD PTR [ebp-0xc]
                                              1b:
                                                  mov
     0x0
                                                         eax,edx
                                                  add
                                              1e:
                                              20:
                                                  leave
                    eip: 0x1b
                                              21: ret
    0xd6
                    ebp: 0xbffefffc
                                            <blue>:
                    esp: 0xbffeffd4
                                              22: push
                                                         ebp
                                              23:
                                                         ebp, esp
                                                  mov
                    eax: 0xd6
                                              46:
                                                   leave
                     Execution context
 Virtual memory
                                              47:
                                                   ret
```

```
?red>:
                                                           ebp
                                                    push
                                                           ebp, esp
                                                    mov
     0x100
                       push retaddress
                                                           esp,0x28
                                                 3:
                                                    sub
                       jmp blue
                                                           DWORD PTR [ebp-0xc],0x0
                                                 6:
 return address
                                                    mov
                                                           eax,DWORD PTR [ebp+0x8]
                                                 d:
                                                    mov
  0xbfff0008
                                                10:
                                                    sub
                                                           eax,0x2a
                     0xbffefffc
                                                           DWORD PTR [esp],eax
                                                13:
                                                    mov
                                                16:
                                                    call
                                                           blue
                                                           edx, DWORD PTR [ebp-0xc]
                                                1b:
                                                    mov
      0x0
                                                           eax,edx
                                                    add
                                                1e:
                                                20:
                                                    leave
                      eip: 0x22
                                                21: ret
      0xd6
                      ebp: 0xbffefffc
                                              <blue>:
Return address (0x1b)
                      esp: 0xbffeffd0
                                                22: push
                                                           ebp
                                                23:
                                                            ebp, esp
                                                    mov
                      eax: 0xd6
                                                46:
                                                     leave
                       Execution context
   Virtual memory
                                                47:
                                                     ret
```

```
red>:
                                                 0:
                                                            ebp
                                                     push
                                                            ebp, esp
                                                     mov
     0x100
                                                            esp,0x28
                                                 3:
                                                     sub
                                                            DWORD PTR [ebp-0xc],0x0
                                                 6:
 return address
                                                     mov
                                                            eax,DWORD PTR [ebp+0x8]
                                                 d:
                                                     mov
  0xbfff0008
                                                10:
                                                     sub
                                                            eax,0x2a
                     0xbffefffc
                                                            DWORD PTR [esp],eax
                                                13:
                                                     mov
                                                16:
                                                     call
                                                           blue
                                                            edx,DWORD PTR [ebp-0xc]
                                                1b:
                                                     mov
      0x0
                                                            eax,edx
                                                1e:
                                                     add
                                                20:
                                                     leave
                      eip: 0x23
                                                21: ret
      0xd6
                      ebp: 0xbffefffc
                                              <blue>:
Return address (0x1b)
                      esp: 0xbffeffd0
                                                22:
                                                            ebp
                                                     push
                                                23:
                                                            ebp, esp
                                                     mov
                      eax: 0xd6
                                                46:
                                                     leave
                       Execution context
   Virtual memory
                                                47:
                                                     ret
```

```
0x100
 return address
  0xbfff0008
                   0xbffefffc
     0x0
                   eip: 0x23
     0xd6
                   ebp: 0xbffefffc
Return address (0x1b)
                   esp: 0xbffeffcc
  0xbffefffc
                   eax: 0xd6
                    Execution context
```

```
red>:
   0:
       push
              ebp
              ebp, esp
    1:
       mov
              esp,0x28
    3:
       sub
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax,0x2a
              DWORD PTR [esp],eax
  13:
       mov
       call
  16:
              blue
              edx, DWORD PTR [ebp-0xc]
  1b:
       mov
              eax,edx
       add
  1e:
  20:
       leave
  21: ret
<blue>:
  22:
               ebp
       push
  23:
               ebp, esp
       mov
```

46:

47:

leave

ret

0x100 return address 0xbfff0008 0xbffefffc 0x0 eip: 0x25 0xd6 ebp: 0xbffefffc Return address (0x1b) esp: 0xbffeffcc 0xbffefffc eax: 0xd6 **Execution context**

*red>: 0: push ebp ebp, esp 1: mov esp,0x283: sub DWORD PTR [ebp-0xc],0x0 6: mov eax,DWORD PTR [ebp+0x8] d: mov 10: sub eax,0x2a DWORD PTR [esp],eax 13: mov 16: call blue edx, DWORD PTR [ebp-0xc] 1b: mov eax,edx add 1e: 20: leave 21: ret <blue>: 22: push ebp ebp, esp 23: mov 46: leave

47:

ret

0x100 return address 0xbfff0008 0x0 0xd6 Return address (0x1b) 0xbffefffc

0xbffefffc

eip: 0x25

ebp: 0xbffeffcc

esp: 0xbffeffcc

eax: 0xd6

Execution context

```
0:
       push
              ebp
              ebp, esp
    1:
       mov
              esp,0x28
    3:
       sub
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax, 0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16:
       call
              blue
              edx, DWORD PTR [ebp-0xc]
  1b:
       mov
              eax,edx
       add
  1e:
  20:
       leave
  21: ret
<blue>:
  22: push
              ebp
              ebp, esp
  23:
       mov
```

46:

47:

leave

ret

0x100

return address

0xbfff0008

0x0

0xd6

Return address (0x1b)

0xbffefffc

0xbffefffc

eip: 0x46

ebp: 0xbffeffcc

esp: 0xbffeffac

Execution context

```
red>:
   0:
              ebp
       push
              ebp, esp
   1:
       mov
              esp,0x28
   3:
       sub
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax,0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16:
       call
              blue
              edx, DWORD PTR [ebp-0xc]
  1b:
       mov
              eax,edx
       add
  1e:
  20:
       leave
  21: ret
<blue>:
  22: push
              ebp
  23:
              ebp, esp
       MOV
```

Skip!

. . .

46:

47:

leave

ret

Execution Example

0x100

return address

0xbfff0008

0x0

0xd6

Return address (0x1b)

0xbffefffc

0xbffefffc

eip: 0x47

ebp: 0xbffeffcc

esp: 0xbffeffac

Execution context

```
red>:
   0:
              ebp
       push
              ebp, esp
       mov
              esp,0x28
   3:
       sub
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax,0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16:
       call
             blue
              edx, DWORD PTR [ebp-0xc]
  1b:
       mov
              eax,edx
       add
  1e:
  20:
       leave
                   mov esp, ebp
  21: ret
                       pop ebp
<blue>:
```

ebp

ebp

22: push

mov

leave

ret

23:

46:

47:

pop ebp

Execution Example

0x100

return address

0xbfff0008

0x0

0xd6

Return address (0x1b)

0xbffefffc

0xbffefffc

eip: 0x47

ebp: 0xbffeffcc

esp: 0xbffeffcc

Execution context

```
0:
       push
              ebp
              ebp, esp
       mov
              esp,0x28
   3:
       sub
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax,0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16:
       call
              blue
              edx, DWORD PTR [ebp-0xc]
  1b:
       mov
              eax,edx
  1e:
       add
  20:
       leave
  21: ret
```

<blue>:

22: push ebp ebp

23: mov

46: leave

47: ret


```
0x100
 return address
  0xbfff0008
                    0xbffefffc
      0x0
                     eip: 0x47
     0xd6
                           Oxbffefffc
Return address (0x1b)
                     esp: 0xbffeffd0
                      Execution context
  Virtual memory
```

```
0:
              ebp
       push
              ebp, esp
       mov
              esp,0x28
   3:
       sub
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax,0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16:
       call
             blue
              edx, DWORD PTR [ebp-0xc]
  1b:
       mov
              eax,edx
  1e:
       add
  20:
       leave
                   mov esp, ebp
  21: ret
                            ebp
<blue>:
  22: push
              ebp
  23:
       mov
              ebp
  46:
       leave
  47:
       ret
```

```
0x100
 return address
  0xbfff0008
                   0xbffefffc
      0x0
                    eip: 0x47
     0xd6
                    ebp: 0xbffefffc
Return address (0x1b)
                    esp: 0xbffeffd0
                     Execution context
                                            47:
```

```
0:
       push
              ebp
              ebp, esp
       mov
              esp,0x28
   3:
       sub
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax,0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16:
       call
              blue
              edx, DWORD PTR [ebp-0xc]
  1b:
       mov
              eax,edx
       add
  1e:
  20:
       leave
  21: ret
<blue>:
  22: push
              ebp
  23:
              ebp, esp
       mov
  46:
       leave
```

ret



Calling Convention

```
<blue>:
                                          int blue(int a1) {
  22:
               ebp
       push
                                              return 1 + purple(a1, b);
  23:
              ebp,esp
       mov
              esp,0x28
  25:
       sub
              DWORD PTR [ebp\0xc],0x1
  28:
       mov
  2f:
               eax, DWORD PTR [ebp-0xc]
       mov
              DWORD PTR [esp+0x4], eax
  32:
       mov
               eax, DWORD PTR [ebp+0x8]
  36:
       mov
                                                          Value in b
              DWORD PTR [esp] eax
  39:
       mov
  3c:
       call
               purple
                                                          Value in a1
                                            a1
                                                                            esp
               edx, DWORD PTR [ebp-0xc]
  41:
       mov
       add
               eax, edx
  44:
                                                         Virtual memory
       leave
  46:
                              Passing parameter values
  47:
       ret
```

in a reverse order

Calling Convention

```
<blue>:
                                         int blue(int a1) {
              ebp
  22:
       push
                                              return 1 + purple(a1, b);
  23:
              ebp,esp
       mov
  25:
              esp,0x28
       sub
              DWORD PTR [ebp\0xc],0x1
  28:
       mov
  2f:
              eax, DWORD PTR [ebp-0xc]
       mov
              DWORD PTR [esp+0x4], eax
  32:
       mov
              eax, DWORD PTR [ebp+0x8]
  36:
       mov
              DWORD PTR [esp] eax
  39:
       mov
  3c:
       call
               purple
              edx, DWORD PTR [ebp-0xc]
  41:
       mov
  44:
       add
              eax, edx
  46:
       leave
                               Storing a return value in
  47:
       ret
```

eax

Key Concepts

*

- Compilation pipeline
- x86 architecture
- Assembly
- Disassembly

Question?