Subscribe now

coming indecate in c

Submitted by NanoDano (/users/nanodano) on Fri, 08/14/2015 - 22:19

Overview

- Intro
- Find a Network Device
- Get Info About Device
- Live Capture
- Print Packet Info
- Processing Packets with pcap_loop()
- · Determining Packet Type
- Finding the Data Payload
- · Loading Pcap File
- · Wireless, Promiscuous, and Monitor Mode
- Using Filters
- Example Filters
- · Closing Handle
- · Sending Packets
- · Bindings to Other Languages
- References

Intro

libpcap allows us to capture or send packets from a live network device or a file. These code examples will walk you through using libpcap to find network devices, get information about devices, process packets in real time or offline, send packets, and even listen to wireless traffic. This is aimed at Debian based Linux distributions but may also work on Mac OSX. Not intended for Windows.

Compiling a pcap program requires linking with the pcap lib. You can install it in Debian based distributions with

```
sudo apt-get install libpcap-dev
```

Once the libpcap dependency is installed, you can compile pcap programs with the following command. You will need to run the program as root or with sudo to have permission to access the network card.

gcc <filename> -lpcap

Find a Network Device

The simplest program to start with will just look for a network device. We won't be able to do anything else if we can't get a device to work with. If you get a device called "any" bound to 0.0.0.0 that is acceptable. You can also us **ifconfig** or **ip addr** to get device names.

```
/* Compile with: gcc find_device.c -lpcap */
#include <stdio.h>
#include <pcap.h>

int main(int argc, char **argv) {
    char *device; /* Name of device (e.g. eth0, wlan0) */
    char error_buffer[PCAP_ERRBUF_SIZE]; /* Size defined in pcap.h */

    /* Find a device */
    device = pcap_lookupdev(error_buffer);
    if (device == NULL) {
        printf("Error finding device: %s\n", error_buffer);
        return 1;
    }

    printf("Network device found: %s\n", device);
    return 0;
}
```

Get Info About Device

Now we can expand on the simple program above. After we find a device, we can call **pcap_lookupnet** and it will tell us what the ip address and subnet mask of the device. It will also fill up the error buffer with an error message if something goes wrong.

~

```
#include <arpa/inet.h>
#include <string.h>
int main(int argc, char **argv) {
    char *device;
    char ip[13];
    char subnet_mask[13];
    bpf_u_int32 ip_raw; /* IP address as integer */
    bpf_u_int32 subnet_mask_raw; /* Subnet mask as integer */
    int lookup_return_code;
    char error_buffer[PCAP_ERRBUF_SIZE]; /* Size defined in pcap.h */
    struct in_addr address; /* Used for both ip & subnet */
    /* Find a device */
    device = pcap_lookupdev(error_buffer);
    if (device == NULL) {
        printf("%s\n", error_buffer);
        return 1;
   3
    /* Get device info */
    lookup_return_code = pcap_lookupnet(
        device,
        &ip raw,
        &subnet_mask_raw,
        error_buffer
    if (lookup return code == -1) {
        printf("%s\n", error_buffer);
        return 1;
    If you call inet_ntoa() more than once
    you will overwrite the buffer. If we only stored
    the pointer to the string returned by inet_ntoa(),
    and then we call it again later for the subnet mask,
    our first pointer (ip address) will actually have
    the contents of the subnet mask. That is why we are
    using a string copy to grab the contents while it is fresh.
    The pointer returned by inet_ntoa() is always the same.
    This is from the man:
    The inet_ntoa() function converts the Internet host address in,
    given in network byte order, to a string in IPv4 dotted-decimal
    notation. The string is returned in a statically allocated
    buffer, which subsequent calls will overwrite.
    /* Get ip in human readable form */
    address.s_addr = ip_raw;
    strcpy(ip, inet_ntoa(address));
    if (ip == NULL) {
        perror("inet_ntoa"); /* print error */
    }
    /* Get subnet mask in human readable form */
    address.s_addr = subnet_mask_raw;
    strcpy(subnet_mask, inet_ntoa(address));
    if (subnet_mask == NULL) {
        perror("inet_ntoa");
        return 1;
    printf("Device: %s\n", device);
    printf("IP address: %s\n", ip);
    printf("Subnet mask: %s\n", subnet_mask);
    return 0;
}
```

The program above will look up the device like the first program, but will go a step further and get information about the device as well. The next step is to use the device to actually capture packets. Later on we'll also look at opening an existing pcap file instead of capturing live.

Live Capture

The next example program will demonstrate how to open a network device for live capturing, and capture a single packet. We will use **pcap_open_live** to get a handle, just like we would when opening a file to get a file handle. Instead of a **FILE** type handle though it is a **pcap_t** type.

Subscribe now

```
#include <pcap.h>
#include <netinet/in.h>
#include <netinet/if_ether.h>
void print_packet_info(const u_char *packet, struct pcap_pkthdr packet_header);
int main(int argc, char *argv[]) {
    char *device:
    char error_buffer[PCAP_ERRBUF_SIZE];
    pcap_t *handle;
    const u_char *packet;
     struct pcap_pkthdr packet_header;
    int packet_count_limit = 1;
    int timeout_limit = 10000; /* In milliseconds */
    device = pcap_lookupdev(error_buffer);
    if (device == NULL) {
        printf("Error finding device: %s\n", error_buffer);
        return 1:
    }
    /* Open device for live capture */
    handle = pcap open live(
            device.
            BUFSIZ.
            packet_count_limit,
            timeout_limit,
            error buffer
        ):
     /* Attempt to capture one packet. If there is no network traffic
     and the timeout is reached, it will return NULL */
     packet = pcap_next(handle, &packet_header);
     if (packet == NULL) {
        printf("No packet found.\n");
    /* Our function to output some info */
    print_packet_info(packet, packet_header);
    return 0;
}
```

The program above will capture a single packet and then call **print_packet_info()**. I left that function out intentionally to keep the snippet above short. Let's take a look at **print_packet_info()** now. You will need to add that function after **main()**.

Print Packet Info

The print_packet_info() function will provide information about what type of ethernet packet it found (IP or ARP), the timestamp, packet length, and the source and destination of the packet.

```
void print_packet_info(const u_char *packet, struct pcap_pkthdr packet_header) {
    printf("Packet capture length: %d\n", packet_header.caplen);
    printf("Packet total length %d\n", packet_header.len);
}
```

Processing Packets with pcap_loop()

We've slowly been adding more and more to our capabilities with pcap. We've covered finding a device, opening a device, how to capture a single packet, and how to pull information from the packet. Capturing a single packet is not very practical though. If you are looking for a single packet, chances are it will not be the very first packet you see, but buried in a stream of many packets. Now we will talk about how to process all of the packets received continuously. This is where **pcap_loop()** comes in. The **pcap_loop()** function is provided by libpcap. This is what the declaration looks like in **pcap.h**.

```
int pcap_loop(pcap_t *p, int cnt, pcap_handler callback, u_char *user)
```

From the previous examples we know that **pcap_t** is the device handle from where we want to capture. The second argument is an int which is the number of packets you want to capture. Pass **0** for unlimited packets. The **pcap_handler** accepts a function name that is the callback to be run on every packet captured. We will look more in depth at that in a moment. The last argument to **pcap_loop** is arguments to the callback function. We do not have any in our example so we pass NULL.

The pcap_handler argument for pcap_loop() is a specially defined function. This is the declartion of the type in pcap.h.

We will define our own callback function to handle packets, but it will have to match the format of the **pcap_handler** type. Here is an empty example. We will create a handler later that actually does something useful.

Sign up for email updates Subscribe now

```
const struct pcap_pkthdr *header,
  const u_char *packet
)
{
    /* Do something with the packet here.
        The print_packet_info() function shows in the
        previous example could be used here. */
    /* print_packet_info(packet, header); */
    return;
}
```

Let's look at a full program example of how to take advantage of **pcap_loop()**. Inside our callback function that handles packets, we will just print out the packet information like we did in our previous example. Since this program will continuously loop and process packets, you will have to use **CTRL-C** to end the program or use the **kill** command.

```
#include <stdio.h>
#include <time.h>
#include <pcap.h>
#include <netinet/in.h>
#include <netinet/if_ether.h>
void my_packet_handler(
    u_char *args,
    const struct pcap_pkthdr *header,
    const u_char *packet
void print_packet_info(const u_char *packet, struct pcap_pkthdr packet_header);
int main(int argc, char *argv[]) {
    char *device;
    char error_buffer[PCAP_ERRBUF_SIZE];
    pcap_t *handle;
    int timeout_limit = 10000; /* In milliseconds */
    device = pcap_lookupdev(error_buffer);
    if (device == NULL) {
        printf("Error finding device: %s\n", error_buffer);
        return 1;
    /* Open device for live capture */
    handle = pcap_open_live(
            device.
            BUFSIZ
            timeout_limit,
            error buffer
        ):
    if (handle == NULL) {
         fprintf(stderr, "Could not open device %s: %s\n", device, error_buffer);
         return 2;
    pcap_loop(handle, 0, my_packet_handler, NULL);
    return 0;
}
void my_packet_handler(
    u_char *args,
    const struct pcap_pkthdr *packet_header,
    const u_char *packet_body
{
    print_packet_info(packet_body, *packet_header);
    return;
}
void print_packet_info(const u_char *packet, struct pcap_pkthdr packet_header) {
    printf("Packet capture length: %d\n", packet_header.caplen);
    printf("Packet total length %d\n", packet_header.len);
```

Determining Packet Type

Packet type can be determined by inspecting the ethernet header and comparing the ether_type value against known constants for IP, ARP, and reverse ARP types.

Subscribe now

```
#include <netinet/in.h>
#include <net/ethernet.h>
/* This function can be used as a callback for pcap_loop() */
void mv packet handler(
    u_char *args,
    const struct pcap_pkthdr* header,
    const u char* packet
) {
    struct ether header *eth header:
    /* The packet is larger than the ether_header struct,
       but we just want to look at the first part of the packet
       that contains the header. We force the compiler
       to treat the pointer to the packet as just a pointer
       to the ether_header. The data payload of the packet comes
       after the headers. Different packet types have different header
       lengths though, but the ethernet header is always the same (14 bytes) */
    eth_header = (struct ether_header *) packet;
    if (ntohs(eth_header->ether_type) == ETHERTYPE_IP) {
        printf("IP\n");
    } else if (ntohs(eth_header->ether_type) == ETHERTYPE_ARP) {
        printf("ARP\n");
    } else if (ntohs(eth_header->ether_type) == ETHERTYPE_REVARP) {
        printf("Reverse ARP\n");
}
int main(int argc, char **argv) {
    pcap_t *handle;
    char error_buffer[PCAP_ERRBUF_SIZE];
    char *device = "eth0";
    int snapshot len = 1028;
    int promiscuous = 0;
    int timeout = 1000;
    handle = pcap_open_live(device, snapshot_len, promiscuous, timeout, error_buffer);
    pcap_loop(handle, 1, my_packet_handler, NULL);
    pcap close(handle);
    return 0;
```

Finding the Data Payload

The payload is not always going to be in the same location. Headers will be different sizes based on the type of packet and what options are present. For this example we are strictly talking about IP packets with TCP on top.

We start with the pointer to the beginning of the packet. The first 14 bytes are the ethernet header. That is always going to be the same because it is defined in the standard. That ethernet header contains the destination then source MAC(hardware) addresses, which are lower level than IP addresses. Each one of those is 6 bytes. There are also two more bytes at the end of the ethernet header that represent the type. With two bytes you could have thousands of different types. They could be ARP packets but we only want IP packets in this situation.

Ethernet is considered the second layer in OSI's model. The only level lower than ethernet is the physical medium that the data uses, like a copper wire, fiber optics, or radio signals.

On top of ethernet, the second layer, we have the third layer: IP. That is our IP address which is one level higher than the hardware MAC address. Layer four is TCP and UDP. Before we can actually get to our payload, we have to get past the ethernet, IP, and TCP layer. That is how we will come up with the formula for calculating the payload location in memory.

IP and TCP header length are variable. The length of the IP header is one of the very first values provided in the IP header. We have to get the IP header length to figure out how much further we have to look to find the beginning of the TCP header. Once we know where the TCP header is we can get the data offset value, which is part of the TCP header. The data offset is how much further we have to go from the start of the TCP packet to the actual payload. Look at this psuedo-code.

```
payload_pointer =
packet_pointer + len(Ethernet header) + len(IP header) + len(TCP header)
```

- The ethernet header is always 14 bytes as defined by standards.
- The IP header length is always stored in a 4 byte integer at byte offset 4 of the IP header.
- The TCP header length is always stored in a 4 byte integer at byte offset 12 of the TCP header.
- The payload starts at packet base location plus all the header lengths.

Now we have enough knowledge to figure out where the payload is in memory. The IP header and TCP are typically about 20 bytes each if there are no options passed. That means the first 54 bytes are the header layers, and the rest is actual data. We should not guess or assume the headers will always be 20 bytes each though. We need to get the actual header length for both IP and TCP layers in order to calculate the offset for the payload. That is what this code example will do.

```
#include <netinet/in.h>
#include <netinet/if_ether.h>
/* Finds the payload of a TCP/IP packet */
void my_packet_handler(
    u_char *args,
    const struct pcap_pkthdr *header,
    const u char *packet
{
    /* First, lets make sure we have an IP packet */
    struct ether_header *eth_header;
    eth_header = (struct ether_header *) packet;
    if (ntohs(eth_header->ether_type) != ETHERTYPE_IP) {
        printf("Not an IP packet. Skipping...\n\n");
    /st The total packet length, including all headers
       and the data payload is stored in
       header->len and header->caplen. Caplen is
       the amount actually available, and len is the
       total packet length even if it is larger
       than what we currently have captured. If the snapshot
       length set with pcap_open_live() is too small, you may
       not have the whole packet. */
    printf("Total packet available: %d bytes\n", header->caplen);
    printf("Expected packet size: %d bytes\n", header->len);
    /* Pointers to start point of various headers */
    const u_char *ip_header;
    const u_char *tcp_header;
    const u_char *payload;
    /* Header lengths in bytes */
    int ethernet_header_length = 14; /* Doesn't change */
    int ip_header_length;
    int tcp header length;
    int payload_length;
    /* Find start of IP header */
    ip_header = packet + ethernet_header_length;
      The second-half of the first byte in ip_header
       contains the IP header length (IHL). ^{*}\!\!/
    ip_header_length = ((*ip_header) & 0x0F);
    /* The IHL is number of 32-bit segments. Multiply
       by four to get a byte count for pointer arithmetic */
    ip_header_length = ip_header_length * 4;
    printf("IP header length (IHL) in bytes: %d\n", ip_header_length);
    /* Now that we know where the IP header is, we can
       inspect the IP header for a protocol number to
       make sure it is TCP before going any further.
       Protocol is always the 10th byte of the IP header */
    u_char protocol = *(ip_header + 9);
    if (protocol != IPPROTO_TCP) {
        printf("Not a TCP packet. Skipping...\n\n");
        return;
    /* Add the ethernet and ip header length to the start of the packet
      to find the beginning of the TCP header */
    tcp_header = packet + ethernet_header_length + ip_header_length;
    /* TCP header length is stored in the first half
       of the 12th byte in the TCP header. Because we only want
       the value of the top half of the byte, we have to shift it
       down to the bottom half otherwise it is using the most
       significant bits instead of the least significant bits */
    tcp_header_length = ((*(tcp_header + 12)) & 0xF0) >> 4;
    /* The TCP header length stored in those 4 bits represents
       how many 32-bit words there are in the header, just like
       the IP header length. We multiply by four again to get a
       byte count. */
    tcp_header_length = tcp_header_length * 4;
    printf("TCP header length in bytes: %d\n", tcp_header_length);
    /st Add up all the header sizes to find the payload offset st/
    int total_headers_size = ethernet_header_length+ip_header_length+tcp_header_length;
    printf("Size of all headers combined: %d bytes\n", total_headers_size);
    payload_length = header->caplen -
        (ethernet_header_length + ip_header_length + tcp_header_length);
    printf("Payload size: %d bytes\n", payload_length);
    payload = packet + total_headers_size;
    printf("Memory address where payload begins: %p\n\n", payload);
```

6/10

Subscribe now

```
if (payload_length > 0) {
        const u_char *temp_pointer = payload;
         int byte_count = 0;
        while (byte_count++ < payload_length) {</pre>
            printf("%c", *temp_pointer);
             temp_pointer++;
        printf("\n");
    return:
}
int main(int argc, char **argv) {
   char *device = "eth0";
    char error_buffer[PCAP_ERRBUF_SIZE];
    pcap_t *handle;
     * Snapshot length is how many bytes to capture from each packet. This includes*/
    int snapshot length = 1024;
    /st End the loop after this many packets are captured st/
    int total_packet_count = 200;
    u_char *my_arguments = NULL;
    handle = pcap_open_live(device, snapshot_length, 0, 10000, error_buffer);
    pcap_loop(handle, total_packet_count, my_packet_handler, my_arguments);
}
```

Loading Pcap File

Loading a pcap file is just like opening a device. Opening a file returns a pcap_t just like opening a network device.

```
pcap_t *pcap_open_offline(const char *fname, char *errbuf);
```

It just needs the filename string and an error buffer.

```
char error_buffer[PCAP_ERRBUF_SIZE];
pcap_t *handle = pcap_open_offline("capture_file.pcap", error_buffer);
```

Once the file is opened just like a device, you can call **pcap_next()** to get one packet at a time, or use pcap_loop().

Wireless, Promiscuous, and Monitor Mode

To turn it on, call

To clarify the difference between promiscuous mode and monitor mode: monitor mode is just for wireless cards and promiscuous is for wireless and wired. Monitor mode lets the card listen to wireless packets without being associated to an access point. Promiscuous mode lets the card listen to all packets, even ones not intended for it.

Use pcap_set_rfmon() to turn on monitor mode. Use pcap_set_promisc() to turn on promiscuous mode. Call them before the device is activated. Pass any non-zero integer to turn it on and 0 to turn off.

```
int pcap_set_rfmon(pcap_t *p, int rfmon);
```

Remember, pcap_t is the device handle opened with pcap_open_live(). Call this before activating the device. pcap_can_set_rfmon() can be used to see if a device has the capability.

We have been using **pcap_open_live()** to get the device handle, but that creates the device handle and activates it at the same time. To set the rfmon mode before activating the device handle must be manually created. Use **pcap_create()** and **pcap_activate()**.

```
char error_buffer[PCAP_ERRBUF_SIZE];
pcap_t *handle = pcap_create("wlan0", error_buffer);
pcap_set_rfmon(handler, 1);
pcap_set_promisc(handler, 1); /* Capture packets that are not yours */
pcap_set_snaplen(handler, 2048); /* Snapshot length */
pcap_set_timeout(handler, 1000); /* Timeout in milliseconds */
pcap_activate(handle);
/* handle is ready for use with pcap_next() or pcap_loop() */
```

Using Filters

You compile textual expressions in to a filter program first. Then you can apply the filters to the pcap handle. You can filter by source or destination, port, or a number of other things. For a full reference of filters, use the man page for pcap-filter.

```
man 7 pcap-filter
```

This is the declaration of the compile and setfilter functions.

Subscribe now

```
int pcap_setfilter(pcap_t *p, struct bpf_program *fp)
```

The example below shows how to compile and set the filter.

```
#include <stdio.h>
#include <pcap.h>
/* For information on what filters are available
  use the man page for pcap-filter
   $ man pcap-filter
int main(int argc, char **argv) {
    char dev[] = "eth0";
    pcap_t *handle;
    char error_buffer[PCAP_ERRBUF_SIZE];
    struct bpf_program filter;
    char filter_exp[] = "port 80";
    bpf_u_int32 subnet_mask, ip;
    if (pcap_lookupnet(dev, &ip, &subnet_mask, error_buffer) == -1) {
        printf("Could not get information for device: %s\n", dev);
        ip = 0;
        subnet_mask = 0;
    handle = pcap_open_live(dev, BUFSIZ, 1, 1000, error_buffer);
    if (handle == NULL) {
        printf("Could not open %s - %s\n", dev, error_buffer);
    if (pcap_compile(handle, &filter, filter_exp, 0, ip) == -1) {
        printf("Bad filter - %s\n", pcap_geterr(handle));
        return 2;
    if (pcap_setfilter(handle, &filter) == -1) {
        printf("Error setting filter - %s\n", pcap_geterr(handle));
        return 2;
    /* pcap_next() or pcap_loop() to get packets from device now */
    /* Only packets over port 80 will be returned. */
}
```

Example Filters

```
# or by IP
host 8.8.8.8
# Packets between hosts
host box2 and box4
# Packets by source
src 10.2.4.1
# Bv destination
dst 99.99.2.2
# By port
port 143
portange 1-1024
# By source/destination port
src port 22
dst port 80
# By Protocol
tcp
udp
icmr
# And
src localhost and dst port 22
src localhost && dst port 22
# Or
port 80 or 22
port 80 || 22
# Grouping
src localhost and (dst port 80 or 22 or 443)
```

Closing Handle

The handle (or descriptor) for the device/file should be closed just like a file. use pcap_close().

```
pcap_close(handle);
```

Sending Packets

You can send packets using pcap_inject(). It could not get any simpler. You pass it a raw pointer and a length and it will send whatever it finds in memory to the handle.

```
int pcap_inject(pcap_t *p, const void *buf, size_t size);
```

```
int bytes_written = pcap_inject(handle, &raw_bytes, sizeof(raw_bytes));
```

Bindings to Other Languages

To this day, **libpcap** is still going strong. There are bindings to almost all other languages. There are bindings to Go (https://github.com/google/gopacket), PHP (https://github.com/marcelog/SimplePcap), Python (http://sourceforge.net/projects/pylibpcap), Ruby (http://sourceforge.net/projects/rubypcap/), Perl (http://search.cpan.org/~kcarnut/Net-Pcap-0.05/Pcap.pm), Java (http://jnetpcap.com/) and more.

I have a page on using the **gopacket** library in Go to capture, analyze, and inject packets with Go (/content/packet-capture-injection-and-analysis-gopacket). Gopacket is more than just a straight wrapper of libpcap and offers its own benefits.

Having a solid understanding of the C library will make it much easier to work with the bindings in other languages. Most of them are direct wrappers so all the function names are the same. Every language has their pros and cons so remember that there are many options available. Personally, Go is the most attractive because of its threading capabilities and speed without the amount of work needed in a C program. If speed is not critical, Python would be my next choice for writing quick and dirty scripts to get what I need. For many situations, the easiest approach is to use **tcpdump** to write to a file and then write programs to analyze the file offline. That can take a lot of disk space though and sometimes you need to operate on the packets in real time so C, C++ and Go might be the most appropriate.

References

It is difficult to memorize all the function calls and what types you have to pass for each argument. Fortunately, it is well documented. There is an online manual at www.tcpdump.org (http://www.tcpdump.org/), but there is a better way to get help. You do not even have to go online or open a browser. Learn to use the man pages efficiently. Here are a few examples of using man.

```
man pcap
man gcap_open_live
man pcap_open_liter
man 7 pcap-filter
```

Sign up for email updat	es Subscribe now X
man man	
0 Comments Dev Dungeon	Login
♥ Recommend	Sort by Best
Start the discussion	
Be the first to comment.	
ALSO ON DEV DUNGEON	
I'm Speaking at GopherCon 2016 about Packet Capturing 2 comments • a year ago•	How to Write GTK Applications with PHP 1 comment • 2 years ago•
devdungeon — Hi Eli, thanks for the reminder. I just pushed up the code examples and the slides to https://github.com/NanoDano	krzysiunet — If you want to use PHP-GTK, please - try that Glade method. That makes life much easier. I'm so happy that PHP-GTK is active again. As for me
"I know how to program, but I don't know what to program"	Working with Images in Go
39 comments • a year ago• Martin Stendorf — Lately i've spent a lot of time with pythonWhen i really had nothing to do, i started looking at some online api's (facebook, twitter etc.) and started	3 comments • 2 years ago• rebelnz — Interesting - I am running go1.3 on linux/amd64 and cannot image.Decode() without registering the image format first
☑ Subscribe	
Search	Q
Join Mailing List	
_	
Email Address *	
Name	
Subscribe	
Tags	
Tags	

- C (/tags/c)
- pcap (/tags/pcap)
- Security (/tags/security)
- sysadmin (/tags/sysadmin)

Related Posts

- Creating Systemd Service Files (/content/creating-systemd-service-files)
- Setting up Tor Proxy and Hidden Services in Linux (/content/setting-tor-proxy-and-hidden-services-linux)
- Working with Files in Go (/content/working-files-go)
- Packet Capture, Injection, and Analysis with Gopacket (/content/packet-capture-injection-and-analysis-gopacket)
- Daemonizing Ruby Scripts (/content/daemonizing-ruby-scripts)
- Manipulate Files with Perl (/content/manipulate-files-perl)
- How to Mix C and Assembly (/content/how-mix-c-and-assembly)
- How to Write Command Line Tools (/content/how-write-command-line-tools)

Mentorship