Adding multiple remotes

When you do <code>git init</code>, you initialize a local Git repository. In general, the purpose is to synchronize this repo with a remote Git repo. To be able to synchronize code with a remote repo, you need to specify where the remote repo exists.

The first step is to add remote repos to your project.

```
# Syntax to add a git remote
git remote add REMOTE-ID REMOTE-URL
```

By convention, the original / primary remote repo is called origin. Here's a real example:

```
# Add remote 1: GitHub.
git remote add origin git@github.com:jigarius/toggl2redmine.git
# Add remote 2: BitBucket.
git remote add upstream git@bitbucket.org:jigarius/toggl2redmine.git
```

In the above example, we add the remote repository of a project called Toggl 2 Redmine

found on GitHub. Use the above command to add one or more remote Git repos – make sure that each repo has its unique ID, i.e. origin, upstream in the above example.

Configure primary remote

Though you can add multiple remotes, usually, each branch of your project can be configured to track a single remote branch. You can setup a branch to track a remote branch as follows:

```
# Change local branch.
git checkout BRANCH
# Configure local branch to track a remote branch.
git branch -u origin/BRANCH
```

Here, BRANCH is the name of the remote branch, which is usually the same as your local branch.

Change remote URL

If you want to change the URL associated to a remote that you've already added, you can do it with the following command:

```
# The syntax is: git remote set-url REMOTE-ID REMOTE-URL
git remote set-url upstream git@foobar.com:jigarius/toggl2redmine.git
```

List all remotes

To see a list of all remotes, simply use the following command:

Remove a remote

If you've added a remote which you no longer require, you can remove it as follows:

```
# The syntax is: git remote remove REMOTE-ID
git remote remove upstream
```

Push to multiple remotes

Now that you have a primary remote repo and other remotes as well, it's time to configure the push. The objective is to push to multiple Git remotes with a single git push command.

To do this, choose a remote ID which will refer to all the remotes. I usually call it all, but there are developers who prefer origin. The idea is to add all the remote repo URLs as "push URLs" to this remote. Here's what you do:

```
# Create a new remote called "all" with the URL of the primary repo.
git remote add all git@github.com:jigarius/toggl2redmine.git
# Re-register the remote as a push URL.
git remote set-url --add --push all
git@github.com:jigarius/toggl2redmine.git
# Add a push URL to a remote. This means that "git push" will also push
```

```
to this git URL.
git remote set-url --add --push all
git@bitbucket.org:jigarius/toggl2redmine.git
```

If you don't want to create an extra remote named all, you can skip the first command and use the remote origin instead of all in the subsequent command(s).

Now, you can push to all remote repositories with a single command!

```
# Replace BRANCH with the name of the branch you want to push. git push all BRANCH
```

Pull from multiple remotes

It is not possible to <code>git pull</code> from multiple repos. However, you can <code>git fetch</code> from multiple repos with the following command:

```
git fetch --all
```

This will *fetch* information from all remote repos. You can switch to the latest version of a branch on a particular remote with the command:

```
# Checkout the branch you want to work with.
git checkout BRANCH
# Reset the branch to match the state as on a specific remote.
git reset --hard REMOTE-ID/BRANCH
```

Conclusion

It is easy to synchronize code between multiple git repositories, especially, pushing to multiple remotes. This is helpful when you're maintaining mirrors / copies of the same repository. All you need to do is set up multiple push URLs on a remote and then perform git push to that remote as you usually do.