### INF4208

# -- Mobile and Wireless networks

DOMGA KOMGUEM Rodrigue -- rodrigue.domga-komguem@facsciences-uy1.cm


The content of this course is adapted from the Book:

"Computer Networking: A Top Down Approach, Chapter 6"


#### Background:

- v # wireless (mobile) phone subscribers now exceeds # wired phone subscribers (5-to-1)!
- v # wireless Internet-connected devices equals # wireline Internet-connected devices
  - = laptops, Internet-enabled phones promise anytime untethered Internet access
- v two important (but different) challenges
  - = wireless: communication over wireless link
  - = mobility: handling the mobile user who changes point of attachment to network


### network




### network









### network




### Characteristics of selected wireless



### network



### network



#### ad hoc mode

- no base stations
- nodes can only transmit to other nodes within link coverage
- nodes organize themselves into a network: route among themselves

### Wireless network taxonomy

	single hop	multiple hops
infrastructure (e.g., APs)	host connects to base station (WiFi, WiMAX, cellular) which connects to larger Internet	host may have to relay through several wireless nodes to connect to larger Internet: mesh net
no infrastructure	no base station, no connection to larger Internet (Bluetooth, ad hoc nets)	no base station, no connection to larger Internet. May have to relay to reach other a given wireless node MANET, VANET

### Chapter 6 outline

#### 6.1 Introduction

#### Wireless

- 6.2 Wireless links, characteristics
- 6.3 Cellular Internet Access
  - = architecture
  - =standards (e.g., GSM)

#### Mobility

- 6.4 Principles:

  addressing and
  routing to mobile
  users
- 6.5 Mobile IP
- 6.6 Handling mobility in cellular networks
- 6.7 Mobility and
  higher-layer
  protocols<sub>Wireless, Mobile Networks 6-11</sub>

### Wireless Link Characteristics (1)


important differences from wired link ....

- = decreased signal strength: radio signal
  attenuates as it propagates through matter
  (path loss)
- = interference from other sources: standardized wireless network frequencies (e.g., 2.4 GHz) shared by other devices (e.g., phone); devices (motors) interfere as well
- = multipath propagation: radio signal reflects off objects ground, arriving ad destination at slightly different times

.... make communication across (even a point to point) wireless link much more "difficult" hetworks 6-12

### Wireless Link Characteristics (2)

- v SNR: signal-to-noise ratio
  - = larger SNR easier to
     extract signal from noise
     (a "good thing")
- v SNR versus BER tradeoffs
  - = given physical layer: increase power -> increase SNR->decrease BER
  - = given SNR: choose physical layer that meets BER requirement, giving highest thruput
    - SNR may change with mobility: dynamically adapt physical layer (modulation technique,



----- QAM256 (8 Mbps)


– – · QAM16 (4 Mbps)

BPSK (1 Mbps)

Wireless, Mobile Networks 6-13


### Wireless network characteristics

Multiple wireless senders and receivers create additional problems (beyond multiple access):



#### Hidden terminal problem

- v B, A hear each other
- v B, C hear each other
- v A, C can not hear each other means A, C unaware of their interference at B



#### Signal attenuation:

- v B, A hear each other
- v B, C hear each other
- v A, C can not hear each other interfering at B

### Chapter 6 outline

6.1 Introduction

#### Wireless

- 6.2 Wireless links, characteristics
- 6.3 IEEE 802.11 wireless LANs ("Wi-Fi")
- 6.4 Cellular Internet Access
  - = architecture
  - =standards (e.g.,

#### Mobility

- 6.5 Principles:

  addressing and
  routing to mobile
  users
- 6.6 Mobile IP
- 6.7 Handling mobility in cellular networks
- 6.8 Mobility and higher-layer protocols<sub>Wireless, Mobile Networks 6-15</sub>

### IEEE 802.11 Wireless LAN

#### 802.11b

- v 2.4-5 GHz unlicensed spectrum
- v up to 11 Mbps
- v direct sequence spread spectrum (DSSS) in physical layer
  - = all hosts use same
    - chipping code
  - v all use CSMA/CA for multiple access
  - v all have base-station and ad-hoc network versions


#### 802.11a

- = 5-6 GHz range
- =up to 54 Mbps

#### 802.11g

- = 2.4-5 GHz range
- =up to 54 Mbps
- 802.11n: multiple antennae
  - = 2.4-5 GHz range
  - =up to 200 Mbps

### 802.11 LAN architecture




- wireless host communicates with base station
  - = base station = access point (AP)
- Basic Service Set (BSS) (aka "cell" ) in infrastructure mode contains:
  - = wireless hosts
  - = access point (AP): base station
  - = ad hoc mode: hosts only


### 802.11: Channels, association

- v 802.11b: 2.4GHz-2.485GHz spectrum divided into 11 channels at different frequencies
  - = AP admin chooses frequency for AP
  - = interference possible: channel can be same as that chosen by neighboring AP!
- v host: must associate with an AP
  - = scans channels, listening for beacon frames containing AP's name (SSID) and MAC address
  - = selects AP to associate with
  - = may perform authentication [Chapter 8]
  - = will typically run DHCP to get IP address in AP's subnet

### 802.11: passive/active

<del>scanning</del>





#### passive scanning:


- ( )beacon frames sent from APs
- ( )association Request frame sent: H1 to selected AP
- ( )association Response frame sent from selected AP to H1


#### active scanning:

- (Й) Probe Request frame broadcast from H1
- (Ў )Probe Response frames sent from APs
- (以) Association Request frame sent: H1 to selected AP
- (A )Association Response frame sent from selected AP to H1

### IEEE 802.11: multiple access

- v avoid collisions: 2<sup>+</sup> nodes transmitting at same time
- v 802.11: CSMA sense before transmitting
  - = don't collide with ongoing transmission by other node
- v 802.11: no collision detection!
  - = difficult to receive (sense collisions) when transmitting due to weak received signals (fading)
  - = can' t sense all collisions in any case: hidden terminal, fading
  - = goal: avoid collisions: CSMA/C(ollision)A(voidance)





### IEEE 802.11 MAC Protocol:

### CSMA/CA


#### 802.11 sender

- 1 if sense channel idle for **DIFS** then transmit entire frame (no CD)
- 2 if sense channel busy then start random backoff time timer counts down while channel idle transmit when timer expires if no ACK, increase random backoff interval, repeat 2

#### 802.11 receiver

- if frame received OK


return ACK after **SIFS** (ACK needed due to hidden terminal problem)



### Avoiding collisions (more)


- idea: allow sender to "reserve" channel rather than random access of data frames: avoid collisions of long data frames
- v sender first transmits *small* request-to-send (RTS) packets to BS using CSMA
  - = RTSs may still collide with each other (but they' re short)
- v BS broadcasts clear-to-send CTS in response to RTS
- v CTS heard by all nodes
  - = aenoidtrdastaitframeracellisions completely
  - = other stations defer transmissions on packets!

#### Collision Avoidance: RTS-CTS




### 802.11 frame:


## addressing



### 802.11 frame:




### 802.11 frame: more



### 802.11: mobility within same

### subnet


- v H1 remains in same IP subnet: IP address can remain same
- v switch: which AP is associated with H1?
  - =self-learning (Ch. 5): switch will see frame from H1 and "remember" which switch port can be used to reach H1




### 802.11: advanced capabilities

#### Rate adaptation

v base station, mobile
 dynamically change
 transmission rate
 (physical layer
 modulation technique)
 as mobile moves, SNR
 varies





- 1. SNR decreases, BER increase as node moves away from base station
- 2. When BER becomes too high, switch to lower transmission rate but with lower BER


### 802.11: advanced capabilities

#### power management

- v node-to-AP: "I am going to sleep until next beacon frame"
  - = AP knows not to transmit frames to this node
  - = node wakes up before next beacon frame
- v beacon frame: contains list of mobiles with AP-to-mobile frames waiting to be sent
  - = node will stay awake if AP-to-mobile frames to be sent; otherwise sleep again until next beacon frame

### 802.15: personal area network

- v less than 10 m diameter
- v replacement for cables (mouse, keyboard, headphones)
- v ad hoc: no infrastructure
- v master/slaves:
  - = slaves request permission to send (to master)
  - = master grants requests
- v 802.15: evolved from Bluetooth specification
  - = 2.4-2.5 GHz radio band
  - = up to 721 kbps



- Master device
- S Slave device
- P Parked device (inactive)

### Chapter 6 outline

6.1 Introduction

#### Wireless

- 6.2 Wireless links, characteristics
- 6.3 IEEE 802.11 wireless LANs ("Wi-Fi")
- 6.4 Cellular Internet access
  - = architecture
  - =standards (e.g.,

### Mobility

- 6.5 Principles:

  addressing and
  routing to mobile
  users
- 6.6 Mobile IP
- 6.7 Handling mobility in cellular networks
- 6.8 Mobility and higher-layer protocolswireless, Mobile Networks 6-31

### Components of cellular network architecture


#### MSC

- v connects cells to wired tel. net.
- v manages call setup (more later!)
- v handles mobility (more later!)

#### cell

- v covers geographical region
- v base station (BS) analogous to 802.11 AP
- v *mobile users* attach to network through BS
- v air-interface:

physical and link layer protocol between mobile and BS




### Cellular networks: the first


### hop

Two techniques for sharing mobile-to-BS radio spectrum


- v combined FDMA/TDMA:
  divide spectrum in
  frequency channels, divide
  each channel into time slots
- v CDMA: code division frequency bands bands



### 2G (voice) network architecture



### 3G (voice+data) network architecture




v voice network unchanged in corg

v data network operates in paralle

Serving GPRS Support Node (SGSN)

Gateway GPRS Support Node (GGSN)

### 3G (voice+data) network architecture



## Chapter 6 outline

6.1 Introduction

#### Wireless

- 6.2 Wireless links, characteristics
- 6.3 IEEE 802.11 wireless LANs ("Wi-Fi")
- 6.4 Cellular Internet Access
  - = architecture
  - =standards (e.g.,


#### Mobility

- 6.5 Principles:


  addressing and
  routing to mobile
  users
- 6.6 Mobile IP
- 6.7 Handling mobility in cellular networks
- 6.8 Mobility and higher-layer protocolswireless, Mobile Networks 6-37

# What is mobility?


v spectrum of mobility, from the *network* perspective:



# Mobility: vocabulary



# Mobility: more vocabulary



# How do *you* contact a mobile friend:

Consider friend frequently changing addresses, how do

v search all phone books?

- v call her parents?
- v expect her to let you know where he/she is?

I wonder where Alice moved to?




### Mobility: approaches

- v let routing handle it: routers advertise permanent address of mobile-nodes-in-residence via usual routing table exchange.
  - = routing tables indicate where each mobile located
  - = no changes to end-systems
- v let end-systems handle it:
  - = indirect routing: communication from correspondent to mobile goes through home agent, then forwarded to remote
  - = direct routing: correspondent gets foreign address of mobile, sends directly to mobile

## Mobility: approaches

- v let routing handle it ters advertise permanent
  address of mobil not esidence via usual routing
  table exchange. Scalable
  to millions of
  mobiles tere each mobile located
  = no changes to en terms
- v let end-systems handle it:
  - = indirect routing: communication from correspondent to mobile goes through home agent, then forwarded to remote
  - = direct routing: correspondent gets foreign address of mobile, sends directly to mobile


### Mobility: registration



#### end result:

- v foreign agent knows about mobile
- v home agent knows location of mobile

### Mobility via indirect routing




### Indirect Routing: comments

- v mobile uses two addresses:
  - = permanent address: used by correspondent (hence mobile location is *transparent* to correspondent)
  - = care-of-address: used by home agent to forward datagrams to mobile
- v foreign agent functions may be done by mobile itself
- v triangle routing: correspondent-home network-mobile
  - = inefficient when correspondent, mobile are in same network

# Indirect routing: moving between networks

- v suppose mobile user moves to another network
  - =registers with new foreign agent
  - =new foreign agent registers with home
    agent
  - =home agent update care-of-address for mobile
  - =packets continue to be forwarded to mobile (but with new care-of-address)
- v mobility, changing foreign networks transparent: on going connections can be Wireless, Mobile Networks 6-47 maintained!


### Mobility via direct routing



### Mobility via direct routing:

#### comments


- v overcome triangle routing problem
- v non-transparent to correspondent: correspondent must get care-of-address from home agent
  - = what if mobile changes visited network?



# Accommodating mobility with direct

### routing

- v anchor foreign agent: FA in first visited network
- v data always routed first to anchor FA
- v when mobile moves: new FA arranges to have data forwarded from old FA (chaining)



## Chapter 6 outline

6.1 Introduction

#### Wireless

- 6.2 Wireless links, characteristics
- 6.3 IEEE 802.11 wireless LANs ("Wi-Fi")
- 6.4 Cellular Internet Access
  - = architecture
  - =standards (e.g.,

#### Mobility


- 6.5 Principles:

  addressing and
  routing to mobile
  users
- 6.6 Mobile IP
- 6.7 Handling mobility in cellular networks
- 6.8 Mobility and higher-layer protocolswireless, Mobile Networks 6-51

## Mobile IP

- v RFC 3344
- v has many features we' ve seen:
  - = home agents, foreign agents, foreign-agent registration, care-of-addresses, encapsulation (packet-within-a-packet)
- v three components to standard:
  - = indirect routing of datagrams
  - = agent discovery
  - = registration with home agent

# Mobile IP: indirect routing




# Mobile IP: agent discovery


agent advertisement: foreign/home agents advertise service by broadcasting ICMP messages (typefield = 9)

H,F bits: home and/or foreign agent


R bit: registration required



# Mobile IP: registration



### Components of cellular network architectu




operated by different providers

# Handling mobility in cellular networks


- v home network: network of cellular provider you subscribe to (e.g., Sprint PCS, Verizon)
  - = home location register (HLR): database in home network containing permanent cell phone #, profile information (services, preferences, billing), information about current location (could be in another network)
- v *visited network:* network in which mobile currently resides
  - = visitor location register (VLR): database with entry for each user currently in network
  - = could be home network

# GSM: indirect routing to



# GSM: handoff with common


### MSC



- v handoff goal: route
   call via new base
   station (without
   interruption)
- v reasons for handoff:
  - = stronger signal to/from new BSS (continuing connectivity, less battery drain)
  - = load balance: free up channel in current BSS
  - = GSM doesnt mandate why to perform handoff (policy), only how (mechanism)
- v handoff initiated by old BSS Wireless, Mobile Networks 6-59


#### GSM: handoff with common

### MSC



- old BSS informs MSC of impending handoff, provides list of 1+ new BSSs
- 2. MSC sets up path (allocates resources) to new BSS
- 3. new BSS allocates radio channel for use by mobile
- 4. new BSS signals MSC, old BSS: ready
- 5. old BSS tells mobile: perform handoff to new BSS
- 6. mobile, new BSS signal to activate new channel
- 7. mobile signals via new BSS to MSC: handoff complete. MSC reroutes call
- 8 MSC-old-BSS residences in the residence of the second se


### GSM: handoff between MSCs



(a) before handoff

- v anchor MSC: first MSC visited during call
  - = call remains routed through anchor MSC
- v new MSCs add on to end of MSC chain as mobile moves to new MSC
- v optional pathminimization step toshorten multi-MSC chain

### GSM: handoff between MSCs



(b) after handoff

- v anchor MSC: first MSC visited during call
  - = call remains routed through anchor MSC
- v new MSCs add on to end of MSC chain as mobile moves to new MSC
- v optional pathminimization step toshorten multi-MSC chain

# Mobility: GSM versus Mobile

GSM element	Comment on GSM element Mobile eleme	
Home system	Network to which mobile user's permanent phone number belongs	Home network
Gateway Mobile Switching Center, or "home MSC". Home Location Register (HLR)	Home MSC: point of contact to obtain routable address of mobile user. HLR: database in home system containing permanent phone number, profile information, current location of mobile user, subscription information	Home agent
Visited System	Network other than home system where mobile user is currently residing	Visited network
Visited Mobile services Switching Center. Visitor Location Record (VLR)	Visited MSC: responsible for setting up calls to/from mobile nodes in cells associated with MSC. VLR: temporary database entry in visited system, containing subscription information for each visiting mobile user	Foreign agent
Mobile Station Roaming Number (MSRN), or "roaming number"	Routable address for telephone call segment between home MSC and visited MSC, visible to neither the mobile nor the correspondent.	Care-of- address

# Wireless, mobility: impact on higher layer protocols

- v logically, impact should be minimal ...
  - = best effort service model remains unchanged
  - =TCP and UDP can (and do) run over wireless, mobile
- v ... but performance-wise:
  - = packet loss/delay due to bit-errors (discarded packets, delays for link-layer retransmissions), and handoff
  - = TCP interprets loss as congestion, will decrease congestion window un-necessarily
  - = delay impairments for real-time traffic
  - = limited bandwidth of wireless links