A Consumer Library Interface to DWARF

David Anderson

1. INTRODUCTION

This document describes an interface to *libdwarf*, a library of functions to provide access to DWARF debugging information records, DWARF line number information, DWARF address range and global names information, weak names information, DWARF frame description information, DWARF static function names, DWARF static variables, and DWARF type information.

The document has long mentioned the "Unix International Programming Languages Special Interest Group" (PLSIG), under whose auspices the DWARF committee was formed around 1991. "Unix International" was disbanded in the 1990's and no longer exists.

The DWARF committee published DWARF2 July 27, 1993.

In the mid 1990's this document and the library it describes (which the committee never endorsed, having decided not to endorse or approve any particular library interface) was made available on the internet by Silcon Graphics, Inc.

In 2005 the DWARF committee began an affiliation with FreeStandards.org. In 2007 FreeStandards.org merged with The Linux Foundation. The DWARF committee dropped its affiliation with FreeStandards.org in 2007 and established the dwarfstd.org website. See "http://www.dwarfstd.org" for current information on standardization activities and a copy of the standard.

1.1 Copyright

Copyright 1993-2006 Silicon Graphics, Inc.

Copyright 2007 David Anderson.

Permission is hereby granted to copy or republish or use any or all of this document without restriction except that when publishing more than a small amount of the document please acknowledge Silicon Graphics, Inc and David Anderson.

This document is distributed in the hope that it would be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.

1.2 Purpose and Scope

The purpose of this document is to document a library of functions to access DWARF debugging information. There is no effort made in this document to address the creation of these records as those issues are addressed separately (see "A Producer Library Interface to DWARF").

Additionally, the focus of this document is the functional interface, and as such, implementation as well as optimization issues are intentionally ignored.

1.3 Document History

A document was written about 1991 which had similar layout and interfaces. Written by people from Hal Corporation, That document described a library for reading DWARF1. The authors distributed paper copies to the committee with the clearly expressed intent to propose the document as a supported interface definition. The committee decided not to pursue a library definition.

SGI wrote the document you are now reading in 1993 with a similar layout and content and organization, but it was complete document rewrite with the intent to read DWARF2 (the DWARF version then in existence). The intent was (and is) to also cover future revisions of DWARF. All the function interfaces were changed in 1994 to uniformly return a simple integer success-code (see DW_DLV_OK etc), generally following the recomendations in the chapter titled "Candy Machine Interfaces" of "Writing Solid Code", a book by Steve Maguire (published by Microsoft Press).

1.4 Definitions

DWARF debugging information entries (DIEs) are the segments of information placed in the .debug_* sections by compilers, assemblers, and linkage editors that, in conjunction with line number entries, are necessary for symbolic source-level debugging. Refer to the latest "DWARF Debugging Information Format" from www.dwarfstd.org for a more complete description of these entries.

This document adopts all the terms and definitions in "DWARF Debugging Information Format" versions 2 and 3. It originally focused on the implementation at Silicon Graphics, Inc., but now attempts to be more generally useful.

1.5 Overview

The remaining sections of this document describe the proposed interface to libdwarf, first by describing the purpose of additional types defined by the interface, followed by descriptions of the available operations. This document assumes you are thoroughly familiar with the information contained in the DWARF Debugging Information Format document.

We separate the functions into several categories to emphasize that not all consumers want to use all the functions. We call the categories Debugger, Internal-level, High-level, and Miscellaneous not because one is more important than another but as a way of making the rather large set of function calls easier to understand.

Unless otherwise specified, all functions and structures should be taken as being designed for Debugger consumers.

The Debugger Interface of this library is intended to be used by debuggers. The interface is low-level (close to dwarf) but suppresses irrelevant detail. A debugger will want to absorb all of some sections at startup and will want to see little or nothing of some sections except at need. And even then will probably want to absorb only the information in a single compilation unit at a time. A debugger does not care about implementation details of the library.

The Internal-level Interface is for a DWARF prettyprinter and checker. A thorough prettyprinter will want to know all kinds of internal things (like actual FORM numbers and actual offsets) so it can check for appropriate structure in the DWARF data and print (on request) all that internal information for human users and libdwarf authors and compiler-writers. Calls in this interface provide data a debugger does not care about

The High-level Interface is for higher level access (it's not really a high level interface!). Programs such as disassemblers will want to be able to display relevant information about functions and line numbers without having to invest too much effort in looking at DWARF.

The miscellaneous interface is just what is left over: the error handler functions.

The following is a brief mention of the changes in this libdwarf from the libdwarf draft for DWARF Version 1 and recent changes.

1.6 Items Changed

Added support for various DWARF3 features, but primarily a new frame-information interface tailorable at run-time to more than a single ABI. See dwarf_set_frame_rule_inital_value() and dwarf_set_frame_rule_table_size(). See also dwarf_get_fde_info_for_reg3() and dwarf_get_fde_info_for_cfa_reg3(). (April 2006)

Added support for DWARF3 .debug_pubtypes section. Corrected various leaks (revising dealloc() calls, adding new functions) and corrected dwarf_formstring() documentation.

Added dwarf_srclines_dealloc() as the previous deallocation method documented for data returned by dwarf_srclines() was incapable of freeing all the allocated storage (14 July 2005).

dwarf_nextglob(), dwarf_globname(), and dwarf_globdie() were all changed to operate on the items in the .debug_pubnames section.

All functions were modified to return solely an error code. Data is returned through pointer arguments. This makes writing safe and correct library-using-code far easier. For justification for this approach, see the book by Steve Maguire titled "Writing Solid Code" at your bookstore.

1.7 Items Removed

Dwarf_Type was removed since types are no longer special.

dwarf_typeof() was removed since types are no longer special.

Dwarf_Ellist was removed since element lists no longer are a special format.

Dwarf Bounds was removed since bounds have been generalized.

dwarf_nextdie() was replaced by dwarf_next_cu_header() to reflect the real way DWARF is organized. The dwarf_nextdie() was only useful for getting to compilation unit beginnings, so it does not seem harmful to remove it in favor of a more direct function.

dwarf_childcnt() is removed on grounds that no good use was apparent.

dwarf_prevline() and dwarf_nextline() were removed on grounds this is better left to a debugger to do. Similarly, dwarf_dieline() was removed.

dwarf_is1stline() was removed as it was not meaningful for the revised DWARF line operations.

Any libdwarf implementation might well decide to support all the removed functionality and to retain the DWARF Version 1 meanings of that functionality. This would be difficult because the original libdwarf draft specification used traditional C library interfaces which confuse the values returned by successful calls with exceptional conditions like failures and 'no more data' indications.

1.8 Revision History

March 93 Work on DWARF2 SGI draft begins

June 94 The function returns are changed to return an error/success code only.

April 2006: Support for DWARF3 consumer operations is close to completion.

2. Types Definitions

2.1 General Description

The *libdwarf.h* header file contains typedefs and preprocessor definitions of types and symbolic names used to reference objects of *libdwarf*. The types defined by typedefs contained in *libdwarf.h* all use the convention of adding Dwarf_ as a prefix and can be placed in three categories:

- Scalar types: The scalar types defined in *libdwarf.h* are defined primarily for notational convenience and identification. Depending on the individual definition, they are interpreted as a value, a pointer, or as a flag.
- Aggregate types: Some values can not be represented by a single scalar type; they must be represented by a collection of, or as a union of, scalar and/or aggregate types.
- Opaque types: The complete definition of these types is intentionally omitted; their use is as handles
 for query operations, which will yield either an instance of another opaque type to be used in another
 query, or an instance of a scalar or aggregate type, which is the actual result.

2.2 Scalar Types

The following are the defined by libdwarf.h:

Dwarf_Ptr is an address for use by the host program calling the library, not for representing pc-values/addresses within the target object file. Dwarf_Addr is for pc-values within the target object file. The sample scalar type assignments above are for a *libdwarf.h* that can read and write 32-bit or 64-bit binaries on a 32-bit or 64-bit host machine. The types must be defined appropriately for each implementation of libdwarf. A description of these scalar types in the SGI/MIPS environment is given in Figure 1.

NAME	SIZE	ALIGNMENT	PURPOSE
Dwarf_Bool	4	4	Boolean states
Dwarf_Off	8	8	Unsigned file offset
Dwarf_Unsigned	8	8	Unsigned large integer
Dwarf_Half	2	2	Unsigned medium integer
Dwarf_Small	1	1	Unsigned small integer
Dwarf_Signed	8	8	Signed large integer
Dwarf_Addr	8	8	Program address
			(target program)
Dwarf_Ptr	4 8	4 8	Dwarf section pointer
			(host program)
Dwarf_Handler	4 8	4 8	Pointer to
			error handler function

Figure 1. Scalar Types

2.3 Aggregate Types

The following aggregate types are defined by *libdwarf.h*: Dwarf_Loc, Dwarf_Locdesc, Dwarf_Block, Dwarf_Frame_Op. Dwarf_Regtable. Dwarf_Regtable3. While most of libdwarf acts on or returns simple values or opaque pointer types, this small set of structures seems useful.

2.3.1 Location Record

The Dwarf_Loc type identifies a single atom of a location description or a location expression.

```
typedef struct {
        Dwarf_Small lr_atom;
        Dwarf_Unsigned lr_number;
        Dwarf_Unsigned lr_number2;
        Dwarf_Unsigned lr_offset;
} Dwarf_Loc;
```

The lr_atom identifies the atom corresponding to the DW_OP_* definition in *dwarf.h* and it represents the operation to be performed in order to locate the item in question.

The lr_number field is the operand to be used in the calculation specified by the lr_atom field; not all atoms use this field. Some atom operations imply signed numbers so it is necessary to cast this to a Dwarf_Signed type for those operations.

The lr_number2 field is the second operand specified by the lr_atom field; only DW_OP_BREGX has this field. Some atom operations imply signed numbers so it may be necessary to cast this to a Dwarf_Signed type for those operations.

The lr_offset field is the byte offset (within the block the location record came from) of the atom specified by the lr_atom field. This is set on all atoms. This is useful for operations DW_OP_SKIP and DW_OP_BRA.

2.3.2 Location Description

The Dwarf_Locdesc type represents an ordered list of Dwarf_Loc records used in the calculation to locate an item. Note that in many cases, the location can only be calculated at runtime of the associated program.

```
typedef struct {
    Dwarf_Addr ld_lopc;
    Dwarf_Addr ld_hipc;
    Dwarf_Unsigned ld_cents;
    Dwarf_Loc* ld_s;
}
```

The ld_lopc and ld_hipc fields provide an address range for which this location descriptor is valid. Both of these fields are set to *zero* if the location descriptor is valid throughout the scope of the item it is associated with. These addresses are virtual memory addresses, not offsets-from-something. The virtual memory addresses do not account for dso movement (none of the pc values from libdwarf do that, it is up to the consumer to do that).

The ld_cents field contains a count of the number of Dwarf_Loc entries pointed to by the ld_s field.

The ld_s field points to an array of Dwarf_Loc records.

2.3.3 Data Block

The Dwarf_Block type is used to contain the value of an attribute whose form is either DW_FORM_block1, DW_FORM_block2, DW_FORM_block4, DW_FORM_block8, or DW_FORM_block. Its intended use is to deliver the value for an attribute of any of these forms.

The bl_len field contains the length in bytes of the data pointed to by the bl_data field.

The bl_data field contains a pointer to the uninterpreted data. Since we use a Dwarf_Ptr here one must copy the pointer to some other type (typically an unsigned char *) so one can add increments to index through the data. The data pointed to by bl_data is not necessarily at any useful alignment.

2.3.4 Frame Operation Codes: DWARF 2

This interface is adequate for DWARF2 but not for DWARF3. A separate interface usable for DWARF3 and for DWARF2 is described below.

The DWARF2 Dwarf_Frame_Op type is used to contain the data of a single instruction of an instruction-sequence of low-level information from the section containing frame information. This is ordinarily used by Internal-level Consumers trying to print everything in detail.

```
typedef struct {
    Dwarf_Small fp_base_op;
    Dwarf_Small fp_extended_op;
    Dwarf_Half fp_register;
    Dwarf_Signed fp_offset;
    Dwarf_Offset fp_instr_offset;
} Dwarf_Frame_Op;
```

fp_base_op is the 2-bit basic op code. fp_extended_op is the 6-bit extended opcode (if fp_base_op indicated there was an extended op code) and is zero otherwise.

fp_register is any (or the first) register value as defined in the Call Frame Instruction Encodings figure in the dwarf document. If not used with the Op it is 0.

fp_offset is the address, delta, offset, or second register as defined in the Call Frame Instruction Encodings figure in the dwarf document. If this is an address then the value should be cast to (Dwarf_Addr) before being used. In any implementation this field *must* be as large as the larger of Dwarf_Signed and Dwarf_Addr for this to work properly. If not used with the op it is 0.

fp_instr_offset is the byte_offset (within the instruction stream of the frame instructions) of this operation. It starts at 0 for a given frame descriptor.

2.3.5 Frame Regtable: DWARF 2

This interface is adequate for DWARF2 but not for DWARF3. A separate interface usable for DWARF3 and for DWARF2 is described below.

The Dwarf_Regtable type is used to contain the register-restore information for all registers at a given PC value. Normally used by debuggers.

The array is indexed by register number. The field values for each index are described next. For clarity we describe the field values for index rules[M] (M being any legal array element index).

dw_offset_relevant is non-zero to indicate the dw_offset field is meaningful. If zero then the dw_offset is zero and should be ignored.

dw_regnum is the register number applicable. If dw_offset_relevant is zero, then this is the register number of the register containing the value for register M. If dw_offset_relevant is non-zero, then this is the register number of the register to use as a base (M may be DW_FRAME_CFA_COL, for example) and the dw_offset value applies. The value of register M is therefore the value of register dw_regnum.P dw_offset should be ignored if dw_offset_relevant is zero. If dw_offset_relevant is non-zero, then the consumer code should add the value to the value of the register dw_regnum to produce the value.

2.3.6 Frame Operation Codes: DWARF 3 (and DWARF2)

This interface is adequate for DWARF3 and for DWARF2. It is new in libdwarf in April 2006.

The DWARF2 Dwarf_Frame_Op3 type is used to contain the data of a single instruction of an instruction-sequence of low-level information from the section containing frame information. This is ordinarily used by Internal-level Consumers trying to print everything in detail.

```
typedef struct {
       Dwarf Small
                       fp base op;
       Dwarf_Small
                        fp extended op;
       Dwarf Half
                        fp register;
        /* Value may be signed, depends on op.
           Any applicable data_alignment_factor has
           not been applied, this is the raw offset. */
       Dwarf Unsigned fp offset or block len;
       Dwarf Small
                      *fp_expr_block;
       Dwarf Off
                        fp_instr_offset;
} Dwarf_Frame_Op3;
```

fp_base_op is the 2-bit basic op code. fp_extended_op is the 6-bit extended opcode (if fp_base_op indicated there was an extended op code) and is zero otherwise.

fp_register is any (or the first) register value as defined in the Call Frame Instruction Encodings figure in the dwarf document. If not used with the Op it is 0.

fp_offset_or_block_len is the address, delta, offset, or second register as defined in the Call Frame Instruction Encodings figure in the dwarf document. Or (depending on the op, it may be the length of the dwarf-expression block pointed to by fp_expr_block. If this is an address then the value should be cast to (Dwarf_Addr) before being used. In any implementation this field *must* be as large as the larger of Dwarf_Signed and Dwarf_Addr for this to work properly. If not used with the op it is 0.

fp_expr_block (if applicable to the op) points to a dwarf-expression block whch is fp_offset_or_block_len bytes long.

fp_instr_offset is the byte_offset (within the instruction stream of the frame instructions) of this operation. It starts at 0 for a given frame descriptor.

2.3.7 Frame Regtable: DWARF 3

This interface is adequate for DWARF3 and for DWARF2. It is new in libdwarf as of April 2006.

The Dwarf_Regtable3 type is used to contain the register-restore information for all registers at a given PC value. Normally used by debuggers.

```
typedef struct Dwarf_Regtable_Entry3_s {
        Dwarf_Small
                            dw_offset_relevant;
        Dwarf Small
                            dw_value_type;
        Dwarf Half
                            dw regnum;
        Dwarf_Unsigned
                            dw_offset_or_block_len;
        Dwarf Ptr
                            dw block ptr;
}Dwarf_Regtable_Entry3;
typedef struct Dwarf Regtable3 s {
   struct Dwarf Regtable Entry3 s
                                     rt3 cfa rule;
   Dwarf Half
                                     rt3_reg_table_size;
    struct Dwarf_Regtable_Entry3_s * rt3_rules;
} Dwarf Regtable3;
```

The array is indexed by register number. The field values for each index are described next. For clarity we describe the field values for index rules[M] (M being any legal array element index). (DW_FRAME_CFA_COL3 DW_FRAME_SAME_VAL, DW_FRAME_UNDEFINED_VAL are not legal array indexes, nor is any index < 0 or > rt3_reg_table_size); The caller of routines using this struct must create data space for rt3_reg_table_size entries of struct Dwarf_Regtable_Entry3_s and arrange that rt3_rules points to that space and that rt3_reg_table_size is set correctly. The caller need not (but may) initialize the contents of the rt3_cfa_rule or the rt3_rules array. The following applies to each rt3_rules rule M:

dw_regnum is the register number applicable. If dw_regnum is DW_FRAME_UNDEFINED_VAL, then the register I has undefined value. If dw_regnum is DW_FRAME_SAME_VAL, then the register I has the same value as in the previous frame.

If dw_regnum is neither of these two, then the following apply:

dw_value_type determines the meaning of the other fields. It is one of DW_EXPR_OFFSET (0), DW_EXPR_VAL_OFFSET(1), DW_EXPR_EXPRESSION(2) or DW_EXPR_VAL_EXPRESSION(3).

If dw_value_type is DW_EXPR_OFFSET (0) then this is as in DWARF2 and the offset(N) rule or the register(R) rule of the DWARF3 and DWARF2 document applies. The value is either: If dw_offset_relevant is non-zero, then dw_regnum is effectively ignored but must be identical to DW_FRAME_CFA_COL3 and the dw_offset value applies. The value of register M is therefore the value of CFA plus the value of dw_offset. The result of the calculation is the address in memory where the value of register M resides. This is the offset(N) rule of the DWARF2 and DWARF3 documents.

dw_offset_relevant is zero it indicates the dw_offset field is not meaningful. The value of register M is the value currently in register dw_regnum (the value DW_FRAME_CFA_COL3 must not appear, only real registers). This is the register(R) rule of the DWARF3 spec.

If dw_value_type is DW_EXPR_OFFSET (1) then this is the the val_offset(N) rule of the DWARF3 spec applies. The calculation is identical to that of DW_EXPR_OFFSET (0) but the value is interpreted as the value of register M (rather than the address where register M's value is stored).

If dw_value_type is DW_EXPR_EXPRESSION (2) then this is the the expression(E) rule of the DWARF3 document.

dw_offset_or_block_len is the length in bytes of the in-memory block pointed at by dw_block_ptr. dw_block_ptr is a DWARF expression. Evaluate that expression and the result is the address where the previous value of register M is found.

If dw_value_type is DW_EXPR_VAL_EXPRESSION (3) then this is the the val_expression(E) rule of the DWARF3 spec.

dw_offset_or_block_len is the length in bytes of the in-memory block pointed at by dw_block_ptr. dw_block_ptr is a DWARF expression. Evaluate that expression and the result is the previous value of register M.

The rule rt3_cfa_rule is the current value of the CFA. It is interpreted exactly like any register M rule (as described just above) except that dw_regnum cannot be CW_FRAME_CFA_REG3 or DW_FRAME_UNDEFINED_VAL or DW_FRAME_SAME_VAL but must be a real register number.

2.3.8 Macro Details Record

The Dwarf_Macro_Details type gives information about a single entry in the .debug.macinfo section.

```
struct Dwarf_Macro_Details_s {
   Dwarf_Off     dmd_offset;
   Dwarf_Small     dmd_type;
   Dwarf_Signed     dmd_lineno;
   Dwarf_Signed     dmd_fileindex;
   char *     dmd_macro;
};
typedef struct Dwarf_Macro_Details_s Dwarf_Macro_Details;
```

dmd offset is the byte offset, within the .debug macinfo section, of this macro information.

dmd_type is the type code of this macro info entry (or 0, the type code indicating that this is the end of macro information entries for a compilation unit. See DW_MACINFO_define, etc in the DWARF document.

dmd_lineno is the line number where this entry was found, or 0 if there is no applicable line number.

dmd_fileindex is the file index of the file involved. This is only guaranteed meaningful on a DW_MACINFO_start_file dmd_type. Set to -1 if unknown (see the functional interface for more details).

dmd_macro is the applicable string. For a DW_MACINFO_define this is the macro name and value. For a DW_MACINFO_undef, or this is the macro name. For a DW_MACINFO_vendor_ext this is the vendor-defined string value. For other dmd_types this is 0.

2.4 Opaque Types

The opaque types declared in *libdwarf.h* are used as descriptors for queries against DWARF information stored in various debugging sections. Each time an instance of an opaque type is returned as a result of a *libdwarf* operation (Dwarf_Debug excepted), it should be free'd, using dwarf_dealloc() when it is no longer of use (read the following documentation for details, as in at least one case there is a special routine provided for deallocation and dwarf_dealloc() is not directly called: see dwarf_srclines()). Some functions return a number of instances of an opaque type in a block, by means of a pointer to the block and a count of the number of opaque descriptors in the block: see the function description for deallocation rules for such functions. The list of opaque types defined in *libdwarf.h* that are pertinent to the Consumer Library, and their intended use is described below.

typedef struct Dwarf_Debug_s* Dwarf_Debug;

An instance of the Dwarf_Debug type is created as a result of a successful call to dwarf_init(), or dwarf_elf_init(), and is used as a descriptor for subsequent access to most libdwarf functions on that object. The storage pointed to by this descriptor should be not be free'd, using the dwarf_dealloc() function. Instead free it with dwarf_finish().

typedef struct Dwarf Die s* Dwarf Die;

An instance of a Dwarf_Die type is returned from a successful call to the dwarf_siblingof(), dwarf_child, or dwarf_offdie() function, and is used as a descriptor for queries about information related to that DIE. The storage pointed to by this descriptor should be free'd, using dwarf_dealloc() with the allocation type DW_DLA_DIE when no longer needed.

typedef struct Dwarf_Line_s* Dwarf_Line;

Instances of Dwarf_Line type are returned from a successful call to the dwarf_srclines() function, and are used as descriptors for queries about source lines. The storage pointed to by these descriptors should be individually free'd, using dwarf_dealloc() with the allocation type DW_DLA_LINE when no longer needed.

typedef struct Dwarf_Global_s* Dwarf_Global;

Instances of Dwarf_Global type are returned from a successful call to the dwarf_get_globals() function, and are used as descriptors for queries about global names (pubnames).

typedef struct Dwarf_Weak_s* Dwarf_Weak;

Instances of Dwarf_Weak type are returned from a successful call to the SGI-specific dwarf_get_weaks() function, and are used as descriptors for queries about weak names. The storage pointed to by these descriptors should be individually free'd, using dwarf_dealloc() with the allocation type DW_DLA_WEAK_CONTEXT (or DW_DLA_WEAK, an older name, supported for compatibility) when no longer needed.

typedef struct Dwarf_Func_s* Dwarf_Func;

Instances of Dwarf_Func type are returned from a successful call to the SGI-specific dwarf_get_funcs() function, and are used as descriptors for queries about static function names.

typedef struct Dwarf_Type_s* Dwarf_Type;

Instances of Dwarf_Type type are returned from a successful call to the SGI-specific dwarf_get_types() function, and are used as descriptors for queries about user defined types.

typedef struct Dwarf_Var_s* Dwarf_Var;

Instances of Dwarf_Var type are returned from a successful call to the SGI-specific dwarf get vars() function, and are used as descriptors for queries about static variables.

typedef struct Dwarf_Error_s* Dwarf_Error;

This descriptor points to a structure that provides detailed information about errors detected by libdwarf. Users typically provide a location for libdwarf to store this descriptor for the user to obtain more information about the error. The storage pointed to by this descriptor should be free'd, using

dwarf_dealloc() with the allocation type DW_DLA_ERROR when no longer needed.

```
typedef struct Dwarf_Attribute_s* Dwarf_Attribute;
```

Instances of Dwarf_Attribute type are returned from a successful call to the dwarf_attrlist(), or dwarf_attr() functions, and are used as descriptors for queries about attribute values. The storage pointed to by this descriptor should be individually free'd, using dwarf_dealloc() with the allocation type DW_DLA_ATTR when no longer needed.

```
typedef struct Dwarf_Abbrev_s* Dwarf_Abbrev;
```

An instance of a Dwarf_Abbrev type is returned from a successful call to dwarf_get_abbrev(), and is used as a descriptor for queries about abbreviations in the .debug_abbrev section. The storage pointed to by this descriptor should be free'd, using dwarf_dealloc() with the allocation type DW_DLA_ABBREV when no longer needed.

```
typedef struct Dwarf_Fde_s* Dwarf_Fde;
```

Instances of Dwarf_Fde type are returned from a successful call to the dwarf_get_fde_list(), dwarf_get_fde_for_die(), or dwarf_get_fde_at_pc() functions, and are used as descriptors for queries about frames descriptors.

```
typedef struct Dwarf_Cie_s* Dwarf_Cie;
```

Instances of Dwarf_Cie type are returned from a successful call to the dwarf_get_fde_list() function, and are used as descriptors for queries about information that is common to several frames.

```
typedef struct Dwarf_Arange_s* Dwarf_Arange;
```

Instances of Dwarf_Arange type are returned from successful calls to the dwarf_get_aranges(), or dwarf_get_arange() functions, and are used as descriptors for queries about address ranges. The storage pointed to by this descriptor should be individually free'd, using dwarf_dealloc() with the allocation type DW_DLA_ARANGE when no longer needed.

3. Error Handling

The method for detection and disposition of error conditions that arise during access of debugging information via *libdwarf* is consistent across all *libdwarf* functions that are capable of producing an error. This section describes the method used by *libdwarf* in notifying client programs of error conditions.

Most functions within *libdwarf* accept as an argument a pointer to a Dwarf_Error descriptor where a Dwarf_Error descriptor is stored if an error is detected by the function. Routines in the client program that provide this argument can query the Dwarf_Error descriptor to determine the nature of the error and perform appropriate processing.

A client program can also specify a function to be invoked upon detection of an error at the time the library is initialized (see dwarf_init()). When a *libdwarf* routine detects an error, this function is called with two arguments: a code indicating the nature of the error and a pointer provided by the client at initialization (again see dwarf_init()). This pointer argument can be used to relay information between the error handler and other routines of the client program. A client program can specify or change both the error handling function and the pointer argument after initialization using dwarf_seterrhand() and dwarf_seterrarg().

In the case where *libdwarf* functions are not provided a pointer to a Dwarf_Error descriptor, and no error handling function was provided at initialization, *libdwarf* functions terminate execution by calling abort (3C).

The following lists the processing steps taken upon detection of an error:

- 1. Check the error argument; if not a *NULL* pointer, allocate and initialize a Dwarf_Error descriptor with information describing the error, place this descriptor in the area pointed to by error, and return a value indicating an error condition.
- If an errhand argument was provided to dwarf_init() at initialization, call errhand()
 passing it the error descriptor and the value of the errarg argument provided to
 dwarf_init(). If the error handling function returns, return a value indicating an error
 condition.
- 3. Terminate program execution by calling abort (3C).

In all cases, it is clear from the value returned from a function that an error occurred in executing the function, since DW DLV ERROR is returned.

As can be seen from the above steps, the client program can provide an error handler at initialization, and still provide an error argument to *libdwarf* functions when it is not desired to have the error handler invoked.

If a libdwarf function is called with invalid arguments, the behaviour is undefined. In particular, supplying a NULL pointer to a libdwarf function (except where explicitly permitted), or pointers to invalid addresses or uninitialized data causes undefined behaviour; the return value in such cases is undefined, and the function may fail to invoke the caller supplied error handler or to return a meaningful error number. Implementations also may abort execution for such cases.

3.1 Returned values in the functional interface

Values returned by libdwarf functions to indicate success and errors are enumerated in Figure 2. The DW_DLV_NO_ENTRY case is useful for functions need to indicate that while there was no data to return there was no error either. For example, dwarf_siblingof() may return DW_DLV_NO_ENTRY to indicate that that there was no sibling to return.

SYMBOLIC NAME	VALUE	MEANING
DW_DLV_ERROR	1	Error
DW_DLV_OK	0	Successful call
DW_DLV_NO_ENTRY	-1	No applicable value

Figure 2. Error Indications

Each function in the interface that returns a value returns one of the integers in the above figure.

If DW_DLV_ERROR is returned and a pointer to a Dwarf_Error pointer is passed to the function, then a Dwarf_Error handle is returned thru the pointer. No other pointer value in the interface returns a value. After the Dwarf_Error is no longer of interest, a dwarf_dealloc(dbg,dw_err,DW_DLA_ERROR) on the error pointer is appropriate to free any space used by the error information.

If DW_DLV_NO_ENTRY is returned no pointer value in the interface returns a value.

If DW_DLV_OK is returned the Dwarf_Error pointer, if supplied, is not touched, but any other values to be returned through pointers are returned. In this case calls (depending on the exact function returning the

error) to $dwarf_dealloc()$ may be appropriate once the particular pointer returned is no longer of interest.

Pointers passed to allow values to be returned thru them are uniformly the last pointers in each argument list.

All the interface functions are defined from the point of view of the writer-of-the-library (as is traditional for UN*X library documentation), not from the point of view of the user of the library. The caller might code:

```
Dwarf_Line line;
Dwarf_Signed ret_loff;
Dwarf_Error err;
int retval = dwarf_lineoff(line,&ret_loff,&err);
for the function defined as
int dwarf_lineoff(Dwarf_Line line,Dwarf_Signed *return_lineoff,Dwarf_Error* err);
```

and this document refers to the function as returning the value thru *err or *return_lineoff or uses the phrase "returns in the location pointed to by err". Sometimes other similar phrases are used.

4. Memory Management

Several of the functions that comprise *libdwarf* return pointers (opaque descriptors) to structures that have been dynamically allocated by the library. To aid in the management of dynamic memory, the function dwarf_dealloc() is provided to free storage allocated as a result of a call to a *libdwarf* function. This section describes the strategy that should be taken by a client program in managing dynamic storage.

4.1 Read-only Properties

All pointers (opaque descriptors) returned by or as a result of a *libdwarf Consumer Library* call should be assumed to point to read-only memory. The results are undefined for *libdwarf* clients that attempt to write to a region pointed to by a value returned by a *libdwarf Consumer Library* call.

4.2 Storage Deallocation

See the section "Returned values in the functional interface", above, for the general rules where calls to dwarf dealloc() is appropriate.

In some cases the pointers returned by a *libdwarf* call are pointers to data which is not free-able. The library knows from the allocation type provided to it whether the space is freeable or not and will not free inappropriately when dwarf_dealloc() is called. So it is vital that dwarf_dealloc() be called with the proper allocation type.

For most storage allocated by <code>libdwarf</code>, the client can free the storage for reuse by calling <code>dwarf_dealloc()</code>, providing it with the <code>Dwarf_Debug</code> descriptor specifying the object for which the storage was allocated, a pointer to the area to be free-ed, and an identifier that specifies what the pointer points to (the allocation type). For example, to free a <code>Dwarf_Die</code> <code>die</code> belonging the the object represented by <code>Dwarf_Debug</code> <code>dbg</code>, allocated by a call to <code>dwarf_siblingof()</code>, the call to <code>dwarf_dealloc()</code> would be:

```
dwarf_dealloc(dbg, die, DW_DLA_DIE);
```

To free storage allocated in the form of a list of pointers (opaque descriptors), each member of the list

should be deallocated, followed by deallocation of the actual list itself. The following code fragment uses an invocation of dwarf_attrlist() as an example to illustrate a technique that can be used to free storage from any *libdwarf* routine that returns a list:

The Dwarf_Debug returned from dwarf_init() or dwarf_elf_init() cannot be free'd using dwarf_dealloc(). The function dwarf_finish() will deallocate all dynamic storage associated with an instance of a Dwarf_Debug type. In particular, it will deallocate all dynamically allocated space associated with the Dwarf_Debug descriptor, and finally make the descriptor invalid.

An Dwarf_Error returned from dwarf_init() or dwarf_elf_init() in case of a failure cannot be free'd using dwarf_dealloc(). The only way to free the Dwarf_Error from either of those calls is to use *free(3)* directly. Every Dwarf_Error must be free'd by dwarf_dealloc() except those returned by dwarf_init() or dwarf_elf_init().

The codes that identify the storage pointed to in calls to dwarf_dealloc() are described in figure 3.

IDENTIFIER	USED TO FREE
DW_DLA_STRING	char*
DW_DLA_LOC	Dwarf_Loc
DW_DLA_LOCDESC	Dwarf_Locdesc
DW_DLA_ELLIST	Dwarf_Ellist (not used)
DW_DLA_BOUNDS	Dwarf_Bounds (not used)
DW_DLA_BLOCK	Dwarf_Block
DW_DLA_DEBUG	Dwarf_Debug (do not use)
DW_DLA_DIE	Dwarf_Die
DW_DLA_LINE	Dwarf_Line
DW_DLA_ATTR	Dwarf_Attribute
DW_DLA_TYPE	Dwarf_Type (not used)
DW_DLA_SUBSCR	Dwarf_Subscr (not used)
DW_DLA_GLOBAL_CONTEXT	Dwarf_Global
DW_DLA_ERROR	Dwarf_Error
DW_DLA_LIST	a list of opaque descriptors
DW_DLA_LINEBUF	Dwarf_Line* (not used)
DW_DLA_ARANGE	Dwarf_Arange
DW_DLA_ABBREV	Dwarf_Abbrev
DW_DLA_FRAME_OP	Dwarf_Frame_Op
DW_DLA_CIE	Dwarf_Cie
DW_DLA_FDE	Dwarf_Fde
DW_DLA_LOC_BLOCK	Dwarf_Loc Block
DW_DLA_FRAME_BLOCK	Dwarf_Frame Block (not used)
DW_DLA_FUNC_CONTEXT	Dwarf_Func
DW_DLA_TYPENAME_CONTEXT	Dwarf_Type
DW_DLA_VAR_CONTEXT	Dwarf_Var
DW_DLA_WEAK_CONTEXT	Dwarf_Weak
DW_DLA_PUBTYPES_CONTEXT	Dwarf_Pubtype

Figure 3. Allocation/Deallocation Identifiers

5. Functional Interface

This section describes the functions available in the *libdwarf* library. Each function description includes its definition, followed by one or more paragraph describing the function's operation.

The following sections describe these functions.

5.1 Initialization Operations

These functions are concerned with preparing an object file for subsequent access by the functions in *libdwarf* and with releasing allocated resources when access is complete.

5.1.1 dwarf_init()

```
int dwarf_init(
    int fd,
    Dwarf_Unsigned access,
    Dwarf_Handler errhand,
    Dwarf_Ptr errarg,
    Dwarf_Debug * dbg,
    Dwarf_Error *error)
```

When it returns DW_DLV_OK, the function dwarf_init() returns thru dbg a Dwarf_Debug descriptor that represents a handle for accessing debugging records associated with the open file descriptor fd. DW_DLV_NO_ENTRY is returned if the object does not contain DWARF debugging information. DW_DLV_ERROR is returned if an error occurred. The access argument indicates what access is allowed for the section. The DW_DLC_READ parameter is valid for read access (only read access is defined or discussed in this document). The errhand argument is a pointer to a function that will be invoked whenever an error is detected as a result of a *libdwarf* operation. The errarg argument is passed as an argument to the errhand function. The file descriptor associated with the fd argument must refer to an ordinary file (i.e. not a pipe, socket, device, /proc entry, etc.), be opened with the at least as much permission as specified by the access argument, and cannot be closed or used as an argument to any system calls by the client until after dwarf_finish() is called. The seek position of the file associated with fd is undefined upon return of dwarf_init().

With SGI IRIX, by default it is allowed that the app close() fd immediately after calling dwarf_init(), but that is not a portable approach (that it works is an accidental side effect of the fact that SGI IRIX uses ELF_C_READ_MMAP in its hidden internal call to elf_begin()). The portable approach is to consider that fd must be left open till after the corresponding dwarf_finish() call has returned.

Since dwarf_init() uses the same error handling processing as other *libdwarf* functions (see *Error Handling* above), client programs will generally supply an error parameter to bypass the default actions during initialization unless the default actions are appropriate.

5.1.2 dwarf_elf_init()

```
int dwarf_elf_init(
    Elf * elf_file_pointer,
    Dwarf_Unsigned access,
    Dwarf_Handler errhand,
    Dwarf_Ptr errarg,
    Dwarf_Debug * dbg,
    Dwarf Error *error)
```

The function dwarf_elf_init() is identical to dwarf_init() except that an open Elf * pointer is passed instead of a file descriptor. In systems supporting ELF object files this may be more space or time-efficient than using dwarf_init(). The client is allowed to use the Elf * pointer for its own purposes without restriction during the time the Dwarf_Debug is open, except that the client should not elf_end() the pointer till after dwarf_finish is called.

5.1.3 dwarf_get_elf()

When it returns DW_DLV_OK, the function dwarf_get_elf() returns thru the pointer elf the Elf * handle used to access the object represented by the Dwarf_Debug descriptor dbg. It returns DW DLV ERROR on error.

Because int dwarf_init() opens an Elf descriptor on its fd and dwarf_finish() does not close that descriptor, an app should use dwarf_get_elf and should call elf_end with the pointer returned thru the Elf** handle created by int dwarf_init().

This function is not meaningful for a system that does not use the Elf format for objects.

5.1.4 dwarf finish()

The function dwarf_finish() releases all *Libdwarf* internal resources associated with the descriptor dbg, and invalidates dbg. It returns DW_DLV_ERROR if there is an error during the finishing operation. It returns DW_DLV_OK for a successful operation.

Because int dwarf_init() opens an Elf descriptor on its fd and dwarf_finish() does not close that descriptor, an app should use dwarf_get_elf and should call elf_end with the pointer returned thru the Elf** handle created by int dwarf_init().

5.2 Debugging Information Entry Delivery Operations

These functions are concerned with accessing debugging information entries.

5.2.1 Debugging Information Entry Debugger Delivery Operations

5.2.2 dwarf_next_cu_header()

```
int dwarf_next_cu_header(
    Dwarf_debug dbg,
    Dwarf_Unsigned *cu_header_length,
    Dwarf_Half *version_stamp,
    Dwarf_Unsigned *abbrev_offset,
    Dwarf_Half *address_size,
    Dwarf_Unsigned *next_cu_header,
    Dwarf_Error *error);
```

The function dwarf_next_cu_header() returns DW_DLV_ERROR if it fails, and DW_DLV_OK if it succeeds.

If it succeeds, *next_cu_header is set to the offset in the .debug_info section of the next compilation-unit header if it succeeds. On reading the last compilation-unit header in the .debug_info section it contains the size of the .debug_info section. The next call to dwarf_next_cu_header() returns DW_DLV_NO_ENTRY without reading a compilation-unit or setting *next_cu_header. Subsequent calls to dwarf_next_cu_header() repeat the cycle by reading the first compilation-unit and so on.

The other values returned through pointers are the values in the compilation-unit header. If any of cu_header_length, version_stamp, abbrev_offset, or address_size is NULL, the argument is ignored (meaning it is not an error to provide a NULL pointer).

5.2.3 dwarf_siblingof()

The function dwarf_siblingof() returns DW_DLV_ERROR and sets the error pointer on error. If there is no sibling it returns DW_DLV_NO_ENTRY. When it succeeds, dwarf_siblingof() returns DW_DLV_OK and sets *return_sib to the Dwarf_Die descriptor of the sibling of die. If die is NULL, the Dwarf_Die descriptor of the first die in the compilation-unit is returned. This die has the DW_TAG_compile_unit tag.

5.2.4 dwarf_child()

The function dwarf_child() returns DW_DLV_ERROR and sets the error die on error. If there is no child it returns DW_DLV_NO_ENTRY. When it succeeds, dwarf_child() returns DW_DLV_OK and sets *return_kid to the Dwarf_Die descriptor of the first child of die. The function dwarf_siblingof() can be used with the return value of dwarf_child() to access the other children of die.

5.2.5 dwarf_offdie()

The function dwarf_offdie() returns DW_DLV_ERROR and sets the error die on error. When it succeeds, dwarf_offdie() returns DW_DLV_OK and sets *return_die to the Dwarf_Die descriptor of the debugging information entry at offset in the section containing debugging information entries i.e the .debug_info section. A return of DW_DLV_NO_ENTRY means that the offset in the section is of a byte containing all 0 bits, indicating that there is no abbreviation code. Meaning this 'die offset' is not the offset of a real die, but is instead an offset of a null die, a padding die, or of some random zero byte: this should not be returned in normal use. It is the user's responsibility to make sure that offset is the start of a valid debugging information entry. The result of passing it an invalid offset could be chaos.

5.3 Debugging Information Entry Query Operations

These queries return specific information about debugging information entries or a descriptor that can be used on subsequent queries when given a Dwarf_Die descriptor. Note that some operations are specific to debugging information entries that are represented by a Dwarf_Die descriptor of a specific type. For example, not all debugging information entries contain an attribute having a name, so consequently, a call to dwarf_diename() using a Dwarf_Die descriptor that does not have a name attribute will return DW_DLV_NO_ENTRY. This is not an error, i.e. calling a function that needs a specific attribute is not an

error for a die that does not contain that specific attribute.

There are several methods that can be used to obtain the value of an attribute in a given die:

- 1. Call dwarf_hasattr() to determine if the debugging information entry has the attribute of interest prior to issuing the query for information about the attribute.
- Supply an error argument, and check its value after the call to a query indicates an unsuccessful return, to determine the nature of the problem. The error argument will indicate whether an error occurred, or the specific attribute needed was missing in that die.
- 3. Arrange to have an error handling function invoked upon detection of an error (see dwarf_init()).
- 4. Call dwarf_attrlist() and iterate through the returned list of attributes, dealing with each one as appropriate.

5.3.1 dwarf_tag()

The function dwarf_tag() returns the *tag* of die thru the pointer tagval if it succeeds. It returns DW_DLV_OK if it succeeds. It returns DW_DLV_ERROR on error.

5.3.2 dwarf_dieoffset()

When it succeeds, the function <code>dwarf_dieoffset()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the position of <code>die</code> in the section containing debugging information entries (the <code>return_offset</code> is a section-relative offset). In other words, it sets <code>return_offset</code> to the offset of the start of the debugging information entry described by <code>die</code> in the section containing die's i.e .debug_info. It returns <code>DW_DLV_ERROR</code> on error.

5.3.3 dwarf_die_CU_offset()

The function dwarf_die_CU_offset() is similar to dwarf_dieoffset(), except that it puts the offset of the DIE represented by the Dwarf_Die die, from the start of the compilation-unit that it belongs to rather than the start of .debug_info (the return_offset is a CU-relative offset).

5.3.4 dwarf_diename()

When it succeeds, the function dwarf_diename() returns DW_DLV_OK and sets *return_name to a pointer to a null-terminated string of characters that represents the name attribute of die. It returns DW_DLV_NO_ENTRY if die does not have a name attribute. It returns DW_DLV_ERROR if an error occurred. The storage pointed to by a successful return of dwarf_diename() should be free'd using the allocation type DW_DLA_STRING when no longer of interest (see dwarf_dealloc()).

5.3.5 dwarf attrlist()

When it returns DW_DLV_OK, the function dwarf_attrlist() sets attrbuf to point to an array of Dwarf_Attribute descriptors corresponding to each of the attributes in die, and returns the number of elements in the array thru attrcount. DW_DLV_NO_ENTRY is returned if the count is zero (no attrbuf is allocated in this case). DW_DLV_ERROR is returned on error. On a successful return from dwarf_attrlist(), each of the Dwarf_Attribute descriptors should be individually free'd using dwarf_dealloc() with the allocation type DW_DLA_ATTR, followed by free-ing the list pointed to by *attrbuf using dwarf_dealloc() with the allocation type DW_DLA_LIST, when no longer of interest (see dwarf_dealloc()).

Freeing the attrlist:

5.3.6 dwarf_hasattr()

When it succeeds, the function dwarf_hasattr() returns DW_DLV_OK and sets *return_bool to

non-zero if die has the attribute attr and zero otherwise. If it fails, it returns DW_DLV_ERROR.

5.3.7 dwarf_attr()

When it returns DW_DLV_OK, the function dwarf_attr() sets *return_attr to the Dwarf_Attribute descriptor of die having the attribute attr. It returns DW_DLV_NO_ENTRY if attr is not contained in die. It returns DW_DLV_ERROR if an error occurred.

5.3.8 dwarf_lowpc()

The function dwarf_lowpc() returns DW_DLV_OK and sets *return_lowpc to the low program counter value associated with the die descriptor if die represents a debugging information entry with this attribute. It returns DW_DLV_NO_ENTRY if die does not have this attribute. It returns DW_DLV_ERROR if an error occurred.

5.3.9 dwarf_highpc()

The function dwarf_highpc() returns DW_DLV_OK and sets *return_highpc the high program counter value associated with the die descriptor if die represents a debugging information entry with this attribute. It returns DW_DLV_NO_ENTRY if die does not have this attribute. It returns DW_DLV_ERROR if an error occurred.

5.3.10 dwarf_bytesize()

When it succeeds, dwarf_bytesize() returns DW_DLV_OK and sets *return_size to the number of bytes needed to contain an instance of the aggregate debugging information entry represented by die. It returns DW_DLV_NO_ENTRY if die does not contain the byte size attribute DW_AT_byte_size. It returns DW_DLV_ERROR if an error occurred.

5.3.11 dwarf_bitsize()

When it succeeds, dwarf_bitsize() returns DW_DLV_OK and sets *return_size to the number of bits occupied by the bit field value that is an attribute of the given die. It returns DW_DLV_NO_ENTRY if die does not contain the bit size attribute DW_AT_bit_size. It returns DW_DLV_ERROR if an error occurred.

5.3.12 dwarf_bitoffset()

When it succeeds, dwarf_bitoffset() returns DW_DLV_OK and sets *return_size to the number of bits to the left of the most significant bit of the bit field value. This bit offset is not necessarily the net bit offset within the structure or class, since DW_AT_data_member_location may give a byte offset to this DIE and the bit offset returned through the pointer does not include the bits in the byte offset. It returns DW_DLV_NO_ENTRY if die does not contain the bit offset attribute DW_AT_bit_offset. It returns DW_DLV_ERROR if an error occurred.

5.3.13 dwarf_srclang()

When it succeeds, dwarf_srclang() returns DW_DLV_OK and sets *return_lang to a code indicating the source language of the compilation unit represented by the descriptor die. It returns DW_DLV_NO_ENTRY if die does not represent a source file debugging information entry (i.e. contain the attribute DW_AT_language). It returns DW_DLV_ERROR if an error occurred.

5.3.14 dwarf_arrayorder()

When it succeeds, dwarf_arrayorder() returns DW_DLV_OK and sets *return_order a code indicating the ordering of the array represented by the descriptor die. It returns DW_DLV_NO_ENTRY if die does not contain the array order attribute DW_AT_ordering. It returns DW_DLV_ERROR if an error occurred.

5.4 Attribute Form Queries

Based on the attribute's form, these operations are concerned with returning uninterpreted attribute data. Since it is not always obvious from the return value of these functions if an error occurred, one should

always supply an error parameter or have arranged to have an error handling function invoked (see dwarf_init()) to determine the validity of the returned value and the nature of any errors that may have occurred.

A Dwarf_Attribute descriptor describes an attribute of a specific die. Thus, each Dwarf_Attribute descriptor is implicitly associated with a specific die.

5.4.1 dwarf_hasform()

The function dwarf_hasform() returns DW_DLV_OK and and puts a non-zero value in the *return_hasform boolean if the attribute represented by the Dwarf_Attribute descriptor attr has the attribute form form. If the attribute does not have that form zero is put into *return hasform. DW DLV ERROR is returned on error.

5.4.2 dwarf_whatform()

When it succeeds, dwarf_whatform() returns DW_DLV_OK and sets *return_form to the attribute form code of the attribute represented by the Dwarf_Attribute descriptor attr. It returns DW_DLV_ERROR on error. An attribute using DW_FORM_indirect effectively has two forms. This function returns the 'final' form for DW_FORM_indirect, not the DW_FORM_indirect itself. This function is what most applications will want to call.

5.4.3 dwarf_whatform_direct()

When it succeeds, dwarf_whatform_direct() returns DW_DLV_OK and sets *return_form to the attribute form code of the attribute represented by the Dwarf_Attribute descriptor attr. It returns DW_DLV_ERROR on error. An attribute using DW_FORM_indirect effectively has two forms. This returns the form 'directly' in the initial form field. So when the form field is DW_FORM_indirect this call returns the DW_FORM_indirect form, which is sometimes useful for dump utilities.

5.4.4 dwarf_whatattr()

When it succeeds, dwarf_whatattr() returns DW_DLV_OK and sets *return_attr to the attribute code represented by the Dwarf_Attribute descriptor attr. It returns DW_DLV_ERROR on error.

5.4.5 dwarf_formref()

When it succeeds, dwarf_formref() returns DW_DLV_OK and sets *return_offset to the CU-relative offset represented by the descriptor attr if the form of the attribute belongs to the REFERENCE class. attr must be a CU-local reference, not form DW_FORM_ref_addr. It is an error for the form to not belong to this class or to be form DW_FORM_ref_addr. It returns DW_DLV_ERROR on error. See also dwarf_global_formref below.

5.4.6 dwarf_global_formref()

When it succeeds, dwarf_global_formref() returns DW_DLV_OK and sets *return_offset to the .debug_info-section-relative offset represented by the descriptor attr if the form of the attribute belongs to the REFERENCE class. attr can be any legal REFERENCE class form including DW_FORM_ref_addr. It is an error for the form to not belong to this class. It returns DW_DLV_ERROR on error. See also dwarf_formref above.

5.4.7 dwarf_formaddr()

When it succeeds, dwarf_formaddr() returns DW_DLV_OK and sets *return_addr to the address represented by the descriptor attr if the form of the attribute belongs to the ADDRESS class. It is an error for the form to not belong to this class. It returns DW_DLV_ERROR on error.

5.4.8 dwarf_formflag()

When it succeeds, dwarf_formflag() returns DW_DLV_OK and sets *return_bool 1 (i.e. true) (if the attribute has a non-zero value) or 0 (i.e. false) (if the attribute has a zero value). It returns DW_DLV_ERROR on error or if the attr does not have form flag.

5.4.9 dwarf_formudata()

The function dwarf_formudata() returns DW_DLV_OK and sets *return_uvalue to the Dwarf_Unsigned value of the attribute represented by the descriptor attr if the form of the attribute belongs to the CONSTANT class. It is an error for the form to not belong to this class. It returns DW_DLV_ERROR on error.

5.4.10 dwarf_formsdata()

The function dwarf_formsdata() returns DW_DLV_OK and sets *return_svalue to the Dwarf_Signed value of the attribute represented by the descriptor attr if the form of the attribute belongs to the CONSTANT class. It is an error for the form to not belong to this class. If the size of the data attribute referenced is smaller than the size of the Dwarf_Signed type, its value is sign extended. It returns DW_DLV_ERROR on error.

5.4.11 dwarf_formblock()

The function dwarf_formblock() returns DW_DLV_OK and sets *return_block to a pointer to a Dwarf_Block structure containing the value of the attribute represented by the descriptor attr if the form of the attribute belongs to the BLOCK class. It is an error for the form to not belong to this class. The storage pointed to by a successful return of dwarf_formblock() should be free'd using the allocation type DW_DLA_BLOCK, when no longer of interest (see dwarf_dealloc()). It returns DW_DLV_ERROR on error.

5.4.12 dwarf_formstring()

The function dwarf_formstring() returns DW_DLV_OK and sets *return_string to a pointer to a null-terminated string containing the value of the attribute represented by the descriptor attr if the form of the attribute belongs to the STRING class. It is an error for the form to not belong to this class. The storage pointed to by a successful return of dwarf_formstring() should not be free'd. The pointer points into existing DWARF memory and the pointer becomes stale/invalid after a call to dwarf finish. dwarf formstring() returns DW DLV ERROR on error.

5.4.12.1 dwarf_loclist_n()

The function dwarf_loclist_n() sets *llbuf to point to an array of Dwarf_Locdesc pointers corresponding to each of the location expressions in a location list, and sets *listlen to the number of elements in the array and returns DW_DLV_OK if the attribute is appropriate.

This is the preferred function for Dwarf_Locdesc as it is the interface allowing access to an entire loclist. (use of dwarf_loclist_n() is suggested as the better interface, though dwarf_loclist() is still supported.)

If the attribute is a reference to a location list (DW_FORM_data4 or DW_FORM_data8) the location list entries are used to fill in all the fields of the Dwarf_Locdesc(s) returned.

If the attribute is a location description (DW_FORM_block2 or DW_FORM_block4) then some of the Dwarf_Locdesc values of the single Dwarf_Locdesc record are set to 'sensible' but arbitrary values. Specifically, ld_lopc is set to 0 and ld_hipc is set to all-bits-on. And *listlen is set to 1.

It returns DW_DLV_ERROR on error. dwarf_loclist_n() works on DW_AT_location, DW_AT_data_member_location, DW_AT_vtable_elem_location, DW_AT_string_length, DW_AT_use_location, and DW_AT_return_addr attributes.

Storage allocated by a successful call of dwarf_loclist_n() should be deallocated when no longer of interest (see dwarf_dealloc()). The block of Dwarf_Loc structs pointed to by the ld_s field of each Dwarf_Locdesc structure should be deallocated with the allocation type DW_DLA_LOC_BLOCK. and the llbuf[] space pointed to should be deallocated with allocation type DW_DLA_LOCDESC. This should be followed by deallocation of the llbuf using the allocation type DW_DLA_LIST.

```
Dwarf_Signed lcnt;
Dwarf_Locdesc **llbuf;
int lres;

lres = dwarf_loclist_n(someattr, &llbuf,&lcnt &error);
if (lres == DW_DLV_OK) {
    for (i = 0; i < lcnt; ++i) {
        /* use llbuf[i] */

        dwarf_dealloc(dbg, llbuf[i]->ld_s, DW_DLA_LOC_BLOCK);
        dwarf_dealloc(dbg,llbuf[i], DW_DLA_LOCDESC);
    }
    dwarf_dealloc(dbg, llbuf, DW_DLA_LIST);
}
```

5.4.12.2 dwarf_loclist()

The function dwarf_loclist() sets *llbuf to point to a Dwarf_Locdesc pointer for the single

location expression it can return. It sets *listlen to 1. and returns DW_DLV_OK if the attribute is appropriate.

It is less flexible than dwarf_loclist_n() in that dwarf_loclist() can handle a maximum of one location expression, not a full location list. If a location-list is present it returns only the first location-list entry location description. Use dwarf_loclist_n() instead.

```
It returns DW_DLV_ERROR on error. dwarf_loclist() works on DW_AT_location, DW_AT_data_member_location, DW_AT_vtable_elem_location, DW AT string length, DW AT use location, and DW AT return addr attributes.
```

Storage allocated by a successful call of dwarf_loclist() should be deallocated when no longer of interest (see dwarf_dealloc()). The block of Dwarf_Loc structs pointed to by the ld_s field of each Dwarf_Locdesc structure should be deallocated with the allocation type DW_DLA_LOC_BLOCK. This should be followed by deallocation of the llbuf using the allocation type DW_DLA_LOCDESC.

```
Dwarf Signed lcnt;
Dwarf_Locdesc *llbuf;
int lres;
lres = dwarf loclist(someattr, &llbuf,&lcnt &error);
if (lres == DW DLV OK) {
        /* lcnt is always 1, (and has always been 1) */ */
        /* use llbuf */
        dwarf_dealloc(dbg, llbuf->ld_s, DW_DLA_LOC_BLOCK);
        dwarf_dealloc(dbg, llbuf, DW_DLA_LOCDESC);
        Earlier version. It works because lcnt is always 1.
          for (i = 0; i < lcnt; ++i) {
              /* use llbuf[i] */
              /* Deallocate Dwarf Loc block of llbuf[i] */
              dwarf dealloc(dbg, llbuf[i].ld s, DW DLA LOC BLOCK);
          dwarf_dealloc(dbg, llbuf, DW_DLA_LOCDESC);
}
```

5.5 Line Number Operations

These functions are concerned with accessing line number entries, mapping debugging information entry objects to their corresponding source lines, and providing a mechanism for obtaining information about line number entries. Although, the interface talks of "lines" what is really meant is "statements". In case there is more than one statement on the same line, there will be at least one descriptor per statement, all with the same line number. If column number is also being represented they will have the column numbers of the start of the statements also represented.

There can also be more than one Dwarf_Line per statement. For example, if a file is preprocessed by a language translator, this could result in translator output showing 2 or more sets of line numbers per translated line of output.

5.5.1 Get A Set of Lines

The function returns information about every source line for a particular compilation-unit. The

compilation-unit is specified by the corresponding die.

5.5.1.1 dwarf_srclines()

The function dwarf_srclines() places all line number descriptors for a single compilation unit into a single block, sets *linebuf to point to that block, sets *linecount to the number of descriptors in this block and returns DW_DLV_OK. The compilation-unit is indicated by the given die which must be a compilation-unit die. It returns DW_DLV_ERROR on error. On successful return, line number information should be free'd using dwarf_srclines_dealloc() when no longer of interest.

The following dealloc code (the only documented method before July 2005) still works, but does not completely free all data allocated. The dwarf_srclines_dealloc() routine was created to fix the problem of incomplete deallocation.

5.5.2 Get the set of Source File Names

The function returns the names of the source files that have contributed to the compilation-unit represented by the given DIE. Only the source files named in the statement program prologue are returned.

When it succeeds dwarf_srcfiles() returns DW_DLV_OK and puts the number of source files named in the statement program prologue indicated by the given die into *srccount. Source files defined in the statement program are ignored. The given die should have the tag DW_TAG_compile_unit. The location pointed to by srcfiles is set to point to a list of pointers to null-terminated strings that name the source files. On a successful return from this function, each of the strings returned should be individually free'd using dwarf_dealloc() with the allocation type DW_DLA_STRING when no longer of interest. This should be followed by free-ing the list using dwarf_dealloc() with the allocation type DW_DLA_LIST. It returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if there is no corresponding statement program (i.e., if there is no line information).

5.5.3 Get information about a Single Table Line

The following functions can be used on the Dwarf_Line descriptors returned by dwarf_srclines() to obtain information about the source lines.

5.5.3.1 dwarf_linebeginstatement()

The function dwarf_linebeginstatement() returns DW_DLV_OK and sets *return_bool to non-zero (if line represents a line number entry that is marked as beginning a statement). or zero ((if line represents a line number entry that is not marked as beginning a statement). It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.5.3.2 dwarf_lineendsequence()

The function dwarf_lineendsequence() returns DW_DLV_OK and sets *return_bool non-zero (in which case line represents a line number entry that is marked as ending a text sequence) or zero (in

which case line represents a line number entry that is not marked as ending a text sequence). A line number entry that is marked as ending a text sequence is an entry with an address one beyond the highest address used by the current sequence of line table entries (that is, the table entry is a DW LNE end sequence entry (see the DWARF specification)).

The function $dwarf_lineendsequence()$ returns DW_DLV_ERROR on error. It never returns $DW_DLV_NO_ENTRY$.

5.5.3.3 dwarf_lineno()

The function dwarf_lineno() returns DW_DLV_OK and sets *return_lineno to the source statement line number corresponding to the descriptor line. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.5.3.4 dwarf_line_srcfileno()

The function dwarf_line_srcfileno() returns DW_DLV_OK and sets *returned_fileno to the source statement line number corresponding to the descriptor file number. When the number returned thru *returned_fileno is zero it means the file name is unknown (see the DWARF2/3 line table specification). When the number returned thru *returned_fileno is non-zero it is a file number: subtract 1 from this file number to get an index into the array of strings returned by dwarf_srcfiles() (verify the resulting index is in range for the array of strings before indexing into the array of strings). The file number may exceed the size of the array of strings returned by dwarf_srcfiles() because dwarf_srcfiles() does not return files names defined with the DW_DLE_define_file operator. The function dwarf_line_srcfileno() returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.5.3.5 dwarf_lineaddr()

The function dwarf_lineaddr() returns DW_DLV_OK and sets *return_lineaddr to the address associated with the descriptor line. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.5.3.6 dwarf_lineoff()

The function dwarf_lineoff() returns DW_DLV_OK and sets *return_lineoff to the column number at which the statement represented by line begins. It sets return_lineoff to -1 if the column number of the statement is not represented (meaning the producer library call was given zero as the column number).

On error it returns DW_DLV_ERROR. It never returns DW_DLV_NO_ENTRY.

5.5.3.7 dwarf_linesrc()

The function dwarf_linesrc() returns DW_DLV_OK and sets *return_linesrc to a pointer to a null-terminated string of characters that represents the name of the source-file where line occurs. It returns DW_DLV_ERROR on error.

If the applicable file name in the line table Statement Program Prolog does not start with a '/' character the string in DW_AT_comp_dir (if applicable and present) or the applicable directory name from the line Statement Program Prolog is prepended to the file name in the line table Statement Program Prolog to make a full path.

The storage pointed to by a successful return of dwarf_linesrc() should be free'd using dwarf_dealloc() with the allocation type DW_DLA_STRING when no longer of interest. It never returns DW_DLV_NO_ENTRY.

5.5.3.8 dwarf lineblock()

The function dwarf_lineblock() returns DW_DLV_OK and sets *return_linesrc to non-zero (i.e. true)(if the line is marked as beginning a basic block) or zero (i.e. false) (if the line is marked as not beginning a basic block). It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.6 Global Name Space Operations

These operations operate on the .debug_pubnames section of the debugging information.

5.6.1 Debugger Interface Operations

5.6.1.1 dwarf_get_globals()

The function dwarf_get_globals() returns DW_DLV_OK and sets *return_count to the count of pubnames represented in the section containing pubnames i.e. .debug_pubnames. It also stores at

*globals, a pointer to a list of Dwarf_Global descriptors, one for each of the pubnames in the .debug_pubnames section. It returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if the .debug pubnames section does not exist.

On a successful return from dwarf_get_globals(), the Dwarf_Global descriptors should be free'd using dwarf_globals_dealloc(). dwarf_globals_dealloc() is new as of July 15, 2005 and is the preferred approach to freeing this memory..

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from dwarf_get_globals(), the Dwarf_Global descriptors should be individually free'd using dwarf_dealloc() with the allocation type DW_DLA_GLOBAL_CONTEXT, (or DW_DLA_GLOBAL, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type DW_DLA_LIST when the descriptors are no longer of interest.

5.6.1.2 dwarf_globname()

The function dwarf_globname() returns DW_DLV_OK and sets *return_name to a pointer to a null-terminated string that names the pubname represented by the Dwarf_Global descriptor, global.

It returns DW_DLV_ERROR on error. On a successful return from this function, the string should be free'd using dwarf_dealloc(), with the allocation type DW_DLA_STRING when no longer of interest. It never returns DW DLV NO ENTRY.

5.6.1.3 dwarf_global_die_offset()

The function dwarf_global_die_offset() returns DW_DLV_OK and sets *return_offset to the offset in the section containing DIE's, i.e. debug_info, of the DIE representing the pubname that is described by the Dwarf_Global descriptor, glob. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.6.1.4 dwarf_global_cu_offset()

The function dwarf_global_cu_offset() returns DW_DLV_OK and sets *return_offset to the offset in the section containing DIE's, i.e. .debug_info, of the compilation-unit header of the compilation-unit that contains the pubname described by the Dwarf_Global descriptor, global. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.6.1.5 dwarf_get_cu_die_offset_given_cu_header_offset()

The function dwarf_get_cu_die_offset_given_cu_header_offset() returns DW_DLV_OK and sets *out_cu_die_offset to the offset of the compilation-unit DIE given the offset in_cu_header_offset of a compilation-unit header. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

This effectively turns a compilation-unit-header offset into a compilation-unit DIE offset (by adding the size of the applicable CU header). This function is also sometimes useful with the dwarf_weak_cu_offset(), dwarf_func_cu_offset(), dwarf_type_cu_offset(), and int dwarf_var_cu_offset() functions.

```
dwarf_get_cu_die_offset_given_cu_header_offset() added Rev 1.45, June, 2001.
```

This function is declared as 'optional' in libdwarf.h on IRIX systems so the _MIPS_SYMBOL_PRESENT predicate may be used at run time to determine if the version of libdwarf linked into an application has this function.

5.6.1.6 dwarf_global_name_offsets()

The function dwarf_global_name_offsets() returns DW_DLV_OK and sets *return_name to a pointer to a null-terminated string that gives the name of the pubname described by the Dwarf_Global descriptor global. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. It also returns in the locations pointed to by die_offset, and cu_offset, the offsets of the DIE representing the pubname, and the DIE representing the compilation-unit containing the pubname, respectively. On a successful return from dwarf_global_name_offsets() the storage pointed to by return_name should be free'd using dwarf_dealloc(), with the allocation type DW_DLA_STRING when no longer of interest.

5.7 DWARF3 Type Names Operations

Section ".debug_pubtypes" is new in DWARF3.

These functions operate on the .debug_pubtypes section of the debugging information. The .debug_pubtypes section contains the names of file-scope user-defined types, the offsets of the DIEs that represent the definitions of those types, and the offsets of the compilation-units that contain the definitions of those types.

5.7.1 Debugger Interface Operations

5.7.1.1 dwarf_get_pubtypes()

The function dwarf_get_pubtypes() returns DW_DLV_OK and sets *typecount to the count of user-defined type names represented in the section containing user-defined type names, i.e. .debug_pubtypes. It also stores at *types, a pointer to a list of Dwarf_Pubtype descriptors, one for each of the user-defined type names in the .debug_pubtypes section. It returns DW_DLV_NOCOUNT on error. It returns DW_DLV_NO_ENTRY if the .debug_pubtypes section does not exist.

On a successful return from dwarf_get_pubtypes(), the Dwarf_Type descriptors should be free'd using dwarf_types_dealloc(). dwarf_types_dealloc() is used for both dwarf_get_pubtypes() and dwarf_get_types() as the data types are the same.

5.7.1.2 dwarf_pubtypename()

The function dwarf_pubtypename() returns DW_DLV_OK and sets *return_name to a pointer to a null-terminated string that names the user-defined type represented by the Dwarf_Pubtype descriptor, type. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. On a successful return from this function, the string should be free'd using dwarf_dealloc(), with the allocation type DW_DLA_STRING when no longer of interest.

5.7.1.3 dwarf_pubtype_die_offset()

The function dwarf_pubtype_die_offset() returns DW_DLV_OK and sets *return_offset to the offset in the section containing DIE's, i.e. .debug_info, of the DIE representing the user-defined type that is described by the Dwarf_Pubtype descriptor, type. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.7.1.4 dwarf_pubtype_cu_offset()

The function dwarf_pubtype_cu_offset() returns DW_DLV_OK and sets *return_offset to the offset in the section containing DIE's, i.e. .debug_info, of the compilation-unit header of the compilation-unit that contains the user-defined type described by the Dwarf_Pubtype descriptor, type. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.7.1.5 dwarf_pubtype_name_offsets()

```
int dwarf_pubtype_name_offsets(
    Dwarf_Pubtype type,
    char ** returned_name,
    Dwarf_Off * die_offset,
    Dwarf_Off * cu_offset,
    Dwarf Error *error)
```

The function dwarf_pubtype_name_offsets() returns DW_DLV_OK and sets *returned_name to a pointer to a null-terminated string that gives the name of the user-defined type described by the Dwarf_Pubtype descriptor type. It also returns in the locations pointed to by die_offset, and cu_offset, the offsets of the DIE representing the user-defined type, and the DIE representing the compilation-unit containing the user-defined type, respectively. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. On a successful return from dwarf_pubtype_name_offsets() the storage pointed to by returned_name should be free'd using dwarf_dealloc(), with the allocation type DW_DLA_STRING when no longer of interest.

5.8 User Defined Static Variable Names Operations

This section is SGI specific and is not part of standard DWARF version 2.

These functions operate on the .debug_varnames section of the debugging information. The .debug_varnames section contains the names of file-scope static variables, the offsets of the DIEs that represent the definitions of those variables, and the offsets of the compilation-units that contain the definitions of those variables.

5.9 Weak Name Space Operations

These operations operate on the .debug_weaknames section of the debugging information.

These operations are SGI specific, not part of standard DWARF.

5.9.1 Debugger Interface Operations

5.9.1.1 dwarf_get_weaks()

The function dwarf_get_weaks() returns DW_DLV_OK and sets *weak_count to the count of weak names represented in the section containing weak names i.e. .debug_weaknames. It returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if the section does not exist. It also stores in *weaks, a pointer to a list of Dwarf_Weak descriptors, one for each of the weak names in the .debug_weaknames section.

On a successful return from this function, the Dwarf_Weak descriptors should be free'd using dwarf_weaks_dealloc() when the data is no longer of interest. dwarf_weaks_dealloc() is new as of July 15, 2005.

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from dwarf_get_weaks() the Dwarf_Weak descriptors should be individually free'd using dwarf_dealloc() with the allocation type DW_DLA_WEAK_CONTEXT, (or DW_DLA_WEAK, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type DW_DLA_LIST when the descriptors are no longer of interest.

5.9.1.2 dwarf_weakname()

The function dwarf_weakname() returns DW_DLV_OK and sets *return_name to a pointer to a null-terminated string that names the weak name represented by the Dwarf_Weak descriptor, weak. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. On a successful return from this function, the string should be free'd using dwarf_dealloc(), with the allocation type DW_DLA_STRING when no longer of interest.

The function dwarf_weak_die_offset() returns DW_DLV_OK and sets *return_offset to the offset in the section containing DIE's, i.e. .debug_info, of the DIE representing the weak name that is described by the Dwarf_Weak descriptor, weak. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.9.1.3 dwarf_weak_cu_offset()

The function dwarf_weak_cu_offset() returns DW_DLV_OK and sets *return_offset to the offset in the section containing DIE's, i.e. .debug_info, of the compilation-unit header of the compilation-unit that contains the weak name described by the Dwarf_Weak descriptor, weak. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.9.1.4 dwarf_weak_name_offsets()

The function dwarf_weak_name_offsets() returns DW_DLV_OK and sets *weak_name to a pointer to a null-terminated string that gives the name of the weak name described by the Dwarf_Weak descriptor weak. It also returns in the locations pointed to by die_offset, and cu_offset, the offsets of the DIE representing the weakname, and the DIE representing the compilation-unit containing the weakname, respectively. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. On a successful return from dwarf_weak_name_offsets() the storage pointed to by weak_name should be free'd using dwarf_dealloc(), with the allocation type DW_DLA_STRING when no longer of interest.

5.10 Static Function Names Operations

This section is SGI specific and is not part of standard DWARF version 2.

These function operate on the .debug_funcnames section of the debugging information. The .debug_funcnames section contains the names of static functions defined in the object, the offsets of the DIEs that represent the definitions of the corresponding functions, and the offsets of the start of the compilation-units that contain the definitions of those functions.

5.10.1 Debugger Interface Operations

5.10.1.1 dwarf_get_funcs()

The function dwarf_get_funcs() returns DW_DLV_OK and sets *func_count to the count of static function names represented in the section containing static function names, i.e. debug_funcnames. It also stores, at *funcs, a pointer to a list of Dwarf_Func descriptors, one for each of the static functions in the .debug_funcnames section. It returns DW_DLV_NOCOUNT on error. It returns DW_DLV_NO_ENTRY if the .debug_funcnames section does not exist.

On a successful return from dwarf_get_funcs(), the Dwarf_Func descriptors should be free'd using dwarf_funcs_dealloc(). dwarf_funcs_dealloc() is new as of July 15, 2005.

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from dwarf_get_funcs(), the Dwarf_Func descriptors should be individually free'd using dwarf_dealloc() with the allocation type DW_DLA_FUNC_CONTEXT, (or DW_DLA_FUNC, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type DW_DLA_LIST when the descriptors are no longer of interest.

5.10.1.2 dwarf_funcname()

The function <code>dwarf_funcname()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_name</code> to a pointer to a null-terminated string that names the static function represented by the <code>Dwarf_Func</code> descriptor, <code>func</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. On a successful return from this function, the string should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

5.10.1.3 dwarf_func_die_offset()

The function dwarf_func_die_offset(), returns DW_DLV_OK and sets *return_offset to the offset in the section containing DIE's, i.e. .debug_info, of the DIE representing the static function that is described by the Dwarf_Func descriptor, func. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.10.1.4 dwarf_func_cu_offset()

The function dwarf_func_cu_offset() returns DW_DLV_OK and sets *return_offset to the offset in the section containing DIE's, i.e. .debug_info, of the compilation-unit header of the compilation-unit that contains the static function described by the Dwarf_Func descriptor, func. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.10.1.5 dwarf_func_name_offsets()

The function dwarf_func_name_offsets() returns DW_DLV_OK and sets *func_name to a pointer to a null-terminated string that gives the name of the static function described by the Dwarf_Func descriptor func. It also returns in the locations pointed to by die_offset, and cu_offset, the offsets of the DIE representing the static function, and the DIE representing the compilation-unit containing the static function, respectively. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. On a successful return from dwarf_func_name_offsets() the storage pointed to by func_name should be free'd using dwarf_dealloc(), with the allocation type DW_DLA_STRING when no longer of interest.

5.11 User Defined Type Names Operations

Section "debug_typenames" is SGI specific and is not part of standard DWARF version 2. (However, an identical section is part of DWARF version 3 named ".debug_pubtypes", see dwarf_get_pubtypes() above.)

These functions operate on the .debug_typenames section of the debugging information. The .debug_typenames section contains the names of file-scope user-defined types, the offsets of the DIEs that represent the definitions of those types, and the offsets of the compilation-units that contain the definitions of those types.

5.11.1 Debugger Interface Operations

5.11.1.1 dwarf_get_types()

The function dwarf_get_types() returns DW_DLV_OK and sets *typecount to the count of user-defined type names represented in the section containing user-defined type names, i.e. .debug_typenames. It also stores at *types, a pointer to a list of Dwarf_Type descriptors, one for each of the user-defined type names in the .debug_typenames section. It returns DW_DLV_NOCOUNT on error. It returns DW_DLV_NO_ENTRY if the .debug_typenames section does not exist.

On a successful return from dwarf_get_types(), the Dwarf_Type descriptors should be free'd using dwarf_types_dealloc(). dwarf_types_dealloc() is new as of July 15, 2005 and frees all memory allocated by dwarf_get_types().

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from dwarf_get_types(), the Dwarf_Type descriptors should be individually free'd using dwarf_dealloc() with the allocation type DW_DLA_TYPENAME_CONTEXT, (or DW_DLA_TYPENAME, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type DW_DLA_LIST when the descriptors

are no longer of interest.

5.11.1.2 dwarf_typename()

The function <code>dwarf_typename()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_name</code> to a pointer to a null-terminated string that names the user-defined type represented by the <code>Dwarf_Type</code> descriptor, <code>type</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. On a successful return from this function, the string should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

5.11.1.3 dwarf_type_die_offset()

The function dwarf_type_die_offset() returns DW_DLV_OK and sets *return_offset to the offset in the section containing DIE's, i.e. .debug_info, of the DIE representing the user-defined type that is described by the Dwarf_Type descriptor, type. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.11.1.4 dwarf_type_cu_offset()

The function dwarf_type_cu_offset() returns DW_DLV_OK and sets *return_offset to the offset in the section containing DIE's, i.e. .debug_info, of the compilation-unit header of the compilation-unit that contains the user-defined type described by the Dwarf_Type descriptor, type. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.11.1.5 dwarf_type_name_offsets()

The function dwarf_type_name_offsets() returns DW_DLV_OK and sets *returned_name to a pointer to a null-terminated string that gives the name of the user-defined type described by the Dwarf_Type descriptor type. It also returns in the locations pointed to by die_offset, and cu_offset, the offsets of the DIE representing the user-defined type, and the DIE representing the compilation-unit containing the user-defined type, respectively. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. On a successful return from dwarf_type_name_offsets() the storage pointed to by returned_name should be free'd using dwarf_dealloc(), with the allocation type DW_DLA_STRING when no longer of interest.

5.12 User Defined Static Variable Names Operations

This section is SGI specific and is not part of standard DWARF version 2.

These functions operate on the .debug_varnames section of the debugging information. The .debug_varnames section contains the names of file-scope static variables, the offsets of the DIEs that represent the definitions of those variables, and the offsets of the compilation-units that contain the definitions of those variables.

5.12.1 Debugger Interface Operations

5.12.1.1 dwarf_get_vars()

The function <code>dwarf_get_vars()</code> returns <code>DW_DLV_OK</code> and sets <code>*var_count</code> to the count of file-scope static variable names represented in the section containing file-scope static variable names, i.e. .debug_varnames. It also stores, at <code>*vars</code>, a pointer to a list of <code>Dwarf_Var</code> descriptors, one for each of the file-scope static variable names in the .debug_varnames section. It returns <code>DW_DLV_ERROR</code> on error. It returns <code>DW_DLV_NO_ENTRY</code> if the .debug_varnames section does not exist.

The following is new as of July 15, 2005. On a successful return from dwarf_get_vars(), the Dwarf_Var descriptors should be free'd using dwarf_vars_dealloc().

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from dwarf_get_vars(), the Dwarf_Var descriptors should be individually free'd using dwarf_dealloc() with the allocation type DW_DLA_VAR_CONTEXT, (or DW_DLA_VAR, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type DW_DLA_LIST when the descriptors are no longer of interest.

5.12.1.2 dwarf_varname()

The function dwarf_varname() returns DW_DLV_OK and sets *returned_name to a pointer to a null-terminated string that names the file-scope static variable represented by the Dwarf_Var descriptor, var. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. On a successful return from this function, the string should be free'd using dwarf_dealloc(), with the allocation type DW_DLA_STRING when no longer of interest.

5.12.1.3 dwarf_var_die_offset()

The function dwarf_var_die_offset() returns DW_DLV_OK and sets *returned_offset to the offset in the section containing DIE's, i.e. .debug_info, of the DIE representing the file-scope static variable that is described by the Dwarf_Var descriptor, var. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.12.1.4 dwarf_var_cu_offset()

The function dwarf_var_cu_offset() returns DW_DLV_OK and sets *returned_offset to the offset in the section containing DIE's, i.e. .debug_info, of the compilation-unit header of the compilation-unit that contains the file-scope static variable described by the Dwarf_Var descriptor, var. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.12.1.5 dwarf_var_name_offsets()

The function dwarf_var_name_offsets() returns DW_DLV_OK and sets *returned_name to a pointer to a null-terminated string that gives the name of the file-scope static variable described by the Dwarf_Var descriptor var. It also returns in the locations pointed to by die_offset, and cu_offset, the offsets of the DIE representing the file-scope static variable, and the DIE representing the compilation-unit containing the file-scope static variable, respectively. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. On a successful return from dwarf_var_name_offsets() the storage pointed to by returned_name should be free'd using dwarf_dealloc(), with the allocation type DW_DLA_STRING when no longer of interest.

5.13 Macro Information Operations

5.13.1 General Macro Operations

5.13.1.1 dwarf find macro value start()

```
char *dwarf_find_macro_value_start(char * macro_string);
```

Given a macro string in the standard form defined in the DWARF document ("name <space> value" or "name(args)<space>value") this returns a pointer to the first byte of the macro value. It does not alter the string pointed to by macro_string or copy the string: it returns a pointer into the string whose address was passed in.

5.13.2 Debugger Interface Macro Operations

Macro information is accessed from the .debug_info section via the DW_AT_macro_info attribute (whose

value is an offset into .debug_macinfo).

No Functions yet defined.

5.13.3 Low Level Macro Information Operations

5.13.3.1 dwarf_get_macro_details()

dwarf_get_macro_details() returns DW_DLV_OK and sets entry_count to the number of details records returned through the details pointer. The data returned thru details should be freed by a call to dwarf_dealloc() with the allocation type DW_DLA_STRING. If DW_DLV_OK is returned, the entry_count will be at least 1, since a compilation unit with macro information but no macros will have at least one macro data byte of 0.

dwarf_get_macro_details() begins at the macro_offset offset you supply and ends at the end of a compilation unit or at maximum_count detail records (whichever comes first). If maximum_count is 0, it is treated as if it were the maximum possible unsigned integer.

dwarf_get_macro_details() attempts to set dmd_fileindex to the correct file in every details record. If it is unable to do so (or whenever the current file index is unknown, it sets dmd fileindex to -1.

dwarf_get_macro_details() returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if there is no more macro information at that macro_offset. If macro_offset is passed in as 0, a DW_DLV_NO_ENTRY return means there is no macro information.

5.14 Low Level Frame Operations

These functions provide information about stack frames to be used to perform stack traces. The information is an abstraction of a table with a row per instruction and a column per register and a column for the canonical frame address (CFA, which corresponds to the notion of a frame pointer), as well as a column for the return address.

From 1993-2006 the interface we'll here refer to as DWARF2 made the CFA be a column in the matrix, but left DW_FRAME_UNDEFINED_VAL, and DW_FRAME_SAME_VAL out of the matrix (giving them high numbers). As of the DWARF3 interfaces introduced in this document in April 2006, there are *two* interfaces.

The original still exists (see. dwarf_get_fde_info_for_reg() and dwarf_get_fde_info_for_all_regs() below) and works adequately for MIPS/IRIX DWARF2 and ABI/ISA sets that are sufficiently similar (but the settings for non-MIPS must be set into libdwarf.h and cannot be changed at runtime).

A new interface set of dwarf_get_fde_info_for_reg3(), dwarf_get_fde_info_for_cfa_reg3(), dwarf_get_fde_info_for_all_regs3() dwarf_set_frame_rule_inital_value(), dwarf_set_frame_rule_table_size() is more flexible and should work for many more architectures and the setting of DW_FRAME_CFA_COL and the size of the table can be set at runtime.

Each cell in the table contains one of the following:

- 1. A register + offset(a)(b)
- 2. A register(c)(d)
- 3. A marker (DW_FRAME_UNDEFINED_VAL) meaning register value undefined
- 4. A marker (DW_FRAME_SAME_VAL) meaning register value same as in caller

(a old DWARF2 interface) When the column is DW_FRAME_CFA_COL: the register number is a real hardware register, not a reference to DW_FRAME_CFA_COL, not DW_FRAME_UNDEFINED_VAL, and not DW_FRAME_SAME_VAL. The CFA rule value should be the stack pointer plus offset 0 when no other value makes sense. A value of DW_FRAME_SAME_VAL would be semi-logical, but since the CFA is not a real register, not really correct. A value of DW_FRAME_UNDEFINED_VAL would imply the CFA is undefined -- this seems to be a useless notion, as the CFA is a means to finding real registers, so those real registers should be marked DW_FRAME_UNDEFINED_VAL, and the CFA column content (whatever register it specifies) becomes unreferenced by anything.

(a new April 2006 DWARF2/3 interface): The CFA is separately accessible and not part of the table. The 'rule number' for the CFA is a number outside the table. So the CFA is a marker, not a register number. See DW_FRAME_CFA_COL3 in libdwarf.h and dwarf_get_fde_info_for_cfa_reg3().

- (b) When the column is not DW_FRAME_CFA_COL, the 'register' will and must be DW_FRAME_CFA_COL, implying that to get the final location for the column one must add the offset here plus the DW_FRAME_CFA_COL rule value.
- (c) When the column is DW_FRAME_CFA_COL, then the register number is (must be) a real hardware register . If it were DW_FRAME_UNDEFINED_VAL or DW_FRAME_SAME_VAL it would be a marker, not a register number.
- (d) When the column is not DW_FRAME_CFA_COL, the register may be a hardware register. It will not be DW_FRAME_CFA_COL.

There is no 'column' for DW FRAME UNDEFINED VAL or DW FRAME SAME VAL.

Figure 3 is machine dependent and represents MIPS cpu register assignments.

NAME	value	PURPOSE
DW_FRAME_CFA_COL	0	column used for CFA
DW_FRAME_REG1	1	integer regster 1
DW_FRAME_REG2	2	integer register 2
		obvious names and values here
DW_FRAME_REG30	30	integer register 30
DW_FRAME_REG31	31	integer register 31
DW_FRAME_FREG0	32	floating point register 0
DW_FRAME_FREG1	33	floating point register 1
		obvious names and values here
DW_FRAME_FREG30	62	floating point register 30
DW_FRAME_FREG31	63	floating point register 31
DW_FRAME_RA_COL	64	column recording ra
DW_FRAME_UNDEFINED_VAL	1034	register val undefined
DW_FRAME_SAME_VAL	1035	register same as in caller

Figure 4. Frame Information Rule Assignments

The following table shows SGI/MIPS specific special cell values: these values mean that the cell has the value *undefined* or *same value* respectively, rather than containing a *register* or *register+offset*. It assumes DW_FRAME_CFA_COL is a table rule, which is not readily accomplished or sensible for some architectures.

NAME	value	PURPOSE
DW_FRAME_UNDEFINED_VAL	1034	means undefined value.
		Not a column or register value
DW_FRAME_SAME_VAL	1035	means 'same value' as
		caller had. Not a column or
		register value

Figure 5. Frame Information Special Values

The following table shows more general special cell values. These values mean that the cell register-number refers to the *cfa-register* or *undefined-value* or *same-value* respectively, rather than referring to a *register in the table*. The generality arises from making DW_FRAME_CFA_COL3 be outside the set of registers and making the cfa rule accessible from outside the rule-table.

NAME	value	PURPOSE
DW_FRAME_UNDEFINED_VAL	1034	means undefined value.
		Not a column or register value
DW_FRAME_SAME_VAL	1035	means 'same value' as
		caller had. Not a column or
		register value
DW_FRAME_CFA_COL3	1036	means 'cfa register'is referred to,
		not a real register, not a column, but the cfa (the cfa
		does have a value, but in the DWARF3 libdwarf interface
		it does not have a 'real register number').

5.14.0.1 dwarf_get_fde_list()

dwarf_get_fde_list() stores a pointer to a list of Dwarf_Cie descriptors in *cie_data, and the count of the number of descriptors in *cie_element_count. There is a descriptor for each CIE in the .debug_frame section. Similarly, it stores a pointer to a list of Dwarf_Fde descriptors in *fde_data, and the count of the number of descriptors in *fde_element_count. There is one descriptor per FDE in the .debug_frame section. dwarf_get_fde_list() returns DW_DLV_EROR on error. It returns DW_DLV_NO_ENTRY if it cannot find frame entries. It returns DW_DLV_OK on a successful return.

On successful return, structures pointed to by a descriptor should be free'd using dwarf_fde_cie_list_dealloc(). This dealloc approach is new as of July 15, 2005.

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did.

```
Dwarf_Signed cnt;
Dwarf_Cie *cie_data;
Dwarf Signed cie count;
Dwarf Fde *fde data;
Dwarf_Signed fde_count;
int fres;
fres = dwarf get fde list(dbg,&cie data,&cie count,
                &fde_data,&fde_count,&error);
if (fres == DW_DLV_OK) {
        for (i = 0; i < cie_count; ++i) {
                /* use cie[i] */
                dwarf_dealloc(dbg, cie_data[i], DW_DLA_CIE);
        for (i = 0; i < fde_count; ++i) {
                /* use fde[i] */
                dwarf_dealloc(dbg, fde_data[i], DW_DLA_FDE);
        dwarf_dealloc(dbg, cie_data, DW_DLA_LIST);
        dwarf_dealloc(dbg, fde_data, DW_DLA_LIST);
}
```

5.14.0.2 dwarf_get_fde_list_eh()

```
int dwarf_get_fde_list_eh(
    Dwarf_Debug dbg,
    Dwarf_Cie **cie_data,
    Dwarf_Signed *cie_element_count,
    Dwarf_Fde **fde_data,
    Dwarf_Signed *fde_element_count,
    Dwarf_Error *error);
```

dwarf_get_fde_list_eh() is identical to dwarf_get_fde_list() except that dwarf_get_fde_list_eh() reads the GNU ecgs section named .eh_frame (C++ exception handling information).

dwarf_get_fde_list_eh() stores a pointer to a list of Dwarf_Cie descriptors in *cie_data, and the count of the number of descriptors in *cie_element_count. There is a descriptor for each CIE in the .debug_frame section. Similarly, it stores a pointer to a list of Dwarf_Fde descriptors in *fde_data, and the count of the number of descriptors in *fde_element_count. There is one descriptor per FDE in the .debug_frame section. dwarf_get_fde_list() returns DW_DLV_EROR on error. It returns DW_DLV_NO_ENTRY if it cannot find exception handling entries. It returns DW_DLV_OK on a successful return.

On successful return, structures pointed to by a descriptor should be free'd using dwarf_fde_cie_list_dealloc(). This dealloc approach is new as of July 15, 2005.

5.14.0.3 dwarf_get_cie_of_fde()

dwarf_get_cie_of_fde() stores a Dwarf_Cie into the Dwarf_Cie that cie_returned points
at.

If one has called dwarf_get_fde_list and does not wish to dwarf_dealloc() all the individual FDEs immediately, one must also avoid dwarf_dealloc-ing the CIEs for those FDEs not immediately dealloc'd. Failing to observe this restriction will cause the FDE(s) not dealloced to become invalid: an FDE contains (hidden in it) a CIE pointer which will be be invalid (stale, pointing to freed memory) if the CIE is dealloc'd. The invalid CIE pointer internal to the FDE cannot be detected as invalid by libdwarf. If one later passes an FDE with a stale internal CIE pointer to one of the routines taking an FDE as input the result will be failure of the call (returning DW_DLV_ERROR) at best and it is possible a coredump or worse will happpen (eventually).

dwarf_get_cie_of_fde() returns DW_DLV_OK if it is successful (it will be unless fde is the NULL pointer). It returns DW_DLV_ERROR if the fde is invalid (NULL).

Each Dwarf_Fde descriptor describes information about the frame for a particular subroutine or function.

int dwarf_get_fde_for_die is SGI/MIPS specific.

5.14.0.4 dwarf_get_fde_for_die()

When it succeeds, dwarf_get_fde_for_die() returns DW_DLV_OK and sets *return_fde to a Dwarf_Fde descriptor representing frame information for the given die. It looks for the DW_AT_MIPS_fde attribute in the given die. If it finds it, is uses the value of the attribute as the offset in the .debug_frame section where the FDE begins. If there is no DW_AT_MIPS_fde it returns DW_DLV_NO_ENTRY. If there is an error it returns DW_DLV_ERROR.

5.14.0.5 dwarf_get_fde_range()

On success, dwarf_get_fde_range() returns DW_DLV_OK. The location pointed to by low_pc is set to the low pc value for this function. The location pointed to by func_length is set to the length of the function in bytes. This is essentially the length of the text section for the function. The location pointed to by fde_bytes is set to the address where the FDE begins in the .debug_frame section. The location pointed to by fde_byte_length is set to the length in bytes of the portion of .debug_frame for this FDE. This is the same as the value returned by dwarf_get_fde_range. The location pointed to by cie_offset is set to the offset in the .debug_frame section of the CIE used by this FDE. The location pointed to by cie_index is set to the index of the CIE used by this FDE. The index is the index of the CIE in the list pointed to by cie_data as set by the function dwarf_get_fde_list(). However, if the function dwarf_get_fde_for_die() was used to obtain the given fde, this index may not be correct. The location pointed to by fde_offset is set to the offset of the start of this FDE in the .debug_frame section. dwarf_get_fde_range() returns DW_DLV_ERROR on error.

5.14.0.6 dwarf_get_cie_info()

```
int dwarf_get_cie_info(
        Dwarf_Cie
                        cie,
        Dwarf_Unsigned *bytes_in_cie,
        Dwarf_Small
                      *version,
                      **augmenter,
        Dwarf_Unsigned *code_alignment_factor,
        Dwarf_Signed *data_alignment_factor,
        Dwarf_Half
                       *return_address_register_rule,
        Dwarf_Ptr
                       *initial_instructions,
        Dwarf_Unsigned *initial_instructions_length,
        Dwarf_Error
                       *error);
```

dwarf_get_cie_info() is primarily for Internal-level Interface consumers. If successful, it returns DW_DLV_OK and sets *bytes_in_cie to the number of bytes in the portion of the frames section for the CIE represented by the given Dwarf_Cie descriptor, cie. The other fields are directly taken from the cie and returned, via the pointers to the caller. It returns DW_DLV_ERROR on error.

5.14.0.7 dwarf_get_fde_instr_bytes()

dwarf_get_fde_instr_bytes() returns DW_DLV_OK and sets *outinstrs to a pointer to a set of bytes which are the actual frame instructions for this fde. It also sets *outlen to the length, in bytes,

of the frame instructions. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. The intent is to allow low-level consumers like a dwarf-dumper to print the bytes in some fashion. The memory pointed to by outinstrs must not be changed and there is nothing to free.

5.14.0.8 dwarf_get_fde_info_for_reg()

This interface is suitable for DWARF2 but is not sufficient for DWARF3. See int dwarf_get_fde_info_for_reg3.

dwarf_get_fde_info_for_reg() returns DW_DLV_OK and sets *offset_relevant to non-zero if the offset is relevant for the row specified by pc_requested and column specified by table_column, for the FDE specified by fde. The intent is to return the rule for the given pc value and register. The location pointed to by register_num is set to the register value for the rule. The location pointed to by offset is set to the offset value for the rule. If offset is not relevant for this rule, *offset_relevant is set to zero. Since more than one pc value will have rows with identical entries, the user may want to know the earliest pc value after which the rules for all the columns remained unchanged. Recall that in the virtual table that the frame information represents there may be one or more table rows with identical data (each such table row at a different pc value). Given a pc_requested which refers to a pc in such a group of identical rows, the location pointed to by row_pc is set to the lowest pc value within the group of identical rows. The value put in *register_num any of the DW_FRAME_* table columns values specified in libdwarf.h or dwarf.h.

dwarf_get_fde_info_for_reg returns DW_DLV_ERROR if there is an error.

It is usable with either dwarf_get_fde_n() or dwarf_get_fde_at_pc().

5.14.0.9 dwarf_get_fde_info_for_all_regs()

dwarf_get_fde_info_for_all_regs() returns DW_DLV_OK and sets *reg_table for the row specified by pc_requested for the FDE specified by fde.

The intent is to return the rules for decoding all the registers, given a pc value. reg_table is an array of rules, one for each register specified in dwarf.h. The rule for each register contains three items -dw_regnum which denotes the register value for that rule, dw_offset which denotes the offset value for that rule and dw_offset_relevant which is set to zero if offset is not relevant for that rule. See dwarf_get_fde_info_fo_reg() for a description of row_pc.

```
dwarf_get_fde_info_for_all_regs returns DW_DLV_ERROR if there is an error. int dwarf_get_fde_info_for_all_regs is SGI/MIPS specific.
```

5.14.0.10 dwarf_set_frame_rule_table_size()

This allows consumers to set the size of the (internal to libdwarf) rule table. It should be at least as large as the number of real registers in the ABI which is to be read in for the dwarf_get_fde_info_for_reg3() or dwarf_get_fde_info_for_all_regs3() functions to work properly. It must be less than the marker values DW_FRAME_UNDEFINED_VAL, DW_FRAME_VAL, DW_FRAME_CFA_COL3.

ddwarf_set_frame_rule_table_size() sets the value value as the size of libdwarf-internal rules tables of dbg. The function returns the previous value of the rules table size setting (taken from the dbg structure).

5.14.0.11 dwarf_set_frame_rule_inital_value()

This allows consumers to set the initial value for rows in the frame tables. By default it is taken from libdwarf.h and is DW_FRAME_REG_INITIAL_VALUE (which itself is either DW_FRAME_SAME_VAL or DW_FRAME_UNDEFINED_VAL). The MIPS/IRIX default is DW_FRAME_SAME_VAL. Comsumer code should set this appropriately and for many architectures (but probably not MIPS) DW_FRAME_UNDEFINED_VAL is an appropriate setting.

dwarf_set_frame_rule_inital_value() sets the value value as the initial value for this dbg when initializing rules tables. The function returns the previous value of the initial setting (taken from the dbg structure).

5.14.0.12 dwarf_get_fde_info_for_reg3()

This interface is suitable for DWARF3 and DWARF2. It returns the values for a particular real register (Not for the CFA register, see dwarf_get_fde_info_for_cfa_reg3() below).

dwarf_get_fde_info_for_re3() returns DW_DLV_OK on success. It sets *value_type to one of DW_EXPR_OFFSET (0), DW_EXPR_VAL_OFFSET(1), DW_EXPR_EXPRESSION(2) or DW_EXPR_VAL_EXPRESSION(3). On call, table_column must be set to the register number of a real register. Not the cfa 'register' or DW_FRAME_SAME_VALUE or DW_FRAME_UNDEFINED_VALUE.

if *value_type has the value DW_EXPR_OFFSET (0) then:

It sets *offset_relevant to non-zero if the offset is relevant for the row specified by pc_requested and column specified by table_column or, for the FDE specified by fde. In this case the *register_num will be set to DW_FRAME_CFA_COL3. This is an offset(N) rule as specified in the DWARF3/2 documents. Adding the value of *offset_or_block_len to the value of the CFA register gives the address of a location holding the previous value of register table_column.

If offset is not relevant for this rule, *offset_relevant is set to zero. *register_num will be set to the number of the real register holding the value of the table_column register. This is the register(R) rule as specifified in DWARF3/2 documents.

The intent is to return the rule for the given pc value and register. The location pointed to by register_num is set to the register value for the rule. The location pointed to by offset is set to the offset value for the rule. Since more than one pc value will have rows with identical entries, the user may want to know the earliest pc value after which the rules for all the columns remained unchanged. Recall that in the virtual table that the frame information represents there may be one or more table rows with identical data (each such table row at a different pc value). Given a pc_requested which refers to a pc in such a group of identical rows, the location pointed to by row_pc is set to the lowest pc value within the group of identical rows.

If *value_type has the value DW_EXPR_VAL_OFFSET (1) then:

This will be a val_offset(N) rule as specified in the DWARF3/2 documents so *offset_relevant will be non zero. The calculation is identical to the DW_EXPR_OFFSET (0) calculation with *offset_relevant non-zero, but the value resulting is the actual table_column value (rather than the address where the value may be found).

If *value_type has the value DW_EXPR_EXPRESSION (1) then:

*offset_or_block_len is set to the length in bytes of a block of memory with a DWARF expression in the block. *block_ptr is set to point at the block of memory. The consumer code should evaluate the block as a DWARF-expression. The result is the address where the previous value of the register may be found. This is a DWARF3/2 expression(E) rule.

If *value_type has the value DW_EXPR_VAL_EXPRESSION (1) then:

The calculation is exactly as for DW_EXPR_EXPRESSION (1) but the result of the DWARF-expression evaluation is the value of the table_column (not the address of the value). This is a DWARF3/2 val_expression(E) rule.

dwarf_get_fde_info_for_reg returns DW_DLV_ERROR if there is an error and if there is an error only the error pointer is set, none of the other output arguments are touched.

It is usable with either dwarf_get_fde_n() or dwarf_get_fde_at_pc().

5.14.0.13 dwarf_get_fde_info_for_cfa_reg3()

```
int dwarf_get_fde_info_for_cfa_reg3(Dwarf_Fde fde,
     Dwarf Addr
                         pc_requested,
     Dwarf Small *
                         value_type,
     Dwarf Signed*
                         offset relevant,
     Dwarf_Signed*
                         register_num,
     Dwarf Signed*
                         offset_or_block_len,
     Dwarf_Ptr *
                         block_ptr ,
     Dwarf Addr *
                         row pc out,
     Dwarf Error *
                         error)
```

This is identical to dwarf_get_fde_info_for_reg3() except the returned values are for the CFA rule. So register number *register_num will be set to a real register, not DW_FRAME_CFA_COL3, DW_FRAME_SAME_VALUE, or DW_FRAME_UNDEFINED_VALUE.

5.14.0.14 dwarf_get_fde_info_for_all_regs3()

dwarf_get_fde_info_for_all_regs3() returns DW_DLV_OK and sets *reg_table for the row specified by pc_requested for the FDE specified by fde. The intent is to return the rules for decoding all the registers, given a pc value. reg_table is an array of rules, the array size specified by the caller. plus a rule for the CFA. The rule for the cfa returned in *reg_table defines the CFA value at pc_requested The rule for each register contains several values that enable the consumer to determine the previous value of the register (see the earlier documentation of Dwarf_Regtable3). dwarf_get_fde_info_for_reg3() and the Dwarf_Regtable3 documentation above for a description of the values for each row.

dwarf_get_fde_info_for_all_regs returns DW_DLV_ERROR if there is an error.

It's up to the caller to allocate space for *reg_table and initialize it properly.

5.14.0.15 dwarf_get_fde_n()

```
int dwarf_get_fde_n(
          Dwarf_Fde *fde_data,
          Dwarf_Unsigned fde_index,
          Dwarf_Fde *returned_fde
          Dwarf_Error *error)
```

dwarf_get_fde_n() returns DW_DLV_OK and sets returned_fde to the Dwarf_Fde descriptor whose index is fde_index in the table of Dwarf_Fde descriptors pointed to by fde_data. The index starts with 0. Returns DW_DLV_NO_ENTRY if the index does not exist in the table of Dwarf_Fde descriptors. Returns DW_DLV_ERROR if there is an error. This function cannot be used unless the block of Dwarf_Fde descriptors has been created by a call to dwarf_get_fde_list().

5.14.0.16 dwarf_get_fde_at_pc()

dwarf_get_fde_at_pc() returns DW_DLV_OK and sets returned_fde to a Dwarf_Fde descriptor for a function which contains the pc value specified by pc_of_interest. In addition, it sets the locations pointed to by lopc and hipc to the low address and the high address covered by this FDE, respectively. It returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if pc_of_interest is not in any of the FDEs represented by the block of Dwarf_Fde descriptors pointed to by fde_data. This function cannot be used unless the block of Dwarf_Fde descriptors has been created by a call to dwarf_get_fde_list().

5.14.0.17 dwarf_expand_frame_instructions()

dwarf_expand_frame_instructions() is a High-level interface function which expands a frame instruction byte stream into an array of Dwarf_Frame_Op structures. To indicate success, it returns DW_DLV_OK. The address where the byte stream begins is specified by instruction, and the length of the byte stream is specified by i_length. The location pointed to by returned_op_list is set to point to a table of returned_op_count pointers to Dwarf_Frame_Op which contain the frame instructions in the byte stream. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. After a successful return, the array of structures should be freed using dwarf_dealloc() with the allocation type DW_DLA_FRAME_BLOCK (when they are no longer of interest).

5.14.0.18 dwarf_get_fde_exception_info()

```
int dwarf_get_fde_exception_info(
    Dwarf_Fde fde,
    Dwarf_Signed * offset_into_exception_tables,
    Dwarf_Error * error);
```

dwarf_get_fde_exception_info() is an IRIX specific function which returns an exception table signed offset thru offset_into_exception_tables. The function never returns DW_DLV_NO_ENTRY. If DW_DLV_NO_ENTRY is NULL the function returns DW_DLV_ERROR. For non-IRIX objects the offset returned will always be zero. For non-C++ objects the offset returned will always be zero. The meaning of the offset and the content of the tables is not defined in this document. The applicable CIE augmentation string (see above) determines whether the value returned has meaning.

5.15 Location Expression Evaluation

An "interpreter" which evaluates a location expression is required in any debugger. There is no interface defined here at this time.

One problem with defining an interface is that operations are machine dependent: they depend on the interpretation of register numbers and the methods of getting values from the environment the expression is applied to.

It would be desirable to specify an interface.

5.15.1 Location List Internal-level Interface

5.15.1.1 dwarf_get_loclist_entry()

```
int dwarf_get_loclist_entry(
    Dwarf_Debug dbg,
    Dwarf_Unsigned offset,
    Dwarf_Addr *hipc_offset,
    Dwarf_Addr *lopc_offset,
    Dwarf_Ptr *data,
    Dwarf_Unsigned *entry_len,
    Dwarf_Unsigned *next_entry,
    Dwarf_Error *error)
```

dwarf_dwarf_get_loclist_entry() returns DW_DLV_OK if successful. DW_DLV_NO_ENTRY is returned when the offset passed in is beyond the end of the .debug_loc section (expected if you start at offset zero and proceed thru all the entries). DW_DLV_ERROR is returned on error. The function reads a location list entry starting at offset and returns through pointers (when successful) the high pc hipc_offset, low pc lopc_offset, a pointer to the location description data data, the length of the location description data entry_len, and the offset of the next location description entry next_entry.

The hipc_offset, low pc lopc_offset are offsets from the beginning of the current procedure, not genuine pc values.

5.16 Abbreviations access

These are Internal-level Interface functions. Debuggers can ignore this.

5.16.1 dwarf_get_abbrev()

The function dwarf_get_abbrev() returns DW_DLV_OK and sets *returned_abbrev to Dwarf_Abbrev descriptor for an abbreviation at offset *offset in the abbreviations section (i.e. debug_abbrev) on success. The user is responsible for making sure that a valid abbreviation begins at offset in the abbreviations section. The location pointed to by length is set to the length in bytes of the abbreviation in the abbreviations section. The location pointed to by attr_count is set to the number of attributes in the abbreviation. An abbreviation entry with a length of 1 is the 0 byte of the last abbreviation entry of a compilation unit. dwarf_get_abbrev() returns DW_DLV_ERROR on error. If the call succeeds, the storage pointed to by *returned_abbrev should be free'd, using dwarf_dealloc() with the allocation type DW_DLA_ABBREV when no longer needed.

5.16.2 dwarf_get_abbrev_tag()

If successful, dwarf_get_abbrev_tag() returns DW_DLV_OK and sets *return_tag to the tag of the given abbreviation. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.16.3 dwarf get abbrev code()

If successful, dwarf_get_abbrev_code() returns DW_DLV_OK and sets *return_code to the abbreviation code of the given abbreviation. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.16.4 dwarf_get_abbrev_children_flag()

The function dwarf_get_abbrev_children_flag() returns DW_DLV_OK and sets returned_flag to DW_children_no (if the given abbreviation indicates that a die with that abbreviation has no children) or DW_children_yes (if the given abbreviation indicates that a die with that abbreviation has a child). It returns DW_DLV_ERROR on error.

5.16.5 dwarf_get_abbrev_entry()

If successful, dwarf_get_abbrev_entry() returns DW_DLV_OK and sets *attr_num to the attribute code of the attribute whose index is specified by index in the given abbreviation. The index starts at 0. The location pointed to by form is set to the form of the attribute. The location pointed to by offset is set to the byte offset of the attribute in the abbreviations section. It returns DW_DLV_NO_ENTRY if the index specified is outside the range of attributes in this abbreviation. It returns DW DLV ERROR on error.

5.17 String Section Operations

The .debug_str section contains only strings. Debuggers need never use this interface: it is only for debugging problems with the string section itself.

5.17.1 dwarf_get_str()

```
int dwarf_get_str(
    Dwarf_Debug dbg,
    Dwarf_Off offset,
    char **string,
    Dwarf_Signed *returned_str_len,
    Dwarf_Error *error)
```

The function dwarf_get_str() returns DW_DLV_OK and sets *returned_str_len to the length of the string, not counting the null terminator, that begins at the offset specified by offset in the .debug_str section. The location pointed to by string is set to a pointer to this string. The next string in the .debug_str section begins at the previous offset + 1 + *returned_str_len. A zero-length string is NOT the end of the section. If there is no .debug_str section, DW_DLV_NO_ENTRY is returned. If there is an error, DW_DLV_ERROR is returned. If we are at the end of the section (that is, offset is one past the end of the section) DW_DLV_NO_ENTRY is returned. If the offset is some other too-large value then DW_DLV_ERROR is returned.

5.18 Address Range Operations

These functions provide information about address ranges. Address ranges map ranges of pc values to the corresponding compilation-unit die that covers the address range.

5.18.1 dwarf_get_aranges()

The function dwarf_get_aranges() returns DW_DLV_OK and sets *returned_arange_count to the count of the number of address ranges in the .debug_aranges section. It sets *aranges to point to a block of Dwarf_Arange descriptors, one for each address range. It returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if there is no .debug_aranges section.

```
Dwarf_Signed cnt;
   Dwarf_Arange *arang;
   int res;
   res = dwarf_get_aranges(dbg, &arang,&cnt, &error);
   if (res == DW_DLV_OK) {
           for (i = 0; i < cnt; ++i) {
                   /* use arang[i] */
                   dwarf_dealloc(dbg, arang[i], DW_DLA_ARANGE);
           dwarf_dealloc(dbg, arang, DW_DLA_LIST);
   }
int dwarf get arange(
        Dwarf_Arange *aranges,
        Dwarf_Unsigned arange_count,
       Dwarf Addr address,
        Dwarf_Arange *returned_arange,
        Dwarf Error *error);
```

The function dwarf_get_arange() takes as input a pointer to a block of Dwarf_Arange pointers, and a count of the number of descriptors in the block. It then searches for the descriptor that covers the given address. If it finds one, it returns DW_DLV_OK and sets *returned_arange to the descriptor. It returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if there is no .debug_aranges entry covering that address.

5.18.2 dwarf_get_cu_die_offset()

The function dwarf_get_cu_die_offset() takes a Dwarf_Arange descriptor as input, and if successful returns DW_DLV_OK and sets *returned_cu_die_offset to the offset in the .debug_info section of the compilation-unit DIE for the compilation-unit represented by the given address range. It returns DW_DLV_ERROR on error.

5.18.3 dwarf_get_arange_cu_header_offset()

The function dwarf_get_arange_cu_header_offset() takes a Dwarf_Arange descriptor as input, and if successful returns DW_DLV_OK and sets *returned_cu_header_offset to the offset in the .debug_info section of the compilation-unit header for the compilation-unit represented by the given address range. It returns DW_DLV_ERROR on error.

This function added Rev 1.45, June, 2001.

This function is declared as 'optional' in libdwarf.h on IRIX systems so the _MIPS_SYMBOL_PRESENT predicate may be used at run time to determine if the version of libdwarf linked into an application has this function.

5.18.4 dwarf_get_arange_info()

The function dwarf_get_arange_info() returns DW_DLV_OK and stores the starting value of the address range in the location pointed to by start, the length of the address range in the location pointed to by length, and the offset in the .debug_info section of the compilation-unit DIE for the compilation-unit represented by the address range. It returns DW_DLV_ERROR on error.

5.19 General Low Level Operations

This function is low-level and intended for use only by programs such as dwarf-dumpers.

5.19.1 dwarf_get_address_size()

The function dwarf_get_address_size() returns DW_DLV_OK on success and sets the *addr_size to the size in bytes of an address. In case of error, it returns DW_DLV_ERROR and does not set *addr_size.

5.20 Utility Operations

These functions aid in the management of errors encountered when using functions in the *libdwarf* library and releasing memory allocated as a result of a *libdwarf* operation.

5.20.1 dwarf_errno()

The function dwarf_errno() returns the error number corresponding to the error specified by error.

5.20.2 dwarf_errmsg()

The function dwarf_errmsg() returns a pointer to a null-terminated error message string corresponding to the error specified by error. The string returned by dwarf_errmsg() should not be deallocated using dwarf_dealloc().

The set of errors enumerated in Figure 3 below were defined in Dwarf 1. These errors are not used by the current implementation of Dwarf 2.

SYMBOLIC NAME	DESCRIPTION
DW_DLE_NE	No error (0)
DW_DLE_VMM	Version of DWARF information newer than libdwarf
DW_DLE_MAP	Memory map failure
DW_DLE_LEE	Propagation of libelf error
DW_DLE_NDS	No debug section
DW_DLE_NLS	No line section
DW_DLE_ID	Requested information not associated with descriptor
DW_DLE_IOF	I/O failure
DW_DLE_MAF	Memory allocation failure
DW_DLE_IA	Invalid argument
DW_DLE_MDE	Mangled debugging entry
DW_DLE_MLE	Mangled line number entry
DW_DLE_FNO	File descriptor does not refer to an open file
DW_DLE_FNR	File is not a regular file
DW_DLE_FWA	File is opened with wrong access
DW_DLE_NOB	File is not an object file
DW_DLE_MOF	Mangled object file header
DW_DLE_EOLL	End of location list entries
DW_DLE_NOLL	No location list section
DW_DLE_BADOFF	Invalid offset
DW_DLE_EOS	End of section
DW_DLE_ATRUNC	Abbreviations section appears truncated
DW_DLE_BADBITC	Address size passed to dwarf bad

Figure 6. List of Dwarf Error Codes

The set of errors returned by SGI Libdwarf functions is listed below. Some of the errors are SGI specific.

SYMBOLIC NAME	DESCRIPTION
DW_DLE_DBG_ALLOC	Could not allocate Dwarf_Debug struct
	Error in fstat()-ing object
	Error in mode of object file
	Incorrect access to dwarf_init()
	Error in elf_begin() on object
	Error in elf_getehdr() on object
	Error in elf_getshdr() on object
	Error in elf_strptr() on object
	Multiple .debug_info sections
	No data in .debug_info section
	Multiple .debug_abbrev sections
	No data in .debug_abbrev section
	Multiple .debug_arange sections
	No data in .debug_arange section
	Multiple .debug_line sections
	No data in .debug_line section
	Multiple .debug_loc sections
	No data in .debug_loc section
	Multiple .debug_macinfo sections
	No data in .debug_macinfo section
	Multiple .debug_pubnames sections
	No data in .debug_pubnames section
	Multiple .debug_str sections
	No data in .debug_str section
	Length of compilation-unit bad
	Incorrect Version Stamp
	Offset in .debug_abbrev bad
	Size of addresses in target bad
	Pointer into .debug_info in DIE null
	Null Dwarf_Die
	Offset in .debug_str bad
	Length of .debug_line segment bad
	Length of .debug_line prolog bad
	Number of operands to line instr bad
DW_DLE_LINE_SET_ADDR_ERROR	Error in DW_LNE_set_address instruction
DW_DLE_LINE_EXT_OPCODE_BAD	Error in DW_EXTENDED_OPCODE instruction
	Null Dwarf_line argument
	Error in included directory for given line
	File number in .debug_line bad
	Failed to allocate required structs
	Null Dwarf_Debug argument
DW_DLE_DEBUG_FRAME_LENGTH_BAD	Error in length of frame
	Bad version stamp for frame
	Bad register specified for return address
	Null Dwarf_Fde argument
	No Dwarf_Debug associated with FDE
	Null Dwarf_Cie argument
DW_DLE_CIE_DBG_NULL	No Dwarf_Debug associated with CIE
	Bad column in frame table specified

Figure 7. List of Dwarf 2 Error Codes (continued)

SYMBOLIC NAME	DESCRIPTION
DW_DLE_PC_NOT_IN_FDE_RANGE	PC requested not in address range of FDE
DW_DLE_CIE_INSTR_EXEC_ERROR	Error in executing instructions in CIE
DW_DLE_FRAME_INSTR_EXEC_ERROR	Error in executing instructions in FDE
DW_DLE_FDE_PTR_NULL	Null Pointer to Dwarf_Fde specified
DW_DLE_RET_OP_LIST_NULL	No location to store pointer to Dwarf_Frame_Op
DW_DLE_LINE_CONTEXT_NULL	Dwarf_Line has no context
DW_DLE_DBG_NO_CU_CONTEXT	dbg has no CU context for dwarf_siblingof()
DW_DLE_DIE_NO_CU_CONTEXT	Dwarf_Die has no CU context
DW_DLE_FIRST_DIE_NOT_CU	First DIE in CU not DW_TAG_compilation_unit
DW_DLE_NEXT_DIE_PTR_NULL	Error in moving to next DIE in .debug_info
DW_DLE_DEBUG_FRAME_DUPLICATE	Multiple .debug_frame sections
DW_DLE_DEBUG_FRAME_NULL	No data in .debug_frame section
DW_DLE_ABBREV_DECODE_ERROR	Error in decoding abbreviation
DW_DLE_DWARF_ABBREV_NULL	Null Dwarf_Abbrev specified
DW_DLE_ATTR_NULL	Null Dwarf_Attribute specified
DW_DLE_DIE_BAD	DIE bad
DW_DLE_DIE_ABBREV_BAD	No abbreviation found for code in DIE
DW_DLE_ATTR_FORM_BAD	Inappropriate attribute form for attribute
DW_DLE_ATTR_NO_CU_CONTEXT	No CU context for Dwarf_Attribute struct
DW_DLE_ATTR_FORM_SIZE_BAD	Size of block in attribute value bad
DW_DLE_ATTR_DBG_NULL	No Dwarf_Debug for Dwarf_Attribute struct
DW_DLE_BAD_REF_FORM	Inappropriate form for reference attribute
DW_DLE_ATTR_FORM_OFFSET_BAD	Offset reference attribute outside current CU
DW_DLE_LINE_OFFSET_BAD	Offset of lines for current CU outside .debug_line
DW_DLE_DEBUG_STR_OFFSET_BAD	Offset into .debug_str past its end
DW_DLE_STRING_PTR_NULL	Pointer to pointer into .debug_str NULL
DW_DLE_PUBNAMES_VERSION_ERROR	Version stamp of pubnames incorrect
DW_DLE_PUBNAMES_LENGTH_BAD	Read pubnames past end of .debug_pubnames
DW_DLE_GLOBAL_NULL	Null Dwarf_Global specified
DW_DLE_GLOBAL_CONTEXT_NULL	No context for Dwarf_Global given
DW_DLE_DIR_INDEX_BAD	Error in directory index read
DW_DLE_LOC_EXPR_BAD	Bad operator read for location expression
DW_DLE_DIE_LOC_EXPR_BAD	Expected block value for attribute not found
DW_DLE_OFFSET_BAD	Offset for next compilation-unit in .debug_info bad
DW_DLE_MAKE_CU_CONTEXT_FAIL	Could not make CU context
DW_DLE_ARANGE_OFFSET_BAD	Offset into .debug_info in .debug_aranges bad
DW_DLE_SEGMENT_SIZE_BAD	Segment size should be 0 for MIPS processors
DW_DLE_ARANGE_LENGTH_BAD	Length of arange section in .debug_arange bad
DW_DLE_ARANGE_DECODE_ERROR	Aranges do not end at end of .debug_aranges
DW_DLE_ARANGES_NULL	NULL pointer to Dwarf_Arange specified
DW_DLE_ARANGE_NULL	NULL Dwarf_Arange specified
DW_DLE_NO_FILE_NAME	No file name for Dwarf_Line struct
DW_DLE_NO_COMP_DIR	No Compilation directory for compilation-unit
DW_DLE_CU_ADDRESS_SIZE_BAD	CU header address size not match Elf class
DW_DLE_ELF_GETIDENT_ERROR	Error in elf_getident() on object
DW_DLE_NO_AT_MIPS_FDE	DIE does not have DW_AT_MIPS_fde attribute
DW_DLE_NO_CIE_FOR_FDE	No CIE specified for FDE
DW_DLE_DIE_ABBREV_LIST_NULL	No abbreviation for the code in DIE found
DW_DLE_DEBUG_FUNCNAMES_DUPLICATE	Multiple .debug_funcnames sections
DW_DLE_DEBUG_FUNCNAMES_NULL	No data in .debug_funcnames section
ZZZZZ_ZZZZZZZ TOTOCI W MVIZZZ TODZZ	1.0 data iii .debug_taileilailles section

Figure 8. List of Dwarf 2 Error Codes (continued)

SYMBOLIC NAME	DESCRIPTION
DW_DLE_DEBUG_FUNCNAMES_VERSION_ERROR	Version stamp in .debug_funcnames bad
DW_DLE_DEBUG_FUNCNAMES_LENGTH_BAD	Length error in reading .debug_funcnames
DW_DLE_FUNC_NULL	NULL Dwarf_Func specified
DW_DLE_FUNC_CONTEXT_NULL	No context for Dwarf_Func struct
DW_DLE_DEBUG_TYPENAMES_DUPLICATE	Multiple .debug_typenames sections
DW_DLE_DEBUG_TYPENAMES_NULL	No data in .debug_typenames section
DW_DLE_DEBUG_TYPENAMES_VERSION_ERROR	Version stamp in .debug_typenames bad
DW_DLE_DEBUG_TYPENAMES_LENGTH_BAD	Length error in reading .debug_typenames
DW_DLE_TYPE_NULL	NULL Dwarf_Type specified
DW_DLE_TYPE_CONTEXT_NULL	No context for Dwarf_Type given
DW_DLE_DEBUG_VARNAMES_DUPLICATE	Multiple .debug_varnames sections
DW_DLE_DEBUG_VARNAMES_NULL	No data in .debug_varnames section
DW_DLE_DEBUG_VARNAMES_VERSION_ERROR	Version stamp in .debug_varnames bad
DW_DLE_DEBUG_VARNAMES_LENGTH_BAD	Length error in reading .debug_varnames
DW_DLE_VAR_NULL	NULL Dwarf_Var specified
DW_DLE_VAR_CONTEXT_NULL	No context for Dwarf_Var given
DW_DLE_DEBUG_WEAKNAMES_DUPLICATE	Multiple .debug_weaknames section
DW_DLE_DEBUG_WEAKNAMES_NULL	No data in .debug_varnames section
DW_DLE_DEBUG_WEAKNAMES_VERSION_ERROR	Version stamp in .debug_varnames bad
DW_DLE_DEBUG_WEAKNAMES_LENGTH_BAD	Length error in reading .debug_weaknames
DW_DLE_WEAK_NULL	NULL Dwarf_Weak specified
DW_DLE_WEAK_CONTEXT_NULL	No context for Dwarf_Weak given

Figure 9. List of Dwarf 2 Error Codes

This list of errors is not necessarily complete; additional errors might be added when functionality to create debugging information entries are added to *libdwarf* and by the implementors of *libdwarf* to describe internal errors not addressed by the above list. Some of the above errors may be unused. Errors may not have the same meaning in different implementations.

5.20.3 dwarf_seterrhand()

The function dwarf_seterrhand() replaces the error handler (see dwarf_init()) with errhand. The old error handler is returned. This function is currently unimplemented.

5.20.4 dwarf_seterrarg()

The function dwarf_seterrarg() replaces the pointer to the error handler communication area (see dwarf_init()) with errarg. A pointer to the old area is returned. This function is currently unimplemented.

5.20.5 dwarf_dealloc()

```
void dwarf_dealloc(
          Dwarf_Debug dbg,
          void* space,
          Dwarf_Unsigned type)
```

The function dwarf_dealloc frees the dynamic storage pointed to by space, and allocated to the given Dwarf_Debug. The argument type is an integer code that specifies the allocation type of the region pointed to by the space. Refer to section 4 for details on *libdwarf* memory management.

CONTENTS

1. INTRODUCTION	1
1.1 Copyright	1
1.2 Purpose and Scope	1
1.3 Document History	2
1.4 Definitions	2
1.5 Overview	
1.6 Items Changed	
1.7 Items Removed	3
1.8 Revision History	3
2. Types Definitions	4
2.1 General Description	4
2.2 Scalar Types	4
2.3 Aggregate Types	
2.3.1 Location Record	
2.3.2 Location Description	6
2.3.3 Data Block	6
2.3.4 Frame Operation Codes: DWARF 2	6
2.3.5 Frame Regtable: DWARF 2	7
2.3.6 Frame Operation Codes: DWARF 3 (and DWARF2)	8
2.3.7 Frame Regtable: DWARF 3	8
2.3.8 Macro Details Record	10
2.4 Opaque Types	10
3. Error Handling	12
3.1 Returned values in the functional interface	13
	14
4. Memory Management	14 14
4.1 Read-only Properties	
4.2 Storage Deallocation	14
5. Functional Interface	16
5.1 Initialization Operations	16
5.1.1 dwarf_init()	16
5.1.2 dwarf_elf_init()	17
5.1.3 dwarf_get_elf()	17

	5.1.4 dwarf_finish()	18
5.2	Debugging Information Entry Delivery Operations	18
	5.2.1 Debugging Information Entry Debugger Delivery	
	Operations	18
	5.2.2 dwarf_next_cu_header()	18
	5.2.3 dwarf_siblingof()	19
	5.2.4 dwarf_child()	19
	5.2.5 dwarf_offdie()	19
5.3	Debugging Information Entry Query Operations	19
	5.3.1 dwarf_tag()	20
	5.3.2 dwarf_dieoffset()	20
	5.3.3 dwarf_die_CU_offset()	20
	5.3.4 dwarf_diename()	21
	5.3.5 dwarf_attrlist()	21
	5.3.6 dwarf_hasattr()	21
	5.3.7 dwarf_attr()	22
	5.3.8 dwarf_lowpc()	22
	5.3.9 dwarf_highpc()	22
	5.3.1@lwarf_bytesize()	22
	5.3.1 tlwarf_bitsize()	23
	5.3.12lwarf_bitoffset()	23
	5.3.1alwarf_srclang()	23
	5.3.14\text{warf_arrayorder()}	23
5.4	Attribute Form Queries	23
	5.4.1 dwarf_hasform()	24
	5.4.2 dwarf_whatform()	24
	5.4.3 dwarf_whatform_direct()	24
	5.4.4 dwarf_whatattr()	24
	5.4.5 dwarf_formref()	25
	5.4.6 dwarf_global_formref()	25
	5.4.7 dwarf_formaddr()	25
	5.4.8 dwarf_formflag()	25
	5.4.9 dwarf_formudata()	26
	5.4.1@lwarf_formsdata()	26
	5.4.1 tlwarf_formblock()	26
	5.4.12\text{warf_formstring()}	26
	5.4.12. Idwarf loclist n()	27

5.4.12.2dwarf_loclist()	27
5.5 Line Number Operations	28
5.5.1 Get A Set of Lines	
5.5.1.1 dwarf_srclines()	29
5.5.2 Get the set of Source File Names	29
5.5.3 Get information about a Single Table Line	30
5.5.3.1 dwarf_linebeginstatement()	30
5.5.3.2 dwarf_lineendsequence()	30
5.5.3.3 dwarf_lineno()	31
5.5.3.4 dwarf_line_srcfileno()	31
5.5.3.5 dwarf_lineaddr()	31
5.5.3.6 dwarf_lineoff()	31
5.5.3.7 dwarf_linesrc()	32
5.5.3.8 dwarf_lineblock()	32
5.6 Global Name Space Operations	32
5.6.1 Debugger Interface Operations	32
5.6.1.1 dwarf_get_globals()	32
5.6.1.2 dwarf_globname()	33
5.6.1.3 dwarf_global_die_offset()	34
5.6.1.4 dwarf_global_cu_offset()	34
5.6.1.5 dwarf_get_cu_die_offset_given_cu_header_off	iset() . 34
5.6.1.6 dwarf_global_name_offsets()	35
5.7 DWARF3 Type Names Operations	35
5.7.1 Debugger Interface Operations	35
5.7.1.1 dwarf_get_pubtypes()	35
5.7.1.2 dwarf_pubtypename()	36
5.7.1.3 dwarf_pubtype_die_offset()	36
5.7.1.4 dwarf_pubtype_cu_offset()	36
5.7.1.5 dwarf_pubtype_name_offsets()	36
5.8 User Defined Static Variable Names Operations	37
5.9 Weak Name Space Operations	37
5.9.1 Debugger Interface Operations	37
5.9.1.1 dwarf_get_weaks()	37
5.9.1.2 dwarf_weakname()	38
5.9.1.3 dwarf_weak_cu_offset()	
5.9.1.4 dwarf_weak_name_offsets()	39
5.10Static Function Names Operations	39

5.10. Debugger Interface Operations	39
5.10.1.ldwarf_get_funcs()	39
5.10.1.2dwarf_funcname()	41
5.10.1.3dwarf_func_die_offset()	41
5.10.1.4dwarf_func_cu_offset()	41
5.10.1.5dwarf_func_name_offsets()	41
5.1 User Defined Type Names Operations	42
5.11. Debugger Interface Operations	42
5.11.1.ldwarf_get_types()	42
5.11.1.2dwarf_typename()	43
5.11.1.3dwarf_type_die_offset()	43
5.11.1.4dwarf_type_cu_offset()	43
5.11.1.5dwarf_type_name_offsets()	44
5.12User Defined Static Variable Names Operations	44
5.12. Debugger Interface Operations	44
5.12.1.ldwarf_get_vars()	44
5.12.1.2dwarf_varname()	45
5.12.1.3dwarf_var_die_offset()	45
5.12.1.4dwarf_var_cu_offset()	46
5.12.1.5dwarf_var_name_offsets()	46
5.13 Macro Information Operations	46
5.13. General Macro Operations	46
5.13.1.ldwarf_find_macro_value_start()	46
5.13. Debugger Interface Macro Operations	46
5.13. L ow Level Macro Information Operations	47
5.13.3.ldwarf_get_macro_details()	47
5.14Low Level Frame Operations	47
5.14.0.ldwarf_get_fde_list()	50
5.14.0.2dwarf_get_fde_list_eh()	51
5.14.0.3dwarf_get_cie_of_fde()	52
5.14.0.4dwarf_get_fde_for_die()	52
5.14.0.5dwarf_get_fde_range()	53
5.14.0.6dwarf_get_cie_info()	53
5.14.0.7dwarf_get_fde_instr_bytes()	53
5.14.0.8dwarf_get_fde_info_for_reg()	54
5.14.0.9dwarf_get_fde_info_for_all_regs()	54
5.14.0.100 warf set frame rule table size()	55

5.14.0.ldwarf_set_frame_rule_inital_value()	55
5.14.0.12\text{warf_get_fde_info_for_reg3()}	55
5.14.0.16 warf_get_fde_info_for_cfa_reg3()	56
5.14.0.ldwarf_get_fde_info_for_all_regs3()	57
5.14.0.1d5warf_get_fde_n()	57
5.14.0.1dswarf_get_fde_at_pc()	58
5.14.0.1d warf_expand_frame_instructions()	58
5.14.0.1dswarf_get_fde_exception_info()	59
5.15Location Expression Evaluation	59
5.15. Location List Internal-level Interface	59
5.15.1.ldwarf_get_loclist_entry()	59
5.16Abbreviations access	59
5.16. Hwarf_get_abbrev()	60
5.16. 2 lwarf_get_abbrev_tag()	60
5.16.3dwarf_get_abbrev_code()	60
5.16.4 warf_get_abbrev_children_flag()	60
5.16.5 warf_get_abbrev_entry()	61
5.17String Section Operations	61
5.17. Hwarf_get_str()	61
5.18Address Range Operations	61
5.18. Hwarf_get_aranges()	61
5.18.21 warf_get_cu_die_offset()	62
5.18.3 warf_get_arange_cu_header_offset()	62
5.18.4 warf_get_arange_info()	63
5.19General Low Level Operations	63
5.19.ldwarf_get_address_size()	63
5.20Utility Operations	63
5.20. Hwarf_errno()	63
5.20.2\text{warf_errmsg()}	64
5.20.3lwarf_seterrhand()	67
5.20.4\text{warf_seterrarg()}	67
5.20.5\text{warf_dealloc()}	67

LIST OF FIGURES

Figure S calar Types	4
Figure E rror Indications	13
Figure Allocation/Deallocation Identifiers	15
Figure Frame Information Rule Assignments	48
Figure Frame Information Special Values	49
Figure List of Dwarf Error Codes	64
Figure List of Dwarf 2 Error Codes (continued)	64
Figure List of Dwarf 2 Error Codes (continued)	65
Figure List of Dwarf 2 Error Codes	67

A Consumer Library Interface to DWARF

David Anderson

ABSTRACT

This document describes an interface to a library of functions to access DWARF debugging information entries and DWARF line number information (and other DWARF2/3 information). It does not make recommendations as to how the functions described in this document should be implemented nor does it suggest possible optimizations.

The document is oriented to reading DWARF version 2 and version 3. There are certain sections which are SGI-specific (those are clearly identified in the document).

rev 1.64, 11 Mar 2007

^{0.} UNIX is a registered trademark of UNIX System Laboratories, Inc. in the United States and other countries.