## Helpful Links:

https://peppe8o.com/raspberry-pi-imager/

https://www.raspberrypi.com/documentation/computers/remote-access.html#ssh

https://www.raspberrypi.com/software/

https://communitv.n8n.io/t/docker-install-of-n8n-requires-login-what-is-it/23786

https://www.realvnc.com/en/connect/download/viewer/

note\* control v wont work on raspberry PI terminal. You need to right click and paste

During set up of Raspberry PI allow SSH and set to password (this will be your raspberry PI Password)

Also ensure set up on internet connect your pc has access to

Get your Raspberry PI ip address by logging into your modem and looking at the connected devices. It can take 1-2 minutes to show up after turning your raspberry PI on

Open terminal

Use command ssh (raspberrypiname)@ipaddress

Example:

ssh testuser@123.123.1.1

Once connected enter command sudo raspi-config

Go down to Interface options press enter

VCN - enter

Enable - yes

Use esc to go back and exit out of this menu

If you are getting an error message due to keygen run this command: ssh-keygen -R <RaspberryPI IP Address>

Open Real VNC Viewer

Download from

https://www.realvnc.com/en/connect/download/viewer/?lai\_vid=K9yPNX9zkHXvk&lai\_sr=0-4&lai\_sl=l

- create an account if needed

Click file - new connection

VNC server is the IP address for your raspberry pi from before

You can name it if you like, leave the rest as is.

To log in you will need to enter the raspberry pi username and password you set up earlier

Update Raspberry PI with the below commands:

sudo apt update sudo apt upgrade

Install Docker Compose

curl -fsSL <u>https://get.docker.com</u> -o get-docker.sh sudo sh get-docker.sh

Check install:

docker --version docker compose version

Then run

sudo usermod -aG docker \$USER

Set Up n8n:

Create project directory

mkdir ~/n8n && cd ~/n8n

Add this to the compose file:

Use this command in your windows pc to send the env file: scp "C:\Users\path\to\file\docker-compose.yml.txt"pi-name@pi-ipaddress:/home/testuser/n8n/ If you send it this way ensure you edit the file name to remove the.txt once sent to your

Raspberry PI

If you are having trouble with this Chat GPT can give you the correct command just tell it the exact location of the file which you can do by right clicking on the file and choosing "copy as path"

Or

Run this command Create docker-compose.yml using

nano docker-compose.yml

Manually enter the below:

services:

n8n:

image: n8nio/n8n:latest container\_name: n8n restart: always

ports:

- "5678:5678"

volumes:

- ~/n8n-data:/home/node/n8n

environment:

- N8N BASIC AUTH ACTIVE=true
- N8N\_BASIC\_AUTH\_USER=username
- N8N BASIC AUTH PASSWORD=password
- N8N\_TELEMETRY\_DISABLED=true
- N8N\_HOST=raspberrypi IP address
- N8N\_SECURE\_COOKIE=false

Create data folder and fix permissions

mkdir -p ~/n8n/n8n-data sudo chown -R 1000:1000 ~/n8n/n8n-data

Then restart/log out/ log in

Start the container Docker compose up -d

Verify it's running docker ps

Open your browser and go to: <a href="http://your-pi-ip:5678">http://your-pi-ip:5678</a>

Log in with the email address you want associated with the account (its fine if you have used this email previously) and password from the .env/ docker compose file.