# MPICH2 Installer's Guide\*

Version 1.0.6

# Mathematics and Computer Science Division Argonne National Laboratory

William Gropp
Ewing Lusk
David Ashton
Pavan Balaji
Darius Buntinas
Ralph Butler
Anthony Chan
Jayesh Krishna
Guillaume Mercier
Rob Ross
Rajeev Thakur
Brian Toonen

October 30, 2007

<sup>\*</sup>This work was supported by the Mathematical, Information, and Computational Sciences Division subprogram of the Office of Advanced Scientific Computing Research, Sci-DAC Program, Office of Science, U.S. Department of Energy, under Contract DE-AC02-06CH11357.

# Contents

1	Inti	roduction	1
<b>2</b>	Qui	ck Start	1
	2.1	Prerequisites	1
	2.2	From A Standing Start to Running an MPI Program	2
	2.3	Compiler Optimization Levels	9
	2.4	Common Non-Default Configuration Options	9
		2.4.1 The Most Important Configure Options	9
		2.4.2 Using the Absoft Fortran compilers with MPICH2	10
	2.5	Shared Libraries	11
	2.6	What to Tell the Users	11
3	Mig	grating from MPICH1	11
	3.1	Configure Options	11
	3.2	Other Differences	12
4	Cho	posing the Communication Device	13
5	Inst	calling and Managing Process Managers	14
	5.1	$\operatorname{mpd} \ \ldots \ldots \ldots \ldots \ldots \ldots \ldots \ldots \ldots \ldots$	14
		5.1.1 Configuring mpd	14
		5.1.2 System Requirements	14
		5.1.3 Using mpd	15
		5.1.4 Options for mpd	16
		5.1.5 Running MPD on multi-homed systems	16
		5.1.6 Running MPD as Root	17

		5.1.7 Running MPD on SMP's	17
		5.1.8 Security Issues in MPD	18
	5.2	SMPD	19
		5.2.1 Configuration	19
		5.2.2 Usage and administration	19
	5.3	gforker	20
6	Test	ing	20
7	Ben	chmarking	<b>21</b>
8	MP	${f E}$	21
9	Win	ndows Version	22
	9.1	Binary distribution	22
	9.2	Source distribution	23
	9.3	cygwin	24
10	All	Configure Options	24
A	Tro	ubleshooting MPDs	<b>27</b>
	A.1	Getting Started with mpd	27
		A.1.1 Following the steps	28
	A.2	Debugging host/network configuration problems	33
	A.3	Firewalls, etc	34

## 1 Introduction

This manual describes how to obtain and install MPICH2, the MPI-2 implementation from Argonne National Laboratory. (Of course, if you are reading this, chances are good that you have already obtained it and found this document, among others, in its doc subdirectory.) This *Guide* will explain how to install MPICH so that you and others can use it to run MPI applications. Some particular features are different if you have system administration privileges (can become "root" on a Unix system), and these are explained here. It is not necessary to have such privileges to build and install MPICH2. In the event of problems, send mail to mpich2-maint@mcs.anl.gov. Once MPICH2 is installed, details on how to run MPI jobs are covered in the MPICH2 User's Guide, found in this same doc subdirectory.

MPICH2 has many options. We will first go through a recommended, "standard" installation in a step-by-step fashion, and later describe alternative possibilities.

# 2 Quick Start

In this section we describe a "default" set of installation steps. It uses the default set of configuration options, which builds the sock communication device and the MPD process manager, for languages C, C++, Fortran-77, and Fortran-90 (if those compilers exist), with compilers chosen automatically from the user's environment, without tracing and debugging options. It uses the VPATH feature of make, so that the build process can take place on a local disk for speed.

## 2.1 Prerequisites

For the default installation, you will need:

- 1. A copy of the distribution, mpich2.tar.gz.
- 2. A C compiler.
- 3. A Fortran-77, Fortran-90, and/or C++ compiler if you wish to write MPI programs in any of these languages.

- 4. Python 2.2 or later version, for building the default process management system, MPD. Most systems have Python pre-installed, but you can get it free from www.python.org. You may assume it is there unless the configure step below complains.
- 5. Any one of a number of Unix operating systems, such as IA32-Linux. MPICH2 is most extensively tested on Linux; there remain some difficulties on systems to which we do not currently have access. Our configure script attempts to adapt MPICH2 to new systems.

Configure will check for these prerequisites and try to work around deficiencies if possible. (If you don't have Fortran, you will still be able to use MPICH2, just not with Fortran applications.)

## 2.2 From A Standing Start to Running an MPI Program

Here are the steps from obtaining MPICH2 through running your own parallel program on multiple machines.

1. Unpack the tar file.

```
tar xfz mpich2.tar.gz
```

If your tar doesn't accept the z option, use

```
gunzip -c mpich2.tar.gz | tar xf -
```

Let us assume that the directory where you do this is /home/you/libraries. It will now contain a subdirectory named mpich2-1.0.6.

2. Choose an installation directory (the default is /usr/local/bin):

```
mkdir /home/you/mpich2-install
```

It will be most convenient if this directory is shared by all of the machines where you intend to run processes. If not, you will have to duplicate it on the other machines after installation. Actually, if you leave out this step, the next step will create the directory for you.

3. Choose a build directory. Building will proceed *much* faster if your build directory is on a file system local to the machine on which the configuration and compilation steps are executed. It is preferable that this also be separate from the source directory, so that the source directories remain clean and can be reused to build other copies on other machines.

```
mkdir /tmp/you/mpich2-1.0.6
```

- 4. Choose any configure options. See Section 2.4.1 for a description of the most important options to consider.
- 5. Configure MPICH2, specifying the installation directory, and running the configure script in the source directory:

where the \ means that this is really one line. (On sh and its derivatives, use 2>&1 | tee configure.log instead of |& tee configure.log). Other configure options are described below. Check the configure.log file to make sure everything went well. Problems should be self-explanatory, but if not, send configure.log to mpich2-maint@mcs.anl.gov. The file config.log is created by configure and contains a record of the tests that configure performed. It is normal for some tests recorded in config.log to fail.

6. Build MPICH2:

```
make |& tee make.log
```

This step should succeed if there were no problems with the preceding step. Check make.log. If there were problems, send configure.log and make.log to mpich2-maint@mcs.anl.gov.

7. Install the MPICH2 commands:

```
make install |& tee install.log
```

This step collects all required executables and scripts in the bin subdirectory of the directory specified by the prefix argument to configure.

8. Add the bin subdirectory of the installation directory to your path:

```
setenv PATH /home/you/mpich2-install/bin: $PATH
```

for csh and tcsh, or

```
export PATH=/home/you/mpich2-install/bin:$PATH
```

for bash and sh. Check that everything is in order at this point by doing

```
which mpd
which mpicc
which mpiexec
which mpirun
```

All should refer to the commands in the bin subdirectory of your install directory. It is at this point that you will need to duplicate this directory on your other machines if it is not in a shared file system such as NFS.

9. MPICH2, unlike MPICH, uses an external process manager for scalable startup of large MPI jobs. The default process manager is called MPD, which is a ring of daemons on the machines where you will run your MPI programs. In the next few steps, you will get this ring up and tested. The instructions given here will probably be enough to get you started. If not, you should refer to Appendix A for troubleshooting help. More details on interacting with MPD can be found by running mpdhelp or any mpd command with the --help option, or by viewing the README file in mpich2/src/pm/mpd. The information provided includes how to list running jobs, kill, suspend, or otherwise signal them, and how to use the gdb debugger via special arguments to mpiexec.

For security reasons, MPD looks in your home directory for a file named .mpd.conf containing the line

#### secretword=<secretword>

where **<secretword>** is a string known only to yourself. *It should not be your normal Unix password*. Make this file readable and writable only by you:

```
cd $HOME
touch .mpd.conf
chmod 600 .mpd.conf
```

Then use an editor to place a line like:

```
secretword=mr45-j9z
```

into the file. (Of course use a different secret word than mr45-j9z.)

10. The first sanity check consists of bringing up a ring of one MPD on the local machine, testing one MPD command, and bringing the "ring" down.

```
mpd &
mpdtrace
mpdallexit
```

The output of mpdtrace should be the hostname of the machine you are running on. The mpdallexit causes the mpd daemon to exit. If you encounter problems, you should check Appendix A on troubleshooting MPD.

11. The next sanity check is to run a non-MPI program using the daemon.

```
mpd &
mpiexec -n 1 /bin/hostname
mpdallexit
```

This should print the name of the machine you are running on. If not, you should check Appendix A on troubleshooting MPD.

12. Now we will bring up a ring of mpd's on a set of machines. Create a file consisting of a list of machine names, one per line. Name this file mpd.hosts. These hostnames will be used as targets for ssh or rsh, so include full domain names if necessary. Check that you can reach these machines with ssh or rsh without entering a password. You can test by doing

```
ssh othermachine date
```

#### rsh othermachine date

If you cannot get this to work without entering a password, you will need to configure ssh or rsh so that this can be done, or else use the workaround for mpdboot in the next step.

13. Start the daemons on (some of) the hosts in the file mpd.hosts.

```
mpdboot -n <number to start> -f mpd.hosts
```

The number to start can be less than 1 + number of hosts in the file, but cannot be greater than 1 + the number of hosts in the file. One mpd is always started on the machine where mpdboot is run, and is counted in the number to start, whether or not it occurs in the file. By default, mpdboot will only start one mpd per machine even if the machine name appears in the hosts file multiple times. The -1 option can be used to override this behavior, but there is typically no reason for a user to need multiple mpds on a single host. The -1 option (that's the digit one, not the letter el) exists mostly to support internal testing. The --help option explains these as well as other useful options. In particular, if your cluster has multiprocessor nodes, you might want to use the --ncpus argument described in Section 5.1.7.

Check to see if all the hosts you listed in mpd.hosts are in the output of

```
mpdtrace
```

and if so move on to the next step.

There is a workaround if you cannot get mpdboot to work because of difficulties with ssh or rsh setup. You can start the daemons "by hand" as follows:

Then log into each of the other machines, put the install/bin directory in your path, and do:

```
mpd -h <hostname> -p <port> &
```

where the hostname and port belong to the original mpd that you started. From each machine, after starting the mpd, you can do

#### mpdtrace

to see which machines are in the ring so far. More details on mpdboot and other options for starting the mpd's are in mpich2-1.0.6/src/pm/mpd/README.

In case of persistent difficulties getting the ring of mpd's up and running on the machines you want, please see Appendix A. There we discuss the mpd's in more detail and describe how you can use the mpdcheck utility to diagnose problems with the networking configuration of your systems.

14. Test the ring you have just created:

```
mpdtrace
```

The output should consist of the hosts where MPD daemons are now running. You can see how long it takes a message to circle this ring with

```
mpdringtest
```

That was quick. You can see how long it takes a message to go around many times by giving mpdringtest an argument:

```
mpdringtest 100
mpdringtest 1000
```

15. Test that the ring can run a multiprocess job:

```
mpiexec -n <number> hostname
```

The number of processes need not match the number of hosts in the ring; if there are more, they will wrap around. You can see the effect of this by getting rank labels on the stdout:

```
mpiexec -1 -n 30 hostname
```

You probably didn't have to give the full pathname of the hostname command because it is in your path. If not, use the full pathname:

```
mpiexec -1 -n 30 /bin/hostname
```

16. Now we will run an MPI job, using the mpiexec command as specified in the MPI-2 standard.

As part of the build process for MPICH2, a simple program to compute the value of  $\pi$  by numerical integration is created in the mpich2-1.0.6/examples directory. If the current directory is the top level MPICH2 build directory, then you can run this program with

```
mpiexec -n 5 examples/cpi
```

The number of processes need not match the number of hosts. The cpi example will tell you which hosts it is running on. By default, the processes are launched one after the other on the hosts in the mpd ring, so it is not necessary to specify hosts when running a job with mpiexec.

There are many options for mpiexec, by which multiple executables can be run, hosts can be specified (as long as they are in the mpd ring), separate command-line arguments and environment variables can be passed to different processes, and working directories and search paths for executables can be specified. Do

```
mpiexec --help
```

for details. A typical example is:

```
mpiexec -n 1 master : -n 19 slave
```

or

```
mpiexec -n 1 -host mymachine master : -n 19 slave
```

to ensure that the process with rank 0 runs on your workstation.

The arguments between ':'s in this syntax are called "argument sets," since they apply to a set of processes. More arguments are described in the *User's Guide*.

The mpirun command from the original MPICH is still available, although it does not support as many options as mpiexec. You might want to use it in the case where you do not have the XML parser required for the use of mpiexec.

If you have completed all of the above steps, you have successfully installed MPICH2 and run an MPI example.

## 2.3 Compiler Optimization Levels

From version 1.0.6 onwards, by default, the MPICH2 library is built with the -O2 optimization level if it is available. The mpicc and other scripts that are used to compile applications do not include any optimization flag by default. If you want to build the MPICH2 library with a specific optimization level, set the environment variable CFLAGS to that level before running configure. If you do not want this CFLAGS value to be included in the mpicc script, set the environment variable MPI\_CFLAGS to MPI\_CFLAGS\_EMPTY. For example, to build a "production" MPICH2 in a GNU environment, you may want to do:

```
setenv CFLAGS -03
setenv MPI_CFLAGS MPI_CFLAGS_EMPTY
```

before running configure. This will cause the MPICH2 library to be built with -O3, but -O3 will not be included in the mpicc script.

## 2.4 Common Non-Default Configuration Options

A list of configure options is found in Section 10. Here we comment on some of them.

#### 2.4.1 The Most Important Configure Options

- -prefix Set the installation directories for MPICH2.
- **-enable-debuginfo** Provide access to the message queues for debuggers such as Totalview.
- **-enable-g** Build MPICH2 with various debugging options. This is of interest primarily to MPICH2 developers. The options

```
--enable-g=dbg,mem,log
```

are recommended in that case.

-enable-fast Configure MPICH2 for fastest performance at the expense of error reporting and other program development aids. This is recommended only for getting the best performance out of proven production applications, and for benchmarking.

- -enable-sharedlibs Build MPICH2 with shared libraries. For example,
  - --enable-sharedlibs=gcc for standard gcc on Linux
  - --enable-sharedlibs=osx-gcc for Mac OS X or
  - --enable-sharedlibs=solaris-cc for cc on Solaris
- -with-pm Select the process manager. The default is mpd; also useful is gforker. You can build with both process managers by specifying

```
--with-pm=mpd:gforker
```

- -without-mpe Configure MPICH2 without the MPE package of program development tools (including the Jumpshot performance viewer)
- -with-java Set the location of Java installation. This option is necessary only if the default Java installation in your PATH does not contain a valid Java installation for Jumpshot, e.g.

```
--with-java=/opt/jdk1.6.0
```

#### 2.4.2 Using the Absoft Fortran compilers with MPICH2

For best results, it is important to force the Absoft Fortran compilers to make all routine names monocase. In addition, if lower case is chosen (this will match common use by many programs), you must also tell the the Absoft compiles to append an underscore to global names in order to access routines such as getarg (getarg is not used by MPICH2 but is used in some of the tests and is often used in application programs). We recommend configuring MPICH2 with the following options

```
setenv F77 f77
setenv FFLAGS "-f -N15"
setenv F90FLAGS "-YALL_NAMES=LCS -YEXT_SFX=_"
./configure ....
```

#### 2.5 Shared Libraries

Shared libraries are currently only supported for gcc on Linux and Mac OS X and for cc on Solaris. To have shared libraries created when MPICH2 is built, specify the following when MPICH2 is configured:

```
configure --enable-sharedlibs=gcc (on Linux)
configure --enable-sharedlibs=osx-gcc (on Mac OS X)
configure --enable-sharedlibs=solaris-cc (on Solaris)
```

#### 2.6 What to Tell the Users

Now that MPICH2 has been installed, the users have to be informed of how to use it. Part of this is covered in the *User's Guide*. Other things users need to know are covered here. (For example, whether they need to run their own mpd rings or use a system-wide one run by root.)

# 3 Migrating from MPICH1

MPICH2 is an all-new rewrite of MPICH1. Although the basic steps for installation have remained the same (configure, make, make install), a number of things have changed. In this section we attempt to point out what you may be used to in MPICH1 that are now different in MPICH2.

## 3.1 Configure Options

The arguments to configure are different in MPICH1 and MPICH2; the Installer's Guide discusses configure. In particular, the newer configure in MPICH2 does not support the -cc=<compiler-name> (or -fc, -c++, or -f90) options. Instead, many of the items that could be specified in the command line to configure in MPICH1 must now be set by defining an environment variable. E.g., while MPICH1 allowed

```
./configure -cc=pgcc
```

MPICH2 requires

```
setenv CC pgcc
```

(or export CC=pgcc for ksh or CC=pgcc; export CC for strict sh) before ./configure. Basically, every option to the MPICH-1 configure that does not start with --enable or --with is not available as a configure option in MPICH2. Instead, environment variables must be used. This is consistent (and required) for use of version 2 GNU autoconf.

#### 3.2 Other Differences

Other differences between MPICH1 and MPICH2 include the handling of process managers and the choice of communication device.

For example, the new mpd has a new format and slightly different semantics for the -machinefile option. Assume that you type this data into a file named machfile:

bp400:2
bp401:2
bp402:2
bp403:2

If you then run a parallel job with this machinefile, you would expect ranks 0 and 1 to run on bp400 because it says to run 2 processes there before going on to bp401. Ranks 2 and 3 would run on bp401, and rank 4 on bp402, e.g.:

```
mpiexec -l -machinefile machfile -n 5 hostname
```

produces:

0: bp400 1: bp400 2: bp401 3: bp401 4: bp402

# 4 Choosing the Communication Device

MPICH2 is designed to be build with many different communication devices, allowing an implementation to be tuned for different communication fabrics. A simple communication device, known as "ch3" (for the third version of the "channel" interface) is provided with MPICH2 and is the default choice.

The ch3 device itself supports a variety of communication methods. These are specified by providing the name of the method after a colon in the --with-device configure option. For example, --with-device=ch3:ssm selects the socket plus shared memory method. The supported methods include:

- ch3:sock This is the default communication method. It uses sockets for all communications between processes. It supports MPI\_THREAD\_MULTIPLE and other levels of thread safety.
- **ch3:ssm** This method uses sockets between nodes and shared memory within a node.
- **ch3:shm** This method only uses shared memory and only works within a single SMP. It does not support the MPI dynamic process routines such as MPI\_Comm\_spawn.
- ch3:nemesis This method is our new, high performance method. It supports sockets, shared memory, and Myrinet-GM at present. It supports MPI\_THREAD\_MULTIPLE and other levels of thread safety. It does not support the MPI dynamic process routines in this release, but will support them in a future release.

Most installations should use either the ch3:ssm or ch3:sock methods. If you need multi-threaded MPI, you must use ch3:sock in this release. If you have a cluster of SMPs and do not need a multi-threaded MPI, then select ch3:ssm. If you are interested in trying out our highest-performance device, and need neither threads nor the dynamic process routines from MPI, then you can use ch3:nemesis.

# 5 Installing and Managing Process Managers

MPICH2 has been designed to work with multiple process managers; that is, although you can start MPICH2 jobs with mpiexec, there are different mechanisms by which your processes are started. An interface (called PMI) isolates the MPICH2 library code from the process manager. Currently three process managers are distributed with MPICH2

**mpd** This is the default, and the one that is described in Section 2.2. It consists of a ring of daemons.

**smpd** This one can be used for both Linux and Windows. It is the only process manager that supports the Windows version of MPICH2.

**gforker** This is a simple process manager that creates all processes on a single machine. It is useful for both debugging and on shared memory multiprocessors.

## $5.1 \mod$

## 5.1.1 Configuring mpd

The mpd process manager can be explicitly chosen at configure time by adding

--with-pm=mpd

to the configure argments. This is not necessary, since mpd is the default.

#### 5.1.2 System Requirements

mpd consists of a number of components written in Python. The configure script should automatically find a version of python in your PATH that has all the features needed to run mpd. If for some reason you need to pick a specific version of Python for mpd to use, you can do so by adding

--with-python=<fullpathname of python interpreter>

to your configure arguments. If your system doesn't have Python, you can get the latest version from http://www.python.org. Most Linux distributions include a moderately current version of Python. MPD requires release 2.2 or later.

The mpd process manager supports the use of the TotalView parallel debugger from Etnus. If totalview is in your PATH when MPICH2 is configured, then an interface module will be automatically compiled, linked, and installed so that you can use TotalView to debug MPICH jobs (See the User's Guide under "Debugging". You can also explicitly enable or disable this capability with --enable-totalview or --disable-totalview as arguments to configure.

#### 5.1.3 Using mpd

In Section 2.2 you installed the mpd ring. Several commands can be used to use, test, and manage this ring. You can find out about them by running mpdhelp, whose output looks like this:

The following mpd commands are available. For usage of any specific one, invoke it with the single argument --help .

```
mpd start an mpd daemon mpdtrace show all mpd's in ring
```

mpdboot start a ring of daemons all at once

mpdringtest test how long it takes for a message to circle the ring

mpdallexit take down all daemons in ring

mpdcleanup repair local Unix socket if ring crashed badly

mpdlistjobs list processes of jobs (-a or --all: all jobs for all users)

mpdkilljob kill all processes of a single job

mpdsigjob deliver a specific signal to the application processes of a job

mpiexec start a parallel job

Each command can be invoked with the --help argument, which prints usage information for the command without running it.

So for example, to see a complete list of the possible arguments for mpdboot, you would run

mpdboot --help

### 5.1.4 Options for mpd

-help causes mpd to print a list and description of all options

In addition to the cmd-line options, mpd will also check for presence of the environment variable MPICH\_PORT\_RANGE (note MPICH instead of MPD) and use only the ports in that range for listening sockets. The range is separated by a colon, e.g., 2000:8000.

## 5.1.5 Running MPD on multi-homed systems

If you plan to use one or more multi-homed systems, it is of course useful if the default hostname is associated with the interface that mpd will need to use for communications. If not however, you can cause mpd to use a specific interface by using the --ifhn (interface-hostname) option, e.g.:

```
n1% mpd --ifhn=192.168.1.1 &
```

If you then run mpiexec on n1 connecting to that mpd, the mpiexec will use the same ifhn for communications with remote processes that connect back to it. mpiexec will also accept a -ifhn option (mpiexec -help) in the unlikely event that you wish it to use a separate interface from the mpd.

mpdboot can also designate the ifhn to be used by both the local and remote mpds which it starts, e.g.:

```
n1% mpdboot --totalnum=3 --ifhn=192.168.1.1
```

where mpd.hosts contains:

```
n2 ifhn=192.168.1.2
n3 ifhn=192.168.1.3
```

will start one mpd locally, one on n2 and one on n3. Each will use the respectively designated ifhn.

#### 5.1.6 Running MPD as Root

MPD can run as root to support multiple users simultaneously. To do this, it easiest to simply do the "make install" in the mpd sub-directory as root. This will cause the mpdroot program to be installed in the bin directory with setuid-root permissions. Individual users then have the option of starting and using their own mpd rings, or they can run with a ring started by root. To use root's ring, they must use an option named MPD\_USE\_ROOT\_MPD. This option may either be set as an environment variable or they can set it in their own .mpd.conf file, e.g.:

When root starts the mpds in the ring, the procedure is the same as for a regular user except that root's configuration file is in /etc/mpd.conf (note that there is no leading dot in the file name).

## 5.1.7 Running MPD on SMP's

Typically one starts one mpd on each host. When a job is started with mpiexec without any particular host specification, the processes are started on the ring of hosts one at a time, in round-robin fashion until all the processes have been started. Thus, if you start a four-process job on a ring of two machines, hosta and hostb, then you will find ranks 0 and 2 on hosta and ranks 1 and 4 on hostb. This might not be what you want, especially if the machines are SMP's and you would like to have consecutive ranks on the same machine as much as possible. If you tell the mpd how many cpus it has to work with by using the --ncpus argument, as in

then the number of processes started the first time the startup message circles the ring will be determined by this argument. That is, in the above four-process example, ranks 0 and 1 will be on hosta and ranks 2 and 3 will be on hostb. This effect only occurs the first time around the ring. That is if you start a six-process job on this ring (two mpd's, each started with --ncpus=2) you will get processes 0, 1, and 4 on hosta and 2, 3, and 5 on hostb. This is for load-balancing purposes. (It is assumed that you do not want 0, 1, 4, and 5 on hosta and only 2 and 3 on hostb; if that is what

you do want, you can control process placement explicitly on the mpiexec command, as described in the *User's Guide*.

#### 5.1.8 Security Issues in MPD

Since the mpd process manager allows the remote execution of processes, it needs to incorporate security features that prevent inappropriate or malicious process creation by someone without permission to do so. In this section we describe how mpd deals with a number of security issues.

The first issue is the starting of the mpd processes themselves. This is done either by the user logging into each machine starting each mpd process "by hand," or else by using the mpdboot program. mpdboot uses ssh by default, although the less secure rsh can be used if the user chooses.

The next issue occurs when a single new mpd joins a ring of existing mpd's. This occurs during mpdboot, or can occur later if the user wishes to expand an existing ring. In this situation a "challenge-response" protocol is followed. A user must have the same secretword set in his .mpd.conf file on each machine. This file must be readable only by the user starting the mpd; otherwise the mpd will refuse to read it. When mpd A wishes to join an existing ring by connecting to mpd B, which is already in the ring, at the port B is listening on, the following sequence of events occurs:

- 1. B temporarily accepts the connection.
- 2. B seeds the random number generator with the high-resolution part of the time of day, generates a random number, and sends it to A.
- A concatenates the random number with the value of secretword in .mpd.conf, encrypts it with md5, and sends the encrypted result to B.
- 4. Meanwhile, B encrypts the (same) random number concatenated with its value of secretword.
- 5. When B receives the encrypted value from A, it compares the encrypted value with its own.
- 6. If the values match, A is allowed to join the ring; otherwise the connection is closed.

Note that the secret word is never sent over the connection in the clear, and the use of the time of day means that there will be no repeating pattern of challenges to be observed.

The third issue concerns how mpiexec connects to the local mpd. This is done through a Unix socket in /tmp rather than through an INET socket. Thus security is preserved through the security of the file system.

Once connections are established, the messages that are sent over them are not encrypted. However, no security information is sent over these connections.

#### 5.2 SMPD

## 5.2.1 Configuration

You may add the following configure options, --with-pm=smpd, to build and install the smpd process manager. The process manager, smpd, will be installed to the bin sub-directory of the installation directory of your choice specified by the --prefix option.

smpd process managers run on each node as stand-alone daemons and need to be running on all nodes that will participate in MPI jobs. smpd process managers are not connected to each other and rely on a known port to communicate with each other. Note: If you want multiple users to use the same nodes they must each configure their smpds to use a unique port per user.

smpd uses a configuration file to store settings. The default location is ~/.smpd. This file must not be readable by anyone other than the owner and contains at least one required option - the access passphrase. This is stored in the configuration file as phrase=<phrase>. Access to running smpds is authenticated using this passphrase and it must not be your user password.

#### 5.2.2 Usage and administration

Users will start the smpd daemons before launching mpi jobs. To get an smpd running on a node, execute

6 TESTING 20

Executing this for the first time will prompt the user to create a ~/.smpd configuration file and passphrase if one does not already exist.

Then users can use mpiexec to launch MPI jobs.

All options to smpd:

#### smpd -s

Start the smpd service/daemon for the current user. You can add -p <port> to specify the port to listen on. All smpds must use the same port and if you don't use the default then you will have to add -p <port> to mpiexec or add the port=<port> to the .smpd configuration file

#### smpd -r

Start the smpd service/daemon in root/multi-user mode. This is not yet implemented.

#### smpd -shutdown [host]

Shutdown the smpd on the local host or specified host. Warning: this will cause the smpd to exit and no mpiexec or smpd commands can be issued to the host until smpd is started again.

## 5.3 gforker

gforker is a simple process manager that runs all processes on a single node; it's version of mpiexec uses the system fork and exec calls to create the new processes. To configure with the gforker process manager, use

```
configure --with-pm=gforker ...
```

# 6 Testing

Once MPICH2 has been installed, you can test it by running some of the example programs in the examples directory. A more thorough test can be run with the command make testing. This will produce a summary on standard output, along with an XML version of the test results in mpich2/test/mpi. In addition, running make testing from the top-level (mpich2) directory will run tests of the commands, such as mpicc and mpiexec, that are included with MPICH2.

Other MPI test suites are available from http://www.mcs.anl.gov/mpi/mpi-test/tsuite.html. As part of the MPICH2 development, we run the MPICH1, MPICH2, C++, and Intel test suites every night and post the results on http://www.mcs.anl.gov/mpi/mpich1/micronotes/mpich2-status/. Other tests are run on an occasional basis.

# 7 Benchmarking

There are many benchmarking programs for MPI implementations. Three that we use are mpptest (http://www.mcs.anl.gov/mpi/mpptest), netpipe (http://www.scl.ameslab.gov/netpipe), and SkaMPI (http://liinwww.ira.uka.de/~skampi). Each of these has different strengths and weaknesses and reveals different properties of the MPI implementation.

In addition, the MPICH2 test suite contains a few programs to test for performance artifacts in the directory test/mpi/perf. An example of a performance artifact is markedly different performance for the same operation when performed in two different ways. For example, using an MPI datatype for a non-contiguous transfer should not be much slower than packing the data into a contiguous buffer, sending it as a contiguous buffer, and then unpacking it into the destination buffer. An example of this from the MPI-1 standard illustrates the use of MPI datatypes to transpose a matrix "on the fly," and one test in test/mpi/perf checks that the MPI implementation performs well in this case.

#### 8 MPE

MPICH2 comes with the same MPE (Multi-Processing Environment) tools that are included with MPICH1. These include several trace libraries for recording the execution of MPI programs and the Jumpshot and SLOG tools for performance visualization. The MPE tools are built and installed by default and should be available without requiring any additional steps. The installation of MPE is documented in mpich2/src/mpe2/INSTALL and the usage of MPE is documented in mpich2/src/mpe2/README and MPICH2 user's guide.

## 9 Windows Version

## 9.1 Binary distribution

The Windows binary distribution uses the Microsoft Installer. Download and execute mpich2-1.x.xxx.msi to install the binary distribution. The default installation path is C:\Program Files\MPICH2. You must have administrator privileges to install mpich2-1.x.xxx.msi. The installer installs a Windows service to launch MPICH applications and only administrators may install services. This process manager is called smpd.exe. Access to the process manager is passphrase protected. The installer asks for this passphrase. Do not use your user password. The same passphrase must be installed on all nodes that will participate in a single MPI job.

Under the installation directory are three sub-directories: include, bin, and lib. The include and lib directories contain the header files and libraries necessary to compile MPI applications. The bin directory contains the process manager, smpd.exe, and the the MPI job launcher, mpiexec.exe. The dlls that implement MPICH2 are copied to the Windows system32 directory.

You can install MPICH in unattended mode by executing

```
msiexec /q /I mpich2-1.x.xxx.msi
```

The smpd process manager for Windows runs as a service that can launch jobs for multiple users. It does not need to be started like the unix version does. The service is automatically started when it is installed and when the machine reboots. smpd for Windows has additional options:

## smpd -register\_spn

Register the Service Principal Name with the domain controller. This command enables passwordless authentication using kerberos. It must be run on each node individually by a domain administrator.

#### 9.2 Source distribution

In order to build MPICH2 from the source distribution under Windows, you must have MS Developer Studio .NET 2003 or later, perl and optionally Intel Fortran 8 or later.

- Download mpich2-1.x.y.tar.gz and unzip it.
- Bring up a Visual Studio Command prompt with the compiler environment variables set.
- Run winconfigure.wsf. If you don't have a Fortran compiler add the --remove-fortran option to winconfigure to remove all the Fortran projects and dependencies. Execute winconfigure.wsf /? to see all available options.
- open mpich2\mpich2.sln
- build the ch3sockRelease mpich2 solution
- build the ch3sockRelease mpich2s project
- build the Release mpich2 solution
- build the fortRelease mpich2 solution
- build the gfortRelease mpich2 solution
- build the sfortRelease mpich2 solution
- build the channel of your choice. The options are sock, shm, and ssm. The shm channel is for small numbers of processes that will run on a single machine using shared memory. The shm channel should not be used for more than about 8 processes. The ssm (sock shared memory) channel is for clusters of smp nodes. This channel should not be used if you plan to over-subscribe the CPU's. If you plan on launching more processes than you have processors you should use the default

sock channel. The ssm channel uses a polling progress engine that can perform poorly when multiple processes compete for individual processors.

## 9.3 cygwin

MPICH2 can also be built under cygwin using the source distribution and the Unix commands described in previous sections. This will not build the same libraries as described in this section. It will build a "Unix" distribution that runs under cygwin.

# 10 All Configure Options

Here is a list of all the configure options currently recognized by the top-level configure. It is the MPICH-specific part of the output of

```
configure --help
```

Not all of these options may be fully supported yet.

```
Optional Features:
  --disable-FEATURE
                          do not include FEATURE (same as --enable-FEATURE=no)
  --enable-FEATURE[=ARG] include FEATURE [ARG=yes]
--enable-cache - Turn on configure caching
--enable-echo - Turn on strong echoing. The default is enable=no.
--enable-strict - Turn on strict debugging with gcc
--enable-coverage - Turn on coverage analysis using gcc and gcov
--enable-error-checking=level - Control the amount of error checking.
level may be
    no
              - no error checking
             - error checking controllable at runtime through environment
    runtime
             - error checking always enabled
--enable-error-messages=level - Control the amount of detail in error
 messages. Level may be
             - Maximum amount of information
             - Only generic messages (no information about the specific
                instance)
    class
              - One message per MPI error class
```

```
- No messages
    none
--enable-timing=level - Control the amount of timing information
collected by the MPICH implementation. level may be
           - Collect no data
    none
    all
            - Collect lots of data
    runtime - Runtime control of data collected
The default is none.
--enable-g=option - Control the level of debugging support in the MPICH
implementation. option may be a list of common separated names including
           - No debugging
   mem
            - Memory usage tracing
   handle - Trace handle operations
   dbg
            - Add compiler -g flags
            - Enable debug event logging
    meminit - Preinitialize memory associated structures and unions to
              eliminate access warnings from programs like valgrind
            - All of the above choices
    all
--enable-fast - pick the appropriate options for fast execution. This
               turns off error checking and timing collection
--enable-f77 - Enable Fortran 77 bindings
--enable-f90 - Enable Fortran 90 bindings
--enable-cxx - Enable C++ bindings
--enable-romio - Enable ROMIO MPI I/O implementation
--enable-debuginfo - Enable support for debuggers
--enable-nmpi-as-mpi - Use MPI rather than PMPI routines for MPI routines,
 such as the collectives, that may be implemented in terms of other MPI
 routines
--enable-mpe - Build the MPE (MPI Parallel Environment) routines
--enable-threads=level - Control the level of thread support in the
MPICH implementation. The following levels are supported.
    single - No threads (MPI_THREAD_SINGLE)
    funneled - Only the main thread calls MPI (MPI_THREAD_FUNNELED)
    serialized - User serializes calls to MPI (MPI_THREAD_SERIALIZED)
    multiple(:impl) - Fully multi-threaded (MPI_THREAD_MULTIPLE)
The following implementations are supported.
    global_mutex - a single global lock guards access to all MPI functions.
The default implementation is global_mutex.
For the ch3:sock channel, a separate build is no longer needed for thread-multiple.
It is compiled by default and is selectable at run time with MPI_Init_thread.
If MPI_Init_thread is not called, the default is funneled .
For other channels, the --enable-threads option is not supported currently, and
the default is funneled.
--enable-weak-symbols - Use weak symbols to implement PMPI routines (default)
--enable-sharedlibs=kind - Enable shared libraries. kind may be
          - Standard gcc and GNU ld options for creating shared libraries
```

```
osx-gcc - Special options for gcc needed only on OS/X
    solaris-cc - Solaris native (SPARC) compilers for 32 bit systems
    cygwin-gcc - Special options for gcc needed only for cygwin
           - same as --disable-sharedlibs
Only gcc, osx-gcc, and solaris-cc are currently supported
--enable-dependencies - Generate dependencies for sourcefiles. This
            requires that the Makefile.in files are also created
            to support dependencies (see maint/updatefiles)
--enable-timer-type=name - Select the timer to use
for MPI_Wtime and internal timestamps. name may be one of
    gethrtime - Solaris timer (Solaris systems only)
    clock_gettime - Posix timer (where available)
    gettimeofday - Most Unix systems
    linux86_cycle - Linux x86; returns cycle counts, not time in seconds
    linuxalpha_cycle - Like linux86_cycle, but for Linux Alpha
    gcc_ia64_cycle - IPF ar.itc timer
--enable-base-cache - Enable the use of a simple cache for the subsidieary
                       configure scripts.
Optional Packages:
  --with-PACKAGE[=ARG]
                          use PACKAGE [ARG=yes]
  --without-PACKAGE
                          do not use PACKAGE (same as --with-PACKAGE=no)
--with-device=name - Specify the communication device for MPICH.
--with-pmi=name - Specify the pmi interface for MPICH.
--with-pm=name - Specify the process manager for MPICH.
      Multiple process managers may be specified as long as they all use
      the same pmi interface by separating them with colons. The
      mpiexec for the first named process manager will be installed.
      Example: --with-pm=forker:mpd:remshell builds the three process
      managers forker, mpd, and remshell; only the mpiexec from forker
      is installed into the bin directory.
--with-logging=name - Specify the logging library for MPICH.
--with-mpe - Build the MPE (MPI Parallel Environment) routines
--with-htmldir=dir - Specify the directory for html documentation
--with-docdir=dir - Specify the directory for documentation
--with-cross=file - Specify the values of variables that configure cannot
determine in a cross-compilation environment
--with-namepublisher=name - Choose the system that will support
                             MPI_PUBLISH_NAME and MPI_LOOKUP_NAME. Options
                             include
                               no (no service available)
                               file:directory (optional directory)
```

```
--with-fwrapname=name - Specify name of library containing Fortran interface
routines
--with-thread-package=package - Thread package to use. Supported thread
packages include:
    posix or pthreads - POSIX threads
    solaris - Solaris threads (Solaris OS only)
    none - no threads
If the option is not specified, the default package is ${MPE_THREAD_DEFAULT}.
If the option is specified, but a package is not given, then the default
is posix.
```

Notes on the configure options. The --with-htmldir and --with-docdir options specify the directories into which the documentation will be installed by make install.

# A Troubleshooting MPDs

## A.1 Getting Started with mpd

mpd stands for multi-purpose daemon. We sometimes use the term mpd to refer to the combination of the mpd daemon and its helper programs that collectively form a process management system for executing parallel jobs, including mpich jobs. The mpd daemon must run on each host where you wish to execute parallel programs. The mpd daemons form a ring to facilitate rapid process startup. Even a single mpd on a single host forms a loop. Therefore, each host must be configured in such a way that the mpds can connect to each other and pass messages via sockets.

It can be rather tricky to configure one or more hosts in such a way that they adequately support client-server applications like mpd. In particular, each host must not only know its own name, but must identify itself correctly to other hosts when necessary. Further, certain information must be readily accessible to each host. For example, each host must be able to map another host's name to its IP address. In this section, we will walk slowly through a series of steps that will help to ensure success in running mpds on a single host or on a large cluster.

If you can **ssh** from each machine to *itself*, and from each machine to each other machine in your set (and back), then you probably have an adequate

environment for mpd. However, there may still be problems. For example, if you are blocking all ports except the ports used by ssh/sshd, then mpd will still fail to operate correctly.

To begin using mpd, the sequence of steps that we recommend is this:

- 1. get one mpd working alone on a first test node
- 2. get one mpd working alone on a second test node
- 3. get two new mpds to work together on the two test nodes
- 4. boot two new mpds on the two test nodes via mpdboot

## A.1.1 Following the steps

- 1. Install mpich2, and thus mpd.
- 2. Make sure the mpich2 bin directory is in your path. Below, we will refer to it as MPDDIR.
- 3. Kill old mpd processes. If you are coming to this guide from elsewhere, e.g. a Quick Start guide for mpich2, because you encountered mpd problems, you should make sure that all mpd processes are terminated on the hosts where you have been testing. mpdallexit may assist in this, but probably not if you were having problems. You may need to use the Unix kill command to terminate the processes.
- 4. Run a first mpd (alone on a first node). As mentioned above, mpd uses client-server communications to perform its work. So, before running an mpd, let's run a simpler program (mpdcheck) to verify that these communications are likely to be successful. Even on hosts where communications are well supported, sometimes there are problems associated with hostname resolution, etc. So, it is worth the effort to proceed a bit slowly. Below, we assume that you have installed mpd and have it in your path.

Select a test node, let's call it n1. Login to n1.

First, we will run mpdcheck as a server and a client. To run it as a server, get into a window with a command-line and run this:

## n1 \$ mpdcheck -s

It will print something like this:

```
server listening at INADDR_ANY on: n1 1234
```

Now, run the client side (in another window if convenient) and see if it can find the server and communicate. Be sure to use the *same* hostname and portnumber printed by the server (above: n1 1234):

```
n1 $ mpdcheck -c n1 1234
```

If all goes well, the server will print something like:

and the client will print:

```
client successfully recvd ack from server:
    ack_from_server_to_client
```

If the experiment failed, you have some network or machine configuration problem which will also be a problem later when you try to use mpd. Even if the experiment succeeded, but the hostname printed by the server was *localhost*, then you will probably have problems later if you try to use mpd on n1 in conjunction with other hosts. In either case, skip to Section A.2 "Debugging host/network configuration problems."

If the experiment succeeded, then you should be ready to try mpd on this one host. To start an mpd, you will use the mpd command. To run parallel programs, you will use the mpiexec program. All mpd commands accept the -h or -help arguments, e.g.:

```
n1 $ mpd --help
n1 $ mpiexec --help
```

Try a few tests:

```
n1 $ mpd &
n1 $ mpiexec -n 1 /bin/hostname
n1 $ mpiexec -l -n 4 /bin/hostname
n1 $ mpiexec -n 2 PATH_TO_MPICH2_EXAMPLES/cpi
```

where PATH\_TO\_MPICH2\_EXAMPLES is the path to the mpich2-1.0.3/examples directory.

To terminate the mpd:

#### n1 \$ mpdallexit

- 5. Run a second mpd (alone on a second node). To verify that things are fine on a second host (say n2), login to n2 and perform the same set of tests that you did on n1. Make sure that you use mpdallexit to terminate the mpd so you will be ready for further tests.
- 6. Run a ring of two mpds on two hosts. Before running a ring of mpds on n1 and n2, we will again use mpdcheck, but this time between the two machines. We do this because the two nodes may have trouble locating each other or communicating between them and it is easier to check this out with the smaller program.

First, we will make sure that a server on n1 can service a client from n2. On n1:

```
n1 $ mpdcheck -s
```

which will print a hostname (hopefully n1) and a portnumber (say 3333 here). On n2:

```
n2 $ mpdcheck -c n1 3333
```

If this experiment fails, skip to Section A.2 "Debugging host/network configuration problems".

Second, we will make sure that a server on n2 can service a client from n1. On n2:

```
n2 $ mpdcheck -s
```

which will print a hostname (hopefully n2) and a portnumber (say 7777 here). On n2:

If this experiment fails, skip to Section A.2 "Debugging host/network configuration problems".

If all went well, we are ready to try a pair of mpds on n1 and n2. First, make sure that all mpds have terminated on both n1 and n2. Use mpdallexit or simply kill them with:

where you have obtained the PID\_OF\_MPD by some means such as the ps command.

On n1:

```
n1 $ mpd &
n1 $ mpdtrace -1
```

This will print a list of machines in the ring, in this case just n1. The output will be something like:

```
n1_6789 (192.168.1.1)
```

The 6789 is the port that the mpd is listeneing on for connections from other mpds wishing to enter the ring. We will use that port in a moment to get an mpd from n2 into the ring. The value in parentheses should be the IP address of n1.

On n2:

where 6789 is the listening port on n1 (from mpdtrace above). Now try:

You should see both mpds in the ring.

To run some programs in parallel:

```
n1 $ mpiexec -n 2 /bin/hostname
n1 $ mpiexec -n 4 /bin/hostname
n1 $ mpiexec -l -n 4 /bin/hostname
n1 $ mpiexec -l -n 4 PATH_TO_MPICH2_EXAMPLES/cpi
```

where PATH\_TO\_MPICH2\_EXAMPLES is the path to the mpich2-1.0.6/examples directory.

To bring down the ring of mpds:

```
n1 $ mpdallexit
```

7. Boot a ring of two mpds via mpdboot. Please be aware that mpdboot uses ssh by default to start remote mpds. It will expect that you can run ssh from n1 to n2 (and from n2 to n1) without entering a password.

First, make sure that you terminate the mpd processes from any prior tests.

On n1, create a file named mpd.hosts containing the name of n2:

n2

Then, on n1 run:

```
n1 $ mpdboot -n 2
n1 $ mpdtrace -l
n1 $ mpiexec -l -n 2 /bin/hostname
```

The mpdboot command should read the mpd.hosts file created above and run an mpd on each of the two machines. The mpdtrace and mpiexec show the ring up and functional. Options that may be useful are:

- --help use this one for extra details on all options
- -v (verbose)
- --chkup tries to verify that the hosts are up before starting mpds
- --chkuponly only performs the verify step, then ends

To bring the ring down:

```
n1 $ mpdallexit
```

If mpdboot works on the two machines n1 and n2, it will probably work on your others as well. But, there could be configuration problems using a new machine on which you have not yet tested mpd. An easy way to check, is to gradually add them to mpd.hosts and try an mpdboot with a -n arg that uses them all each time. Use mpdallexit after each test.

## A.2 Debugging host/network configuration problems

We use mpdcheck as our first attempt to debug host or network configuration problems. If you run:

#### n1 \$ mpdcheck --help

you should receive a fairly long help message describing a wide variety of arguments which can be supplied to mpdcheck to help you debug.

The first thing to try is to simply login to a node, say n1 and run:

#### n1 \$ mpdcheck

mpdcheck will produce no output here if it finds no problems. If mpdcheck does find potenital problems, it will print them with \*\*\* at the beginning of the line. You can cause mpdcheck to be verbose by using the -v option, e.g.:

## n1 \$ mpdcheck -v

Also, if mpdcheck offers comments about how you might repair certain problems, you can get a longer version of those messages by using the -l option, e.g.:

## n1 \$ mpdcheck -1

If you run mpdcheck on each node and find no problems, you may still wish to use it further to debug issues between two nodes. For example, you might login to n1 and create file named mpd.hosts which contains the name of another node which is having trouble communicating with n1, e.g. n2. Then, you may want to run:

### n1 \$ mpdcheck -f mpd.hosts

This test will see if n1 is having trouble discovering information about n2. If not, you wish to try:

```
n1 $ mpdcheck -f mpd.hosts -ssh
```

This will also try to test ssh support between n1 and n2.

If these 2 experiments go OK, you should probably try them again but this time logged into n2 and trying to connect back to n1. Do not forget to change the contents of mpd.hosts to contain the name of n1.

If none of these get you past the problems, you may need to ask for help. If so, it will probably useful to run mpdcheck once more on each of the nodes which are of concern:

```
n1 $ mpdcheck -pc
n2 $ mpdcheck -pc
```

These will produce quite a bit of output which may be useful in determining the problem. The -pc option does not really try to offer any comemnts about what may be wrong. It merely prints potentially useful debugging info.

#### A.3 Firewalls, etc.

If the output from any of mpdcheck, mpd, or mpdboot leads you to believe that one or more of your hosts are having trouble communicating due to firewall issues, we can offer a few simple suggestions. If the problems are due to an "enterprise" firewall computer, then we can only point you to your local network admin for assistance.

In other cases, there are a few quick things that you can try to see if there some common protections in place which may be causing your problems.

First, you might see if iptables is active. You will probably need to be root to do this:

```
n1 # iptables -L
```

This will show a set of 3 current iptables chains being applied for each of INPUT, FORWARD, and OUTPUT. If the chains are non-empty, then you may have something blocked. This could be a result of a software firewall package you are running (e.g. shorewall) or some home-grown set of chains. If you are unfamiliar with iptables, you will need to get local help to decipher the rules and determine if any of them may be affecting you. There are options such as -F to iptables that will disable the chains, but that is dangerous of course if you require them for protection.

Next, you might see if any tcp-wrappers are active. You may need to be root to do this:

## n1 # cat /etc/hosts.deny /etc/hosts.allow

If there are any uncommented lines, they likely designate any (or ALL) daemons which have their tcp communications blocked. This can be particularly problematic for mpdboot which uses ssh (and thus the ssh daemon, sshd).

Next, you might wish to see if you have available ephemeral ports:

This should print a range something like:

32768 61000