



# Radiance Data Assimilation in WRFDA

## Zhiquan Liu (liuz@ucar.edu) NCAR/NESL/MMM


## Outline


- An introduction of radiance data assimilation
  - Principal of satellite measurements
  - Introduction to the Radiative Transfer theory
  - Elements of Radiance DA

Practical aspects with WRFDA


# Part I: An Introduction of radiance data assimilation

## Environment monitoring satellites





#### Cross-track scan geometry of satellite instruments




#### What do satellite instruments measure?

They DO NOT measure TEMPERATURE
They DO NOT measure HUMIDITY
They DO NOT measure WIND


Satellite (**passive**) instruments simply measure the **radiance** (energy in specific unit) that reaches the top of the atmosphere (TOA) at frequency range  $v_1 \sim v_2$ . The measured radiance is related to geophysical atmospheric variables by the **radiative transfer** equation. Radiances are often converted to "**brightness temperature**" (equivalent blackbody temperature, by inverting Plank function).

#### Passive Sensors from Weather/Environment Satellites




Electromagnetic Spectrum

#### Atmospheric Gas Absorption-Transmission



#### Radiative Transfer: Forward model




Surface emission R<sub>s</sub>

Up-welling atmosphere emission  $R_A$ 


Reflected solar radiation  $R_0$ 

Down-welling & reflected atmos.

Emission (R<sub>D</sub>)



### Weighting functions of different channels



WRFDA Tutorial, July 2014

### Radiance Assimilation in 3D/4D-VAR


Solving the inverse problem by minimizing a cost function


$$J(\mathbf{x}) = \frac{1}{2} (\mathbf{x} - \mathbf{x}_b)^{\mathrm{T}} \mathbf{B}^{-1} (\mathbf{x} - \mathbf{x}_b) + \frac{1}{2} [\mathbf{y} - H(\mathbf{x})]^{\mathrm{T}} \mathbf{R}^{-1} [\mathbf{y} - H(\mathbf{x})]$$

**Observation operators include Radiative Transfer Model** 

- 1. Solving the inverse problem along with other observations in a more consistent way.
- 2. Pixels are no longer independent each other due to the horizontal correlation in B.
- 3. Can affect no-measured quantities through multivariate correlation in B.

## Radiance obs is biased





#### Variational Bias Correction (VarBC) in WRFDA (T. Auligné)

Modeling of errors in satellite radiances:

$$y = H(x_t) + B(\beta) + \varepsilon$$

$$y = H(x_t) + B(\beta) + \varepsilon \qquad \begin{cases} \langle \varepsilon \rangle = 0 \\ B(\beta) = \sum_{i=1}^{N} \beta_i p_i \end{cases}$$

**Bias-correction coefficients** 

#### **Predictors:**

- Offset (i.e., 1)
- 1000-300mb thickness
- 200-50mb thickness
- Surface skin temperature
- Total column water vapor
- Scan, Scan<sup>2</sup>, Scan<sup>3</sup>

Bias parameters can be estimated within the variational assimilation, jointly with the atmospheric model state (Der ber and Wu 1998) (Dee 2005) (Auligné et al. 2007)

Inclusion of the bias parameters in the control vector :  $\mathbf{x}^T \rightarrow [\mathbf{x}, \boldsymbol{\beta}]^T$ 

$$J_{b}: background term for x$$


$$J_{0}: corrected observation term$$

$$J(x,\beta) = (x_{b} - x)^{T} B_{x}^{-1} (x_{b} - x) + [y - H(x) - B(\beta)]^{T} R^{-1} [y - H(x) - B(\beta)]$$

$$+ (\beta_{b} - \beta)^{T} B_{\beta}^{-1} (\beta_{b} - \beta)$$

$$J_{p}: background term for β$$


Can be used for radiance offline monitoring by removing  $J_b$  term and other obs., and using some analysis fields as reference.




## **Observation Thinning**

Dense data are very likely correlated, which is not taken into account in the observation covariance matrix R.

#### No Thinning



#### 120km Thinning Mesh







## Part II: Practice with WRFDA

- Data Ingest (sources, instruments)
- Radiative transfer model
- Channel selection
- Variational Bias correction
- Diagnostics and monitoring

#### Data Ingest (V3.6.1)

- NCEP global BUFR format radiance data within a 6-h time window (27 sensors from 12 satellites)
  - 6 HIRS from NOAA16, 17, 18, 19, METOP-2/3
  - 7 AMSU-A from NOAA15/16/18/19, EOS-2, METOP-2/3
  - 3 AMSU-B from NOAA15, 16, 17
  - 4 MHS from NOAA18, 19, METOP-2/3
  - 1 AIRS from EOS-2
  - 2 IASI from METOP-2/3
  - 1 ATMS from NPP
  - 3 SEVIRI from MSG-1/2/3
- NRL/AFWA/NESDIS produced DMSP-16/17/18/19 SSMI/S BUFR radiance data.
- FY-3 MWTS and MWHS, CMA binary format.

#### NCEP near real-time ftp server with radiance BUFR data

ftp://ftp.ncep.noaa.gov/pub/data/nccf/com/gfs/prod/gdas.\${yyyymmddhh}

NOAA Historical archive: <a href="http://nomads.ncdc.noaa.gov/data/gdas/">http://nomads.ncdc.noaa.gov/data/gdas/</a>

NCAR archive: <a href="http://dss.ucar.edu/datasets/ds735.0/">http://dss.ucar.edu/datasets/ds735.0/</a>

#### **NCEP** naming convention

```
gdas1.t00z.1bamua.tm00.bufr_d
gdas1.t00z.1bamub.tm00.bufr_d
gdas1.t00z.1bhrs3.tm00.bufr_d
gdas1.t00z.1bhrs4.tm00.bufr_d
gdas1.t00z.1bmhs.tm00.bufr_d
gdas1.t00z.airsev.tm00.bufr_d
```

#### **WRF-Var naming convention**


amsua.bufr amsub.bufr hirs3.bufr hirs4.bufr mhs.bufr airs.bufr

Direct input to WRFDA, no pre-processing required.

Quality control, thinning, time and domain check, bias correction are done inside WRF-Var

Namelist switches to decide if **reading** the data or not

Use\_amsuaobs
Use\_amsubobs
Use\_hirs3obs
Use\_hirs4obs
Use\_mhsobs
Use\_airsobs
Use\_eos\_amsuaobs
Use\_ssmisobs



#### **Choose Radiative Transfer Model**

Controlled by the namelist variable: "rtm\_option"

#### **2=CRTM** (Community Radiative Transfer Model)

JCSDA (Joint Center for Satellite Data Assimilation)

ftp://ftp.emc.ncep.noaa.gov/jcsda/CRTM/

Latest released version: CRTM REL-2.1.3,

Version included in WRFDA: CRTM REL-2.1.3

CRTM code and (limited) coeffs included in WRFDA release (since V3.2.1)

#### 1=RTTOV (Radiative Transfer for TOVS)

EUMETSAT (European Organisation for the Exploitation of Meteorological Satellites)

Latest released version: RTTOV11,

Version used in WRFDA: RTTOV11

#### Channel selection and error specification

```
WRFDA/var/run/radiance info>ls -1
  total 160
               1 hclin
                       users
                               1588 Aug 22 17:01 dmsp-16-ssmis.info
  -rw-r--r--
              1 hclin
                               17790 Aug 22 17:01 eos-2-airs.info
  -rw-r--r--
                       users
  -rw-r--r--
               1 hclin
                       users
                                1033 Aug 22 17:01 eos-2-amsua.info
               1 hclin
                               1036 Aug 22 17:01 metop-2-amsua.info
                       users
  -rw-r--r--
                                391 Aug 22 17:01 metop-2-mhs.info
              1 hclin
  -rw-r--r--
                       users
  -rw-r--r-- 1 hclin users
                               1021 Aug 22 17:01 noaa-15-amsua.info
              1 hclin users
                                391 Aug 22 17:01 noaa-15-amsub.info
  -rw-r--r--
                               1277 Aug 22 17:01 noaa-15-hirs.info
  -rw-r--r 1 hclin users
  -rw-r--r--
               1 hclin
                       users
                                1021 Aug 22 17:01 noaa-16-amsua.info
               1 hclin
                                 391 Aug 22 17:01 noaa-16-amsub.info
  -rw-r--r--
                       users
               1 hclin users
                               1275 Aug 22 17:01 noaa-16-hirs.info
  -rw-r--r--
  -rw-r--r-- 1 hclin
                                391 Aug 22 17:01 noaa-17-amsub.info
                       users
               1 hclin users
                               1277 Aug 22 17:01 noaa-17-hirs.info
  -rw-r--r--
  -rw-r--r-- 1 hclin users
                               1036 Aug 22 17:01 noaa-18-amsua.info
  -rw-r--r 1 hclin
                                1286 Aug 22 17:01 noaa-18-hirs.info
                       users
               1 hclin
                                 391 Aug 22 17:01 noaa-18-mhs.info
  -rw-r--r--
                       users
metop-2-mhs.info -1: not used; 1: used
                                         error for each channel
sensor channel IR/MW use idum varch polarisation(0:vertical;1:horizontal)
                           0.2500000000E+01
   203
          1
                        0
                                             0.000000000E+00
                  -1
   203
                           0.2500000000E+01
                                             0.000000000E+00
                  -1
                        0
          2
   203
                   1
                        0
                           0.250000000E+01
                                             0.100000000E+01
   203
                           0.200000000E+01
                                             0.1000000000E+01
                   1
                        0
          5
                   1
                           0.2000000000E+01/
                                             0.000000000E+00
   203
                        0
```

WRFDA Tutorial, July 2014

21

#### Setup and run WRFDA with radiances

To run **WRFDA**, first create a working directory, for example, WRFDA/var/test, then follow the steps below: cd WRFDA/var/test (go to the working directory) In -sf WRFDA/run/LANDUSE.TBL ./LANDUSE.TBL In -sf \$DAT DIR/rc/2007010200/wrfinput d01 ./fg (link first guess file as fg) In -sf WRFDA/var/obsproc/obs\_gts\_2007-01-02\_00:00:00.3DVAR ./ob.ascii (link OBSPROC processed observation file as ob.ascii) In -sf \$DAT DIR/be/be.dat ./be.dat (link background error statistics as be.dat) In -sf WRFDA/var/da/da wrfvar.exe ./da wrfvar.exe (link executable) In -sf \$DAT DIR/2007010200/gdas1.t00z.1bamua.tm00.bufr d ./amsua.bufr In -sf ~WRFDA/var/run/radiance info ./radiance info In -sf ~WRFDA/var/run/VARBC.in. (CRTM only) > ln -sf WRFDA/var/run/crtm\_coeffs /crtm\_coeffs #(crtm\_coeffs is a directory) (RTTOV only) > ln -sf your\_path/rtcoef\_rttov10/rttov7pred51L\_/rttov\_coeffs #(rttov\_coeffs is a directory) vi namelist.input (&wrfvar4, &wrfvar14, &wrfvar21, &wrfvar22)

da wrfvar.exe >&! wrfda.log

#### Control which instruments to be assimilated and Which CRTM/RTTOV coeffs files to be loaded

```
RTMINIT NSENSOR = 14
RTMINIT PLATFORM = 1, 1, 1, 1, 9,10, 1, 1, 1, 1, 1, 10, 9, 2
RTMINIT SATID = 15,16,18,19, 2, 2,15,16,17,18, 19, 2, 2,16
RTMINIT SENSOR = 3, 3, 3, 3, 3, 4, 4, 4, 15, 15, 15, 11, 10
NOAA-15-AMSUA (1, 15,3)
NOAA-16-AMSUA
NOAA-18-AMSUA
NOAA-19-AMSUA
EOS-2-AMSUA (9, 2, 3)
METOP-2-AMSUA (10, 2, 3)
NOAA-15-AMSUB (1, 15, 4)
NOAA-16-AMSUB
NOAA-17-AMSUB
NOAA-18-MHS
               (1, 18, 15)
NOAA-19-MHS
METOP-2-MHS (10, 2, 15)
EOS-2-AIRS (9, 2, 11)
DMSP-16-SSMIS (2, 16, 10)
```

**CRTM and RTTOV share** the same "instrument triplet" convention for user's config.

This facilitates the user's config. When switch b.w. two RTMs.

## more sensors supported, from RTTOV11 Users Guide (Table 2 & 3) http://nwpsaf.eu/deliverables/rtm/docs rttov11/users guide 11 v1.3.pdf

#### ~var/da/da\_radiance/module\_radiance.f90

Instrument triplets platform\_id satellite\_id sensor\_id

platform\_id satellite\_id

Platform	RTTOV id	Sat id range	
NOAA <sup>9</sup>	1	1 to 18	
DMSP	2	8 to 16	
Meteosat	3	5 to 7	
GOES	4	8 to 12	
GMS	5	5	
FY-2	6	2 to 3	
TRMM	7	1	
ERS	8	1 to 2	
EOS	9	1 to 2	
METOP	10	1 to 3	
ENVISAT	11	1	
MSG	12	1 to 2	
FY-1	13	3	
ADEOS	14	1 to 2	
MTSAT	15	1	
CORIOLIS	16	1	

¶ Includes TIROS-N

Table 2. Platforms supported by RTTOV\_8\_7 as at 17 Nov 2005 in normal text. Platforms in italics are not yet supported by RTTOV\_8\_7 but soon will be.

#### sensor\_id

			D==0\( -	DTT01/0
Sensor	RTTOV id	Sensor	RTTOV-7	RTTOV-8
		Channel #	Channel #	Channel #
HIRS	0	1 to 19	1 to 19	1 to 19
MSU	1	1 to 4	1 to 4	1 to 4
SSU	2	1 to 3	1 to 3	1 to 3
AMSU-A	3	1 to 15	1 to 15	1 to 15
AMSU-B	4	1 to 5	1 to 5	1 to 5
AVHRR	5	3b to 5	1 to 3	1 to 3
SSMI	6	1 to 7	1 to 7	1 to 4
VTPR1	7	1 to 8	1 to 8	1 to 8
VTPR2	8	1 to 8	1 to 8	1 to 8
TMI	9	1 to 9	1 to 5	1 to 9
SSMIS	10	1 to 24*	1 to 24*	1 to 21
AIRS	11	1 to 2378	1 to 2378	1 to 2378
HSB	12	1 to 4	1 to 4	1 to 4
MODIS	13	1 to 17	1 to 17	1 to 17
ATSR	14	1 to 3	1 to 3	1 to 3
MHS	15	1 to 5	1 to 5	1 to 5
IASI	16	1 to 8461	N/A	1 to 8461
AMSR	17	1 to 14	1 to 14	1 to 7
MVIRI	20	1 to 2	1 to 2	1 to 2
SEVIRI	21	4 to 11	1 to 8	1 to 8
GOES-Imager	22	1 to 4	1 to 4	1 to 4
GOES-Sounder	23	1 to 18	1 to 18	1 to 18
GMS/MTSAT	24	1 to 4	1 to 4	1 to 4
imager				
FY2-VISSR	25	1 to 2	1 to 2	1 to 2
FY1-MVISR	26	1 to 3	1 to 3	1 to 3
CriS	27	TBD	N/A	TBD
CMISS	28	TBD	N/A	TBD
VIIRS	29	TBD	N/A	TBD
WINDSAT	30	1 to 10	N/A	1 to 5

<sup>\*</sup>channels 19-21 are not simulated accurately

Table 3. Instruments supported by RTTOV\_8\_7 as at 17 Nov 2005. Sensors in italics are not yet supported by RTTOV\_8\_7 but soon will be.

#### Radiance namelist variables

**THINNING:** Logical, TRUE will perform thinning

**THINNING\_MESH** (30): Real array with dimension RTMINIT\_NSENSOR, values in dicate thinning mesh (in KM) for different sensors.

QC\_RAD=true: Logical, control if perform quality control, always set to TRUE.

**WRITE\_IV\_RAD\_ASCII**: Logical, control if output Observation minus Background files, which are ASCII format and separated by sensors and processors.

**WRITE\_OA\_RAD\_ASCII:** Logical, control if output Observation minus Analysis file s (including also O minus B), which are ASCII format and separated by sensors and processors.

**ONLY\_SEA\_RAD:** Logical, control if only assimilating radiance over water.

USE\_CRTM\_KMATRIX: new from Version 3.1.1, much faster. Set to TRUE. USE\_RTTOV\_KMATRIX: new from version 3.3, much faster. Set to TRUE

## Radiance namelist (VarBC related)

**USE\_VARBC=true** 

freeze\_varbc=false (VarBC coeffs not change during minimization)

varbc\_factor=1. (for scaling the VarBC preconditioning)

varbc\_nbgerr=5000, (default value prior to V3.3.1 is 1 which is improper)

varbc\_nobsmin=500. (defines the minimum number of observations required for the computation of the predictor statistics during the first assimilation cycle. If there are not enough data (according to "VARBC\_NOBSMIN") on the first cycle, the next cycle will perform a coldstart again)

## Radiance namelist (new for V3.6)

```
crtm_coef_path='./crtm_coeffs'
```

```
crtm_mwwater_coef='FASTEM5.MWwater.EmisCoeff.bin'
crtm_irwater_coef='Nalli.IRwater.EmisCoeff.bin'
crtm_irland_coef='USGS.IRland.EmisCoeff.bin'
```

```
rttov_emis_atlas_ir=0,
rttov_emis_atlas_mw=0,
```

#### **Variational Bias Correction (VarBC)**

Cold start from an empty coeffs file

**VARBC.in** file is an ASCII file that controls all of what is going into the VarBC.

#### Sample VARBC.in

10000

10000

3 0 0 0 0 0 0 0 0

10000

----> Chanl id Chanl nb Pred use(-1/0/1) Param

10000

VARBC version 1.0 - Number of instruments: For the first cycle 33 Platform id Sat id Sensor id Nchanl Npredmax ----> Bias predictor statistics: Mean & Std & Nbgerr 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0 10000 10000 10000 10000 10000 10000 10000 10000 ----> Chanl id Chanl nb Pred use(-1/0/1) Param Not used any more. Now controlled by namelist "varbc\_nbgerr" Platform id Sat id Sensor id Nchanl Npredmax 1 16 4 3 8 ----> Bias predictor statistics: Mean & Std & Nbgerr 1.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 1.0 1.0 1.0 1.0 1.0 1.0 1.0

10000

10000

10000

10000

#### Sample VARBC.out (output from WRF-Var, used as VARBC.in for the next cycle)


```
VARBC version 1.0 - Number of instruments:
Platform id Sat id Sensor id Nchanl Npredmax
1 15 4 5 8
----> Bias predictor statistics: Mean & Std & Nbgerr
     1.0
            9273.1
                     8677.8
                               290.4
                                         24.0
                                                  51.7
                                                          3502.8 260484.8
     0.0
                      293.3
                                         12.3
             273.5
                               8.0
                                                  28.9
                                                          2827.2 252657.9
            10000
                      10000
   10000
                               10000
                                        10000
                                                 10000
                                                         10000
                                                                    10000
 ----> Chanl id Chanl nb Pred use(-1/0/1) Param
       1 0 0 0 0 0 0 0 0 -3.400
                                                0.000
                                                       0.000
                                        0.000
                                                              0.000
                                                                      0.000
                                                                             0.000
                                                                                     0.000
       2 0 0 0 0 0 0 0 0 -0.200
                                        0.000
                                                0.000
                                                       0.000
                                                              0.000
                                                                     0.000
                                                                             0.000
                                                                                     0.000
       3 1 1 1 1 1 1 1 1 1.213
                                       -0.062
                                                      -0.070
                                                              0.008
                                                                     -0.230
                                                0.003
                                                                            -0.111
                                                                                    -0.024
                                                       0.015 - 0.059
       4 1 1 1 1 1 1 1 1 3.056
                                        0.050
                                                0.053
                                                                      0.304
                                                                             0.241
                                                                                     0.203
       5 1 1 1 1 1 1 1 1
                                 0.869
                                        0.034
                                               -0.089
                                                       0.074
                                                              0.019
                                                                     -0.118 \quad -0.031
                                                                                     0.022
Platform id Sat id Sensor id Nchanl Npredmax
1 16 4 5 8
----> Bias predictor statistics: Mean & Std & Nbgerr
     1.0
            9280.2
                     8641.2
                               290.0
                                         24.1
                                                  52.6
                                                          3568.9 264767.4
     0.0
             209.5
                      245.9
                                 7.9
                                         11.3
                                                  28.3
                                                          2792.1
                                                                 249977.0
   10000
             10000
                      10000
                               10000
                                        10000
                                                  10000
                                                          10000
                                                                    10000
----> Chanl id Chanl nb Pred use(-1/0/1) Param
       1 0 0 0 0 0 0 0
                                 0.000
                                                       0.000
                                                              0.000
                                                                      0.000
                                                                             0.000
                                                                                    0.000
        0 0 0 0 0 0 0
                                -0.800
                                                       0.000
                                                                      0.000
                                                                                     0.000
                                        0.000
                                                0.000
                                                              0.000
                                                                             0.000
         (1 1 1 1 1 1 1 1)
                                0.372
                                       -0.028
                                                0.010
                                                       0.060
                                                              0.025
                                                                      0.117
                                                                             0.023
                                                                                    -0.042
         1 1 1 1 1 1 1 1/
                                0.968
                                        0.016
                                               -0.003
                                                      -0.041
                                                              0.045
                                                                     -0.018
                                                                            -0.030
                                                                                    -0.028
       5 1 1 1 1 1 1 1
                                -3.290
                                        0.073 - 0.093
                                                       0.096
                                                              0.018
                                                                      0.011
                                                                             0.010
                                                                                     0.004
```

Control whether'a cold-start (if 0) Or warm-start (if 1) VarBC Or turn-off (if -1) Bias correction coefficients for 8 predictors (used only for warm-start case)

#### Radiance output Post-Processing/Visualization

- ~WRFDA/var/scripts/da\_rad\_diags.ksh (included in the TOOLS bundle that can be downloaded from http://www.mmm.ucar.edu/wrf/users/wrfda/download/tools.html
  - WRFDA will output radiance inv\* or oma\* ASCII files separated for different sensors and CPUs.
  - Script converts ASCII files to one NETCDF file for each sensor (a Fortran90 program), then plot \*.nc files with a NCL script
  - NCL script can plot various graphics
    - Channel TB, Histogram, scatter plot, time series etc.
    - Can be included in the script to routinely produce graphics after WRF-Var runs
    - Users can control (by simple script parameter setup) to plot over smaller domain, only over land or sea, QCed or no-QCed observations.

#### Time series of radiance OMB/OMA for DMSP-16 SSMI/S



#### **Conclusions**

#### Radiance data assimilation are important

Major source of information over ocean and Southern Hemisphere

#### Radiance DA is not trivial

- Very easy to degrade the analysis!
- Each sensor requires a lot of attention (observation operator, bias correction, QC, observation error, cloud/rain detection, ...)
- Challenge for regional DA: lower model top, bias correction

#### • It's only the beginning...

- New generation of satellite instruments
- Future developments will increase satellite impact
  - Better representation of surface emissivity over land
  - Use of cloudy/rainy radiances
  - •

## • Get familiar with radiance DA with more practice

wrfhelp@ucar.edu