## PASTIX version 5.2 Quick Reference Guide

November 22, 2012

### Calling PaStiX with a global matrix

```
#include ''pastix.h''
 void pastix ( pastix_data_t ** pastix_data, MPI_Comm
                                                               pastix_comm,
                                              pastix_int_t * colptr,
               pastix_int_t
                                 n,
                                              pastix_float_t * avals,
               pastix_int_t
                              * row.
               pastix_int_t
                                 perm,
                                              pastix_int_t * invp,
               pastix_float_t * b,
                                              pastix_int_t
                                                               rhs.
                                              double
               pastix_int_t
                              * iparm.
                                                            * dparm );
#include ''pastix_fortran.h''
 pastix_data_ptr_t :: pastix_data
 integer
                      :: pastix_comm
 pastix_int_t
                      :: n, rhs, ia(n), ja(nnz)
 pastix_float_t
                     :: avals(nnz), b(n)
 pastix_int_t
                      :: perm(n), invp(n), iparm(64)
 real*8
                      :: dparm(64)
 call pastix_fortran ( pastix_data, pastix_comm, n, ia, ja, avals,
                       perm, invp, b, rhs, iparm, dparm)
                       Area used to store information between calls. Should be given as
 pastix_data
                       NULL for first call.
                       MPI communicator used to solve the system.
 pastix_comm
```

Matrix dimension. Number of non-zeros. nnz

Matrix in CSC format (see example below). colptr, row, avals

Permutation vector. perm Inverse permutation vector. invp

Right-hand side(s) and solution(s) as output.

Number of right-hand side(s). rhs Vector of integer parameters. iparm Vector of real parameters. dparm

In the current release, the matrix must be given in Compressed Sparse Column format in Fortran numbering (starts from 1).

### Calling PaStiX with a local matrix

```
#include ''pastix.h''
 void dpastix ( pastix_data_t ** pastix_data, MPI_Comm
                                                              pastix_comm,
               pastix_int_t
                                 n,
                                             pastix_int_t * colptr.
                                             pastix_float_t * avals,
               pastix_int_t
                              * row.
               pastix_int_t
                              * loc2glb,
               pastix_int_t
                                             pastix_int_t
                                                          * invp.
                              * perm,
               pastix_float_t * b,
                                             pastix_int_t
                                                              rhs,
                                             double
               pastix_int_t
                              * iparm,
                                                           * dparm );
```

#include ''pastix\_fortran.h''

pastix\_data\_ptr\_t :: pastix\_data integer :: pastix\_comm

pastix\_int\_t :: n, rhs, ia(n+1), ja(nnz)

pastix\_float\_t :: avals(nnz), b(n)

pastix\_int\_t :: loc2glb(n), perm(n), invp(n), iparm(64)

real\*8 :: dparm(64)

call dpastix\_fortran ( pastix\_data, pastix\_comm, n, ia, ja, avals, loc2glob perm, invp, b, rhs, iparm, dparm )

Additional parameter:

Local to global column number correspondance, all columns must loc2glb be distributed once and loc2glob must be ordered increasingly.

The distribution of the CSC matrix is given through the loc2glb vector (see example below).

```
dCSC matrix example:
                                                 On processor one:
                                                                  \{1, 3, 5, 6\}
                                                   colptr
                                                                  \{1, 3, 3, 4, 5\}
                                                   row
                                                   avals
                                                             = \{1, 2, 5, 6, 8\}
                                                   loc2glb
                                                                \{1, 3, 5\}
                                                 On processor two:
                                                   colptr
                                                                  \{1, 3, 4\}
       0
                                                   row
                                                             = \{2, 4, 4\}
       4
                7
                      0
                                                   avals
                                                             = \{3, 4, 7\}
                                                   loc2glb =
                                                                \{2,4\}
```

Integer parameters and outputs.							
Keyword	Index	Definition	Default	IN/OUT			
IPARM_MODIFY_PARAMETER	0	Indicate if parameters have been set by user	API_YES	IN			
IPARM_START_TASK	1	Indicate the first step to execute (see PASTIX steps)	API_TASK_ORDERING	IN			
IPARM_END_TASK	2	Indicate the last step to execute (see Pastix steps)	API_TASK_CLEAN	IN			
IPARM_VERBOSE	3	Verbose mode (see Verbose modes)	API_VERBOSE_NO	IN			
IPARM_DOF_NBR	4	Degree of freedom per node	1	IN			
IPARM_ITERMAX	5	Maximum iteration number for refinement	250	IN			
IPARM_MATRIX_VERIFICATION	6	Check the input matrix	API_NO	IN			
IPARM_ONLY_RAFF	8	Refinement only	API_NO	IN			
IPARM_CSCD_CORRECT	9	Indicate if the cscd has been redistributed after blend	API_NO	IN			
IPARM_NBITER	10	Number of iterations performed in refinement	-	OUT			
IPARM_TRACEFMT	11	Trace format (see Trace modes)	API_TRACE_PICL	IN			
IPARM_GRAPHDIST	12	Specify if the given graph is distributed or not	API_YES	IN			
IPARM_AMALGAMATION_LEVEL	13	Amalgamation level	5	IN			
IPARM_ORDERING	14	Choose ordering	API_ORDER_SCOTCH	IN			
IPARM_DEFAULT_ORDERING	15	Use default ordering parameters with Scotch or Metis	API_YES	IN			
IPARM_ORDERING_SWITCH_LEVEL	16	Ordering switch level (see Scotch User's Guide)	120	IN			
IPARM_ORDERING_CMIN	17	Ordering cmin parameter (see Scotch User's Guide)	0	IN			
IPARM_ORDERING_CMAX	18	Ordering cmax parameter (see Scotch User's Guide)	100000	IN			
IPARM_ORDERING_FRAT	19	Ordering frat parameter (see Scotch User's Guide)	8	IN			
IPARM_STATIC_PIVOTING	20	Static pivoting	-	OUT			
IPARM_METIS_PFACTOR	21	METIS pfactor	0	IN			
IPARM_NNZEROS	22	Number of nonzero entries in the factorized matrix	-	OUT			
IPARM_ALLOCATED_TERMS	23	Maximum memory allocated for matrix terms	_	OUT			
IPARM_BASEVAL	24	Baseval used for the matrix	0	IN			
IPARM_MIN_BLOCKSIZE	25	Minimum block size	60	IN			
IPARM_MAX_BLOCKSIZE	26	Maximum block size	120	IN			
IPARM_SCHUR	27	Schur mode	API_NO	IN			
IPARM_ISOLATE_ZEROS	28	Isolate null diagonal terms at the end of the matrix	API_NO	IN			
IPARM_RHSD_CHECK	29	Set to API_NO to avoid RHS redistribution	API_YES	IN			
IPARM_FACTORIZATION	30	Factorization mode (see Factorization modes)	API_FACT_LDLT	IN			
IPARM_NNZEROS_BLOCK_LOCAL	31	Number of nonzero entries in the local block factorized matrix	_	OUT			
IPARM_CPU_BY_NODE	32	Number of CPUs per SMP node	0	IN			
IPARM_BINDTHRD	33	Thread binding mode (see Thread binding modes)	API_BIND_AUTO	IN			
IPARM_THREAD_NBR	34	Number of threads per MPI process	1	IN			
IPARM_LEVEL_OF_FILL	36	Level of fill for incomplete factorization	1	IN			
IPARM_IO_STRATEGY	37	IO strategy (see Checkpoints modes)	API_IO_NO	IN			
IPARM_RHS_MAKING	38	Right-hand-side making (see Right-hand-side modes)	API_RHS_B	IN			
IPARM_REFINEMENT	39	Refinement type (see Refinement modes)	API_RAF_GMRES	IN			
IPARM_SYM	40	Symmetric matrix mode (see Symmetric modes)	API_SYM_YES	IN			
IPARM_INCOMPLETE	41	Incomplete factorization	API_NO	IN			
IPARM_ABS	42	ABS level (Automatic Blocksize Splitting)	1	IN			
IPARM_ESP	42	ESP (Enhanced Sparse Parallelism)	API_NO	IN			
IPARM_GMRES_IM	43	GMRES restart parameter	25	IN			
	1	Free user CSC					
IPARM_FREE_CSCUSER	45		API_CSC_PRESERVE	IN			
IPARM_FREE_CSCPASTIX	46	Free internal CSC (Use only without call to Refin. step)	API_CSC_PRESERVE	IN			
IPARM_OOC_LIMIT	47	Out of core memory limit (Mo)	2000	IN			
IPARM_THREAD_COMM_MODE	51	Threaded communication mode (see Communication modes)	API_THREAD_MULT	IN on next page .			

continued from previous page							
Keyword	Index	Definition	Default	IN/OUT			
IPARM_NB_THREAD_COMM	52	Number of thread(s) for communication	1	IN			
IPARM_INERTIA	54	Return the inertia (symmetric matrix without pivoting)	-	OUT			
IPARM_ESP_NBTASKS	55	Return the number of tasks generated by ESP	-	OUT			
IPARM_ESP_THRESHOLD	56	Minimal block sizee to switch in ESP mode (128 * 128)	16384	IN			
IPARM_DOF_COST	57	Degree of freedom for cost computation (If different from IPARM_DOF_NBR)	0	IN			
IPARM_MURGE_REFINEMENT	58	Enable refinement in MURGE	API_YES	IN			
IPARM_STARPU	59	Use StarPU runtime	API_NO	IN			
IPARM_AUTOSPLIT_COMM	60	Automatically split communicator to have one MPI task by node	API_NO	IN			
IPARM_PID	62	Pid of the first process (used for naming the log directory)	-1	OUT			
IPARM_ERROR_NUMBER	63	Return value	-	OUT			
IPARM_CUDA_NBR	64	Number of cuda devices	0	IN			
IPARM_TRANSPOSE_SOLVE	65	Use transposed matrix during solve	API_NO	IN			

Floating point parameters and outputs.							
Keyword	Index	Definition	Default	IN/OUT			
DPARM_FILL_IN	1	Fill-in	-	OUT			
DPARM_MEM_MAX	2	Maximum memory (-DMEMORY_USAGE)	-	OUT			
DPARM_EPSILON_REFINEMENT	5	Epsilon for refinement	$1e^{-12}$	IN			
DPARM_RELATIVE_ERROR	6	Relative backward error	-	OUT			
DPARM_EPSILON_MAGN_CTRL	10	Epsilon for magnitude control	$1e^{-31}$	IN			
DPARM_ANALYZE_TIME	18	Time for Analyse step (wallclock)	-	OUT			
DPARM_PRED_FACT_TIME	19	Predicted factorization time	-	OUT			
DPARM_FACT_TIME	20	Time for Numerical Factorization step (wallclock)	-	OUT			
DPARM_SOLV_TIME	21	Time for Solve step (wallclock)	-	OUT			
DPARM_FACT_FLOPS	22	Numerical Factorization flops (rate!)	-	OUT			
DPARM_SOLV_FLOPS	23	Solve flops (rate!)	-	OUT			
DPARM_RAFF_TIME	24	Time for Refinement step (wallclock)	-	OUT			

## PaStiX API : Macros

PASTIX step modes (index IPARM_START_TASK and IPARM_END_TASK)					
API_TASK_INIT	0	Set default parameters			
API_TASK_ORDERING	1	Ordering			
API_TASK_SYMBFACT	2	Symbolic factorization			
API_TASK_ANALYSE	3	Tasks mapping and scheduling			
API_TASK_NUMFACT	4	Numerical factorization			
API_TASK_SOLVE	5	Numerical solve			
API_TASK_REFINE	6	Numerical refinement			
API_TASK_CLEAN	7	Clean			

Boolean modes (All boolean except IPARM_SYM)				
API_NO	0	No		
API_YES	1	Yes		

Symmetric modes (index IPARM_SYM)				
API_SYM_YES	0	Symmetric matrix		
API_SYM_NO	1	Nonsymmetric matrix		
API_SYM_HER	2	Hermitian		

Factorization modes (index IPARM_FACTORISATION)				
API_FACT_LLT	0	$LL^t$ Factorization		
API_FACT_LDLT	1	$LDL^t$ Factorization		
API_FACT_LU	2	LU Factorization		
API_FACT_LDLH	3	$LDL^h$ hermitian factorization		

Verbose modes (index IPARM_VERBOSE)			
API_VERBOSE_NOT	0	Silent mode, no messages	
API_VERBOSE_NO	1	Some messages	
API_VERBOSE_YES	2	Many messages	
API_VERBOSE_CHATTERBOX	3	Like a gossip	
API_VERBOSE_UNBEARABLE	4	Really talking too much	

Check-points modes (index IPARM_IO)			
API_IO_NO	0	No output or input	
API_IO_LOAD	1	Load ordering during ordering step and symbol ma-	
		trix instead of symbolic factorisation.	
API_IO_SAVE	2	Save ordering during ordering step and symbol ma-	
		trix instead of symbolic factorisation.	
API_IO_LOAD_GRAPH	4	Load graph during ordering step.	
API_IO_SAVE_GRAPH	8	Save graph during ordering step.	
API_IO_LOAD_CSC	16	Load CSC(d) during ordering step.	
API_IO_SAVE_CSC	32	Save CSC(d) during ordering step.	

Right-hand-side modes (index IPARM_RHS)				
API_RHS_B	0	User's right hand side		
API_RHS_1	1	$\forall i, X_i = 1$		
API_RHS_I	2	$\forall i, X_i = i$		
API_RHS_O	3			

Refinement modes (index IPARM_REFINEMENT)				
API_RAF_GMRES	0	GMRES		
API_RAF_PIVOT	1	Iterative Refinement (only for $LU$ factorization)		
API_RAF_GRAD	1	Conjugate Gradient ( $LL^t$ or $LDL^t$ factorization)		

Comunication modes (index IPARM_NB_THREAD_COMM)				
Comunication modes (mu	EX IP			
API_THREAD_MULTIPLE	1	All threads communicate.		
API_THREAD_FUNNELED	2	One thread perform all the MPI Calls.		
API_THREAD_COMM_ONE	4	One dedicated communication thread will receive		
		messages.		
API_THREAD_COMM_DEFINED	8	Then number of threads receiving the messages is		
		given by IPARM_NB_THREAD_COMM.		
API_THREAD_COMM_NBPROC	16	One communication thread per computation thread		
		will receive messages.		

Trace modes (index IPARM_TRACEFMT)		
API_TRACE_PICL	0	Use PICL trace format
API_TRACE_PAJE	1	Use Paje trace format
API_TRACE_HUMREAD	2	Use human-readable text trace format
API_TRACE_UNFORMATED	3	Unformated trace format

CSC Management modes	(inde	x IPARM_FREE_CSCUSER and IPARM_FREE_CSCPASTIX)
API_CSC_PRESERVE	0	Do not free the CSC

Ordering modes (index IPARM_ORDERING)		
API_ORDER_SCOTCH	0	Use Scotch ordering

CSC Management modes	(inde:	x IPARM_FREE_CSCUSER and IPARM_FREE_CSCPASTIX)
API_CSC_FREE	1	Free the CSC when no longer needed

Ordering modes (index IPARM_ORDERING)		
API_ORDER_METIS	1	Use Metis ordering
API_ORDER_PERSONAL	2	Apply user's permutation
API_ORDER_LOAD	3	Load ordering from disk

Thread-binding modes (index IPARM_BINTHRD)			
API_BIND_NO 0 Do not bind thread			
API_BIND_AUTO	1	Default binding	
API_BIND_TAB	2	Use vector given by pastix_setBind	

Ordering modes (index IPARM_ORDERING)		
API_REALSINGLE	0	Use Scotch ordering
API_REALDOUBLE	1	Use Metis ordering
API_COMPLEXSINGLE	2	Apply user's permutation
API_COMPLEXDOUBLE	3	Load ordering from disk

#### PaStiX API: Functions

#### Getting local node information

These functions are called when PASTIX is used with a distributed matrix.

```
{\bf pastix\_int\_t} \ {\bf pastix\_getLocalNodeNbr} \ ( \ {\bf pastix\_data\_t} \ ** \ {\bf pastix\_data} \ );
```

pastix\_data Area used to store information between calls.

Return the node number in the new distribution computed by the analyze step (Analyze step must have already been executed).

pastix\_data Area used to store information between calls. nodelst Array to receive the list of local nodes.

Fill nodelst with the list of local nodes

(nodelst must be at least nodenbr\*sizeof(pastix\_int\_t), where nodenbr is obtained from pastix\_getLocalNodeNbr).

#### Binding threads

pastix\_data Area used to store information between calls.
thrdnbr Number of threads (== length of bindtab).
bindtab List of processors for threads to be binded on.

Assign threads to processors.

#### Checking the CSC

void pastix_checkMatrix ( MPI_Comm	n pastix_comm,	int	verb,
int	flagsym,	int	flagcor,
$\operatorname{pastix\_int\_t}$	n,	pastix_int_t *	* colptr,
$\operatorname{pastix\_int\_t}$	** row,	pastix_float_t *	* avals,
pastix int t	** loc2glob ):	int	dof

pastix\_comm PASTIX MPI communicator.
verb Verbose mode (see Verbose modes).

flagsym Indicates if the matrix is symmetric (see Symmetric modes).

flagcor Indicates if the matrix can be reallocated (see Boolean modes).

n Matrix dimension.
colptr, row, avals Matrix in CSC format.

loc2glb Local to global column number correspondance.

Check and correct the user matrix in CSC format.

#### Checking the symmetry of a CSCD

Check the graph symmetry.

#### Correcting the symmetry of a CSCD

```
int cscd_symgraph ( pastix_int_t
                                           pastix_int_t * ia,
                   pastix_int_t * ja,
                                          pastix_float_t * a,
                   pastix_int_t * newn, pastix_int_t ** newia,
                   pastix_int_t ** newja, pastix_float_t ** newa,
                   pastix_int_t * 12g
                                          MPI_Comm
                                                            comm,
                      Number of local columns.
n
                      Starting index of each column in ja and a.
ia
                      Row of each element.
ja
                      Value of each element.
a
                      New number of local columns.
newn
                      Starting index of each columns in newja and newa.
newia
                      Row of each element.
newja
                      Values of each element.
newa
                      Global number of each local column.
12g
                      MPI communicator.
comm
```

Symmetrize the graph.

#### Adding a CSCD into an other one

```
int cscd_addlocal ( pastix_int_t
                                               n,
                                                      pastix_int_t * ia.
                   pastix_int_t
                                             * ja,
                                                      pastix_float_t *
                   pastix_int_t
                                                      pastix_int_t
                                               12g,
                                                                       addn,
                   pastix_int_t
                                               addia, pastix_int_t
                                                                      addja.
                   pastix_float_t
                                                     pastix_int_t
                                                                    * addl2g.
                   pastix_int_t
                                                     pastix_int_t ** newia,
                   pastix_int_t
                                             ** newja, pastix_float_t ** newa
                   CSCD_OPERATIONS_t
                                               OP ):
```

```
Size of first CSCD matrix (same as newn).
                       Column starting positions in first CSCD matrix.
ia
                       Rows in first CSCD matrix.
ja
                       Values in first CSCD matrix (can be NULL).
                       Global column number map for first CSCD matrix.
12g
addn
                       Size of the second CSCD matrix (to be added to base).
addia
                       Column starting positions in second CSCD matrix.
                       Rows in second CSCD matrix.
addja
                       Values in second CSCD (can be NULL \rightarrow add \emptyset).
adda
                       Global column number map for second CSCD matrix.
add12g
                       Size of output CSCD matrix (same as n).
newn
                       Column starting positions in output CSCD matrix.
newia
                       Rows in output CSCD matrix.
newja
                       Values in outpur CSCD matrix.
newa
malloc_flag
                       Flag: Function call is internal to PASTIX.
OΡ
                       Specifies treatment of overlapping CSCD elements.
```

Adds CSCD matrix adda to a, producing newa (allocated in the function).

The operation OP can be: CSCD\_ADD, CSCD\_KEEP, CSCD\_MAX, CSCD\_MIN, and CSCD\_OVW (overwrite).

#### Building a CSCD from a CSC

```
void csc_dispatch ( pastix_int_t
                                    gN.
                                                  pastix_int_t * gcolptr,
                   pastix_int_t
                                                  pastix_float_t *
                                                                   gavals,
                                    grow,
                   pastix_float_t *
                                                  pastix_int_t * gperm,
                                    grhs,
                   pastix_int_t
                                    ginvp,
                   pastix_int_t * 1N,
                                                  pastix_int_t ** lcolptr,
                   pastix_int_t ** lrow,
                                                  pastix_float_t ** lavals,
                   pastix_float_t ** 1rhs,
                                                  pastix_int_t ** lperm,
                   pastix_int_t ** loc2glob.
                                                  int
                                                                   dispatch,
                   MPI_Comm
                                    pastix_comm );
```

```
Global CSC matrix number of columns.
gN
gcolptr, grows,
                       Global CSC matrix
gavals
gperm
                       Permutation table for global CSC matrix.
ginvp
                       Inverse permutation table for global CSC matrix.
lN
                       Local number of columns (output).
lcolptr, lrows,
                       Local CSCD matrix (output).
lavals
                       Local part of the right hand side (output).
lrhs
                       Local part of the permutation table (output).
lperm
                       Global numbers of local columns (before permutation).
loc2glob
                       Dispatching mode:
dispatch
                         CSC_DISP_SIMPLE Cut in n_{proc} parts of consecutive columns
                         CSC_DISP_CYCLIC Use a cyclic distribution.
                       PaStiX MPI communicator.
pastix_comm
```

n,

Distribute a CSC into a CSCD.

int cscd\_redispatch ( pastix\_int\_t

### Redistributing a CSCd

```
pastix_int_t
                                      ja,
                                             pastix_float_t * a,
                                   *
                     pastix_float_t * rhs,
                                             pastix_int_t * 12g
                     pastix_int_t
                                       dn,
                                             pastix_int_t ** dia,
                     pastix_int_t
                                   ** dja,
                                             pastix_float_t ** da,
                     pastix_float_t ** drhs, pastix_int_t * dl2g,
                     MPI_Comm
                                       comm);
                      Number of local columns
n
                      First cscd starting index of each column in ja and a
ia
                      Row of each element in first CSCD
jа
                      Value of each CSCD in first CSCD (can be NULL)
a
                      Right-hand-side member corresponding to the first CSCD (can be
rhs
                      NULL)
12g
                      Local to global column numbers for first CSCD
dn
                      Number of local columns
                      New CSCD starting index of each column in ja and a
dia
                      Row of each element in new CSCD
dja
                      Value of each CSCD in new CSCD
da
                      Right-hand-side member corresponding to the new CSCD
rhs
                      Local to global column numbers for new CSCD
dl2g
                      MPI communicator
comm
```

pastix\_int\_t \* ia,

Redistribute the first cscd, distributed with 12g local to global array, into a new one using dl2g as local to global array.

### PaStiX API: Murge Interface

#### Description

Murge is a common interface definition to multiple solver. It has been initiated by HIPS and PaStiX solvers developpers in january 2009.

A documentation about this new interface can be found at http://murge.gforge.inria.fr/.

Few function were added specificaly to PaStiX implementation of murge.

#### PaStiX specific implementation: Analyze step

INTS MURGE\_Analyze ( INTS id );

id Solver instance identification number.

Perform matrix analyze:

- Compute a new ordering of the unknows
- Compute the symbolic factorisation of the matrix
- Distribute column blocks and computation on processors

This function is not needed to use Murge interface, it only forces analyze step when user wants.

If this function is not used, analyze step will be performed when getting new distribution from MURGE, or filling the matrix.

#### PaStiX specific implementation: Factorization step

INTS MURGE\_Factorize ( INTS id);

Solver instance identification number.

Perform matrix factorization.

id

This function is not needed to use Murge interface, it only forces factorization when user wants.

If this function is not used, factorization will be performed with solve, when getting solution from MURGE.

#### PaStiX specific implementation: Assembly sequences

 $\begin{tabular}{ll} INTS & MURGE\_AssemblySetSequence (INTS & id , & INTL & coefnbr, \\ & INTS * ROWs, & INTS * COLs, \\ & INTS & op, & INTS & op2, \\ & INTS & mode, & INTS & nodes, \\ & INTS * id\_seq); \end{tabular}$ 

id Solver instance identification number.

coefnbr Number of local entries in the sequence.

ROWs List of rows of the sequence.
COLs List of columns of the sequence.

op Operation to perform for coefficient which appear several tim (see

MURGE\_ASSEMBLY\_OP).

op2 Operation to perform when a coefficient is set by two different pro-

cessors (see MURGE\_ASSEMBLY\_OP).

mode Indicates if user ensure he will respect solvers distribution (see

MURGE\_ASSEMBLY\_MODE).

nodes Indicate if entries are given one by one or by node:

0 : entries are entered value by value,1 : entries are entries node by node.

id\_seq Sequence ID.

Create a sequence of entries to build a matrix and store it for being reused.

id Solver instance identification number.

id\_seq Sequence ID.

values Values to insert in the matrix.

Assembly the matrix using a stored sequence.

INTS MURGE\_AssemblyDeleteSequence ( INTS id , INTS id\_seq);

id Solver instance identification number.

id\_seq Sequence ID.

Destroy an assembly sequence.

## How-to compile PASTIX

### Requirements

The PASTIX team recommends that you get the SCOTCH (http://gforge.inria.fr/projects/scotch/) and compile it.

Then go into PASTIX directory. Select the config file corresponding to your machine in \${PASTIX\_DIR}/config/ and copy it to \${PASTIX\_DIR}/config.in.

Now edit this file, select the options you want, and set the correct path for \${SCOTCH\_HOME}. If you want to use METIS, you also have to compile it and edit the path in config.in.

### Compilation

Makefile tags (from the root directory)			
make help	print this help		
make all	build PaStiX library		
make debug	build PaStiX library in debug mode		
make drivers	build matrix drivers library		
make debug drivers	build matrix drivers library in debug mode		
make examples	build examples (will run 'make all' and 'drivers' if required)		
make murge	build Murge examples		
make python	Build python wrapper and run an example		
make clean	remove all binaries and objects directories		
make cleanall	remove all binaries, objects and dependencies directories		

### Compilation options (config.in)

General options	
-DDISTRIBUTED	Enable distributed mode dpastix (PT-Scotch required)
-DFORCE_LONG	Use long integers
-DFORCE_DOUBLE	Use double floating coefficients
-DFORCE_COMPLEX	Use complex coefficients
-DFORCE_NOMPI	Compile without MPI support
-DFORCE_NOSMP	Compile without Thread support

	Preprocessing options	
ĺ	-DMETIS	Use Metis ordering library (needs -L\${METIS_HOME} -lmetis)
	-DWITH_SCOTCH	Activate Scotch ordering library

Solver options - $See \partix_{HOME/sopalin/src/sopalin_define.h}$			
-DNUMA_ALLOC	-DNUMA_ALLOC Allocate the coefficient vector locally on each thread.		
-DNO_MPI_TYPE	Copy into communication buffers to avoid using MPI types.		
-DTEST_IRECV Use nonblocking receives			
-DTHREAD_COMM	Receive on dedicated threads (persistent communications).		
-DPASTIX_FUNNELED	Use main thread for all communications.		

Statistics and Debug options - See \$PASTIX_HOME/sopalin/src/sopalin_define.h		
-DMEMORY_USAGE Show memory allocations (may slow down execution)		
-DSTATS_SOPALIN	Show parallelization memory overhead	
-DVERIF_MPI	Check MPI Communications for success	
-DFLAG_ASSERT	Adds some checks during factorization	

# Checkpoints in PaStiX

You can save ordering and solver structures on disk to start directly from step 3 (Tasks Mapping and Scheduling) when launching PASTIX again.

Set iparm[IPARM\_IO\_STRATEGY] to API\_IO\_SAVE and call step 1 (Ordering) and 2 (Symbolic Factorization). This will create two files, ordergen and symbolgen in the working directory. Copy (or move, or link) ordergen and symbolgen to ordername and symbolname.

Set iparm[IPARM\_IO\_STRATEGY] to API\_IO\_LOAD and then call PASTIX again from step 3.

## Out-Of-Core in PASTIX

An out-of-core version of  ${\sf PASTIX}$  is under development.

You will then have to set iparm[IPARM\_OOC\_LIMIT] to fix the memory limit size.

OOC compilation options	
-D00C	Simple OOC without contribution buffer management
-DOOC_FTGT	OOC with contribution buffer management
-DOOC_CLOCK	Compute time spent waiting for data to be loaded

## Dynamic Scheduling in PASTIX

Solver scheduling strategy	duling strategy - Static scheduling used by default	
-DPASTIX_DYNSCHED	Dynamic scheduling	

## Using StarPU in PASTIX

Using StarPU in PASTIX	
-DWITH_STARPU	Enable StarPU, needs IPARM_STARPU to be set to API_YES
-DFORCE_NO_CUDA	Disable CUDA kernels (only $LL^t$ and $LU$ GEMM provided)

## Splitting communicators in PASTIX

One can run PASTIX on a communicator and get sequential and MPI+Threads parts runned on one MPI task per node and one thread by processor, MPI only parts runned on the whole communicator using IPARM\_AUTOSPLIT\_COMM.

	Options linked to IPARM_A	sions linked to IPARM_AUTOSPLIT_COMM		
-DWITH_SEM_BARRIER Semaphore barrier on idle MPI entity (less CPU consuming				

## Multiple Arithmetic in PASTIX

default	simple	double	simple complex	double complex
pastix	$s_pastix$	d_pastix	c_pastix	$z_{\mathtt{pastix}}$
dpastix	$s_{-}dpastix$	$d_{-}dpastix$	$c\_dpastix$	$z_{-}dpastix$
<function></function>	s_ <function></function>	d_ <function></function>	c_ <function></function>	$z_{-}$ function>