Module Interface Specification for RSSC

Xingzhi Liu

November 21, 2020

1 Revision History

Date	Version	Notes
Nov. 19, 2020	1.0	Initial Release

2 Symbols, Abbreviations and Acronyms

See SRS Documentation at https://github.com/XingzhiMac/CAS741-Proj/

Contents

1	Rev	vision History				
2	Symbols, Abbreviations and Acronyms					
3	Introduction					
4	Not	cation	-			
5	Mo	dule Decomposition	-			
6	MIS	S of Control Module				
	6.1	Module				
	6.2	Uses				
	6.3	Syntax				
		6.3.1 Exported Constants				
		6.3.2 Exported Access Programs				
	6.4	Semantics				
		6.4.1 State Variables				
		6.4.2 Access Routine Semantics				
7	MIS	S of Input Parameters Module	Į			
	7.1	Module				
	7.2	Uses				
	7.3	Syntax				
		7.3.1 Exported Constants				
		7.3.2 Exported Access Programs				
	7.4	Semantics				
		7.4.1 State Variables				
		7.4.2 Environment Variables				
		7.4.3 Assumptions				
		7.4.4 Access Routine Semantics				
		7.4.5 Local Functions				
8	MIS	S of Point Module	9			
	8.1	Module				
	8.2	Uses				
	8.3	Syntax	9			
		8.3.1 Exported Constants	9			
		8.3.2 Exported Access Programs				
	8.4	Semantics				
	J	8.4.1 State Variables				
		8.4.2 Environment Variables				

		8.4.3	Assumptions			 		 										9
		8.4.4	Access Routine Semantics			 		 										9
		8.4.5	Local Functions			 		 									•	10
9	MIS	of Wa	all Module															11
	9.1		le			 		 										11
	9.2																	11
	9.3		· · · · · · · · · · · · · · · · · · ·															11
	0.0	9.3.1	Exported Constants															11
		9.3.2	Exported Constants Exported Access Program															11
	9.4		atics															11
	J.T	9.4.1	State Variables															11
		9.4.2	Environment Variables															12
		9.4.3	Assumptions															12
		9.4.4	Access Routine Semantics															12
		9.4.4	Local Functions															14
		9.4.0	Local Pulicuons		•	 • •	•	 	•	• •	•	• •	•	•	 •	•	•	14
10	MIS	of Flo	oor Map Module															15
	10.1	Modul	e			 		 										15
	10.2	Uses				 		 										15
	10.3	Syntax	<u> </u>			 		 										15
		10.3.1	Exported Constants			 		 										15
		10.3.2	Exported Access Program	s.		 		 										15
	10.4	Seman	atics			 		 										15
		10.4.1	State Variables			 		 										15
		10.4.2	Environment Variables .			 		 										15
		10.4.3	Assumptions			 		 										15
		10.4.4	Access Routine Semantics			 		 										15
		10.4.5	Local Functions			 		 									•	16
11	л л т с	e of To	wation Finder															17
11			uation Finder															17
			e															17
																		17
	11.5		Exported Constants															17 17
			Exported Constants															
	11 /		Exported Access Program															17
	11.4		tics															17
			State Variables															17
			Environment Variables .															17
			Assumptions															17
			Access Routine Semantics															17
		11.4.5	Local Functions			 		 										18

12.1 Module 19 12.2 Uses 19 12.3 Syntax 19 12.3.1 Exported Constants 19 12.3.2 Exported Access Programs 19 12.4 Semantics 19 12.4.1 State Variables 19 12.4.2 Environment Variables 19 12.4.3 Assumptions 19 12.4.4 Access Routine Semantics 20 12.4.5 Local Functions 20 13 MIS of Intersection Module 21 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23 14.3 Syntax 23
12.3 Syntax 19 12.3.1 Exported Constants 19 12.3.2 Exported Access Programs 19 12.4 Semantics 19 12.4.1 State Variables 19 12.4.2 Environment Variables 19 12.4.3 Assumptions 19 12.4.4 Access Routine Semantics 20 12.4.5 Local Functions 20 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
12.3.1 Exported Constants 19 12.3.2 Exported Access Programs 19 12.4 Semantics 19 12.4.1 State Variables 19 12.4.2 Environment Variables 19 12.4.3 Assumptions 19 12.4.4 Access Routine Semantics 20 12.4.5 Local Functions 20 13 MIS of Intersection Module 21 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
12.3.2 Exported Access Programs 19 12.4 Semantics 19 12.4.1 State Variables 19 12.4.2 Environment Variables 19 12.4.3 Assumptions 19 12.4.4 Access Routine Semantics 20 12.4.5 Local Functions 20 13 MIS of Intersection Module 21 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4.2 Semantics 21 13.4.3 Semantics 21 13.4.4 State Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
12.4 Semantics 19 12.4.1 State Variables 19 12.4.2 Environment Variables 19 12.4.3 Assumptions 19 12.4.4 Access Routine Semantics 20 12.4.5 Local Functions 20 13 MIS of Intersection Module 21 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4.2 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
12.4.1 State Variables 19 12.4.2 Environment Variables 19 12.4.3 Assumptions 19 12.4.4 Access Routine Semantics 20 12.4.5 Local Functions 20 13 MIS of Intersection Module 21 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
12.4.2 Environment Variables 19 12.4.3 Assumptions 19 12.4.4 Access Routine Semantics 20 12.4.5 Local Functions 20 13 MIS of Intersection Module 21 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
12.4.3 Assumptions 19 12.4.4 Access Routine Semantics 20 12.4.5 Local Functions 20 13 MIS of Intersection Module 21 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
12.4.4 Access Routine Semantics 20 12.4.5 Local Functions 20 13 MIS of Intersection Module 21 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
12.4.5 Local Functions 20 13 MIS of Intersection Module 21 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13 MIS of Intersection Module 21 13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.1 Module 21 13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.2 Uses 21 13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.3 Syntax 21 13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.3.1 Exported Constants 21 13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.3.2 Exported Access Programs 21 13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.4 Semantics 21 13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.4.1 State Variables 21 13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.4.2 Environment Variables 21 13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.4.3 Assumptions 21 13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.4.4 Access Routine Semantics 21 13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
13.4.5 Local Functions 22 14 MIS of Linear Path Loss Module 23 14.1 Module 23 14.2 Uses 23
14 MIS of Linear Path Loss Module 23 14.1 Module 14.2 Uses
14.1 Module 23 14.2 Uses 23
14.1 Module 23 14.2 Uses 23
14.2 Uses
14.3 Symax
14.3.1 Exported Constants
14.3.1 Exported Constants 23 14.3.2 Exported Access Programs 23
14.4 Semantics
14.4.1 State Variables
14.4.2 Environment variables
14.4.4 Access Routine Semantics
14.4.4 Access Routine Semantics
14.4.0 Local runchons
15 MIS of Line-Of-Sight Signal Module 25
15.1 Module
15.2 Uses
15.3 Syntax

	15.3.1 Exported Constants	25
	15.3.2 Exported Access Programs	25
15.4	Semantics	25
	15.4.1 State Variables	25
	15.4.2 Environment Variables	25
	15.4.3 Assumptions	25
	15.4.4 Access Routine Semantics	25
	15.4.5 Local Functions	26
16 MI	of Specular Reflection Module	27
	Module	27
	Uses	27
	Syntax	27
	16.3.1 Exported Constants	27
	16.3.2 Exported Access Programs	27
16.4	Semantics	27
201	16.4.1 State Variables	27
	16.4.2 Environment Variables	27
	16.4.3 Assumptions	27
	16.4.4 Access Routine Semantics	27
	16.4.5 Local Functions	28
	10.1.6 Bood Functions	20
17 MI	of First-Order Reflection Signal Module	2 9
	S of First-Order Reflection Signal Module Module	29 29
17.1		_
17.1 17.2	Module	29
17.1 17.2	Module	29 29
17.1 17.2	Module	29 29 29
17.5 17.5 17.5	Module	29 29 29 29
17.5 17.5 17.5	Module	29 29 29 29 29
17.5 17.5 17.5	Module	29 29 29 29 29 29
17.5 17.5 17.5	Module	29 29 29 29 29 29 29
17.5 17.5 17.5	Module	29 29 29 29 29 29 29 29
17.5 17.5 17.5	Module	29 29 29 29 29 29 29 29
17.5 17.5 17.4	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions	29 29 29 29 29 29 29 29 30 30
17.1 17.1 17.2 17.4	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions For Received Signal Strength Module	29 29 29 29 29 29 29 29 30 30 31
17.5 17.5 17.4 18.MI 18.3	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions 8 of Received Signal Strength Module Module	29 29 29 29 29 29 29 29 30 30 31
17.1 17.2 17.4 18.1 18.1 18.2	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions S of Received Signal Strength Module Module Uses	29 29 29 29 29 29 29 29 30 30 31 31
17.1 17.2 17.4 18.1 18.1 18.2	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions Sof Received Signal Strength Module Module Uses Syntax	29 29 29 29 29 29 29 29 30 30 31 31 31
17.1 17.2 17.4 18.1 18.1 18.2	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions 6 of Received Signal Strength Module Module Uses Syntax 18.3.1 Exported Constants	29 29 29 29 29 29 29 29 30 30 31 31 31 31
17.1 17.2 17.2 17.4 18.1 18.2 18.3	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions 6 of Received Signal Strength Module Module Uses Syntax 18.3.1 Exported Constants 18.3.2 Exported Access Programs	29 29 29 29 29 29 29 29 30 30 31 31 31 31 31
17.1 17.2 17.2 17.4 18.1 18.2 18.3	Module Uses Syntax 17.3.1 Exported Constants 17.3.2 Exported Access Programs Semantics 17.4.1 State Variables 17.4.2 Environment Variables 17.4.3 Assumptions 17.4.4 Access Routine Semantics 17.4.5 Local Functions 6 of Received Signal Strength Module Module Uses Syntax 18.3.1 Exported Constants	29 29 29 29 29 29 29 29 30 30 31 31 31 31

		18.4.2 Environment Variables	31
		18.4.3 Assumptions	31
		18.4.4 Access Routine Semantics	31
		18.4.5 Local Functions	32
19	MIS	of Output Module	33
	19.1	Module	33
	19.2	Uses	33
	19.3	Syntax	33
		19.3.1 Exported Constants	33
		19.3.2 Exported Access Programs	33
	19.4		33
			33
		19.4.2 Environment Variables	33
		19.4.3 Access Routine Semantics	33
		19.4.4 Local Functions	33
20	MIS	of Specification Parameters	34
	20.1	Module	34
	20.2	Uses	34
	20.3	Syntax	34
		20.3.1 Exported Constants	34
	20.4	Semantics	34

3 Introduction

The following document details the Module Interface Specifications for Radio Signal Strength Calculator. It is intended to ease navigation through the program for design and maintenance purposes.

Complementary documents include the System Requirement Specifications and Module Guide. The full documentation and implementation can be found at https://github.com/XingzhiMac/CAS741-Proj/.

4 Notation

The structure of the MIS for modules comes from Hoffman and Strooper (1995), with the addition that template modules have been adapted from Ghezzi et al. (2003). The mathematical notation comes from Chapter 3 of Hoffman and Strooper (1995). For instance, the symbol := is used for a multiple assignment statement and conditional rules follow the form $(c_1 \Rightarrow r_1|c_2 \Rightarrow r_2|...|c_n \Rightarrow r_n)$.

The following table summarizes the primitive data types used by RSSC.

Data Type	Notation	Description
Boolean	Boolean	a 1-bit data with two possible values (0 and 1)
character	char	a single symbol or digit
integer	\mathbb{Z}	a number without a fractional component in $(-\infty, \infty)$
natural number	\mathbb{N}	a number without a fractional component in $[1, \infty)$
non-negative integer	\mathbb{N}_0	a number without a fractional component in $[0, \infty)$
real	\mathbb{R}	any number in $(-\infty, \infty)$

The specification of RSSC uses some derived data types: sets, strings, and tuples. Sets are lists filled with elements of the same data type. In this document, a set of data in type T is represented as set[T]. Strings are lists of characters. Tuples contain a list of values, potentially of different types.

In addition, RSSC defines the following classes as its unique data types: Point (defined in section 8), Wall (defined in section 9), FloorMap (defined in section 10), LinearPath (defined in section 12), LineOfSight (defined in section 15), and FirstOrderReflection (defined in section 17).

5 Module Decomposition

The following table is taken directly from the Module Guide document for this project.

Level 1	Level 2
Hardware-Hiding	
	Input Parameters
Behaviour-Hiding	Output
	Control Module
	Received Signal Strength
	Specification Parameters Module
	Point
Software Decision	Wall
	Floor Map
	Equation Finder
	Linear Signal Path
	Intersection
	Linear Path Loss
	Line-Of-Sight Signal
	Specular Reflection
	First Order Reflection Signal

Table 1: Module Hierarchy

6 MIS of Control Module

6.1 Module

main

6.2 Uses

Param (section 7), FloorMap(section 10), ReceivedSignalStrength(section 18), Output(section 19)

6.3 Syntax

6.3.1 Exported Constants

6.3.2 Exported Access Programs

Name	In	Out	Exceptions
main	-	-	_

6.4 Semantics

6.4.1 State Variables

None

6.4.2 Access Routine Semantics

main():

• transition: Modify the state of Param module and the environment variables for the Output module by following these steps:

Get (filenameTSM: string), (filenameSP: string), (filenameWALL: string), and (filenameOut: string) from user

Param.load_params(filenameTSM, filenameSP, filenameWALL)

```
map = FloorMap.create()
```

```
\begin{array}{l} [P_{sp}^{dBm}] := \text{empty set} \\ \text{For } (sampling\_point: \ \text{Point}) \ \text{in Param.} [Pos_{sp}] : \\ P_{sp}^{dBm} := \text{ReceivedSignalStrength.get\_received\_power}(map, \ sampling\_point) \\ \text{Add } P_{sp}^{dBm} \ \text{into the set } [P_{sp}^{dBm}] \end{array}
```

Output.output(filename Out, Param.[Pos_{sp}], [P_{sp}^{dBm}])

7 MIS of Input Parameters Module

7.1 Module

Param

7.2 Uses

SpecParam (section 20), Point (section 8)

7.3 Syntax

7.3.1 Exported Constants

None

7.3.2 Exported Access Prøgrams

You never use this outstale making this module. Function.

This a local function.

Name	In	Out	Exceptions
load_params /	s1: string,		FileError
	s2: string,		
	s3: string		
verify_params	-	-	badTransmittance,
			badReflectance, bad-
			TransmissionPower,
			badSignalFrequency,
			badPosition, inconsis-
			tent Wall Params
Pos_{tsm}	-	Point	-
$[Pos_{sp}]$	-	set[Point]	-
[C]	-	set[Point]	-
[D]	-	set[Point]	-
[T]	-	$\operatorname{set}[\mathbb{R}]$	-
[R]	-	$\operatorname{set}[\mathbb{R}]$	-
P_{tsm}^{dBm}	-	$\mathbb R$	-
f	_	\mathbb{R}	_

7.4 Semantics

7.4.1 State Variables

 Pos_{tsm} : Point $[Pos_{sp}]$: set[Point] [C]: set[Point] [D]: set[Point]

 $[T] \colon \operatorname{set}[\mathbb{R}] \\ [R] \colon \operatorname{set}[\mathbb{R}] \\ P_{tsm}^{dBm} \colon \mathbb{R} \\ f \colon \mathbb{R}$

 $length_C$: \mathbb{R} $length_D$: \mathbb{R} $length_T$: \mathbb{R} $length_R$: \mathbb{R}

7.4.2 Environment Variables

tsmFile: set[string] spFile: set[string] wallFile: set[string]

7.4.3 Assumptions

- load_params will be called before any of the state variables be accessed.
- tsmFile contains the string equivalents of the numeric values for Pos_{tsm} , P_{tsm}^{dBm} and f, each on a new line.
- spFile contains the string equivalents of elements in the user-input item $[Pos_{sp}]$, each on a new line, in the form of two numbers separated with a comma.
- wallFile contains the string equivalents of elements in the user-input items [C], [D], [T], and [R]. Each line is in the form of 6 numbers separated by 5 commas (each line should be " $x_{C_x}, y_{C_x}, x_{D_x}, y_{D_x}, T_x, R_x$ ").

7.4.4 Access Routine Semantics

Param. $Pos_{tsm}()$:

- output: $out := Pos_{tsm}$
- exception: none

Param. $[Pos_{sp}]()$:

- output: $out := [Pos_{sp}]$
- exception: none

Param.[C]():

- output: out := [C]
- exception: none

Param.[D]():

- output: out := [D]
- exception: none

Param.[T]():

- output: out := [T]
- exception: none

Param.[R]():

- output: out := [R]
- exception: none

Param. $P_{tsm}^{dBm}()$:

- $\bullet \ \text{output:} \ out := P_{tsm}^{dBm}$
- exception: none

Param.f():

- output: out := f
- exception: none

Param. $length_C()$:

- ullet output: out := number of elements in the user-input item [C]
- exception: none

Param. $length_D()$:

- output: out := number of elements in the user-input item [D]
- exception: none

Param. $length_T()$:

- ullet output: out := number of elements in the user-input item [T]
- exception: none

Param. $length_R()$:

- output: out := number of elements in the user-input item [R]
- exception: none

load_params(s1: string, s2: string, s3: string):

• transition:

The file names s1, s2, and s3 are associated with tsmFile, spFile, and wallsFile respectively.

The state variables are modified with the following procedures:

- 1. Read data from the three files to populate the state variables from ?? from Pos_{tsm} to f).
- 2. Store the lengths of [C], [D], [T], and [R] as $length_C$, $length_D$, $length_T$, and $length_R$ respectively.
- 3. verify_params()
- exception: $exc := any of the file names (s1, s2, or s3) cannot be found OR of any file's format (tsmFile, spFile, or wallsFile) is incorrect <math>\Rightarrow$ FileError

verify_params():

- output: out := none
- exception: exc :=
 - $\neg (T_{min} \leq T_x \leq T_{max} \ \forall \ T_x \in [T]) \Rightarrow \text{badTransmittance}$
 - $\neg (R_{min} \leq R_x \leq R_{max} \ \forall \ R_x \in [R]) \Rightarrow \text{badReflectance}$
 - $\neg (P_{min}^{dBm} \leq P_{tsm}^{dBm} \leq P_{max}^{dBm}) \Rightarrow \text{badTransmissionPower}$
 - $\neg (f_{min} \leq f \leq f_{max}) \Rightarrow \text{badSignalFrequency}$
 - $\neg (x_{min} \le x_{C_x} \le x_{max} \ \forall \ C_x \in [C]) \Rightarrow \text{badPosition}$
 - $\neg (y_{min} \leq y_{C_x} \leq y_{max} \ \forall \ C_x \in [C]) \Rightarrow \text{badPosition}$
 - $\neg (x_{min} \le x_{D_x} \le x_{max} \ \forall \ D_x \in [D]) \Rightarrow \text{badPosition}$
 - $\neg (y_{min} \le y_{D_x} \le y_{max} \ \forall \ D_x \in [D]) \Rightarrow \text{badPosition}$
 - $\neg (length_C = length_D = length_T = length_R) \Rightarrow inconsistent Wall Params$

7.4.5 Local Functions

8 MIS of Point Module

8.1 Module

Point

8.2 Uses

None

8.3 Syntax

8.3.1 Exported Constants

None

8.3.2 Exported Access Programs

Name	In	Out	Exceptions
create	x -coordinate: \mathbb{R} ,	Point	-
	y_coordinate: \mathbb{R}		
$set_coordinates$	x -coordinate: \mathbb{R} ,	-	-
	y_coordinate: \mathbb{R}		
${\tt get_coordinates}$	-	$x: \mathbb{R}, y: \mathbb{R}$	-

8.4 Semantics

8.4.1 State Variables

 $x:\mathbb{R}$

 $y: \mathbb{R}$

8.4.2 Environment Variables

None

8.4.3 Assumptions

None

8.4.4 Access Routine Semantics

create(x_coordinate: \mathbb{R} , y_coordinate: \mathbb{R}):

```
• transition:
```

 $x := x_coordinate$ $y := y_coordinate$

• output: out := self

 $set_coordinates(x_coordinate: \ \mathbb{R}, \ y_coordinate: \ \mathbb{R}):$

• transition:

 $x := x_coordinate$ $y := y_coordinate$

• output: none

get_coordinates():

• output: out := x, y

8.4.5 Local Functions

MIS of Wall Module 9

Module 9.1

Wall

9.2 Uses

Template, Template, Tome that
It seems form that
you are using brall as an MOT Point (section 8), EquationFinder (section 11)

9.3 Syntax

Exported Constants 9.3.1

None

9.3.2 **Exported Access Programs**

Name	In	Out	Exceptions
create	start: Point,	Wall	invalidWall
	end: Point		
set_start_point	Point	-	invalidWall
$\operatorname{set_end_point}$	Point	-	invalidWall
get_start_point	-	Point	-
$\operatorname{get_end_point}$	-	Point	-
$set_transmittance$	\mathbb{R}	-	-
$set_reflectance$	\mathbb{R}	-	-
get_transmittance	-	\mathbb{R}	-
$get_reflectance$	-	\mathbb{R}	-
$\operatorname{get_unit_normal}$	-	$n1:\mathbb{R},\ n2:\mathbb{R}$	-
$get_line_equation$	-	$m1:\mathbb{R},\ m2:\mathbb{R},$	-
		$k:\mathbb{R}$	

Semantics 9.4

State Variables 9.4.1

 C_x : Point D_x : Point

 $T_x:\mathbb{R}$

 $R_x: \mathbb{R}$

 $m1:\mathbb{R}$

 $m2:\mathbb{R}$

 $k: \mathbb{R}$

Rather than get lawsmithens, a better nome for the getter night be tx?

 $n1:\mathbb{R}$ $n2:\mathbb{R}$ 9.4.2**Environment Variables** None 9.4.3Assumptions None 9.4.4Access Routine Semantics create(start: Point, end: Point, transmittance: \mathbb{R} , reflectance: \mathbb{R}): • transition: $C_x := \text{start}$ $D_x := end$ $T_x := \text{transmittance}$ $R_x := \text{reflectance}$ Use Equation Finder Module to find equation parameters: $m1, m2, k := \text{EquationFinder.find}_\text{equation(start, end)}$ Find the unit normal vector: $n1, n2 := \operatorname{find_unit_normal}(C_x, D_x)$ \(\tag{\text{furthermodel}}\) • output: out := self• exception: $exc := C_x$ and D_x have the same coordinates \Rightarrow invalidWall start-point(start: Point):

• transition:

• $C_x := \text{start}$ When $C_x := \text{start}$ set_start_point(start: Point): Use Equation Finder Module to find equation parameters: $m1, m2, k := \text{EquationFinder.find_equation}(C_x, D_x)$

Find the unit normal vector:

 $n1, n2 := \text{find_unit_normal}(C_x, D_x)$

- output: none
- exception: $exc := C_x$ and D_x have the same coordinates \Rightarrow invalidWall set_end_point(end: Point):
 - transition:

```
D_x := end
```

Use Equation Finder Module to find equation parameters: $m1, m2, k := \text{EquationFinder.find_equation}(C_x, D_x)$

Find the unit normal vector: $n1, n2 := \text{find_unit_normal}(C_x, D_x)$

- output: none
- exception: $exc := C_x$ and D_x have the same coordinates \Rightarrow invalidWall get_start_point():
 - output: $out := C_x$
 - exception: none

get_end_point():

- output: $out := D_x$
- exception: none

 $set_{transmittance}(transmittance: \mathbb{R}):$

- transition: $T_x := \text{transmittance}$
- output: none
- exception: none

 $set_reflectance(resistance: \mathbb{R}):$

- transition: $R_x := \text{resistance}$
- output: none
- exception: none

get_transmittance():

- \bullet output: out := T
- exception: none

get_reflectance():

- output: out := R
- exception: none

get_unit_normal():

- output: out := n1, n2
- exception: none

get_line_equation():

- output: out := m1, m2, k
- exception: none

9.4.5 Local Functions

 $\operatorname{find_unit_normal}(C_x, D_x)$:

- transition:
 - $x_{C_x}, y_{C_x} := C_x.get_coordinates()$
 - $x_{D_x}, y_{D_x} := D_x.\text{get_coordinates()}$

$$[n1 \quad n2] := [(x_{D_x} - x_{C_x}) \quad (y_{D_x} - y_{C_x})] \quad \begin{bmatrix} 0 & -1 \\ 1 & 0 \end{bmatrix} \cdot \frac{1}{\sqrt{(y_{D_x} - y_{C_x})^2 + (x_{D_x} - x_{C_x})^2}}$$

- output: out := n1, n2
- exception: none

MIS of Floor Map Module 10

10.1 Module

FloorMap

10.2 Uses

Param(section 7), Point(section 8), Wall(section 9)

10.3 Syntax

10.3.1**Exported Constants**

None

10.3.2Exported Access Programs

Name	In	Out	Exceptions
create	-	FloorMap	-
get _wall	\mathbb{N}_0	Wall	invalidIndex
get _map	-	FloorMap	-

Semantics 10.4

State Variables 10.4.1

The rame hall-lied suggests a sequence.

De you when a set or a sequence?

It you need access to the ith wall,

you would have a sequence. If you

don't need to plut distinct halls, a

before the FloorMap object can be accessed. Set I the, $wall_list: set[Wall]$ wall_list_length: \mathbb{N}_{σ}

Environment Variables 10.4.2

None

10.4.3 Assumptions

 $\operatorname{create}()$ will be called before the FloorMap object can be accessed.

Access Routine Semantics 10.4.4

create():

• transition:

Get parameters of all walls from Input Parameters Module (section 7): Let $list_C = Param.[C]()$;

```
Let list_D = \operatorname{Param}.[D]();
Let list_T = \operatorname{Param}.[T]();
Let list_R = \operatorname{Param}.[R]();
Then:

wall_list_length := \operatorname{Param}.length_C()
Then create wall_list as such:

for i = \{0, 1, 2, \dots, (\text{wall_list_length - 1})\},

wall_list(i) := \operatorname{Wall.create}(list_C(i), list_D(i), list_T(i), list_R(i))

• output: out := \operatorname{self}

• exception: none

get_wall(index: \mathbb{N}_0):

• output: out := \operatorname{wall_list(index)}

• exception: \operatorname{exc} := \neg(0 \leq \operatorname{index} \leq \operatorname{wall_list_length - 1}) \Rightarrow \operatorname{invalidIndex}

get_map():

• output: out := \operatorname{self}

• exception: none
```

10.4.5 Local Functions

11 MIS of Equation Finder

11.1 Module

Equation Finder

11.2 Uses

Point(section 8)

11.3 Syntax

11.3.1 Exported Constants

None

11.3.2 Exported Access Programs

Name	In	Out	Exceptions
find_equation	start: Point,	$m1: \mathbb{R}, m2: \mathbb{R},$	-
	end: Point	k: ℝ	

11.4 Semantics

11.4.1 State Variables

None

11.4.2 Environment Variables

None

11.4.3 Assumptions

None

11.4.4 Access Routine Semantics

find_equation(start: Point, end: Point):

• output:

Let
$$x_{C_x}, y_{C_x} = \text{start.get_coordinates}();$$

Let $x_{D_x}, y_{D_x} = \text{end.get_coordinates}();$
Then
$$m1 := \begin{cases} -\frac{y_{D_x} - y_{C_x}}{x_{D_x} - x_{C_x}} & \text{if } x_{D_x} - x_{C_x} \neq 0 \\ 1 & \text{else} \end{cases}$$



$$m2 := \begin{cases} 1 & \text{if } x_{D_x} - x_{C_x} \neq 0 \\ 0 & \text{else} \end{cases}$$

$$k := m1 \cdot x_{C_x} + m2 \cdot y_{C_x} = m1 \cdot x_{D_x} + m2 \cdot y_{D_x}$$

$$out := m1, m2, k$$

• exception: none

11.4.5 Local Functions

12 MIS of Linear Signal Path Module

12.1 Module

LinearPath

12.2 Uses

Point (section 8), EquationFinder (section 11)

12.3 Syntax

12.3.1 Exported Constants

None

12.3.2 Exported Access Programs

Name	In	Out	Exceptions
create	start: Point,	LinearPath	_
	end: Point		
$get_equation$	-	$m1: \mathbb{R}, \ m2: \mathbb{R},$	-
		$k:\mathbb{R}$	
get_start_point	-	Point	-
$\operatorname{get_end_point}$	-	Point	-
$\operatorname{get_length}$	-	\mathbb{R}	-

12.4 Semantics

12.4.1 State Variables

E: PointF: Point

 $m1:\mathbb{R}$

 $m2:\mathbb{R}$

 $k:\mathbb{R}$

 $length: \mathbb{R}$

12.4.2 Environment Variables

None

12.4.3 Assumptions

12.4.4 Access Routine Semantics

create(start: Point, end: Point):

- transition:
 - $E := \operatorname{start}$
 - F := end

Use Equation Finder Module to find the path's equation parameters: $m1, m2, k := \text{EquationFinder.find} \cdot \text{equation}(E, F)$

Let $x_E, y_E = E.\text{get_coordinates}();$ Let $x_F, y_F = F.\text{get_coordinates}();$

The find the physical length of the linear path:

 $length := \sqrt{(x_E - x_F)^2 + (y_E - y_F)^2}$

- output: out := self
- exception: none

get_equation():

- output: out := m1, m2, k
- exception: none

get_start_point():

- \bullet output: out := E
- exception: none

get_end_point():

- output: out := F
- exception: none

get_length():

- output: out := length
- exception: none

12.4.5 Local Functions

13 MIS of Intersection Module

13.1 Module

Intersection

13.2 Uses

Point (section 8), Wall (section 9), LinearPath (section 12)

13.3 Syntax

13.3.1 Exported Constants

None

13.3.2 Exported Access Programs

Name	In	Out	Exceptions
find_intersection	Wall, L	in- Point	-
	earPath		
is_valid	Wall, L	in- Boolean	-
	earPath		

13.4 Semantics

13.4.1 State Variables

None

13.4.2 Environment Variables

None

13.4.3 Assumptions

None

13.4.4 Access Routine Semantics

find_intersection(wall: Wall, path: LinearPath):

$$\begin{array}{ll} \bullet \ \ \text{output:} \\ \text{Let} \ M = \begin{bmatrix} wall.m1 & wall.m2 \\ path.m1 & path.m2 \end{bmatrix}; \end{array}$$

Let
$$K = \begin{bmatrix} wall.k \\ path.k \end{bmatrix}$$
;
$$t' := \text{Point.create}(x,y) \text{ such that } M \begin{bmatrix} x \\ y \end{bmatrix} = K, \text{ if } det(M) \neq 0; \text{ or } t' := \text{Point.create}(0,0), \text{ if } det(M) = 0.$$

$$out := t'$$

exception: none

is_valid(wall: Wall, path: LinearPath):

output:
$$\text{Let } M = \begin{bmatrix} wall.m1 & wall.m2 \\ path.m1 & path.m2 \end{bmatrix};$$

$$\text{Let } K = \begin{bmatrix} wall.k \\ path.k \end{bmatrix};$$

If $det(M) \neq 0$,

$$t' := \text{Point.create}(x, y) \text{ such that } M \begin{bmatrix} x \\ y \end{bmatrix} = K$$

 $\max(\min(wall.C_x.x, wall.D_x.x), \min(path.C_x.x, path.D_x.x)) < t'.x < \min(\max(wall.C_x.x, wall.D_x.x))$ and

 $\max(\min(wall.C_x.y, wall.D_x.y), \min(path.C_x.y, path.D_x.y)) < t'.x < \min(\max(wall.C_x.y, wall.D_x.y)) < t'.x <$

Ind := 1;

otherwise Ind := 0.

If det(M) = 0,

Ind := 0.

out := Ind

• exception: none

Local Functions 13.4.5

None

You could use a consideral expression for this consideral expression for this $(C_1 \Rightarrow R_1 \mid C_2 \Rightarrow) r_2 \mid ... \mid C_n = r_n)$ (do calsed in Mayman I Stroper

14 MIS of Linear Path Loss Module

14.1 Module

LinearLoss

14.2 Uses

FloorMap (section 10), LinearPath (section 12), Intersection (section 13)

14.3 Syntax

14.3.1 Exported Constants

None

14.3.2 Exported Access Programs

Name	In	Out	Exceptions
find_linear_path_loss	path:LinearPath, f: \mathbb{R}	\mathbb{R}	-

14.4 Semantics

14.4.1 State Variables

None

14.4.2 Environment Variables

None

14.4.3 Assumptions

FloorMap.create() will be called before calling FloorMap.get_map().

14.4.4 Access Routine Semantics

find_linear_path_loss (path: LinearPath, $freq : \mathbb{R}$):

• output:

The output is dependent on two parameters: FSPL and T_{total} . Update FSPL:

```
map: FloorMap.get_map()

FSPL := (\frac{4\pi \cdot path.length}{3 \times 10^8})^2
```

Update T_{total} : $T_{total} := \prod_{x=0}^{N_w} (wall_x \cdot T_x^{Ind_{t,x}})$ Is Wis the Where long th A $N_w := map.wall_list_length - 1$ $wall_x := \text{map.get_wall}(x)$ $Ind_{t,x} := Intersection.is_valid(wall_x, path)$ $out := \frac{T_{total}}{FSPL}$ wa? • exception: none **Local Functions** 14.4.5

will & Tx low like withouth

The implies wall is a segrence in the rotation. If you are using wall as a set, the rotation would be something lite

* (w: Wall / w Ewall list:

W. galpleram * W. T.

You seem to mix whether wall is a set or a soprence. Make a choice and make it considered throughout

15 MIS of Line-Of-Sight Signal Module

15.1 Module

 ${\bf Line Of Sight}$

15.2 Uses

Param (section 7), Point (section 8), LinearPath (section 12), LinearLoss (section 14)

15.3 Syntax

15.3.1 Exported Constants

 $\phi_{LOS} := 0$

15.3.2 Exported Access Programs

Name	In	Out	Exceptions
create	$sampling_point:$	LineOfSight	-
	Point		
get_path_length	-	\mathbb{R}	-
$get_amplitude$	-	\mathbb{R}	-
get_phase_angle	-	\mathbb{R}	-

15.4 Semantics

15.4.1 State Variables

 Pos_{sp} : Point $d_{tsm,sp}$: \mathbb{R} P_{LOS} : \mathbb{R}

15.4.2 Environment Variables

None

15.4.3 Assumptions

None

15.4.4 Access Routine Semantics

create(sampling_point: Point):

```
• transition:
       Update Pos_{sp}:
       Pos_{sp} := \text{sampling\_point}
       Update d_{tsm,sp}:
       freq := Param.f()
       Pos_{tsm} := Param.Pos_{tsm}()
       path := LinearPath.create(Pos_{tsm}, Pos_{sp})
       d_{tsm,sp} := path.get_length()
       Update P_{LOS}:
       P_{tsm}^{dBm} := \underset{10}{\text{Param.}} P_{tsm}^{dBm}()
P_{tsm} := 10^{\frac{P_{tsm}^{dBm} - 30}{10}}
       P_{LOS} := P_{tsm} \cdot \text{LinearLoss.find\_linear\_path\_loss}(path, freq)
    • output: out := self
    • exception: none
get_path_length():
    • output: out := d_{tsm,sp}
    • exception: none
get_amplitude():
    • output: out := P_{LOS}
    • exception: none
get_phase_angle():
    • output: out := \phi_{LOS}
```

15.4.5 Local Functions

• exception: none

16 MIS of Specular Reflection Module

16.1 Module

Specular

16.2 Uses

Point (section 8), Wall (section 9), LinearPath (section 12), Intersection (section 13)

16.3 Syntax

16.3.1 Exported Constants

None

16.3.2 Exported Access Programs

Name	In	Out	Exceptions
get_mirrored_paths	$wall_x$:Wall,	$path_{RS1}$:LinearPath,	_
	start:Point,	$path_{RS2}$:LinearPath,	
	end:Point	$Ind_{r,x}$: Boolean	

16.4 Semantics

16.4.1 State Variables

None

16.4.2 Environment Variables

None

16.4.3 Assumptions

None

16.4.4 Access Routine Semantics

get_mirrored_paths($wall_x$:Wall, start:Point, end:Point):

• output:

```
Let n := [wall_x.n1 \quad wall_x.n2];

Let t := [wall_x.C_x.x \quad wall_x.C_x.y];

Let p := [start.x \quad start.y)];

Then solve
```

```
 \begin{aligned} & \left[ p_x' \quad p_y' \right] = p - 2n(n \cdot (p-t)) \\ & \text{for the values of } p_x' \text{ and } p_y'. \\ & \text{let } p' := \text{Point.create}(p_x', p_y'); \\ & \text{Let } mirrored\_path := \text{LinearPath.create}(p', end); \\ & \text{Then} \\ & t' := \text{Intersection.find\_intersection}(wall_x, mirrored\_path); \\ & Ind_{r,x} := \text{Intersection.is\_valid}(wall_x, mirrored\_path); \\ & path_{RS1} := \text{LinearPath.create}(p, t'); \\ & path_{RS2} := \text{LinearPath.create}(t', end); \\ & out := path_{RS1}, path_{RS2}, Ind_{r,x} \end{aligned}
```

• exception: none

16.4.5 Local Functions

17 MIS of First-Order Reflection Signal Module

17.1 Module

FirstOrderReflection

17.2 Uses

Param (section 7), Wall (section 9), LinearLoss (section 12), LineOfSight (section 15), Specular (section 16)

17.3 Syntax

17.3.1 Exported Constants

None

17.3.2 Exported Access Programs

Name	In		Out	Exceptions
create	$wall_x$:	Wall,	FirstOrderReflection	_
	sampling	$_point:$		
	Point,	LOS:		
	LineOfSig	ght		
$get_amplitude$	-		\mathbb{R}	-
get_phase_angle	-		\mathbb{R}	-

17.4 Semantics

17.4.1 State Variables

 Pos_{sp} : Point

 $path_{RS1}$: LinearPath $path_{RS2}$: LinearPath $Ind_{r,x}$: Boolean

 P_{FORS} : \mathbb{R} ϕ_{FORS} : \mathbb{R}

17.4.2 Environment Variables

None

17.4.3 Assumptions

17.4.4 Access Routine Semantics

create($wall_x$:Wall, sampling_point: Point, LOS: LineOfSight):

```
• transition:
       Update Pos_{sn}:
       Pos_{sp} := sampling\_point
       Update path_{RS1}, path_{RS2}, and Ind_{r,x}:
       freq := Param.f()
       Pos_{tsm} := Param.Pos_{tsm}()
       path_{RS1}, path_{RS2}, Ind_{r,x} := Specular.get\_mirrored\_paths(wall_x, Pos_{tsm}, Pos_{sp})
       Update P_{FORS}:
       If Ind_{r,x} = 1:
       P_{tsm}^{dBm} := \operatorname{Param.} P_{tsm}^{dBm}()
      P_{tsm} := 10^{\frac{P_{tsm}^{dBm} - 30}{10}}
       transmittance_{RS1} := LinearLoss.find\_linear\_path\_loss(path_{RS1}, freq)
       transmittance_{RS2} := LinearLoss.find\_linear\_path\_loss(path_{RS2}, freq)
       P_{FORS} := P_{tsm} \cdot transmittance_{RS1} \cdot transmittance_{RS2} \cdot wall_x.get\_reflectance()
       Otherwise:
       P_{FORS} := 0
       Update \phi_{FORS}:
       If Ind_{r,x} = 1:
       \phi_{FORS} := 2\pi f \frac{path_{RS1}.length + path_{RS2}.length - LOS.d_{tsm,sp}}{3\times10^8} Otherwise:
       \phi_{FORS} := 0
    • output: out := self
    • exception: none
get_amplitude():
    • output: out := P_{FORS}
    • exception: none
get_phase_angle():
    • output: out := \phi_{FORS}
    • exception: none
```

17.4.5 Local Functions

18 MIS of Received Signal Strength Module

18.1 Module

Received Signal Strength

18.2 Uses

FloorMap (section 10), LineOfSight (section 15), FirstOrderReflection (section 17)

18.3 Syntax

18.3.1 Exported Constants

None

18.3.2 Exported Access Programs

Name	In		Out	Exceptions
get_received_power	map:	FloorMap,	\mathbb{R}	$\overline{\text{invalidReceivedStrength}}$
	sampling	ag_point :		
	Point			

18.4 Semantics

18.4.1 State Variables

None

18.4.2 Environment Variables

None

18.4.3 Assumptions

FloorMap.create() will be called before calling FloorMap.get_map() in this module.

18.4.4 Access Routine Semantics

get_received_power(map: FloorMap, sampling_point: Point):

• output:

```
Get Floor Map:
```

 $map := FloorMap.get_map()$

 $map_complexity := map.wall_list_length - 1$

```
Find Line-Of-Sight Signal
LOS := LineOfSight.create(sampling\_point)
Find First-Order reflection signals by wall:
For x in (0, 1, 2, \dots, map\_complexity):
wall_x := map.get\_wall(x)
FORS(x) := FirstOrderReflection.create(wall_x, sampling\_point, LOS)
Find total received signal:
P_{LOS} := LOS.get\_amplitude()
\phi_{LOS} := LOS.get\_phase\_angle()
P_{FORS_x} := FORS(x).get\_amplitude()
\begin{aligned} \phi_{FORS_x} &:= FORS(x).\text{get\_ampfitude()} \\ \phi_{FORS_x} &:= FORS(x).\text{get\_phase\_angle()} \\ P_{sp} \angle \phi_{sp} &:= P_{LOS} \angle \phi_{LOS} + \sum_{x=0}^{map\_complexity} P_{FORS_x} \angle \phi_{FORS_x} \\ P_{sp}^{dBm} &:= 30 + 10 \log_{10}(P_{sp}) \end{aligned}
out := P_{sp}^{dBm}
```

 \bullet exception: $exc:=(P_{tsm}^{dBm} \leq P_{sp}^{dBm}) \Rightarrow$ invalid Received Strength

18.4.5 **Local Functions**

19 MIS of Output Module

19.1 Module

Output

19.2 Uses

Param (section 7), Point (section 8)

19.3 Syntax

19.3.1 Exported Constants

None

19.3.2 Exported Access Programs

Name	In	Out	Exceptions
output	fname: string,	-	-
	$[Pos_{sp}]$:		
	set[Point],		
	$[P_{sp}^{dBm}]$: set $[\mathbb{R}]$		

19.4 Semantics

19.4.1 State Variables

None

19.4.2 Environment Variables

file: a text file

19.4.3 Access Routine Semantics

output(fname, $[Pos_{sp}], [P_{sp}^{dBm}]$):

- transition: write to environment variable named fname the calculated received signal strengths $[P_{sp}^{dBm}]$ and their corresponding sampling points in $[Pos_{sp}]$. Each line of the output file will be 3 numbers separated by comma: $[Pos_{sp}.x, Pos_{sp}.y, P_{sp}^{dBm}]$.
- exception: none

19.4.4 Local Functions

MIS of Specification Parameters 20

20.1Module

SpecParam

20.2 Uses

None

20.3 **Syntax**

20.3.1 Exported Constants

From ?? in SRS $P_{max}^{dBm} := 15 \text{ (dBm)}$ $P_{min}^{dBm} := -30 \text{ (dBm)}$ $f_{min} := 30 \text{ (Hz)}$ $f_{max} := 3 \times 10^{11} \text{ (Hz)}$ $x_{min} := -20 \text{ (m)}$ $x_{max} := 20 \text{ (m)}$ $y_{min} := -20 \text{ (m)}$ $y_{max} := 20 \text{ (m)}$

20.4

N/A

Great work! first invanishing the steps of the steps of the steps of the supposed, but the steps of the step of t

References

Carlo Ghezzi, Mehdi Jazayeri, and Dino Mandrioli. Fundamentals of Software Engineering. Prentice Hall, Upper Saddle River, NJ, USA, 2nd edition, 2003.

Daniel M. Hoffman and Paul A. Strooper. Software Design, Automated Testing, and Maintenance: A Practical Approach. International Thomson Computer Press, New York, NY, USA, 1995. URL http://citeseer.ist.psu.edu/428727.html.