原 x264源代码简单分析:x264命令行工具(x264.exe)

2015年05月08日 18:30:23 阅读数:11985

H.264源代码分析文章列表:

【编码 - x264】

x264源代码简单分析:概述

x264源代码简单分析:x264命令行工具(x264.exe)

x264源代码简单分析:编码器主干部分-1

x264源代码简单分析:编码器主干部分-2

x264源代码简单分析:x264_slice_write()

x264源代码简单分析:滤波(Filter)部分

x264源代码简单分析:宏块分析(Analysis)部分-帧内宏块(Intra)

x264源代码简单分析:宏块分析(Analysis)部分-帧间宏块(Inter)

x264源代码简单分析:宏块编码(Encode)部分

x264源代码简单分析:熵编码(Entropy Encoding)部分

FFmpeg与libx264接口源代码简单分析

【解码 - libavcodec H.264 解码器】

FFmpeg的H.264解码器源代码简单分析:概述

FFmpeg的H.264解码器源代码简单分析:解析器(Parser)部分

FFmpeg的H.264解码器源代码简单分析:解码器主干部分

FFmpeg的H.264解码器源代码简单分析:熵解码(EntropyDecoding)部分

FFmpeg的H.264解码器源代码简单分析:宏块解码(Decode)部分-帧内宏块(Intra)


FFmpeg的H.264解码器源代码简单分析:宏块解码(Decode)部分-帧间宏块(Inter)

FFmpeg的H.264解码器源代码简单分析:环路滤波(Loop Filter)部分

本文简单分析x264项目中的命令行工具(x264.exe)的源代码。该命令行工具可以调用libx264将YUV格式像素数据编码为H.264码流。


函数调用关系图

X264命令行工具的源代码在x264中的位置如下图所示。



单击查看更清晰的图片

X264命令行工具的源代码的调用关系如下图所示。



X264 Source Analysis - x264.c 雷霄骅 (Lei Xiaohua) leixiaohua1020@126.com http://blog.csdn.net/leixiaohua1020

单击查看更清晰的图片

从图中可以看出,X264命令行工具调用了libx264的几个API完成了H.264编码工作。使用libx264的API进行编码可以参考《 最简单的视频编码器:基于libx264(编码YU V为H.264) 》,这个流程中最关键的API包括:

x264_param_default():设置参数集结构体x264_param_t的缺省值。

x264_encoder_open():打开编码器。

x264_encoder_headers():输出SPS, PPS, SEI等信息。

x264_encoder_encode():编码输出一帧图像。

x264_encoder_close():关闭编码器。

在X264命令行工具中,main()首先调用parse()解析输入的命令行参数,然后调用encode()进行编码。parse()首先调用x264_param_default()为存储参数的结构体x264_param_t赋默认值;然后在一个大循环中调用getopt_long()逐个解析输入的参数,并作相应的处理;最后调用select_input()和s

elect_output()解析输入文件格式(例如yuv,y4m...)和输出文件格式(例如raw,flv,MP4...)。encode()首先调用x264_encoder_open()打开H. 264编码器,然后调用x264_encoder_headers()输出H.264码流的头信息(例如SPS、PPS、SEI),接着进入一个循环并且调用encode_frame()逐帧编码视频,最后调用x264_encoder_close()关闭解码器。其中encode_frame()中又调用了x264_encoder_encode()完成了具体的编码工作。下文将会对上述流程展开分析。

main()

main()是x264控制台程序的入口函数,定义如下所示。

```
[cpp] 📳 🔝
      //主函数
 2.
      int main( int argc, char **argv )
 3.
      {
       //参数集
 4.
 5.
          x264 param t param:
      cli_opt_t opt = {0};
 6.
 7.
          int ret = 0;
 8.
          FAIL\_IF\_ERROR(\ x264\_threading\_init(),\ "unable\ to\ initialize\ threading \verb|\| n"\ )
 9.
10.
11.
      #ifdef WIN32
12.
       FAIL_IF_ERROR( !get_argv_utf8( &argc, &argv ), "unable to convert command line to UTF-8\n" )
13.
14.
      GetConsoleTitleW( org_console_title, CONSOLE_TITLE_SIZE );
      _setmode( _fileno( stdin ), _0_BINARY );
_setmode( _fileno( stdout ), _0_BINARY );
15.
16.
17.
           _setmode( _fileno( stderr ), _0_BINARY );
18.
19.
      /* Parse command line */
20.
           //解析命令行输入
21.
22.
      if( parse( argc, argv, ¶m, &opt ) < 0 )</pre>
23.
              ret = -1;
24.
25.
      #ifdef WIN32
      /* Restore title; it can be changed by input modules *,
26.
27.
          SetConsoleTitleW( org_console_title );
28.
29.
      /* Control-C handler */
30.
31.
          signal( SIGINT, sigint_handler );
      //编码
32.
33.
          if( !ret )
      ret = encode( ¶m, &opt );
34.
35.
      /* clean up handles */
36.
          if( filter.free )
37.
38.
             filter.free( opt.hin );
39.
          else if( opt.hin )
40.
             cli_input.close_file( opt.hin );
41.
          if( opt.hout )
42.
              cli_output.close_file( opt.hout, 0, 0 );
43.
          if( opt.tcfile_out )
44.
              fclose( opt.tcfile_out );
45.
          if( opt.qpfile )
      fclose( opt.qpfile );
46.
47.
48.
      #ifdef WIN32
49.
          SetConsoleTitleW( org console title );
         free( argv );
50.
51.
      #endif
52.
53.
           return ret:
54.
```

可以看出main()的定义很简单,它主要调用了两个函数:parse()和encode()。main()首先调用parse()解析输入的命令行参数,然后调用encode()进行编码。下面分别分 析这两个函数。

parse()

parse()用于解析命令行输入的参数(存储于argv[]中)。它的定义如下所示。

```
char : input intename - NOLE,
          const char *demuxer = demuxer_names[0];
      char *output filename = NULL;
6.
          const char *muxer = muxer names[0];
7.
         char *tcfile name = NULL;
8.
          x264 param t defaults:
9.
         char *profile = NULL;
10.
          char *vid_filters = NULL;
11.
12.
          int b_thread_input = 0;
13.
          int b_turbo = 1;
14.
          int b_user_ref = 0;
15.
          int b_user_fps = 0;
16.
          int b_user_interlaced = 0;
17.
          cli_input_opt_t input_opt;
18.
         cli_output_opt_t output_opt;
19.
          char *preset = NULL;
         char *tune = NULL;
20.
          //初始化参数默认值
21.
         x264 param default( &defaults ):
22.
23.
          cli_log_level = defaults.i_log_level;
24.
25.
          memset( &input_opt, 0, sizeof(cli_input_opt_t) );
26.
          memset( &output_opt, 0, sizeof(cli_output_opt_t) );
27.
          input_opt.bit_depth = 8;
          input_opt.input_range = input_opt.output_range = param->vui.b_fullrange = RANGE_AUTO;
28.
29.
          int output_csp = defaults.i_csp;
30.
         opt->b_progress = 1;
31.
32.
      /* Presets are applied before all other options. */
33.
          for( optind = \theta;; )
34.
35.
              int c = getopt long( argc, argv, short options, long options, NULL );
              if( c == -1 )
36.
37.
                  break;
              if( c == OPT_PRESET )
38.
39.
                  preset = optarg;
              if( c == OPT TUNE )
40.
41.
                  tune = optarg;
42.
              else if( c == '?' )
43.
                  return -1;
44.
45.
46.
     if( preset && !strcasecmp( preset, "placebo" ) )
47.
              b_turbo = 0;
48.
          //设置preset, tune
49.
          if( x264 param default preset( param, preset, tune ) < 0 )</pre>
50.
          return -1:
51.
      /* Parse command line options */
52.
          //解析命令行诜项
53.
54.
        for(optind = 0::)
55.
56.
              int b_error = 0;
57.
              int long_options_index = -1;
58.
59.
              int c = getopt_long( argc, argv, short_options, long_options, &long_options_index );
60.
61.
              if( c == -1 )
62.
              {
63.
64.
65.
              //不同的选项做不同的处理
              switch( c )
66.
67.
                  case 'h':
68.
                      help( &defaults, 0 );//"-h"帮助菜单
69.
70.
                     exit(0);
71.
                  case OPT LONGHELP:
72.
                   help( &defaults, 1 );
73.
                      exit(0):
74.
                   case OPT FULLHELP:
75.
                      help( &defaults, 2 );
76.
                      exit(0);
77.
                  case 'V':
78.
                     print version info();//打印版本信息
79.
                      exit(0);
                  case OPT FRAMES:
80.
                      param->i_frame_total = X264_MAX( atoi( optarg ), 0 );
81.
                      break:
82.
                  case OPT SEEK:
83.
                     opt->i_seek = X264_MAX( atoi( optarg ), 0 );
84.
85.
                      break;
86.
                  case 'o':
87.
                      output_filename = optarg;//输出文件路径
88.
                      break;
89.
                  case OPT_MUXER:
90.
                      FAIL\_IF\_ERROR(\ parse\_enum\_name(\ optarg,\ muxer\_names,\ \&muxer\ ),\ "Unknown\ muxer\ `\$s'\n",\ optarg\ )
91.
                      break;
92.
                  case OPT DEMUXER:
                      FAIL IF ERROR( parse enum name( optarg, demuxer names, &demuxer ), "Unknown demuxer `%s'\n", optarg )
93.
94.
                      break;
                  case OPT INDEX:
```

```
96
                       input opt.index file = optarg;
 97.
                       break:
 98
                    case OPT OPFILE:
 99.
                        opt->qpfile = x264_fopen( optarg, "rb" );
100.
                       FAIL_IF_ERROR( !opt->qpfile, "can't open qpfile `%s'\n", optarg )
101.
                        if( !x264_is_regular_file( opt->qpfile ) )
102.
103.
                            x264 cli log( "x264", X264 LOG ERROR, "qpfile incompatible with non-regular file `%s'\n", optarg );
104.
                           fclose( opt->qpfile );
105.
                           return -1;
106.
107.
                       break:
                    case OPT THREAD INPUT:
108.
109.
                       b_tnead_input = 1;
110.
                       break:
111.
                    case OPT QUIET:
112
                       cli_log_level = param->i_log_level = X264_LOG_NONE;//设置log级别
113.
                       break;
114.
                     case 'v':
115.
                       cli_log_level = param->i_log_level = X264_LOG_DEBUG;//设置log级别
116.
                       break:
117.
                    case OPT LOG LEVEL:
118.
                      if( !parse_enum_value( optarg, log_level_names, &cli_log_level ) )
119.
                           cli_log_level += X264_LOG_NONE;
120.
                       else
121.
                           cli log level = atoi( optarg );
                       param->i_log_level = cli_log_level;//设置log级别
122.
123.
                       break:
124.
                    case OPT NOPROGRESS:
125.
                       opt->b_progress = 0;
126.
                       break:
127
                    case OPT TUNE:
128.
                    case OPT_PRESET:
129
                       break;
130.
                    case OPT PROFILE:
131.
                       profile = optarg;
132.
                       break;
133.
                    case OPT_SLOWFIRSTPASS:
134.
                       b turbo = 0;
135.
                       break:
                    case 'r':
136.
137.
                       b user ref = 1:
138.
                       goto generic option;
139.
                    case OPT FPS:
140
                      b_user_fps = 1;
141.
                        param->b_vfr_input = 0;
142.
                       goto generic_option;
143.
                    case OPT_INTERLACED:
144.
                       b_user_interlaced = 1;
145.
                       goto generic_option;
146.
                    case OPT_TCFILE_IN:
147.
                       tcfile_name = optarg;
148.
                       break;
                    case OPT TCFILE OUT:
149.
                       opt->tcfile out = x264_fopen( optarg, "wb" );
150.
151.
                       FAIL_IF_ERROR( !opt->tcfile_out, "can't open `%s'\n", optarg )
152.
                       break:
153.
                    case OPT TIMEBASE:
154.
                       input_opt.timebase = optarg;
155.
                       break:
156.
                    case OPT_PULLDOWN:
157.
                       FAIL\_IF\_ERROR(\ parse\_enum\_value(\ optarg,\ pulldown\_names,\ \&opt->i\_pulldown\ ),\ "Unknown\ pulldown\ `%s'\n",\ optarg\ )
158.
                       break:
159.
                    case OPT VIDEO FILTER:
160.
                       vid_filters = optarg;
161.
                       break;
                    case OPT_INPUT_FMT:
162.
163.
                       input opt.format = optarg;//输入文件格式
164.
                       break:
                    case OPT INPUT RES:
165.
166.
                      input_opt.resolution = optarg;//输入分辨率
167.
                       break:
                    case OPT INPUT CSP:
168
169.
                       input_opt.colorspace = optarg;//输入色域
170
                       break:
171.
                    case OPT INPUT DEPTH:
172.
                       input_opt.bit_depth = atoi( optarg );//输入颜色位深
173.
                       break;
174.
                    case OPT DTS COMPRESSION:
175.
                       output_opt.use_dts_compress = 1;
176.
                       break;
177.
                    case OPT OUTPUT CSP:
178.
                       FAIL IF ERROR( parse enum value( optarg, output csp names, &output csp ), "Unknown output csp `%s'\n", optarg )
179.
                        // correct the parsed value to the libx264 csp value
       #if X264 CHROMA FORMAT
180.
                       static const uint8_t output_csp_fix[] = { X264_CHROMA_FORMAT, X264_CSP_RGB };
181.
182.
       #else
183.
                        static const uint8_t output_csp_fix[] = { X264_CSP_I420, X264_CSP_I422, X264_CSP_I444, X264_CSP_RGB };
184.
       #endif
185
                        param->i_csp = output_csp = output_csp_fix[output_csp];
186
                        break;
```

```
187
                    case OPT INPUT RANGE:
188.
                       FAIL IF ERROR( parse enum value( optarg, range names, &input opt.input range ), "Unknown input range `%s'\n", optarg
189
                       input opt.input range += RANGE AUTO;
190.
                       break:
                    case OPT RANGE:
191.
                       FAIL_IF_ERROR( parse_enum_value( optarg, range_names, ¶m->vui.b_fullrange ), "Unknown range `%s'\n", optarg );
192.
193.
                       input_opt.output_range = param->vui.b_fullrange += RANGE_AUTO;
                       break;
194
195
                    default:
196.
       generic_option:
197.
198.
                       if( long_options_index < 0 )</pre>
199.
200.
                            for( int i = 0; long_options[i].name; i+
201.
                               if( long options[i].val == c )
202.
203.
                                    long options index = i;
204.
                                   break:
205.
                           if( long_options_index < 0 )</pre>
206
207.
                            {
208
                                /* getopt_long already printed an error message
209.
                                return -1;
210.
211.
212.
                       //解析以字符串方式输入的参数
213.
                        //即选项名称和选项值都是字符串
214.
                       b_error |= x264_param_parse( param, long_options[long_options_index].name, optarg );
215.
216.
217.
218.
               if( b error )
219.
                    const char *name = long_options_index > 0 ? long_options[long_options_index].name : argv[optind-2];
220.
                   x264 cli log( "x264", X264_LOG_ERROR, "invalid argument: %s = %s\n", name, optarg );
221.
222.
                   return -1;
223.
               }
224.
225
226.
            /* If first pass mode is used, apply faster settings. */
227.
            if( b turbo )
228.
               x264_param_apply_fastfirstpass( param );
229.
230.
          /* Apply profile restrictions. */
231.
            //设置profile
232.
           if( x264_param_apply_profile( param, profile ) < 0 )</pre>
233.
               return -1:
234.
235.
            /* Get the file name */
           FAIL_IF_ERROR( optind > argc - 1 || !output_filename, "No %s file. Run x264 --help for a list of options.\n"
236.
237.
                          optind > argc - 1 ? "input" : "output" )
238.
            //根据文件名的后缀确定输出的文件格式(raw H264, flv, mp4...)
239.
            if( select_output( muxer, output_filename, param ) )
240.
               return -1;
241.
            FAIL_IF_ERROR( cli_output.open_file( output_filename, &opt->hout, &output_opt ), "could not open output file `%s'\n", output_fil
       ename )
242.
          //输入文件路径
243.
            input filename = argv[optind++];
244.
           video_info_t info = {0};
245.
            char demuxername[5];
246.
247.
            /* set info flags to be overwritten by demuxer as necessary. */
248.
          //设置info结构体
249.
            info.csp
                           = param->i csp;
250.
           info.fps_num = param->i_fps_num;
251.
            info.fps_den
                           = param->i_fps_den;
252
           info.fullrange = input_opt.input_range == RANGE_PC;
253.
            info.interlaced = param->b_interlaced;
254.
           if( param->vui.i_sar_width > 0 && param->vui.i_sar_height > 0 )
255.
256.
               info.sar_width = param->vui.i_sar_width;
257.
               info.sar_height = param->vui.i_sar_height;
258.
259.
            info.tff
                           = param->b tff;
260.
           info.vfr = param->b vfr input;
261.
           input opt.seek = opt->i seek;
262.
263.
            input opt.progress = opt->b progress;
264.
           input_opt.output_csp = output_csp;
265.
            //设置输入文件的格式(yuv,y4m...)
266.
           if( select_input( demuxer, demuxername, input_filename, &opt->hin, &info, &input_opt ) )
267.
               return -1;
268.
269.
            FAIL_IF_ERROR( !opt->hin && cli_input.open_file( input_filename, &opt->hin, &info, &input_opt ),
270.
                    "could not open input file `%s'\n", input_filename )
271.
272.
            x264_reduce_fraction( &info.sar_width, &info.sar_height );
273.
            x264 reduce fraction( &info.fps num, &info.fps den );
            x264_cli_log( demuxername, X264_LOG_INFO, "%dx%d%c %u:%u @ %u/%u fps (%cfr)\n", info.width,
274.
                         info.height, info.interlaced ? 'i' : 'p', info.sar_width, info.sar_height,
275.
```

```
276
                          info.fps_num, info.fps_den, info.vfr ? 'v' : 'c' );
277.
278.
        if( tcfile_name )
279.
280.
                FAIL_IF_ERROR( b_user_fps, "--fps + --tcfile-in is incompatible.\n" )
                FAIL\_IF\_ERROR(\ timecode\_input.open\_file(\ tcfile\_name,\ \&opt->hin,\ \&info,\ \&input\_opt\ ),\ "timecode\_input\ failed\n"\ )
281.
282.
                cli input = timecode input;
283.
284.
        else FAIL_IF_ERROR( !info.vfr && input_opt.timebase, "--timebase is incompatible with cfr input\n" )
285.
286.
           /* init threaded input while the information about the input video is unaltered by filtering */
287.
       #if HAVE THREAD
       if( info.thread safe && (b thread input || param->i threads > 1
288.
289.
                \label{eq:continuous} $$\| (param->i\_threads == X264\_THREADS\_AUTO \&\& x264\_cpu\_num\_processors() > 1)) ) $$
290.
291.
                if( thread_input.open_file( NULL, &opt->hin, &info, NULL ) )
292.
293.
                    fprintf( stderr, "x264 [error]: threaded input failed\n" );
294.
                    return -1;
295.
296.
               cli input = thread input;
297.
298.
299.
            /* override detected values by those specified by the user */
300.
            if( param->vui.i sar width > 0 && param->vui.i sar height > 0 )
301.
302.
303.
                info.sar width = param->vui.i sar width;
304.
               info.sar_height = param->vui.i_sar_height;
305.
        if( b_user_fps )
306.
307.
308.
                info.fps num = param->i fps num;
309.
                info.fps_den = param->i_fps_den;
310.
311.
            if( !info.vfr )
312.
        {
313.
                info.timebase num = info.fps den;
                info.timebase den = info.fps num:
314.
315.
316.
           if( !tcfile name && input opt.timebase )
317.
318.
                uint64 t i user timebase num;
319.
                uint64 t i user timebase den:
320.
                int ret = sscanf( input_opt.timebase, "%"SCNu64"/%"SCNu64, &i_user_timebase_num, &i_user_timebase_den );
321.
                FAIL\_IF\_ERROR( \ !ret, \ "invalid argument: \ timebase = \$s\n", \ input\_opt.timebase \ )
322.
                else if( ret == 1 )
323.
324.
                    i user timebase num = info.timebase num;
325.
                    i_user_timebase_den = strtoul( input_opt.timebase, NULL, 10 );
326.
327.
                FAIL_IF_ERROR( i_user_timebase_num > UINT32_MAX || i_user_timebase_den > UINT32_MAX,
328.
                                "timebase you specified exceeds H.264 maximum\n" )
                opt->timebase convert multiplier = ((double)i user timebase den / info.timebase den)
329.
                                                 * ((double)info.timebase_num / i_user_timebase_num);
330.
331.
                info.timebase num = i user timebase num;
               info.timebase_den = i_user_timebase_den;
332.
333.
                info.vfr = 1:
334.
335.
            if( b_user_interlaced )
336.
337.
                info.interlaced = param->b_interlaced;
338.
                info.tff = param->b tff;
339.
340.
            if( input_opt.input_range != RANGE_AUTO )
341.
                info.fullrange = input_opt.input_range;
342.
343.
            //初始化滤镜filter
           //filter可以认为是一种"扩展"了的输入源
344.
345.
            if( init vid filters( vid filters, &opt->hin, &info, param, output csp ) )
346.
               return -1;
347.
348.
            /st set param flags from the post-filtered video st/
349.
            param->b_vfr_input = info.vfr;
350.
            param->i_fps_num = info.fps_num;
351.
            param->i_fps_den = info.fps_den;
352.
           param->i_timebase_num = info.timebase_num;
            param->i_timebase_den = info.timebase_den;
353.
354.
           param->vui.i_sar_width = info.sar_width;
355.
            param->vui.i_sar_height = info.sar_height;
356.
357.
            info.num frames = X264 MAX( info.num frames - opt->i seek, 0 );
358.
            if( (!info.num_frames || param->i_frame_total < info.num_frames)</pre>
                && param->i frame total > 0 )
359.
360.
               info.num frames = param->i frame total;
361.
            param->i frame total = info.num frames;
362.
363.
            if( !b_user_interlaced && info.interlaced )
364
365.
        #if HAVE INTERLACED
366.
              x264_cli_log( "x264", X264_LOG_WARNING, "input appears to be interlaced, enabling %cff interlaced mode.\n"
```

```
If you want otherwise, use --no-interlaced or --%cff\n",
367.
368.
                            info.tff ? 't' : 'b', info.tff ? 'b' : 't' );
369.
               param->b interlaced = 1;
               param->b_tff = !!info.tff;
370.
371.
       #else
               x264\_cli\_log(\ "x264",\ X264\_LOG\_WARNING,\ "input\ appears\ to\ be\ interlaced,\ but\ not\ compiled\ with\ interlaced\ support\n"\ );
372.
373.
       #endif
374.
       }
375.
           \prime * if the user never specified the output range and the input is now rgb, default it to pc */
376.
       int csp = param->i_csp & X264_CSP_MASK;
377.
           if( csp >= X264_CSP_BGR && csp <= X264_CSP_RGB )</pre>
378.
379.
               if( input_opt.output_range == RANGE_AUTO )
380.
                 param->vui.b_fullrange = RANGE_PC;
381.
               /* otherwise fail if they specified tv */
382.
               FAIL IF ERROR( !param->vui.b fullrange, "RGB must be PC range"
383.
384.
385.
           /* Automatically reduce reference frame count to match the user's target level
          * if the user didn't explicitly set a reference frame count. */
386.
           if( !b user ref )
387.
388.
389.
               390.
               for( int i = 0; x264_levels[i].level_idc != 0; i++ )
391.
                   if( param->i_level_idc == x264_levels[i].level_idc )
392
393.
                       while( mbs * param->i_frame_reference > x264_levels[i].dpb && param->i_frame_reference > 1 )
394.
                          param->i_frame_reference--;
395.
396.
397.
398.
399.
400.
           return 0:
401.
```

下面简单梳理parse()的流程:

- (1) 调用x264_param_default()为存储参数的结构体x264_param_t赋默认值
- (2) 调用x264_param_default_preset()为x264_param_t赋值
- (3) 在一个大循环中调用getopt_long()逐个解析输入的参数,并作相应的处理。举几个例子:

a)"-h":调用help()打开帮助菜单。

b)"-V"调用print_version_info()打印版本信息。

c)对于长选项,调用x264_param_parse()进行处理。

- (4) 调用select_input()解析输出文件格式(例如raw, flv, MP4...)
- (5) 调用select_output()解析输入文件格式(例如yuv, y4m...)

下文按照顺序记录parse()中涉及到的函数:

```
x264_param_default()
x264_param_default_preset()
help()
print_version_info()
x264_param_parse()
select_input()
select_output()
```

x264 param default()

x264_param_default()是一个x264的API。该函数用于设置x264中x264_param_t结构体的默认值。函数的声明如下所示。

```
1. /* x264_param_default:
2. * fill x264_param_t with default values and do CPU detection */
3. void x264_param_default( x264_param_t * );
```

x264_param_default()的定义如下所示。

```
[cpp] 📳 📑
1.
2.
     * x264_param_default:
3.
     //初始化参数默认值
4.
5.
     void x264 param default( x264 param t *param )
6.
     {
7.
     memset( param, 0, sizeof( x264_param_t ) );
8.
9.
10.
     /* CPU autodetect */
11.
         param->cpu = x264_cpu_detect();
12.
         param->i_threads = X264_THREADS_AUTO;
         param->i lookahead threads = X264 THREADS AUTO;
```

```
14.
           param->b deterministic = 1:
 15.
           param->i_sync_lookahead = X264_SYNC_LOOKAHEAD_AUTO;
 16.
           /* Video properties */
param->i_csp = X264_CHROMA_FORMAT ? X264_CHROMA_FORMAT : X264_CSP_I420;
 17.
 18.
 19.
           param->i_width
                                  = 0;
           param->i_height = 0;
 20.
 21.
           param->vui.i_sar_width = 0;
 22.
           param->vui.i_sar_height= 0;
 23.
           param->vui.i_overscan = 0; /* undef */
 24.
           param->vui.i_vidformat = 5; /* undef */
 25.
           param->vui.b_fullrange = -1; /* default depends on input */
           param->vui.i_colorprim = 2; /* undef */
 26.
 27.
           param->vui.i_transfer = 2; /* undef */
           param->vui.i_colmatrix = -1; /* default depends on input */
 28.
           param->vui.i_chroma_loc= 0; /* left center */
 29.
           param->i_fps_num = 25;
 30.
 31.
           param->i fps den
                                  = 1:
           param->i_level_idc = -1;
 32.
           param->i_slice_max_size = 0;
 33.
 34.
           param->i_slice_max_mbs = 0;
 35.
           param->i_slice_count = 0;
 36.
 37.
           /* Encoder parameters */
       //编码参数--最常见
 38.
 39.
           param->i_frame_reference = 3;
 40.
           param->i_keyint_max = 250;
 41.
           param->i_keyint_min = X264_KEYINT_MIN_AUTO;
 42.
           param->i bframe = 3;
 43.
           param->i scenecut threshold = 40:
           param->i bframe adaptive = X264 B ADAPT FAST;
 44.
 45.
           param->i bframe bias = 0;
 46.
           param->i_bframe_pyramid = X264_B_PYRAMID_NORMAL;
 47.
           param->b interlaced = 0;
 48.
           param->b_constrained_intra = 0;
 49.
 50.
           param->b_deblocking_filter = 1;
 51.
           param->i_deblocking_filter_alphac0 = 0;
 52.
           param->i_deblocking_filter_beta = 0;
 53.
 54.
           param->b cabac = 1;
 55.
           param->i_cabac_init_idc = 0;
 56.
       //码率控制模块 Rate Control
 57.
           param->rc.i rc method = X264 RC CRF;
           param->rc.i bitrate = 0;
 58.
           param->rc.f rate tolerance = 1.0;
 59.
 60.
           param->rc.i vbv max bitrate = 0;
 61.
           param->rc.i_vbv_buffer_size = 0;
 62.
           param->rc.f vbv buffer init = 0.9;
 63.
           param->rc.i_qp_constant = 23 + QP_BD_OFFSET;
 64.
           param->rc.f_rf_constant = 23;
 65.
           param -> rc.i_qp_min = 0;
 66.
           param->rc.i_qp_max = QP_MAX;
 67.
           param->rc.i_qp_step = 4;
           param->rc.f_ip_factor = 1.4;
 68.
           param->rc.f_pb_factor = 1.3;
 69.
 70.
           param->rc.i_aq_mode = X264_AQ_VARIANCE;
 71.
           param->rc.f aq strength = 1.0;
          param->rc.i lookahead = 40;
 72.
 73.
 74.
           param->rc.b stat write = 0:
           param->rc.psz_stat_out = "x264_2pass.log";
 75.
 76.
           param->rc.b_stat_read = 0;
           param->rc.psz_stat_in = "x264_2pass.log";
 77.
           param->rc.f_qcompress = 0.6;
 78.
 79.
           param->rc.f_qblur = 0.5;
 80.
           param->rc.f_complexity_blur = 20;
           param->rc.i_zones = 0;
 81.
 82.
          param->rc.b_mb_tree = 1;
 83.
 84.
       /* Log */
           //日志模块
 85.
 86.
          param->pf_log = x264_log_default;
           param->p_log_private = NULL;
 87.
       param->i_log_level = X264_LOG_INFO;
 88.
 89.
 90.
           //分析模块 Analysis
 91.
           param->analyse.intra = X264_ANALYSE_I4x4 | X264_ANALYSE_I8x8;
 92.
 93.
           param->analyse.inter = X264_ANALYSE_I4x4 | X264_ANALYSE_I8x8
 94.
                               | X264_ANALYSE_PSUB16x16 | X264_ANALYSE_BSUB16x16;
 95.
           param->analyse.i_direct_mv_pred = X264_DIRECT_PRED_SPATIAL;
 96.
           param->analyse.i_me_method = X264_ME_HEX;
 97.
           param->analyse.f_psy_rd = 1.0;
 98.
           param->analyse.b_psy = 1;
 99.
           param->analyse.f_psy_trellis = 0;
100.
           param->analyse.i me range = 16;
           param->analyse.i_subpel_refine = 7;
101.
           param->analyse.b_mixed_references = 1;
102.
103.
           param->analyse.b chroma me = 1:
104.
           param->analyse.i mv range thread = -1;
```

```
105.
           param->analyse.i_mv_range = -1; // set from level_idc
106.
           param->analyse.i_chroma_qp_offset = 0;
107.
           param->analyse.b_fast_pskip = 1;
108.
           param->analyse.b_weighted_bipred = 1;
109.
           param->analyse.i_weighted_pred = X264_WEIGHTP_SMART;
110.
           param->analyse.b dct decimate = 1;
111.
           param->analyse.b transform 8x8 = 1:
           param->analyse.i trellis = 1;
112.
           param->analyse.i luma deadzone[0] = 21;
113.
114.
           param->analyse.i_luma_deadzone[1] = 11;
115.
           param->analyse.b psnr = 0;
116.
           param->analyse.b_ssim = 0;
117.
118.
       param->i_cqm_preset = X264_CQM_FLAT;
119.
           memset( param->cqm_4iy, 16, sizeof( param->cqm_4iy ) );
120.
           memset( param->cqm_4py, 16, sizeof( param->cqm_4py ) );
121.
           memset( param->cqm_4ic, 16, sizeof( param->cqm_4ic ) );
122.
           memset( param->cqm_4pc, 16, sizeof( param->cqm_4pc ) );
           memset( param->cqm_8iy, 16, sizeof( param->cqm_8iy ) );
123.
124.
           memset( param->cqm_8py, 16, sizeof( param->cqm_8py ) );
125.
           memset( param->cqm 8ic, 16, sizeof( param->cqm 8ic ) );
126.
           memset( param->cqm_8pc, 16, sizeof( param->cqm_8pc ) );
127.
128.
       param->b repeat headers = 1;
129.
           param -> b annexb = 1:
           param->b_aud = 0;
130.
131.
           param->b vfr input = 1;
132.
           param->i nal hrd = X264 NAL HRD NONE;
133.
           param->b_tff = 1;
134.
           param->b_pic_struct = 0;
135.
           param->b fake interlaced = 0;
136.
           param->i_frame_packing = -1;
137.
           param->b_opencl = 0;
           param->i_opencl_device = 0;
138.
139.
           param->opencl device id = NULL;
140.
           param->psz_clbin_file = NULL;
141. }
```

从源代码可以看出,x264_param_default()对输入的存储参数的结构体x264_param_t的成员变量进行了赋值工作。

x264_param_default_preset()

x264_param_default_preset()是一个libx264的API,用于设置x264的preset和tune。该函数的声明如下所示。

```
1. /* Multiple tunings can be used if separated by a delimiter in ",./-+",
2. * however multiple psy tunings cannot be used.
3. * film, animation, grain, stillimage, psnr, and ssim are psy tunings.
4. *
5. * returns 0 on success, negative on failure (e.g. invalid preset/tune name). */
6. int x264 param default preset(x264 param t *, const char *preset, const char *tune );
```

x264_param_default_preset()的定义如下所示。

```
[cpp] 📳 👔
1.
      //设置nreset, tune
2.
      int x264_param_default_preset( x264_param_t *param, const char *preset, const char *tune )
3.
4.
         x264_param_default( param );
5.
 6.
          if( preset && x264_param_apply_preset( param, preset ) < 0 )</pre>
     return -1;
8.
9.
10.
      //设置tune
          if( tune && x264_param_apply_tune( param, tune ) < 0 )
11.
            return -1;
12.
13.
          return 0:
14.
```

从源代码可以看出,x264_param_default_preset()调用x264_param_apply_preset()设置preset,调用x264_param_apply_tune()设置tune。记录一下这两个函数。

x264_param_apply_preset()

x264 param apply preset()用于设置preset。该函数的定义如下所示。

```
1. //设置preset
2. static int x264_param_apply_preset( x264_param_t *param, const char *preset )
{
4. char *end;
5. int i = strtol( preset, &end, 10 );
6. if( *end == 0 && i >= 0 && i < sizeof(x264_preset_names)/sizeof(*x264_preset_names)-1 )
7. preset = x264_preset_names[i];
8.
```

```
//几种不同的preset设置不同的参数
10.
          if( !strcasecmp( preset, "ultrafast" ) )
11.
12.
              param->i_frame_reference = 1;
13.
              param->i_scenecut_threshold = 0;
14.
              param->b_deblocking_filter = 0;//不使用去块滤波
              param->b cabac = 0;//不使用CABAC
15.
              param->i_bframe = 0;//不使用B帧
16.
17.
              param->analyse.intra = 0;
18.
              param->analyse.inter = 0;
              param->analyse.b transform 8x8 = 0;//不使用8x8DCT
19.
              param->analyse.i me method = X264 ME DIA;//运动搜索方法使用"Diamond
20.
21.
              param->analyse.i subpel refine = 0;
              param -> rc.i_aq_mode = 0;
22.
23.
              param->analyse.b mixed references = 0;
24.
              param->analyse.i trellis = 0;
25.
              param->i_bframe_adaptive = X264_B_ADAPT_NONE;
26.
              param->rc.b_mb_tree = 0;
27.
              param->analyse.i_weighted_pred = X264_WEIGHTP_NONE;//不使用加权
28.
              param->analyse.b_weighted_bipred = 0;
29.
              param->rc.i_lookahead = 0;
30.
31.
          else if( !strcasecmp( preset, "superfast" ) )
32.
33.
              param->analyse.inter = X264_ANALYSE_I8x8|X264_ANALYSE_I4x4;
34.
              param->analyse.i me method = X264 ME DIA;//钻石模板
35.
              param->analyse.i_subpel_refine = 1;//亚像素运动估计质量为1
36.
              param->i frame reference = 1;
37.
              param->analyse.b mixed references = 0:
38.
              param->analyse.i trellis = 0;
39.
              param->rc.b mb tree = 0;
40.
              param->analyse.i_weighted_pred = X264_WEIGHTP_SIMPLE;
41.
              param -> rc.i_lookahead = 0;
42.
43.
          else if( !strcasecmp( preset, "veryfast" ) )
44.
45.
              param->analyse.i_me_method = X264_ME_HEX;//六边形模板
46.
              param->analyse.i_subpel_refine = 2;
47.
              param->i_frame_reference = 1;
48.
              param->analyse.b mixed references = 0;
49.
              param->analyse.i trellis = 0;
              param->analyse.i weighted pred = X264 WEIGHTP SIMPLE;
50.
51.
              param->rc.i lookahead = 10;
52.
          else if( !strcasecmp( preset, "faster" ) )
53.
54.
55.
              param->analyse.b_mixed_references = 0;
56.
              param->i_frame_reference = 2;
57.
              param->analyse.i_subpel_refine = 4;
              param->analyse.i_weighted_pred = X264_WEIGHTP_SIMPLE;
58.
59.
              param->rc.i lookahead = 20;
60.
61.
          else if( !strcasecmp( preset, "fast" ) )
62.
63.
              param->i frame reference = 2;
64.
              param->analyse.i_subpel_refine = 6;
              param->analyse.i weighted pred = X264 WEIGHTP SIMPLE;
65.
              param->rc.i lookahead = 30:
66.
67.
      else if( !strcasecmp( preset, "medium" ) )
68.
69.
70.
              /* Default is medium */
71.
72.
         else if( !strcasecmp( preset, "slow" ) )
73.
              param->analyse.i_me_method = X264_ME_UMH;//UMH相对复杂
74.
              param->analyse.i_subpel_refine = 8;//亚像素运动估计质量为8
75.
76.
              param->i_frame_reference = 5;
77.
              param->i bframe adaptive = X264 B ADAPT TRELLIS;
78.
              param->analyse.i_direct_mv_pred = X264_DIRECT_PRED_AUTO;
79.
              param->rc.i lookahead = 50;
80.
          else if( !strcasecmp( preset, "slower" ) )
81.
82.
83.
              param->analyse.i_me_method = X264_ME_UMH;
84.
              param->analyse.i_subpel_refine = 9;
85.
              param->i_frame_reference = 8;
86.
              param->i_bframe_adaptive = X264_B_ADAPT_TRELLIS;
87.
              param->analyse.i_direct_mv_pred = X264_DIRECT_PRED_AUTO;
88.
              param->analyse.inter |= X264_ANALYSE_PSUB8x8;
89.
              param->analyse.i_trellis = 2;
90.
              param->rc.i_lookahead = 60;
91.
      else if( !strcasecmp( preset, "veryslow" ) )
92.
93.
94.
              param->analyse.i me method = X264 ME UMH:
95.
              param->analyse.i subpel refine = 10;
96.
              param->analyse.i me range = 24;
97.
              param->i_frame_reference = 16;
98.
              param->i_bframe_adaptive = X264_B_ADAPT_TRELLIS;
99.
              param->analyse.i_direct_mv_pred = X264_DIRECT_PRED_AUTO;
```

```
param->analyse.inter |= X264_ANALYSE_PSUB8x8;
101.
               param->analyse.i_trellis = 2;
102.
               param->i bframe = 8;
103.
               param->rc.i_lookahead = 60;
104.
            else if( !strcasecmp( preset, "placebo" ) )
105.
       {
106.
107.
               param->analyse.i me method = X264 ME TESA;//TESA很慢
108.
               param->analyse.i_subpel_refine = 11;
109.
               param->analyse.i_me_range = 24;
110.
               param->i_frame_reference = 16;
111.
               param->i_bframe_adaptive = X264_B_ADAPT_TRELLIS;
112.
               param->analyse.i_direct_mv_pred = X264_DIRECT_PRED_AUTO;
113.
               param->analyse.inter |= X264_ANALYSE_PSUB8x8;
114.
               param->analyse.b_fast_pskip = 0;
115.
               param->analyse.i_trellis = 2;
116.
               param->i bframe = 16;
117.
               param->rc.i_lookahead = 60;
118.
119.
           else
120.
          {
               x264_log( NULL, X264_LOG_ERROR, "invalid preset '%s'\n", preset );
121.
122.
               return -1;
123.
124.
           return 0:
125.
     }
```

可以看出x264_param_apply_preset()通过strcasecmp()比较字符串的方法得到输入的preset类型;然后根据preset类型,设定 x264_param_t中相应的参数。

x264_param_apply_tune()

x264_param_apply_tune()用于设置tune。该函数的定义如下所示。

```
[cpp] 📳 🔝
      //设置tune
2.
      static int x264_param_apply_tune( x264_param_t *param, const char *tune )
3.
      {
4.
          char *tmp = x264 malloc( strlen( tune ) + 1 );
5.
          if( !tmp )
            return -1;
6.
          tmp = strcpy( tmp, tune );
7.
        //分解一个字符串为一个字符串数组。第2个参数为分隔符
8.
          char *s = strtok( tmp, ",./-+" );
9.
      int psy_tuning_used = 0;
10.
11.
12.
      //设置
13.
          //这里是循环的,可以设置多次
14.
         while( s )
15.
16.
              if( !strncasecmp( s, "film", 4 ) )
17.
18.
                  if( psy tuning used++ ) goto psy failure;
19.
                  param->i_deblocking_filter_alphac0 = -1;
                  param->i deblocking filter beta = -1;
20.
21.
                  param->analyse.f psy trellis = 0.15;
22.
23.
              else if( !strncasecmp( s, "animation", 9 ) )
24.
25.
                  if( psy_tuning_used++ ) goto psy_failure;
26.
                  \verb|param->i_frame_reference| = param->i_frame_reference| > 1 ? param->i_frame_reference*2 :
27.
                  param->i_deblocking_filter_alphac0 = 1;
28.
                  param->i_deblocking_filter_beta = 1;
29
                  param->analyse.f_psy_rd = 0.4;
30.
                  param->rc.f_aq_strength = 0.6;
31.
                  param->i bframe += 2;
32.
33.
              else if( !strncasecmp( s, "grain", 5 ) )
34.
35.
                  if( psy tuning used++ ) goto psy failure;
                  param->i deblocking filter alphac0 = -2;
36.
                  param->i_deblocking_filter_beta = -2;
37.
38.
                  param->analyse.f_psy_trellis = 0.25;
39.
                  param->analyse.b dct decimate = 0;
40
                  param->rc.f pb factor = 1.1;
41.
                  param->rc.f_ip_factor = 1.1;
42
                  param->rc.f_aq_strength = 0.5;
43.
                  param->analyse.i_luma_deadzone[0] = 6;
44.
                  param->analyse.i_luma_deadzone[1] = 6;
45.
                  param->rc.f_qcompress = 0.8;
46.
47.
              else if( !strncasecmp( s, "stillimage", 10 ) )
48.
49.
                  if( psy tuning used++ ) goto psy failure;
                  param->i_deblocking_filter_alphac0 = -3;
50.
51.
                  param->i deblocking filter beta = -3;
                  param->analyse.f_psy_rd = 2.0;
52.
53.
                  param->analyse.f psy trellis = 0.7;
54.
                  param -> rc.f_aq_strength = 1.2;
55
              }
```

```
else if( !strncasecmp( s, "psnr", 4 ) )
 57.
                {
 58.
                    if( psy_tuning_used++ ) goto psy_failure;
 59.
                    param->rc.i_aq_mode = X264_AQ_NONE;
 60.
                    param->analyse.b psy = 0;
 61.
               else if( !strncasecmp( s, "ssim", 4 ) )
 62.
 63.
                {
                    if( psy_tuning_used++ ) goto psy_failure;
 64.
                    param->rc.i_aq_mode = X264_AQ_AUTOVARIANCE;
 65.
 66.
                    param->analyse.b_psy = 0;
 67.
                }
 68.
                else if( !strncasecmp( s, "fastdecode", 10 ) )
 69.
 70.
                    param->b_deblocking_filter = 0;
 71.
                    param->b_cabac = 0;
 72.
                    param->analyse.b_weighted_bipred = 0;
 73.
                    param->analyse.i_weighted_pred = X264_WEIGHTP_NONE;
 74.
               }
 75.
                else if( !strncasecmp( s. "zerolatency". 11 ) )
 76.
               {
 77.
                    //zerolatencv速度快
                    param->rc.i lookahead = 0;
 78.
 79.
                    param->i sync lookahead = 0;
 80.
                    param->i_bframe = 0;//不使用B帧
 81.
                    param->b_sliced_threads = 1;
 82.
                    param->b_vfr_input = 0;
 83.
                    param -> rc.b_mb_tree = 0;
 84.
 85.
                else if( !strncasecmp( s, "touhou", 6 ) )
 86.
 87.
                    if( psy tuning used++ ) goto psy failure;
 88.
                    param->i frame reference = param->i frame reference > 1 ?
                    param->i deblocking filter alphac0 = -1;
 89.
 90.
                    param->i deblocking filter beta = -1;
 91.
                    param->analyse.f psy trellis = 0.2;
                    param->rc.f aq strength = 1.3;
 92.
                    if( param->analyse.inter & X264_ANALYSE_PSUB16x16 )
 93.
                       param->analyse.inter |= X264_ANALYSE_PSUB8x8;
 94.
 95.
                }
 96
               else
 97.
 98.
                    x264_log( NULL, X264_LOG_ERROR, "invalid tune '%s'\n",
 99.
                    x264 free( tmp );
100.
                    return -1;
101.
102.
                if( 0 )
103.
104.
           psy_failure:
                    x264 log( NULL, X264 LOG WARNING, "only 1 psy tuning can be used: ignoring tune %s\n", s );
105.
106.
                s = strtok( NULL, ",./-+" );
107.
108.
109.
            x264 free( tmp );
110.
            return 0;
111.
```

可以看出x264_param_apply_tune()首先通过strtok()得到存储tune[]数组;然后通过strncasecmp()比较字符串的方法判断当前的tune类型;最后根据tune类型,设定 x26 4_param_t中相应的参数。

help()

help()用于打印帮助菜单。在x264命令行程序中添加"-h"参数后会调用该函数。该函数的定义如下所示。

```
[cpp] 📳 📑
1.
      //longhelp标识是否展开更长的帮助菜单
2.
      {f static} {f void} help( {f x264\_param\_t} *defaults, {f int} longhelp )
3.
4.
      {
5.
          char buf[50];
      //H0(),H1(),H2()都是printf()
6.
7.
          //H1(),H2()只有"长帮助菜单"的情况下才会调用printf()
8.
      #define H0 printf
9.
      #define H1 if(longhelp>=1) printf
10.
      #define H2 if(longhelp==2) printf
11.
          H0( "x264 core:%d%s\n"
12.
             "Syntax: x264 [options] -o outfile infile\n"
13.
14.
              "Infile can be raw (in which case resolution is required),\n"
              " or YUV4MPEG (*.y4m),\n"
15.
              " or Avisynth if compiled with support (%s).\n"
16.
17.
              " or libav* formats if compiled with lavf support (%s) or ffms support (%s).\n"
              "Outfile type is selected by filename:\n"
18.
              " .264 -> Raw bytestream\n"
19.
              " .mkv -> Matroska\n"
20.
21.
                .flv -> Flash Video\n"
              " .mp4 -> MP4 if compiled with GPAC or L-SMASH support (%s)\n" \,
22.
              "Output hit denth. %d (configured at compile tim
```

```
output bit depth. ou (confiigured at compile time)(h
 24.
 25.
                "Options:\n"
 26.
                "\n"
                " -h, --help
" --longhelp
 27.
                                                 List basic options\n'
 28.
                                                List more options\n"
                       --fullhelp
                                                 List all options\n"
 29.
 30.
               X264 BUILD, X264 VERSION,
 31.
       #if HAVE_AVS
 32.
 33.
                "yes",
 34.
       #else
 35.
 36.
       #endif
 37.
       #if HAVE_LAVF
 38.
              "yes",
 39.
 40.
 41.
 42.
       #if HAVE_FFMS
 43.
                "yes",
       #else
 44.
                "no",
 45.
       #endif
 46.
 47.
       #if HAVE GPAC
 48.
              "gpac",
 49.
        #elif HAVE LSMASH
             "lsmash",
 50.
 51.
 52.
 53.
       x264_bit_depth
 54.
 55.
              );
       H0( "Example usage:\n" );
 56.
           H0( "\n" );
 57.
       H0(" Constant quality mode:\n");
H0(" x264 --crf 24 -o <output
 58.
                            x264 --crf 24 -o <output> <input>\n" );
 59.
       H0( "\n" );
 60.
       H0( " Two-pass with a bitrate of 1000kbps:\n" );
H0( " x264 --pass 1 --bitrate 1000 -o <output> <input>\n" );
 61.
 62.
           H0("
 63.
                             x264 --pass 2 --bitrate 1000 -o <output> <input>\n" );
       H0( "\n" );
 64.
           H0(" Lossless:\n");
H0(" x264 --qp 0 -o <output> <input>\n");
 65.
 66.
 67.
           H0( "\n" );
       H0( " Maximum PSNR at the cost of speed and visual quality:\n" );
H0( " x264 --preset placebo --tune psnr -o <output> <input>\
           H0( " x264 --preset placebo --tune psnr -o <output> <input>\n" ); H0( "\n" );
 68.
 69.
 70.
       HO( " Constant bitrate at 1000kbps with a 2 second-buffer:\n");
HO( " x264 --vbv-bufsize 2000 --bitrate 1000 -o <output> <input>\n" );
 71.
 72.
           H0( "\n" );
 73.
           H0( "Presets:\n" );
 74.
 75.
           H0( "\n" );
           H0( " --profile <string> Force the limits of an H.264 profile\n"
 76.
 77.
                                                     Overrides all settings.\n" );
 78.
        H2 (
       #if X264 CHROMA_FORMAT <= X264_CSP_I420
 79.
 80.
       #if BIT_DEPTH==8
 81.
                                                      - baseline:\n"
 82.
                                                       --no-8x8dct --bframes 0 --no-cabac\n
 83.
                                                        --cqm flat --weightp 0\n"
                                                       No interlaced.\n"
 84.
 85.
                                                       No lossless.\n"
                                                       main:\n"
 86.
                                                        --no-8x8dct --cqm flat\n"
 87.
                                                       No lossless.\n"
 88.
                                                       high:\n"
 89.
 90.
                                                       No lossless.\n"
 91.
       #endif
 92.
                                                       high10:\n"
 93.
                                                       No lossless.\n"
 94.
                                                       Support for bit depth 8-10.\n"
 95.
       #endif
 96.
       #if X264_CHROMA_FORMAT <= X264_CSP_I422</pre>
 97.
                                                      - high422:\n"
                                                       No lossless.\n"
 98.
 99.
                                                       Support for bit depth 8-10.\n"
100.
                                                       Support for 4:2:0/4:2:2 chroma subsampling.\n"
101.
       #endif
102.
                                                       high444:\n"
                                                       Support for bit depth 8-10.\n"
103.
                                                       Support for 4:2:0/4:2:2/4:4:4 chroma subsampling.\n");
104.
105.
                else H0(
106.
       #if X264_CHROMA_FORMAT <= X264_CSP_I420
107.
       #if BIT_DEPTH==8
108.
109.
                "baseline, main, high, "
110.
111.
112.
       #endif
       #if X264_CHROMA_FORMAT <= X264_CSP_I422
113.
            "high422,"
```

```
115.
        #endif
                "high444\n"
116.
117.
                       );
118
            H0( "
                       --preset <string>
                                                Use a preset to select encoding settings [medium]\n"
119.
                                                     Overridden by user settings.\n");
120
           H2( "
                                                     - ultrafast:\n"
121.
                                                       --no-8x8dct --aq-mode 0 --b-adapt 0\n"
122.
                                                       --bframes 0 --no-cabac --no-deblock\n"
123.
                                                       --no-mbtree --me dia --no-mixed-refs\n"
124.
                                                       --partitions none --rc-lookahead 0 --ref 1\n'
125.
                                                       --scenecut 0 --subme 0 --trellis 0\n"
                                                       --no-weightb --weightp 0\n"
126.
127.
                                                     - superfast:\n"
                                                      --no-mbtree --me dia --no-mixed-refs\n"
128.
                                                       --partitions i8x8,i4x4 --rc-lookahead 0\n"
129.
                                                      --ref 1 --subme 1 --trellis 0 --weightp 1\n"
130.
131.
                                                     - vervfast:\n"
132.
                                                      --no-mixed-refs --rc-lookahead 10\n"
133.
                                                       --ref 1 --subme 2 --trellis 0 --weightp 1\n"
134.
                                                      faster:\n"
135
                                                       --no-mixed-refs --rc-lookahead 20\n"
136.
                                                       --ref 2 --subme 4 --weightp 1\n"
137.
                                                      fast:\n"
                                                      --rc-lookahead 30 --ref 2 --subme 6\n
138.
139.
                                                       --weightp 1\n'
140.
                                                      medium:\n"
141.
                                                       Default settings apply.\n"
142.
                                                      slow:\n"
143.
                                                       --b-adapt 2 --direct auto --me umh\n"
                                                       --rc-lookahead 50 --ref 5 --subme 8\n"
144.
145.
                                                      slower:\n"
146.
                                                      --b-adapt 2 --direct auto --me umh\n"
147
                                                       --partitions all --rc-lookahead 60\n"
148.
                                                       --ref 8 --subme 9 --trellis 2\n"
149
                                                      veryslow:\n"
150.
                                                      --b-adapt 2 --bframes 8 --direct auto\n"
151.
                                                       --me umh --merange 24 --partitions all\n"
152.
                                                       --ref 16 --subme 10 --trellis 2\n"
153.
                                                       --rc-lookahead 60\n"
154.
                                                      placebo:\n"
155.
                                                       --bframes 16 --b-adapt 2 --direct auto\n"
                                                       --slow-firstpass --no-fast-pskip\n"
156.
                                                       --me tesa --merange 24 --partitions all\n"
157.
                                                       --rc-lookahead 60 --ref 16 --subme 11\n"
158.
                                                       --trellis 2\n" ):
159.
160.
        else H0( "
                                                         - ultrafast, superfast, veryfast, faster, fast\n"
161.
                                                          - medium,slow,slower,veryslow,placebo\n" );
162.
            H0("
                                                Tune the settings for a particular type of source\n"
163.
                                                 or situation\n"
164.
                                                    Overridden by user settings.\n"
165.
                                                     Multiple tunings are separated by commas.\n"
166.
                                                     Only one psy tuning can be used at a time.\n");
167.
            H2(
                                                     - film (psy tuning):\n"
                                                      --deblock -1:-1 --psy-rd <unset>:0.15\n"
168.
169.
                                                     - animation (psy tuning):\n"
170.
                                                      --bframes {+2} --deblock 1:1\n"
                                                       --psy-rd 0.4:<unset> --aq-strength 0.6\n"
171.
                                                       --ref {Double if >1 else 1}\n"
172.
173.
                                                     - grain (psy tuning):\n"
174.
                                                      --aq-strength 0.5 --no-dct-decimate\n"
175.
                                                       --deadzone-inter 6 --deadzone-intra 6\n"
176
                                                       --deblock -2:-2 --ipratio 1.1 \n"
177.
                                                       --pbratio 1.1 --psy-rd <unset>:0.25\n"
178
                                                       --acomp 0.8\n"
179.
                                                     - stillimage (psy tuning):\n"
180
                                                      --aq-strength 1.2 --deblock -3:-3\n"
                                                       --psy-rd 2.0:0.7\n"
181.
182.
                                                      psnr (psy tuning):\n"
183.
                                                       --aq-mode 0 --no-psy\n"
184.
                                                      ssim (psy tuning):\n"
185.
                                                       --ag-mode 2 --no-psy\n"
                                                      fastdecode:\n"
186.
187.
                                                       --no-cabac --no-deblock --no-weighth\n'
                                                       --weightp 0\n"
188.
189.
                                                     zerolatency:\n"
190.
                                                      --bframes 0 --force-cfr --no-mbtree\n"
191.
                                                       --sync-lookahead 0 --sliced-threads\n'
192.
                                                       --rc-lookahead 0\n" );
193.
            else H0( '
                                                          - psy tunings: film,animation,grain,\n"
194.
                                                                        stillimage,psnr,ssim\n"
195.
                                                          other tunings: fastdecode,zerolatency\n" );
                                                 Don't force these faster settings with --pass 1:\n"
196.
197.
                                                     --no-8x8dct --me dia --partitions none\n"
198.
                                                     --ref 1 --subme {2 if >2 else unchanged}\n"
199.
                                                     --trellis 0 --fast-pskip\n" );
200.
            else H1( "
                            --slow-firstpass
                                                    Don't force faster settings with --pass 1\n" );
            H0( "\n" );
201.
            H0( "Frame-type options:\n" );
202.
            H0( "\n" ):
203.
           H0(" -I, --keyint <integer or \"infinite\"> Maximum GOP size [%d]\n", defaults->i_keyint_max );
H2(" -i, --min-keyint <integer> Minimum GOP size [auto]\n");
204.
205.
```

```
H2( " --no-scenecut
                                              Disable adaptive I-frame decision\n" );
           H2( "
207.
                      --scenecut <integer>
                                               How aggressively to insert extra I-frames [%d]\n", defaults->i_scenecut_threshold );
           H2( " --intra-refresh
208.
                                               Use Periodic Intra Refresh instead of IDR frames\n" );
           H1( " -b, --bframes <integer>
209.
                                               Number of B-frames between I and P [%d]\n", defaults->i_bframe );
           H1( " --b-adapt <integer>
                                               Adaptive B-frame decision method [%d]\n"
210.
211.
                                                   Higher values may lower threading efficiency.\n"
                                                   - 0: Disabled\n"
212.
213.
                                                   - 1: Fast\n"
                                                   - 2: Optimal (slow with high --bframes) \n", defaults->i_bframe_adaptive );
214.
           H2( "
215.
                       --h-hias <integer>
                                               Influences how often B-frames are used [%d]\n", defaults->i_bframe_bias );
           H1( "
                      --b-pyramid <string>
216.
                                               Keep some B-frames as references [%s]\n"
217
                                                   - none: Disabled\n"
                                                   - strict: Strictly hierarchical pyramid\n"
218.
219.
                                                    normal: Non-strict (not Blu-ray compatible)\n",
220.
               strtable_lookup( x264_b_pyramid_names, defaults->i_bframe_pyramid ) );
221.
            H1( "
                      --open-gop
                                               Use recovery points to close GOPs\n
222.
                                               Only available with b-frames\n" );
223.
           H1( "
                                               Disable CABAC\n" );
                       --no-cabac
           H1( "
                   -r, --ref <integer>
224.
                                               Number of reference frames [%d]\n", defaults->i frame reference );
225.
           H1(
                      --no-deblock
                                               Disable loop filter\n" ):
           H1( " -f, --deblock <alpha:beta>
                                              Loop filter parameters [%d:%d]\n".
226.
                                              defaults->i deblocking filter alphac0, defaults->i deblocking filter beta );
227.
228.
           H2( " --slices <integer>
                                              Number of slices per frame; forces rectangular\n"
229.
                                               slices and is overridden by other slicing options\n" );
           else H1( " --slices <integer>
                                                 Number of slices per frame\n" ):
230.
231.
           H2( "
                      --slices-max <integer> Absolute maximum slices per frame; overrides\n"
232
                                              slice-max-size/slice-max-mbs when necessary\n" );
           H2( "
233.
                       --slice-max-size <integer> Limit the size of each slice in bytes\n");
234.
           H2( "
                      --slice-max-mbs <integer> Limit the size of each slice in macroblocks (max)\n");
           H2( "
                       --slice-min-mbs <integer> Limit the size of each slice in macroblocks (min)\n");
235.
236
           H0( "
                      --tff
                                              Enable interlaced mode (top field first)\n" );
           H0( "
237.
                                               Enable interlaced mode (bottom field first)\n" );
238.
           H2( "
                      --constrained-intra
                                              Enable constrained intra prediction.\n" );
239.
                      --pulldown <string>
                                               Use soft pulldown to change frame rate\n"
           H0(
                                                  - none, 22, 32, 64, double, triple, euro (requires cfr input)\n"
240.
           H2( "
241.
                                               Flag stream as interlaced but encode progressive.\n"
                       --fake-interlaced
242.
                                              Makes it possible to encode 25p and 30p Blu-Ray\n"
243.
                                               streams. Ignored in interlaced mode.\n" );
           H2( "
244.
                   --frame-packing <integer> For stereoscopic videos define frame arrangement\n"
245.
                                                   - \theta: checkerboard - pixels are alternatively from L and R\n"
246.
                                                   - 1: column alternation - L and R are interlaced by column\n"
247.
                                                   - 2: row alternation - L and R are interlaced by row\n"
                                                   - 3: side by side - L is on the left, R on the right\n"
248.
249.
                                                    4: top bottom - L is on top, R on bottom\n"
                                                   - 5: frame alternation - one view per frame\n" );
250.
251.
            H0( "\n" );
252.
           H0( "Ratecontrol:\n" );
           H0( "\n" );
253.
           H1( " -q, --qp <integer>
254.
                                               Force constant OP (0-%d, 0=lossless)\n", OP MAX ):
                 -B, --bitrate <integer>
                                              Set bitrate (kbit/s)\n" );
255.
           H0(
           H0( " --crf <float>
256.
                                              Quality-based VBR (%d-51) [%.1f]\n", 51 - QP_MAX_SPEC, defaults->rc.f_rf_constant ]
           H1( "
257.
                      --rc-lookahead <integer> Number of frames for frametype lookahead [%d]\n", defaults->rc.i lookahead );
           H0( "
258
                      --vbv-maxrate <integer> Max local bitrate (kbit/s) [%d]\n", defaults->rc.i vbv max bitrate );
           H0( "
259.
                      --vbv-bufsize <integer> Set size of the VBV buffer (kbit) [%d]\n", defaults->rc.i_vbv_buffer_size );
           H2( "
                     --vbv-init <float>
260.
                                              Initial VBV buffer occupancy [%.1f]\n", defaults->rc.f_vbv_buffer_init );
           H2( "
261.
                      --crf-max <float>
                                               With CRF+VBV, limit RF to this value\n"
262.
                                                  May cause VBV underflows!\n" );
           H2( "
                                               Set min QP [%d]\n", defaults->rc.i_qp_min );
263.
                      --gpmin <integer>
           H2( "
                     --qpmax <integer>
                                               Set max QP [%d]\n", defaults->rc.i qp max );
264
           H2( "
                                               Set max QP step [%d]\n", defaults->rc.i_qp_step );
265.
                       --qpstep <integer>
266
           H2( "
                      --ratetol <float>
                                               Tolerance of ABR ratecontrol and VBV [%.1f]\n", defaults->rc.f_rate_tolerance )
           H2( "
267.
                      --ipratio <float>
                                               QP factor between I and P [%.2f]\n", defaults->rc.f_ip_factor);
268.
           H2( "
                      --pbratio <float>
                                               QP factor between P and B [\%.2f]\n", defaults->rc.f pb factor );
           H2( "
269.
                      --chroma-qp-offset <integer> QP difference between chroma and luma [%d]\n", defaults-
       >analyse.i chroma gp offset );
270.
                                              AO method [%dl\n"
         H2( "
                     --aq-mode <integer>
271.
                                                   - 0: Disabled\n'
                                                   - 1: Variance AO (complexity mask)\n"
272
273.
                                                   - 2: Auto-variance AQ (experimental)\n", defaults->rc.i_aq_mode );
274.
           H1( " --aq-strength <float>
                                              Reduces blocking and blurring in flat and \ensuremath{\text{N}} "
275.
                                               textured areas. [%.1f]\n", defaults->rc.f_aq_strength );
276.
           H1( "\n" );
277.
           H0( " -p, --pass <integer>
                                               Enable multipass ratecontrol\n"
278
                                                  - 1: First pass, creates stats file\n"
279.
                                                   2: Last pass, does not overwrite stats file\n" );
280.
           H2( "
                                                   - 3: Nth pass, overwrites stats file\n" );
           H1( "
281.
                                               Filename for 2 pass stats [\"%s\"]\n", defaults->rc.psz stat out );
                      --stats <string>
282.
           H2( "
                      --no-mbtree
                                               Disable mb-tree ratecontrol.\n");
                                               QP curve compression [%.2f]\n", defaults->rc.f gcompress );
283.
           H2(
                      --gcomp <float>
           H2( "
                      --cplxblur <float>
                                              Reduce fluctuations in QP (before curve compression) [%.1f]\n", defaults-
284.
       >rc.f_complexity_blur );
                      --qblur <float>
285
           H2( "
                                               Reduce fluctuations in QP (after curve compression) [%.1f]\n", defaults->rc.f qblur );
           H2( "
                       --zones <zone0>/<zone1>/... Tweak the bitrate of regions of the video\n" );
286.
           H2( "
287
                                               Each zone is of the form\n"
288.
                                                  <start frame>,<end frame>,<option>\n"
289.
                                                   where <option> is either\n"
290.
                                                      q=<integer> (force QP)\n"
291.
                                                      b=<float> (bitrate multiplier)\n" );
292.
        H2( "
                  --qpfile <string>
                                               Force frametypes and QPs for some or all frames\n"
293
                                               Format of each line: framenumber frametype QP\n'
294.
                                               QP is optional (none lets x264 choose). Frametypes: I,i,K,P,B,b.\n"
```

```
295.
                                                  K=<I or i> depending on open-gop setting\n"
296.
                                              QPs are restricted by qpmin/qpmax.\n" );
           H1( "\n" ):
297.
298
           H1( "Analysis:\n" );
299.
           H1( "\n" );
           300
                                                  - p8x8, p4x4, b8x8, i8x8, i4x4\n"
301.
                                                  - none, all\n"
302.
303.
                                                  (p4x4 requires p8x8. i8x8 requires --8x8dct.)\n" );
304.
           H1( "
                      --direct <string>
                                              Direct MV prediction mode [\"%s\"]\n"
305.
                                                   none, spatial, temporal, auto\n",
306.
                                              strtable_lookup( x264_direct_pred_names, defaults->analyse.i_direct_mv_pred
           H2( "
                      --no-weightb
                                              Disable weighted prediction for B-frames\n" );
307.
           H1( "
                                              Weighted prediction for P-frames [%d]\n"
308.
                      --weightp <integer>
                                                  - 0: Disabled\n"
309.
310.
                                                  - 1: Weighted refs\n"
311.
                                                  - 2: Weighted refs + Duplicatesn", defaults->analyse.i_weighted_pred );
312
           H1( "
                                              Integer pixel motion estimation method [\"%s\"]\n",
313.
                                              strtable_lookup( x264_motion_est_names, defaults->analyse.i_me_method ) );
314
           H2( "
                                                  - dia: diamond search, radius 1 (fast)\n"
                                                  - hex: hexagonal search, radius 2\n"
315.
316
                                                  - umh: uneven multi-hexagon search\n"
317.
                                                  - esa: exhaustive search\n"
318.
                                                  - tesa: hadamard exhaustive search (slow)\n" );
319.
           else H1( "
                                                       - dia, hex, umh\n" );
           H2( "
                                              Maximum motion vector search range [%d]\n", defaults->analyse.i_me_range );
320.
                      --merange <integer>
                                              Maximum motion vector length [-1 (auto)]\n" );
321.
           H2(
                      --mvrange <integer>
           H2( "
                      --mvrange-thread <int>
322.
                                              Minimum buffer between threads [-1 (auto)]\n" ):
                                              Subpixel motion estimation and mode decision [%d]\n", defaults->analyse.i_subpel_refine );
323.
           H1(
                  -m. --subme <integer>
           H2( "
                                                  - 0: fullpel only (not recommended)\n"
324.
325.
                                                  - 1: SAD mode decision, one gpel iteration\n"
326.
                                                  - 2: SATD mode decision\n"
327
                                                  - 3-5: Progressively more qpel\n"
328.
                                                  - 6: RD mode decision for I/P-frames\n"
329
                                                  - 7: RD mode decision for all frames\n'
330.
                                                  - 8: RD refinement for I/P-frames\n"
331.
                                                  - 9: RD refinement for all frames\n"
                                                  - 10: QP-RD - requires trellis=2, aq-mode>0\n"
332.
333.
                                                  - 11: Full RD: disable all early terminations\n" );
334.
           else H1( "
                                                     decision quality: 1=fast, 11=best\n" );
335.
           H1( "
                      --psy-rd <float:float> Strength of psychovisual optimization [\"\$.1f:\$.1f\"]\n"
336.
                                                 #1: RD (requires subme>=6)\n"
337.
                                                  #2: Trellis (requires trellis, experimental)\n".
338.
                                              defaults->analyse.f_psy_rd, defaults->analyse.f_psy_trellis );
           H2( "
339.
                      --no-psy
                                              Disable all visual optimizations that worsen\n"
                                              both PSNR and SSIM.\n" );
340.
341.
           H2( "
                      --no-mixed-refs
                                              Don't decide references on a per partition basisn");
           H2( "
                      --no-chroma-me
342
                                              Ignore chroma in motion estimation\n");
           H1( "
343.
                      --no-8x8dct
                                              Disable adaptive spatial transform size\n" ):
344.
           H1( " -t, --trellis <integer>
                                              Trellis RD quantization. [%d]\n"
345.
                                                  - 0: disabled\n"
346
                                                  - 1: enabled only on the final encode of a MB\n"
347.
                                                   - 2: enabled on all mode decisions\n", defaults->analyse.i_trellis );
348.
           H2( "
                                              Disables early SKIP detection on P-frames\n" );
                      --no-fast-pskip
           H2( "
349.
                      --no-dct-decimate
                                              Disables coefficient thresholding on P-frames\n" );
           H1( "
350.
                      --nr <integer>
                                              Noise reduction [%d]\n", defaults->analyse.i noise reduction );
           H2( "\n" );
351.
           H2( "
352.
                      --deadzone-inter <int> Set the size of the inter luma quantization deadzone [%dl\n". defaults-
       >analyse.i_luma_deadzone[0] );
353.
           H2("
                      --deadzone-intra <int> Set the size of the intra luma quantization deadzone [%d]\n", defaults-
       >analyse.i luma deadzone[1] );
           H2( "
H2( "
354
                                                 Deadzones should be in the range 0 - 32.\n");
355.
                      --cam <strina>
                                              Preset quant matrices [\"flat\"]\n"
                                                  - jvt, flat\n" );
356.
357.
           H1( "
                      --cqmfile <string>
                                              Read custom quant matrices from a JM-compatible file\n");
358.
           H2( "
                                                 Overrides any other --cqm* options.\n" );
                      --cqm4 <list>
                                              Set all 4x4 quant matrices\n"
359.
           H2(
360.
                                                 Takes a comma-separated list of 16 integers.\n" );
361.
           H2( "
                      --cqm8 <list>
                                              Set all 8x8 quant matrices\n'
                                                Takes a comma-separated list of 64 integers.\n" );
362.
           H2( "
363.
                      --cqm4i, --cqm4p, --cqm8i, --cqm8p <list>\n"
                                             Set both luma and chroma quant matrices\n" );
364.
           H2( "
                      --cqm4iy, --cqm4ic, --cqm4py, --cqm4pc <list>\n"
365.
                                            Set individual quant matrices\n" );
366.
367.
           H2( "\n" ):
           H2( "Video Usability Info (Annex E):\n" );
368
369.
           H2( "The VUI settings are not used by the encoder but are merely suggestions to\n" );
370
           H2( "the playback equipment. See doc/vui.txt for details. Use at your own risk.\n" );
           H2( "\n" );
371.
372.
           H2( " --overscan <string> Specify crop overscan setting [\"s"]\n"
                                                   undef, show, crop\n",
373.
374.
                                              strtable lookup( x264 overscan names, defaults->vui.i overscan ) );
375.
           H2( "
                      --videoformat <string>
                                             Specify video format [\"%s\"]\n"
376.
                                                  component, pal, ntsc, secam, mac, undef\n",
377.
                                              strtable lookup( x264 vidformat names, defaults->vui.i vidformat ) );
           H2( " --range <string>
                                              Specify color range [\"%s\"]\n"
378.
                                                  - %s\n", range names[0], stringify_names( buf, range_names ) );
379.
           H2( " --colorprim <string>
380.
                                              Specify color primaries [\"%s\"]\n"
381.
                                                  - undef, bt709, bt470m, bt470bg, smpte170m,\n'
382
                                                    smpte240m, film, bt2020\n",
383
                                              strtable_lookup( x264_colorprim_names, defaults->vui.i_colorprim ) );
```

```
H2( "
                  --transfer <string> Specify transfer characteristics [\"%s\"]\n"
385
                                                   undef, bt709, bt470m, bt470bg, smpte170m,\n"
386.
                                                    smpte240m, linear, log100, log316,\n"
387.
                                                     iec61966-2-4, bt1361e, iec61966-2-1,\n'
                                                    bt2020-10, bt2020-12\n",
388.
389.
                                               strtable lookup( x264 transfer names, defaults->vui.i transfer ) );
           H2( "
                                              Specify color matrix setting [\"%s\"]\n"
390.
                      --colormatrix <string>
                                                   - undef, bt709, fcc, bt470bg, smpte170m,\n'
391.
392.
                                                    smpte240m, GBR, YCgCo, bt2020nc, bt2020c\n",
393.
                                               strtable lookup( x264 colmatrix names. defaults->vui.i colmatrix ) ):
394.
           H2( " --chromaloc <integer>
                                              Specify chroma sample location (0 to 5) [%d]\n",
395.
                                              defaults->vui.i_chroma_loc );
396
397.
           H2("
                                               Signal HRD information (requires vbv-bufsize)\n"
                      --nal-hrd <string>
                                                   - none, vbr, cbr (cbr not allowed in .mp4)\n" );
398
                                               Force hard-CBR and generate filler (implied by\n"
399.
           H2( "
                      --filler
400.
                                               --nal-hrd cbr)\n" );
           H2( "
401.
                      --pic-struct
                                               Force pic_struct in Picture Timing SEI\n" );
           H2( "
                                              Add 'left,top,right,bottom' to the bitstream-level\n'
402.
                      --crop-rect <string>
403.
                                              cropping rectangle\n" ):
404.
           H0( "\n" );
405.
           H0( "Input/Output:\n" );
406.
407
           H0( "\n" );
           H0( " -o, --output <string>
408.
                                              Specify output file\n" );
           H1( "
409
                      --muxer <string>
                                               Specify output container format [\"%s\"]\n"
410.
                                                  - %s\n", muxer_names[0], stringify_names( buf, muxer_names ) );
411
           H1( "
                                               Specify input container format [\"%s\"]\n"
                      --demuxer <string>
                                                   - %s\n", demuxer_names[0], stringify_names( buf, demuxer_names ) )
412.
413.
           H1( "
                      --input-fmt <string>
                                               Specify input file format (requires lavf support)\n" );
           H1( "
414.
                     --input-csp <string>
                                              Specify input colorspace format for raw input\n" );
415.
           print_csp_names( longhelp );
416.
           H1( "
                 --output-csp <string>
                                              Specify output colorspace [\"%s\"]\n"
417.
                                                   - %s\n". output csp names[0]. stringify names( buf. output csp names ) ):
                      --input-depth <integer> Specify input bit depth for raw input\n" );
           H1( "
418.
           H1( "
419.
                      --input-range <string>
                                              Specify input color range [\"%s\"]\n"
420.
                                                  - %s\n", range names[0], stringify names( buf, range names ) );
           H1( "
                                              Specify input resolution (width x height)\n" );
421.
                      --input-res <intxint>
           H1( "
                                              Filename for input index file\n" );
422.
                      --index <string>
           H0("
423.
                      --sar width:height
                                               Specify Sample Aspect Ratio\n" );
           H0( "
424
                      --fps <float|rational>
                                              Specify framerate\n" );
           H0( "
                      --seek <integer>
425.
                                              First frame to encode\n" );
426
           H0( "
                      --frames <integer>
                                              Maximum number of frames to encode\n" );
           H0("
                      --level <string>
                                               Specify level (as defined by Annex A)\n" );
427.
                                              Enable compatibility hacks for Blu-ray support\n" );
428
           H1( "
                      --bluray-compat
           H1( "
429.
                      --avcintra-class <integer> Use compatibility hacks for AVC-Intra class\n"
430.
                                                  - 50, 100, 200\n");
431.
           H1( "
                                               Don't optimize headers based on video content\n"
                      --stitchable
432.
                                              Ensures ability to recombine a segmented encode\n" );
           H1( "\n" );
433.
           H1( " -v, --verbose
434.
                                              Print stats for each frame\n" ):
                                              Don't show the progress indicator while encoding\n" );
435.
           H1(
                      --no-progress
           H0( "
436.
                      --auiet
                                              Ouiet Mode\n" ):
           H1( "
437.
                      --log-level <string>
                                              Specify the maximum level of logging [\"%s\"]\n"
438.
                                                  - %s\n", strtable_lookup( log_level_names, cli_log_level - X264_LOG_NONE ),
439.
                                               stringify_names( buf, log_level_names ) );
440.
           H1( "
                      --psnr
                                              Enable PSNR computation\n" );
441.
                                               Enable SSIM computation\n" );
           H1( "
                      --ssim
           H1( "
                      --threads <integer>
                                              Force a specific number of threads\n" );
442.
443.
           H2( "
                      --lookahead-threads <integer> Force a specific number of lookahead threads\n" );
444.
           H2( "
                      --sliced-threads
                                              Low-latency but lower-efficiency threading\n" );
445.
           H2 (
                                              Run Avisynth in its own thread\n" );
                      --thread-input
446.
           H2( "
                      --sync-lookahead <integer> Number of buffer frames for threaded lookahead\n" );
447.
           H2(
                      --non-deterministic
                                              Slightly improve quality of SMP, at the cost of repeatability\n" );
           H2( "
448.
                      --cpu-independent
                                              Ensure exact reproducibility across different cpus.\n"
449.
                                                  as opposed to letting them select different algorithms\n" );
           H2( "
450.
                      --asm <integer>
                                              Override CPU detection\n" ):
           H2( "
451.
                      --no-asm
                                              Disable all CPU optimizations\n" );
           H2( "
452
                      --opencl
                                              Enable use of OpenCL\n" );
           H2( "
453.
                      --opencl-clbin <string> Specify path of compiled OpenCL kernel cache\n" );
           H2( "
454
                      --opencl-device <integer> Specify OpenCL device ordinal\n" );
           H2( "
455.
                      --dump-yuv <string>
                                              Save reconstructed frames\n" );
           H2( "
                      --sps-id <integer>
                                              Set SPS and PPS id numbers [%d]\n", defaults->i_sps_id );
456
457.
           H2( "
                                              Use access unit delimiters\n" );
                      --aud
458
           H2( "
                      --force-cfr
                                              Force constant framerate timestamp generation \n");
           H2( "
459.
                      --tcfile-in <string>
                                               Force timestamp generation with timecode file\n" );
460.
           H2( "
                      --tcfile-out <string>
                                              Output timecode v2 file from input timestamps\n" );
461.
           H2(
                      --timebase <int/int>
                                              Specify timebase numerator and denominator\n'
462.
                             <integer>
                                              Specify timebase numerator for input timecode file\n"
463.
                                               or specify timebase denominator for other input\n" ):
           H2( "
                                              Eliminate initial delay with container DTS hack\n" );
464.
                     --dts-compress
           H0( "\n" );
465.
           H0( "Filtering:\n" );
466.
           H0( "\n" );
467
           H0("
468.
                      --vf, --video-filter <filter0>/<filter1>/... Apply video filtering to the input file\n"
469.
           H0( "\n" );
           HO( " Filter options may be specified in <filter>:<option>=<value> format.\n" );
470.
471
           H0( "\n" );
           H0( " Available filters:\n" );
472.
473.
           x264_register_vid_filters();
474.
           x264 vid filter help( longhelp );
```

```
4/5. | He( "\n" );
4/6. | }
```

help()中主要有3个宏定义:H0(),H1()和H2()。这三个宏定义实质上都是printf()。它们之间的区别在于:H0()无论如何都会调用print();H1()在longhelp大于等于1的时候才会调用print();而H2()在longhelp等于2时候才会调用print()。

print_version_info()

print_version_info()用于打印x264的版本信息。在x264命令行程序中添加"-V"参数后会调用该函数。该函数的定义如下所示。

```
[cpp] 📳 👔
      //打印版本信息
2.
      static void print_version_info( void )
3.
4.
      #ifdef X264 POINTVER
5.
         printf( "x264 "X264_POINTVER"\n" );
6.
      #else
         printf( "x264 0.%d.X\n", X264 BUILD ):
7.
8.
      #endif
      #if HAVE SWSCALE
9.
       printf( "(libswscale %d.%d.%d)\n", LIBSWSCALE_VERSION_MAJOR, LIBSWSCALE_VERSION_MINOR, LIBSWSCALE_VERSION_MICRO );
10.
11.
      #endif
12.
      #if HAVE LAVF
13.
          printf( "(libavformat %d.%d.%d)\n", LIBAVFORMAT_VERSION_MAJOR, LIBAVFORMAT_VERSION_MINOR, LIBAVFORMAT_VERSION_MICRO );
14.
      #endif
15.
      #if HAVE_FFMS
16.
         printf( "
      (ffmpegsource %d.%d.%d.%d)\n", FFMS_VERSION >> 24, (FFMS_VERSION & 0xff0000) >> 16, (FFMS_VERSION & 0xff000) >> 8, FFMS_VERSION & 0xff
17.
         printf( "built on " __DATE__ ", " );
18.
19.
      #ifdef INTEL COMPILER
        printf( "intel: %.2f (%d)\n", __INTEL_COMPILER / 100.f, __INTEL_COMPILER_BUILD_DATE );
20.
21.
      #elif defined(__GNUC__)
22.
        printf( "gcc: " __VERSION__ "\n" );
23.
      #elif defined( MSC FULL VER)
24.
        printf( "msvc: %.2f (%u)\n", _MSC_VER / 100.f, _MSC_FULL_VER );
25.
      #else
26.
         printf( "using an unknown compiler\n" );
27.
         printf( "configuration: --bit-depth=%d --chroma-format=%s\n", x264_bit_depth, X264_CHROMA_FORMAT ? (output_csp_names[0]+1) : "al
28.
      l");
29.
         printf( "x264 license: " );
30.
      #if HAVE_GPL
31.
         printf( "GPL version 2 or later\n" );
      #else
32.
33.
         printf( "Non-GPL commercial\n" ):
34.
      #endif
35.
      #if HAVE SWSCALE
      const char *license = swscale_license();
36.
          printf( "libswscale%s%s license: %s\n", HAVE_LAVF ? "/libavformat" : "", HAVE_FFMS ? "/ffmpegsource" : "" , license );
37.
38.
      if( !strcmp( license, "nonfree and unredistributable" ) ||
             (!HAVE_GPL && (!strcmp( license, "GPL version 2 or later" )
39.
40.
                       || !strcmp( license, "GPL version 3 or later" ))))
41.
              printf( "WARNING: This binary is unredistributable!\n" );
      #endif
42.
43.
```

该函数定义比较浅显易懂,不再详细记录。

x264_param_parse()

x264_param_parse()是一个x264的APl。该函数以字符串键值对的方式设置x264_param_t结构体的一个成员变量。该函数的声明如下所示。

x264_param_parse()的定义如下所示。

```
char *name_but = NULL;
          int b_error = 0;
8.
      int name_was_bool;
          int value_was_null = !value;
11.
12.
      if( !name )
              return X264 PARAM BAD NAME;
13.
          if( !value )
14.
15.
              value = "true":
16.
17.
          if( value[0] == '=' )
            value++;
18.
19.
20.
      if( strchr( name, '_' ) ) // s/_/-/g
21.
22.
23.
              name_buf = strdup(name);
24.
              while( (c = strchr( name_buf, '_' )) )
                 *c = '-';
25.
26.
             name = name_buf;
27.
28.
          if( (!strncmp( name, "no-", 3 ) && (i = 3)) ||
29.
            (!strncmp( name, "no", 2 ) && (i = 2)) )
30.
31.
32.
              name += i;
              value = atobool(value) ? "false" : "true";
33.
34.
35.
          name_was_bool = 0;
36.
37.
      #define OPT(STR) else if( !strcmp( name, STR ) )
38.
      #define OPT2(STR0, STR1) else if( !strcmp( name, STR0 ) || !strcmp( name,
39.
          //OPT()实际上就是strcmp()
40.
41.
          OPT("asm")
42.
43.
              p->cpu = isdigit(value[0]) ? atoi(value) :
                    !strcasecmp(value, "auto") || atobool(value) ? x264_cpu_detect() : 0;
44.
              if( b error )
45.
46.
47.
                  char *buf = strdup(value):
                 char *tok, UNUSED *saveptr=NULL, *init;
48.
49.
                  b_error = 0;
50.
                  p \rightarrow cpu = 0;
51.
                  for( init=buf; (tok=strtok_r(init, ",", &saveptr)); init=NULL )
52.
53.
                      for( i=0; x264_cpu_names[i].flags && strcasecmp(tok, x264_cpu_names[i].name); i++ );
54.
                      p->cpu |= x264_cpu_names[i].flags;
55.
                      if( !x264_cpu_names[i].flags )
56.
                      b error = 1;
57.
                  free( buf );
58.
                  if( (p->cpu&X264_CPU_SSSE3) && !(p->cpu&X264_CPU_SSE2_IS_SLOW) )
59.
60.
                    p->cpu |= X264_CPU_SSE2_IS_FAST;
61.
              }
62.
63.
          OPT("threads")
64.
65.
              if( !strcasecmp(value, "auto") )
                 p->i_threads = X264_THREADS_AUTO;
66.
67.
68.
              p->i_threads = atoi(value);
69.
70.
      OPT("lookahead-threads")
71.
72.
              if( !strcasecmp(value, "auto") )
                 p->i lookahead threads = X264 THREADS AUTO;
73.
74.
              else
75.
                  p->i lookahead threads = atoi(value);
76.
77.
          OPT("sliced-threads")
78.
             p->b_sliced_threads = atobool(value);
79.
          OPT("sync-lookahead")
80.
81.
              if( !strcasecmp(value, "auto") )
82.
                 p->i_sync_lookahead = X264_SYNC_LOOKAHEAD_AUTO;
83.
84.
                 p->i_sync_lookahead = atoi(value);
85.
86.
      OPT2("deterministic", "n-deterministic")
              p->b_deterministic = atobool(value);
87.
          OPT("cpu-independent")
88.
89.
              p->b_cpu_independent = atobool(value);
      OPT2("level", "level-idc")
90.
91.
92.
              if( !strcmp(value, "1b") )
93.
                  p->i_level_idc = 9;
94.
              else if( atof(value) < 6 )</pre>
95.
                  p->i_level_idc = (int)(10*atof(value)+.5);
                  n si lovol ido = atoi(valuo).
```

```
p->1 tevet fut = atof(vatue);
  98.
  99.
                    OPT("bluray-compat")
                          p->b_bluray_compat = atobool(value);
100.
101.
                    OPT("avcintra-class")
102.
                         p->i_avcintra_class = atoi(value);
                    OPT("sar")
103.
104.
105.
                           \verb|b_error = ( 2 != sscanf( value, "%d:%d", \&p->vui.i_sar_width, \&p->vui.i_sar_height ) \& \& ar_width | b_error = ( 2 != sscanf( value, "%d:%d", \&p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_sar_width | b_error = ( 2 != sscanf( value, "%d:%d", &p->vui.i_s
106.
                                 2 != sscanf( value, "%d/%d", &p->vui.i_sar_width, &p->vui.i_sar_height ) );
107.
108.
             OPT("overscan")
109.
                           b_error |= parse_enum( value, x264_overscan_names, &p->vui.i_overscan );
110.
                    OPT("videoformat")
111.
                           b_error |= parse_enum( value, x264_vidformat_names, &p->vui.i_vidformat );
                    OPT("fullrange")
112.
113.
                           b error |= parse enum( value, x264 fullrange names, &p->vui.b fullrange ):
                   OPT("colorprim")
114.
115.
                           b error |= parse enum( value, x264 colorprim names, &p->vui.i colorprim );
116.
                    OPT("transfer")
117.
                           b_error |= parse_enum( value, x264_transfer_names, &p->vui.i_transfer );
118.
                    OPT("colormatrix")
119.
                           b_error |= parse_enum( value, x264_colmatrix_names, &p->vui.i_colmatrix );
120.
             OPT("chromaloc")
121.
122.
                           p->vui.i_chroma_loc = atoi(value);
123.
                           b_error = ( p->vui.i_chroma_loc < 0 || p->vui.i_chroma_loc > 5 );
124.
125.
                    OPT("fps")
126.
                 {
                           if( sscanf( value, "%u/%u", &p->i_fps_num, &p->i_fps_den ) == 2 )
127.
128.
                                ;
                           else
129.
130.
                           {
131.
                                   float fps = atof(value);
132.
                                 if( fps > 0 && fps <= INT_MAX/1000 )</pre>
133.
134.
                                         p - i_fps_num = (int)(fps * 1000 + .5)
135.
                                         p \rightarrow i_fps_den = 1000;
136.
137.
                                  else
138.
                                  {
139.
                                         p->i fps num = atoi(value);
140.
                                         p->i_fps_den = 1;
141.
142.
                          }
143.
             OPT2("ref", "frameref")
144.
145.
                           p->i frame reference = atoi(value);
                    OPT("dpb-size")
146.
147.
                           p->i_dpb_size = atoi(value);
148.
                    OPT("keyint")
149.
150.
                            if( strstr( value, "infinite" ) )
151.
                                 p->i_keyint_max = X264_KEYINT_MAX_INFINITE;
152.
153.
                                  p->i keyint max = atoi(value);
154.
                    OPT2("min-keyint", "keyint-min")
155.
156.
157.
                           p->i keyint min = atoi(value);
158.
                           if( p->i keyint max < p->i keyint min )
159.
                                  p->i_keyint_max = p->i_keyint_min;
160.
161.
                     OPT("scenecut")
162
163.
                           p->i_scenecut_threshold = atobool(value);
164.
                           if( b_error || p->i_scenecut_threshold )
165.
166.
                                  b error = 0;
167.
                                  p->i_scenecut_threshold = atoi(value);
168.
169.
170.
                   OPT("intra-refresh")
171.
                           p->b intra refresh = atobool(value):
                    OPT("bframes")
172.
173.
                           p->i bframe = atoi(value):
                    OPT("b-adapt")
174.
175
176.
                           p->i_bframe_adaptive = atobool(value);
177.
                            if( b_error )
178.
179.
180.
                                  p->i_bframe_adaptive = atoi(value);
181.
                           }
182.
183.
                     OPT("b-bias")
184.
                           p->i bframe bias = atoi(value);
185.
                    OPT("b-pyramid")
186.
                           b error |= parse enum( value, x264 b pyramid names, &p->i bframe pyramid );
187.
188
                           if( h error )
```

```
189
190.
                   b_error = 0;
191.
                   p->i_bframe_pyramid = atoi(value);
192.
193.
194.
           OPT("open-gop")
195.
               p->b open gop = atobool(value);
           OPT("nf")
196.
197.
               p->b deblocking filter = !atobool(value);
           OPT2("filter", "deblock")
198.
199.
               200.
201.
202.
203.
                   p->b_deblocking_filter = 1;
204.
205.
               else if( sscanf( value, "%d", &p->i_deblocking_filter_alphac0 ) )
206.
207.
                   p->b_deblocking_filter = 1;
208.
                   p->i_deblocking_filter_beta = p->i_deblocking_filter_alphac0;
209.
               }
210.
               else
211.
                   p->b deblocking filter = atobool(value);
212.
213.
           OPT("slice-max-size")
214.
               p->i_slice_max_size = atoi(value);
215.
           OPT("slice-max-mbs")
216.
              p->i_slice_max_mbs = atoi(value);
217.
           OPT("slice-min-mbs")
               p->i_slice_min_mbs = atoi(value);
218.
219.
           OPT("slices")
220.
              p->i_slice_count = atoi(value);
221.
           OPT("slices-max")
222.
              p->i slice count max = atoi(value);
223.
           OPT("cabac")
224.
              p->b cabac = atobool(value):
225.
           OPT("cabac-idc")
226.
              p->i cabac init_idc = atoi(value);
227.
           OPT("interlaced")
228.
              p->b interlaced = atobool(value);
229.
           OPT("tff")
230.
              p->b_interlaced = p->b_tff = atobool(value);
231.
           OPT("bff")
232.
233.
               p->b_interlaced = atobool(value);
234.
               p->b_tff = !p->b_interlaced;
235.
236.
           OPT("constrained-intra")
237.
               p->b_constrained_intra = atobool(value);
238.
           OPT("cqm")
239.
               if( strstr( value, "flat" ) )
240.
                  p->i_cqm_preset = X264_CQM FLAT;
241.
242.
               else if( strstr( value, "jvt" ) )
                  p->i_cqm_preset = X264_CQM_JVT;
243.
244.
               else
245.
                  p->psz_cqm_file = strdup(value);
246.
247.
           OPT("cqmfile")
248.
               p->psz_cqm_file = strdup(value);
249.
           OPT("cqm4")
250.
251.
               p->i_cqm_preset = X264_CQM_CUSTOM;
252.
               b error |= parse cqm( value, p->cqm 4iy, 16 );
253.
               b error |= parse cqm( value, p->cqm 4py, 16 );
               b_error |= parse_cqm( value, p->cqm_4ic, 16 );
254.
255.
               b_error |= parse_cqm( value, p->cqm_4pc, 16 );
256.
257.
           OPT("cqm8")
258.
259.
               p->i_cqm_preset = X264_CQM_CUSTOM;
260.
               b_error |= parse_cqm( value, p->cqm_8iy, 64 );
261.
               b_error |= parse_cqm( value, p->cqm_8py, 64 );
262.
               b_error |= parse_cqm( value, p->cqm_8ic, 64 );
263.
               b_error |= parse_cqm( value, p->cqm_8pc, 64 );
264.
265.
           OPT("cqm4i")
266.
          {
267.
               p->i cqm preset = X264 CQM CUSTOM;
268.
               b error |= parse cqm( value, p->cqm 4iy, 16 );
               b_error |= parse_cqm( value, p->cqm_4ic, 16 );
269.
270.
           OPT("cqm4p")
271.
272.
273.
               p -> i\_cqm\_preset = X264\_CQM\_CUSTOM;
274
               b_error |= parse_cqm( value, p->cqm_4py, 16 );
275.
               b_error |= parse_cqm( value, p->cqm_4pc, 16 );
276
277.
           OPT("cqm4iy")
278.
               p->i cqm preset = X264 CQM CUSTOM;
```

```
b error |= parse_cqm( value, p->cqm_4iy, 16 );
280.
281.
           OPT("cam4ic")
282.
283.
284.
               p->i cqm preset = X264 CQM CUSTOM;
285.
               b_error |= parse_cqm( value, p->cqm_4ic, 16 );
286.
287.
288.
289.
                p->i_cqm_preset = X264_CQM_CUSTOM;
290.
               b_error |= parse_cqm( value, p->cqm_4py, 16 );
291.
292.
           OPT("cqm4pc")
293.
294.
               p->i cgm preset = X264 CQM CUSTOM;
295.
               b_error |= parse_cqm( value, p->cqm_4pc, 16 );
296.
           OPT("cam8i")
297.
298.
           {
299.
               p->i cqm preset = X264 CQM CUSTOM;
300.
               b_error |= parse_cqm( value, p->cqm_8iy, 64 );
301.
               b_error |= parse_cqm( value, p->cqm_8ic, 64 );
302.
303.
           OPT("cqm8p")
304.
       {
               p->i_cqm_preset = X264_CQM_CUSTOM;
305.
306.
               b_error |= parse_cqm( value, p->cqm_8py, 64 );
307.
               b error |= parse cqm( value, p->cqm 8pc, 64 );
308.
309.
           OPT("log")
               p->i log level = atoi(value);
310.
311.
           OPT("dump-yuv")
312.
               p->psz_dump_yuv = strdup(value);
313.
           OPT2("analyse", "partitions")
314.
315.
               p->analyse.inter = 0;
316.
               if( strstr( value, "none" ) ) p->analyse.inter = \theta;
                                              p->analyse.inter = ~0;
317.
               if( strstr( value, "all" ) )
318.
319.
                if( strstr( value, "i4x4" ) ) p->analyse.inter |= X264_ANALYSE_I4x4;
               if( strstr( value, "i8x8" ) ) p->analyse.inter |= X264 ANALYSE I8x8;
320.
321.
               if( strstr( value, "p8x8" ) ) p->analyse.inter |= X264_ANALYSE_PSUB16x16;
               if( strstr( value, "p4x4" ) ) p->analyse.inter |= X264_ANALYSE_PSUB8x8;
322.
               if( strstr( value, "b8x8" ) ) p->analyse.inter |= X264_ANALYSE_BSUB16x16;
323.
324.
           OPT("8x8dct")
325.
326.
               p->analyse.b_transform_8x8 = atobool(value);
           OPT2("weightb", "weight-b")
327.
328.
               p->analyse.b_weighted_bipred = atobool(value);
329.
           OPT("weightp")
330.
               p->analyse.i_weighted_pred = atoi(value);
331.
           OPT2("direct", "direct-pred")
332.
               b_error |= parse_enum( value, x264_direct_pred_names, &p->analyse.i_direct_mv_pred );
333.
           OPT("chroma-qp-offset")
334.
               p->analyse.i_chroma_qp_offset = atoi(value);
335.
336.
               b_error |= parse_enum( value, x264_motion_est_names, &p->analyse.i_me_method );
337.
           OPT2("merange", "me-range")
338.
               p->analyse.i me range = atoi(value):
           OPT2("mvrange", "mv-range")
339.
               p->analyse.i_mv_range = atoi(value);
340.
341.
           OPT2("mvrange-thread", "mv-range-thread")
342.
               p->analyse.i_mv_range_thread = atoi(value);
343.
           OPT2("subme", "subg")
344.
               p->analyse.i_subpel_refine = atoi(value);
345.
           OPT("psy-rd")
346.
347.
                if( 2 == sscanf( value, "%f:%f", &p->analyse.f_psy_rd, &p->analyse.f_psy_trellis ) ||
                   2 == sscanf( value, "%f,%f", &p->analyse.f_psy_rd, &p->analyse.f_psy_trellis ) ||
348.
                   2 == sscanf( value, "%f|%f", &p->analyse.f_psy_rd, &p->analyse.f_psy_trellis ))
349.
350.
351.
               else if( sscanf( value, "%f", &p->analyse.f psy rd ) )
352.
353.
                   p->analyse.f psy trellis = 0;
354.
               }
355.
               else
356
               {
357.
                   p->analyse.f_psy_rd = 0;
358.
                   p->analyse.f_psy_trellis = 0;
359.
               }
360.
361.
           OPT("psy")
362.
               p->analyse.b_psy = atobool(value);
363.
364.
               p->analyse.b_chroma_me = atobool(value);
365.
           OPT("mixed-refs")
366.
               p->analyse.b mixed references = atobool(value);
367.
           OPT("trellis")
368.
               p->analyse.i trellis = atoi(value);
369.
           OPT("fast-pskip")
370.
               p->analyse.b fast pskip = atobool(value);
```

```
371.
           OPT("dct-decimate")
372.
               p->analyse.b_dct_decimate = atobool(value);
373.
           OPT("deadzone-inter")
374.
               p->analyse.i_luma_deadzone[0] = atoi(value);
375.
           OPT("deadzone-intra")
376.
               p->analyse.i luma deadzone[1] = atoi(value);
377.
           OPT("nr")
378.
              p->analyse.i_noise_reduction = atoi(value);
           OPT("bitrate")
379.
380.
        {
381.
               p->rc.i bitrate = atoi(value):
382.
               p->rc.i_rc_method = X264_RC_ABR;
383.
384.
           OPT2("qp", "qp_constant")
385.
386
               p->rc.i_qp_constant = atoi(value);
               p->rc.i_rc_method = X264_RC_CQP;
387.
388.
389.
           OPT("crf")
390.
        {
391.
               p->rc.f rf constant = atof(value);
392.
               p->rc.i_rc_method = X264_RC_CRF;
393.
394.
       OPT("crf-max")
395.
               p->rc.f rf constant max = atof(value);
           OPT("rc-lookahead")
396.
397.
               p->rc.i_lookahead = atoi(value);
398.
           OPT2("qpmin", "qp-min")
399.
               p->rc.i_qp_min = atoi(value);
           OPT2("qpmax", "qp-max")
400.
401.
               p->rc.i_qp_max = atoi(value);
402.
           OPT2("qpstep", "qp-step")
403.
               p->rc.i_qp_step = atoi(value);
           OPT("ratetol")
404.
405.
               p->rc.f rate tolerance = !strncmp("inf", value, 3) ? 1e9 : atof(value);
406.
           OPT("vbv-maxrate")
407.
               p->rc.i vbv max bitrate = atoi(value);
408.
           OPT("vbv-bufsize")
409.
               p->rc.i vbv buffer size = atoi(value);
           OPT("vbv-init")
410.
411.
               p->rc.f_vbv_buffer_init = atof(value);
412.
           OPT2("ipratio", "ip-factor")
413.
               p->rc.f_ip_factor = atof(value);
414.
           OPT2("pbratio", "pb-factor")
415.
               p->rc.f_pb_factor = atof(value);
416.
           OPT("aq-mode")
417.
               p->rc.i_aq_mode = atoi(value);
418.
           OPT("aq-strength")
419.
               p->rc.f_aq_strength = atof(value);
420.
           OPT("pass")
421.
           {
422.
               int pass = x264 clip3( atoi(value), 0, 3 );
423.
               p->rc.b stat write = pass & 1:
424.
               p->rc.b_stat_read = pass & 2;
425.
       OPT("stats")
426.
427.
428.
               p->rc.psz_stat_in = strdup(value);
429.
               p->rc.psz_stat_out = strdup(value);
430.
431.
           OPT("qcomp")
432.
               p->rc.f_qcompress = atof(value);
433.
           OPT("mbtree")
434.
               p->rc.b mb tree = atobool(value);
435.
           OPT("qblur")
436.
              p->rc.f gblur = atof(value);
           OPT2("cplxblur", "cplx-blur")
437.
438.
              p->rc.f complexity blur = atof(value);
           OPT("zones")
439.
440.
              p->rc.psz_zones = strdup(value);
441.
           OPT("crop-rect")
442
               b_error |= sscanf( value, "%u,%u,%u,%u", &p->crop_rect.i_left, &p->crop_rect.i_top,
443.
                                                        &p->crop_rect.i_right, &p->crop_rect.i_bottom ) != 4;
444.
           OPT("psnr")
445.
               p->analyse.b_psnr = atobool(value);
446.
           OPT("ssim")
447.
               p->analyse.b_ssim = atobool(value);
448.
           OPT("aud")
449.
               p->b_aud = atobool(value);
           OPT("sps-id")
450.
451.
               p->i sps id = atoi(value):
       OPT("global-header")
452.
453.
               p->b repeat headers = !atobool(value);
           OPT("repeat-headers")
454.
455.
               p->b_repeat_headers = atobool(value);
           OPT("annexb")
456.
457.
               p->b_annexb = atobool(value);
458.
           OPT("force-cfr")
459.
               p->b_vfr_input = !atobool(value);
460.
           OPT("nal-hrd")
461.
               b_error |= parse_enum( value, x264_nal_hrd_names, &p->i_nal_hrd );
```

```
OPT("filler")
462.
463.
               p->rc.b filler = atobool(value);
          OPT("pic-struct")
464.
465.
              p->b_pic_struct = atobool(value);
466.
           OPT("fake-interlaced")
467.
              p->b_fake_interlaced = atobool(value);
      OPT("frame-packing")
468.
469.
              p->i_frame_packing = atoi(value);
470.
      OPT("stitchable")
471.
              p->b_stitchable = atobool(value);
472.
      OPT("opencl")
473.
              p->b_opencl = atobool( value );
       OPT("opencl-clbin")
474.
475.
              p->psz clbin file = strdup( value );
       OPT("opencl-device")
476.
477.
              p->i_opencl_device = atoi( value );
       else
478.
479.
              return X264 PARAM BAD NAME;
       #undef OPT
480.
481.
       #undef OPT2
482.
       #undef atobool
483.
       #undef atoi
484.
       #undef atof
485.
486.
       if( name_buf )
487.
               free( name_buf );
488.
489.
           b_error |= value_was_null && !name_was_bool;
490.
          return b error ? X264 PARAM BAD VALUE : 0;
491. }
```

x264_param_parse()中判断参数的宏OPT()和OPT2()实质上就是strcmp()。由此可见该函数的流程首先是调用strcmp()判断当前输入参数的名称name,然后再调用atoi(),或者atof(),或者atobool()等将当前输入参数值value转换成相应类型的值并赋值给对应的参数。

x264_param_apply_profile()

x264 param apply profile()是一个x264的API。该函数用于设置x264的profile,它的声明如下所示。

```
1. /* (can be NULL, in which case the function will do nothing)

2. *

3. * Does NOT guarantee that the given profile will be used: if the restrictions

4. * of "High" are applied to settings that are already Baseline-compatible, the

5. * stream will remain baseline. In short, it does not increase settings, only

6. * decrease them.

7. *

8. * returns 0 on success, negative on failure (e.g. invalid profile name). */

9. int x264_param_apply_profile( x264_param_t *, const char *profile );
```

x264_param_apply_profile()的定义如下所示。

```
[cpp]
      //设置profile
 2.
      int x264_param_apply_profile( x264_param_t *param, const char *profile )
3.
 4.
          if( !profile )
 5.
              return 0;
6.
          //字符串到整型
          int p = profile string to int( profile );
7.
         //检查profile设置是否正确
8.
9.
          if(p < 0)
      {
10.
              x264_log( NULL, X264_LOG_ERROR, "invalid profile: %s\n", profile );
11.
12.
              return -1:
13.
      if( p < PROFILE_HIGH444_PREDICTIVE && ((param->rc.i_rc_method == X264_RC_CQP && param->rc.i_qp_constant <=</pre>
14.
              (param->rc.i_rc_method == X264_RC_CRF && (int)(param->rc.f_rf_constant + QP_BD_0FFSET) <= 0)) )
15.
16.
17.
              x264_log( NULL, X264_LOG_ERROR, "%s profile doesn't support lossless\n", profile );
18.
19.
      if( p < PROFILE_HIGH444_PREDICTIVE && (param->i_csp & X264_CSP_MASK) >= X264_CSP_I444 )
20.
21.
          {
22.
              x264 log( NULL, X264 LOG ERROR, "%s profile doesn't support 4:4:4\n", profile );
23.
              return -1;
24.
25.
          if( p < PROFILE HIGH422 && (param->i csp & X264 CSP MASK) >= X264 CSP I422 )
26.
              x264 log( NULL, X264 LOG ERROR, "%s profile doesn't support 4:2:2\n", profile ):
27.
28.
              return -1;
29.
      if( p < PROFILE_HIGH10 && BIT_DEPTH > 8 )
30.
31.
32.
              x264_log( NULL, X264_LOG_ERROR, "%s profile doesn't support a bit depth of %d\n", profile, BIT_DEPTH );
33.
34.
35.
          //根据不同的Profile做设置
36.
          //Baseline基本型
37.
          if( p == PROFILE_BASELINE )
38.
39.
              //不支持DCT8x8
              param->analyse.b transform 8x8 = 0;
40.
              //不使用CABAC
41.
42.
              param->b cabac = 0;
43.
              param->i_cqm_preset = X264_CQM_FLAT;
44.
              param->psz_cqm_file = NULL;
45.
              //没有B帧
46.
              param->i bframe = 0;
47.
              //没有加权
48.
              param->analyse.i_weighted_pred = X264_WEIGHTP_NONE;
49.
50.
              if( param->b_interlaced )
51.
52.
                  x264_log( NULL, X264_LOG_ERROR, "baseline profile doesn't support interlacing\n'
53.
                  return -1;
54.
              if( param->b_fake_interlaced )
55.
56.
                  x264_log( NULL, X264_LOG_ERROR, "baseline profile doesn't support fake interlacing\n" );
57.
58.
                  return -1:
59.
              }
60.
61.
          //Main主型
62.
          else if( p == PROFILE_MAIN )
63.
64.
              param->analyse.b transform 8x8 = 0;
65.
66.
              param->i_cqm_preset = X264_CQM_FLAT;
              param->psz_cqm_file = NULL;
67.
68.
69.
          return 0:
70.
```

从定义可以看出,x264_param_apply_profile()首先调用了一个函数profile_string_to_int()将输入的profile字符串转换为int类型的profile;然后会检查该profile的设置是否合理;最后会根据profile对x264_param_t中的参数进行相应的设置。 该函数中调用的profile_string_to_int()的定义如下。

```
[cpp] 📳 📑
       static int profile_string_to_int( const char *str )
 2.
       {
 3.
           if( !strcasecmp( str, "baseline" ) )
 4.
              return PROFILE_BASELINE;
 5.
           if( !strcasecmp( str, "main" ) )
 6.
              return PROFILE_MAIN;
          if( !strcasecmp( str, "high" ) )
 7.
              return PROFILE HIGH;
 8.
          if( !strcasecmp( str, "high10" ) )
 9.
              return PROFILE_HIGH10;
 10.
          if( !strcasecmp( str, "high422" ) )
 11.
              return PROFILE_HIGH422;
 12.
           if( !strcasecmp( str, "high444" ) )
 13.
              return PROFILE_HIGH444_PREDICTIVE;
 14.
 15.
           return -1;
16. }
```

从定义可以看出profile_string_to_int()根据输入的字符串str返回不同的整型变量。

select_output()

select output()用于设定输出的文件格式。该函数的定义如下所示。

```
//根据文件名的后缀确定输出的文件格式(raw H264, flv, mp4...)
 2.
      static int select_output( const char *muxer, char *filename, x264_param_t *param )
 3.
 4.
          //从文件路径字符串中解析出扩展名,存入ext
          //解析的方式就是反向搜索字符"."
 5.
     const char *ext = get_filename_extension( filename );
 6.
 8.
     //strcasecmp(char *s1, char *s2)用于忽略大小写比较字符串.
 9.
          //参数s1和s2字符串相等则返回0。s1大于s2则返回大于0 的值,s1 小于s2 则返回小于0的值。
10.
         if( !strcmp( filename, "-" ) || strcasecmp( muxer, "auto" ) )
11.
12.
            ext = muxer;
          //后缀为"mp4"
13.
      if( !strcasecmp( ext, "mp4" ) )
14.
15.
      #if HAVE_GPAC || HAVE_LSMASH
16.
17.
             cli_output = mp4_output;
             param->b_annexb = 0;
18.
19.
             param->b_repeat_headers = 0;
20.
             if( param->i_nal_hrd == X264_NAL_HRD_CBR )
21.
                 x264\_cli\_log( "x264", X264\_LOG\_WARNING, "cbr nal-hrd is not compatible with mp4\n" );
22.
23.
                 param->i_nal_hrd = X264_NAL_HRD_VBR;
24.
25.
      #else
             x264 cli log( "x264", X264 LOG ERROR, "not compiled with MP4 output support\n" );
26.
27.
              return -1:
      #endif
28.
29.
30.
      else if( !strcasecmp( ext, "mkv" ) )
31.
32.
             //设定cli_output_t
33.
              cli_output = mkv_output;
34.
             //不加起始码0×00000001
35.
             param->b_annexb = 0;
             //不再每个Keyframe前面加SPS和PPS
36.
37.
             param->b_repeat_headers = 0;
38.
39.
          else if( !strcasecmp( ext. "flv" ) )
      {
40.
41.
             cli output = flv output:
42.
             param->b annexb = 0;
43.
             param->b_repeat_headers = 0;
44.
45.
            cli_output = raw_output;//不符合上述后缀,则输出裸流
46.
47.
          return 0;
48.
```

从函数定义可以看出,select_output()首先调用get_filename_extension()从输入文件路径的字符串中提取出了扩展名,然后根据不同的扩展名设定不同的输出格式。其中get_filename_extension()是一个提取扩展名的函数,定义如下所示。

可以看出get_filename_extension()从字符串的末尾开始向前搜索点符号".",并且将"."后面的内容作为提取出来的扩展名。

select_input()

select_input()用于设定输入的文件格式。该函数的定义如下所示。

```
[cpp] 📳 📑
      //设置输入文件的格式(yuv,y4m...)
 2.
      static int select_input( const char *demuxer, char *used_demuxer, char *filename,
3.
                              hnd_t *p_handle, video_info_t *info, cli_input_opt_t *opt )
 4.
      {
 5.
          int b_auto = !strcasecmp( demuxer, "auto" );
     //从文件路径字符串中解析出扩展名,存入ext
6.
          //解析的方式就是反向搜索字符"."
7.
      const char *ext = b auto ? get filename extension( filename ) :
8.
          int b regular = strcmp( filename, "-" );
9.
     if( !b_regular && b_auto )
10.
11.
             ext = "raw":
      b_regular = b_regular && x264_is_regular_file_path( filename );
12.
13.
          if( b_regular )
14.
15.
              FILE *f = x264_fopen( filename, "r" );
16.
           if( f )
17.
18.
                 b_regular = x264_is_regular_file( f );
19.
                  fclose( f );
20.
21.
22.
      const char *module = b auto ? ext : demuxer;
23.
      //strcasecmp(char *s1, char *s2)用于忽略大小写比较字符串.
24.
          //参数s1和s2字符串相等则返回0。s1大于s2则返回大于0 的值,s1 小于s2 则返回小于0的值。
25.
26.
          if( !strcasecmp( module, "avs" ) || !strcasecmp( ext, "d2v" ) || !strcasecmp( ext, "dga" ) )
27.
28.
29.
      #if HAVE AVS
30.
             cli_input = avs_input;
31.
              module = "avs";
32.
      #else
33.
              x264\_cli\_log(\ "x264",\ X264\_LOG\_ERROR,\ "not\ compiled\ with\ AVS\ input\ support\n"\ );
34.
      #endif
35.
36.
      }
37.
          else if( !strcasecmp( module, "y4m" ) )
             cli input = y4m input;
38.
          else if( !strcasecmp( module, "raw" ) || !strcasecmp( ext, "yuv" ) )
39.
40.
             cli input = raw input;
41.
          else
42.
43.
      #if HAVE FFMS
44.
           if( b_regular && (b_auto || !strcasecmp( demuxer, "ffms" )) &&
45.
                  !ffms_input.open_file( filename, p_handle, info, opt ) )
46.
47.
                  module = "ffms";
                 b_auto = 0;
48.
49.
                  cli_input = ffms_input;
50.
51.
      #endif
52.
     #if HAVE_LAVF
             if( (b auto || !strcasecmp( demuxer, "lavf" )) &&
53.
54.
                !lavf_input.open_file( filename, p_handle, info, opt )
55.
              {
                 module = "lavf";
56.
                 b auto = 0:
57.
58.
                 cli input = lavf input;
59.
60.
      #endif
61.
      #if HAVE_AVS
62.
      if( b_regular && (b_auto || !strcasecmp( demuxer, "avs" )) &&
                  !avs_input.open_file( filename, p_handle, info, opt ) )
63.
64.
65.
                  module = "avs";
                 b_auto = 0;
66.
67.
                 cli input = avs input;
68.
69.
      #endif
             if( b_auto && !raw_input.open_file( filename, p_handle, info, opt ) )
70.
71.
72.
                 module = "raw";
73.
                 b_auto = 0;
74.
                 cli_input = raw_input;
75.
76.
77.
              FAIL_IF_ERROR( !(*p_handle), "could not open input file `%s' via any method!\n", filename )
78.
79.
          strcpy( used demuxer, module );
80.
81.
          return 0;
82.
```

从源代码中可以看出,select_input()首先调用get_filename_extension()获取输入文件名的扩展名;然后根据扩展名设置不同的输入格式。

encode()

encode()编码YUV为H.264码流,该函数的定义如下所示。

```
[cpp] 📳 👔
      //编码(在内部有一个循环用于一帧一帧编码)
1.
2.
     static int encode( x264_param_t *param, cli_opt_t *opt )
3.
4.
         x264 t *h = NULL;
5.
          x264 picture t pic;
 6.
     cli_pic_t cli_pic;
7.
         const cli_pulldown_t *pulldown = NULL; // shut up gcc
8.
9.
         int
                 i_frame = 0;
     int i_frame_output = 0;
10.
         int64_t i_end, i_previous = 0, i_start = 0;
11.
     int64_t i_file = 0;
12.
13.
         int
                i frame size;
14.
     int64_t last_dts = 0;
15.
         int64 t prev dts = 0;
         int64 t first dts = 0;
16.
        define MAX PTS WARNING 3 /* arbitrary */
17.
     int pts_warning_cnt = 0;
18.
19.
         int64 t largest pts = -1;
20.
         int64_t second_largest_pts = -1;
21.
         int64_t ticks_per_frame;
22.
         double duration;
23.
          double pulldown_pts = 0;
24.
      int retval = 0;
25.
26.
     opt->b_progress &= param->i_log_level < X264_LOG_DEBUG;</pre>
27.
28.
     /* set up pulldown */
         if( opt->i_pulldown && !param->b_vfr_input )
29.
      {
30.
31.
             param -> b pulldown = 1:
32.
             param->b pic struct = 1;
33.
             \verb"pulldown" = \&pulldown" \_values[opt->i\_pulldown];
34.
             param->i_timebase_num = param->i_fps_den;
35.
             FAIL_IF_ERROR2( fmod( param->i_fps_num * pulldown->fps_factor, 1 ),
36.
                            "unsupported framerate for chosen pulldown\n" )
37.
             param->i_timebase_den = param->i_fps_num * pulldown->fps_factor;
38.
         //打开编码器
39.
40.
      h = x264_encoder_open( param );
41.
         FAIL IF ERROR2( !h, "x264 encoder open failed\n" );
42.
        //获得参数
43.
         x264_encoder_parameters( h, param );
      //一些不是裸流的封转格式(FLV,MP4等)需要一些参数,例如宽高等等
44.
          //cli output t是代表输出媒体文件的结构体
45.
      FAIL IF ERROR2( cli output.set param( opt->hout, param ), "can't set outfile param\n" );
46.
47.
          //计时
     i_start = x264_mdate();
48.
49.
50.
     /* ticks/frame = ticks/second / frames/second */
         ticks per_frame = (int64 t)param->i_timebase_den * param->i_fps_den / param->i_timebase_num / param->i_fps_num;
51.
52.
     FAIL_IF_ERROR2( ticks_per_frame < 1 && !param->b_vfr_input, "ticks_per_frame invalid: %"PRId64"\n", ticks_per_frame )
53.
          ticks_per_frame = X264_MAX( ticks_per_frame, 1 );
54.
          //如果不是在每个keyframe前面都增加SPS/PPS/SEI的话,就在整个码流前面加SPS/PPS/SEI
55.
     //Header指的就是SPS/PPS/SEI
56.
57.
          if( !param->b_repeat_headers )
58.
             // Write SPS/PPS/SEI
59.
             x264 nal t *headers;
60.
             int i nal:
61.
             //获得文件头 (SPS、PPS、SEI)
62.
63.
             FAIL\_IF\_ERROR2( \ x264\_encoder\_headers( \ h, \ \&headers, \ \&i\_nal \ ) < 0, \ "x264\_encoder\_headers \ failed \ " \ )
64.
             //把文件头写入输出文件
65.
             FAIL_IF_ERROR2( (i_file = cli_output.write_headers( opt->hout, headers )) < 0, "error writing headers to output file\n" );
66.
67.
68.
     if( opt->tcfile_out )
             fprintf( opt->tcfile_out, "# timecode format v2\n" );
69.
70.
71.
          /* Encode frames */
      //循环进行编码
72.
73.
          for( : !b ctrl c && (i frame < param->i frame total || !param->i frame total): i frame++ )
74.
75.
             //从输入源中获取1帧YUV数据,存于cli pic
             //cli_vid_filter_t可以认为是x264一种"扩展"后的输入源,可以在像素域对图像进行拉伸裁剪等工作。
76.
             //原本代表输入源的结构体是cli input t
77.
             78.
79.
                break;
             //初始化x264_picture_t结构体pic
80.
81.
             x264_picture_init( &pic );
82.
             //cli_pic到pic
83.
             convert_cli_to_lib_pic( &pic, &cli_pic );
```

```
84
                if( !param->b vfr input )
 85.
 86.
                   pic.i pts = i frame;
 87.
 88.
               if( opt->i pulldown && !param->b vfr input )
 89.
 90.
                    pic.i_pic_struct = pulldown->pattern[ i_frame % pulldown->mod ];
 91.
                    pic.i_pts = (int64_t)(pulldown_pts + 0.5);
 92.
                    pulldown_pts += pulldown_frame_duration[pic.i_pic_struct];
 93.
 94.
               else if( opt->timebase_convert_multiplier )
 95.
                   pic.i_pts = (int64_t)( pic.i_pts * opt->timebase_convert_multiplier + 0.5 );
 96.
 97.
                if( pic.i pts <= largest pts )</pre>
 98.
                    if( cli log level >= X264 LOG DEBUG || pts warning cnt < MAX PTS WARNING )</pre>
 99.
                       x264_cli_log( "x264", X264_LOG_WARNING, "non-strictly-monotonic pts at frame %d (%"PRId64" <= %"PRId64")\n",
100.
101.
                                     i_frame, pic.i_pts, largest_pts );
102.
                    else if( pts_warning_cnt == MAX_PTS_WARNING )
103
                        x264_cli_log( "x264", X264_LOG_WARNING, "too many nonmonotonic pts warnings, suppressing further ones\n" );
104.
                    pts_warning_cnt++;
105
                    pic.i_pts = largest_pts + ticks_per_frame;
106.
107.
                second_largest_pts = largest_pts;
108.
109.
                largest_pts = pic.i_pts;
110.
                if( opt->tcfile_out )
111.
                    fprintf( opt->tcfile_out, "%.6f\n", pic.i_pts * ((double)param->i_timebase_num / param->i_timebase_den) * 1e3 );
112.
113.
               if( opt->qpfile )
114.
               parse qpfile( opt, &pic, i frame + opt->i seek );
115.
               prev dts = last dts;
116.
                //编码pic中存储的1帧YUV数据
117.
118.
               i_frame_size = encode_frame( h, opt->hout, &pic, &last_dts );
119.
                if( i_frame_size < 0 )</pre>
120.
121.
                    b_ctrl_c = 1; /* lie to exit the loop */
122.
                    retval = -1;
123.
124.
               else if( i_frame_size )
125.
126.
                   i file += i frame size;
127.
                    i frame output++:
                   if( i frame output == 1 )
128.
129.
                        first dts = prev dts = last dts;
130.
                //释放外理宗的YIIV数据
131.
132.
               if( filter.release_frame( opt->hin, &cli_pic, i_frame + opt->i_seek ) )
133.
                    break:
134.
135.
                 /* update status line (up to 1000 times per input file) */
               if( opt->b_progress && i_frame_output )
136.
                    i_previous = print_status( i_start, i_previous, i_frame_output, param-
137.
       >i_frame_total, i_file, param, 2 * last_dts - prev_dts - first_dts );
138.
139.
            /* Flush delayed frames */
140.
           //输出编码器中剩余的帧
141.
            //x264_encoder_delayed_frames()返回剩余的帧的个数
142.
           while( !b ctrl c && x264 encoder delayed frames( h ) )
143.
144.
               prev dts = last dts;
145.
                //编码
               //注意第3个参数为NULL
146.
147
                i_frame_size = encode_frame( h, opt->hout, NULL, &last_dts );
148.
               if( i_frame_size < 0 )</pre>
149
150.
                   b ctrl c = 1; /* lie to exit the loop */
151.
                    retval = -1;
152.
153.
                else if( i_frame_size )
154.
155.
                    i file += i frame size;
156.
                   i frame output++;
157.
                    if( i frame output == 1 )
                       first_dts = prev_dts = last_dts;
158.
159.
               //输出一些统计信息
160.
161.
                \textbf{if}( \text{ opt->b\_progress \&\& i\_frame\_output })
162.
                   i_previous = print_status( i_start, i_previous, i_frame_output, param-
       >i_frame_total, i_file, param, 2 * last_dts - prev_dts - first_dts );
163.
164.
        fail:
            if( pts_warning_cnt >= MAX_PTS_WARNING && cli_log_level < X264_LOG_DEBUG )</pre>
165.
166.
               x264_cli_log( "x264", X264_LOG_WARNING, "%d suppressed nonmonotonic pts warnings\n", pts_warning_cnt-MAX_PTS_WARNING);
167.
168.
            /* duration algorithm fails when only 1 frame is output */
169.
            if( i frame output == 1 )
170.
               duration = (double)param->i fps den / param->i fps num;
171.
            else if( b ctrl c )
              duration = (double)(2 * last dts - prev dts - first dts) * param->i timebase num / param->i timebase den;
172
```

```
1/3.
174.
              175.
           //计时
176
          i_end = x264_mdate();
177.
            * Erase progress indicator before printing encoding stats. */
178.
          if( opt->b progress )
179.
              fprintf( stderr,
                                                                                                        \r" );
          //关闭编码器
180.
181.
          if( h )
              x264_encoder_close( h );
182.
183.
           fprintf( stderr, "\n" );
184.
185
           if( b ctrl c )
186.
              fprintf(\ stderr,\ "aborted\ at\ input\ frame\ %d,\ output\ frame\ %d\n",\ opt->i\_seek\ +\ i\_frame,\ i\_frame\_output\ );
187.
           //关闭输出文件
188.
          cli_output.close_file( opt->hout, largest_pts, second_largest_pts );
189.
          opt->hout = NULL;
190.
191.
           if(i_frame_output > 0)
192.
193.
              double fps = (double)i_frame_output * (double)1000000 /
194.
                       (double)( i_end - i_start );
195.
              fprintf(\ stderr,\ "encoded\ %d\ frames,\ %.2f\ fps,\ %.2f\ kb/s\n",\ i\_frame\_output,\ fps
196.
                       (double) i file * 8 / ( 1000 * duration ) );
197.
198.
199.
200
           return retval;
201.
      }
```

从源代码可以梳理出来encode()的流程:

- (1) 调用x264_encoder_open()打开H.264编码器。
- (2) 调用x264_encoder_parameters()获得当前的参数集x264_param_t,用于后续步骤中的一些配置。
- (3)调用输出格式(H.264裸流、FLV、mp4等)对应cli_output_t结构体的set_param()方法,为输出格式的封装器设定参数。其中参数源自于上一步骤得到的x264_param_t。
- (4) 如果不是在每个keyframe前面都增加SPS/PPS/SEI的话,就调用x264_encoder_headers()在整个码流前面加SPS/PPS/SEI。
- (5) 进入一个循环中进行一帧一帧的将YUV编码为H.264:
 - a)调用输入格式(YUV、Y4M等)对应的cli_vid_filter_t结构体get_frame()方法,获取一帧YUV数据。
 - b)调用encode_frame()编码该帧YUV数据为H.264数据,并且输出出来。该函数内部调用x264_encoder_encode()完成编码工作,调用输出格式对应cli_output_t结构体的write_frame()完成了输出工作。
 - c)调用输入格式(YUV、Y4M等)对应的cli_vid_filter_t结构体release_frame()方法,释放刚才获取的YUV数据。
 - d)调用print_status()输出一些统计信息。
- (6) 编码即将结束的时候,进入另一个循环,输出编码器中缓存的视频帧:
 - a)不再传递新的YUV数据,直接调用encode_frame(),将编码器中缓存的剩余几帧数据编码输出出来。
 - b)调用print_status()输出一些统计信息。
- (7) 调用x264_encoder_close()关闭H.264编码器。

encode()的流程中涉及到libx264的几个关键的API,在这里暂时不做详细分析(后续文章中再进行补充):

```
x264_encoder_open():打开H.264编码器。
x264_encoder_headers():输出SPS/PPS/SEI。
x264_encoder_encode():编码一帧数据。
x264_encoder_close():关闭H.264编码器。
```

此外上述流程中涉及到两个比较简单的函数:encode_frame()和print_status()。其中encode_frame()用于编码一帧数据,而print_status()用于输出一帧数据编码后的统计信息。下文记录一下这两个函数的定义。

encode_frame()

encode_frame()的定义如下。

```
[cpp] 📳 📑
      //编码1帧
 2.
      static int encode_frame( x264_t *h, hnd_t hout, x264_picture_t *pic, int64_t *last_dts )
3.
 4.
         x264_picture_t pic_out;
 5.
          x264_nal_t *nal;
6.
         int i_nal;
         int i frame size = 0;
7.
      //编码API
8.
          //编码x264 picture t为x264 nal t
9.
      i_frame_size = x264_encoder_encode( h, &nal, &i_nal, pic, &pic_out );
10.
11.
12.
      FAIL IF ERROR( i frame size < 0, "x264 encoder encode failed\n" );
13.
14.
     if( i_frame_size )
15.
16.
             //通过cli_output_t中的方法输出
17.
              //输出raw H.264流的话,等同于直接fwrite()
18.
             //其他封装格式,则还需进行一定的封装
19.
              i_frame_size = cli_output.write_frame( hout, nal[0].p_payload, i_frame_size, &pic_out );
20.
             *last_dts = pic_out.i_dts;
21.
22.
23.
          return i frame size;
24.
```

从源代码可以看出,encode_frame()内部调用x264_encoder_encode()完成编码工作,调用输出格式对应cli_output_t结构体的write_frame()完成了输出工作。其中有关cli_output_t结构体的知识将在后文中记录。

print_status()

print status()的定义如下。

```
[cpp] 📳 📑
      //打印一些和时间有关的统计信息
2.
      static int64_t print_status( int64_t i_start, int64_t i_previous, int i_frame, int i_frame_total, int64_t i_file, x264_param_t *param
      , int64_t last_ts )
3.
4.
         char buf[200];
5.
          int64_t i_time = x264_mdate();
     if( i previous && i time - i previous < UPDATE INTERVAL )</pre>
6.
7.
              return i previous:
      int64_t i_elapsed = i_time - i_start;
8.
          double fps = i_elapsed > 0 ? i_frame * 1000000. / i elapsed : 0;
9.
10.
         double bitrate;
11.
         if( last ts )
12.
             bitrate = (double) i_file * 8 / ( (double) last_ts * 1000 * param->i_timebase_num / param->i_timebase_den );
13.
          else
14.
             bitrate = (double) i_file * 8 / ( (double) 1000 * param->i_fps_den / param->i_fps_num );
15.
          if( i_frame_total )
16.
17.
              //形成输出的字符串
             int eta = i_elapsed * (i_frame_total - i_frame) / ((int64_t)i_frame * 1000000);
18.
19.
              sprintf( buf, "x264 [%.1f%%] %d/%d frames, %.2f fps, %.2f kb/s, eta %d:%02d:%02d",
                     100. * i_frame / i_frame_total, i_frame, i_frame_total, fps, bitrate,
20.
21.
                      eta/3600, (eta/60)%60, eta%60 );
22.
23.
          else
             sprintf( buf, "x264 %d frames: %.2f fps, %.2f kb/s", i_frame, fps, bitrate );
24.
          //輸出到stderr
25.
         fprintf( stderr, "%s \r", buf+5 );
26.
27.
          //设置到标题栏?
28.
         x264_cli_set_console_title( buf );
29.
          fflush( stderr ); // needed in windows
30.
          return i_time;
31.
```

print_status()的代码不再详细记录,它的输出效果如下图中红框中的文字。

```
x264 [9.3%] 140/1505 frames, 84.85 fps, 356.48 kb/s, eta 0.00:16

Lenevo@LEIXH /d/tutorial_code/simplest_encoder/encoder_sourcecode/x264
$ x264 -o ourtine_640x360.hz64 ourtine_640x360.yuv
yuv [info]: 640x360p 8:0 @ 2571 fps (cfr)
x264 [info]: using cpu capabilities: MHX2 SSE2Fast SSSE3 SSE4.2 AUX
x264 [info]: profile High, level 3.0
[19.3x] 140/1505 frames, 84.85 fps, 356.48 kb/s, eta 9:00:16

http://blog.csdn.net/leixiaohua1020
```

X264控制台程序中和输入输出相关的结构体

在x264控制台程序中有3个和输入输出相关的结构体:

cli output t:输出格式对应的结构体。输出格式一般为H.264裸流、FLV、MP4等。

cli_input_t:输入格式对应的结构体。输入格式一般为纯YUV像素数据,Y4M格式数据等。

cli_vid_filter_t:输入格式滤镜结构体。滤镜可以对输入数据做一些简单的处理,例如拉伸、裁剪等等(当然滤镜也可以不作任何处理,直接 读取输入数据)。

在x264的编码过程中,调用cli_vid_filter_t结构体的get_frame()读取YUV数据,调用cli_output_t的write_frame()写入数据。下面简单分析一下它们之间的关系。

cli_output_t

x264项目中和cli_output_t结构体相关的源代码都位于根目录的output文件夹下。cli_output_t的定义位于output\output.h,如下所示。

```
[cpp] 🗐 🔝
       typedef struct
 3.
           int (*open_file)( char *psz_filename, hnd_t *p_handle, cli_output_opt_t *opt );
 4.
      int (*set_param)( hnd_t handle, x264_param_t *p_param );
           int (*write headers)( hnd t handle, x264 nal t *p nal );
 5.
      int (*write_frame)( hnd_t handle, uint8_t *p_nal, int i_size, x264_picture_t *p_picture );
 6.
          int (*close_file)( hnd_t handle, int64_t largest_pts, int64_t second_largest_pts );
 7.
      } cli output t;
 8.
 9.
 10.
      extern const cli_output_t raw_output;
 11.
       extern const cli_output_t mkv_output;
 12.
      extern const cli_output_t mp4_output;
13. extern const cli_output_t flv_output;
```

从源代码中可以看出,cli_output_t中一共包含了open_file(),set_param(),write_headers(),write_frame(),close_file()五个接口。在x264中有raw_output,mkv_outp ut,mp4_output,flv_output这几个cli_output_t结构体,分别对应H.264裸流,MKV,MP4,FLV格式。下面举例看两个结构体:raw_output和flv_output。

raw_output (H.264裸流的cli_output_t结构体)

raw output的定义位于output\raw.c,该文件内容如下所示。

```
[cpp] 📳 🔝
 1.
      #include "output.h"
 2.
 3.
       static int open_file( char *psz_filename, hnd_t *p_handle, cli_output_opt_t *opt )
 4.
 5.
          if( !strcmp( psz_filename, "-" ) )
              *p handle = stdout;
 6.
          else if( !(*p_handle = x264_fopen( psz_filename, "w+b" )) )
 8.
        return -1:
 9.
10.
      return 0:
11.
      }
12.
13.
      static int set_param( hnd_t handle, x264_param_t *p_param )
14.
      {
15.
          return 0:
16.
17.
18.
      static int write_headers( hnd_t handle, x264_nal_t *p_nal )
19.
20.
       int size = p_nal[0].i_payload + p_nal[1].i_payload + p_nal[2].i_payload;
21.
22.
      if( fwrite( p_nal[0].p_payload, size, 1, (FILE*)handle ) )
23.
              return size;
         return -1:
24.
25.
26.
      static int write_frame( hnd_t handle, uint8_t *p_nalu, int i_size, x264_picture_t *p_picture )
27.
28.
29.
          if( fwrite( p_nalu, i_size, 1, (FILE*)handle ) )
30.
              return i_size;
31.
          return -1;
32.
33.
34.
      static int close_file( hnd_t handle, int64_t largest_pts, int64_t second_largest_pts
35.
36.
       if( !handle || handle == stdout )
37.
              return 0;
38.
          return fclose( (FILE*)handle ):
39.
40.
41.
42.
      const cli_output_t raw_output = { open_file, set_param, write_headers, write_frame, close_file };
```

可以看出raw_output中的函数定义都比较简单,只是封装了fwrite(),fclose()等函数。

flv_output的定义位于output\flv.c,如下所示。

```
1. | const cli_output_t flv_output = { open_file, set_param, write_headers, write_frame, close_file };
```

该文件内容比较多,只举例看一下其中的两个函数:open_file()和write_frame()。

open_file()

flv_output 中的open_file()的定义如下所示。

```
1.
       \textbf{static int} \  \, \textbf{write\_header(} \  \, \textbf{flv\_buffer *c })
 2.
 3.
            {\sf flv\_put\_tag(\ c,\ "FLV"\ );\ //\ Signature}
      flv_put_tag( c, 1 ); // Version
flv_put_byte( c, 1 ); // Video Only
flv_put_be32( c, 9 ); // DataOffset
flv_put_be32( c, 0 ); // PreviousTagSize0
 4.
 5.
 6.
 7.
 8.
 9.
            return flv flush data( c );
10.
      }
11.
12.
       static int open_file( char *psz_filename, hnd_t *p_handle, cli_output_opt_t *opt )
13.
14.
            *p handle = NULL;
15.
            flv_hnd_t *p_flv = calloc( 1, sizeof(flv_hnd_t) );
      if( !p_flv )
16.
17.
                return -1:
18.
           p_flv->b_dts_compress = opt->use_dts_compress;
19.
20.
21.
            p_flv->c = flv_create_writer( psz_filename );
      if( !p_flv->c )
22.
23.
                return -1;
24.
25.
            CHECK( write_header( p_flv->c ) );
26.
       *p_handle = p_flv;
27.
       return 0;
28.
29. }
```

可以看出flv_output 中的open_file()中完成了FLV封装格式文件头的创建。

write_frame()

flv_output 中的write_frame()的定义如下所示。

```
1.
      static int write_frame( hnd_t handle, uint8_t *p_nalu, int i_size, x264_picture_t *p_picture )
 2.
3.
          flv_hnd_t *p_flv = handle;
 4.
      flv_buffer *c = p_flv->c;
5.
6.
      \#define\ convert\_timebase\_ms(\ timestamp,\ timebase\ )\ (int64\_t)((timestamp)\ *\ (timebase)\ *\ 1000\ +\ 0.5)
7.
8.
      if( !p flv->i framenum )
9.
10.
              p_flv->i_delay_time = p_picture->i_dts * -1;
11.
              \textbf{if}( \ !p\_flv->b\_dts\_compress \&\& p\_flv->i\_delay\_time \ )
                 x264_cli_log( "flv", X264_LOG_INFO, "initial delay %"PRId64" ms\n",
12.
13.
                                 convert_timebase_ms( p_picture->i_pts + p_flv->i_delay_time, p_flv->d_timebase ) );
14.
15.
16.
          int64_t dts;
17.
          int64_t cts;
18.
      int64 t offset;
19.
20.
      if( p_flv->b_dts_compress )
21.
22.
              if( p flv->i framenum == 1 )
23.
                  p_flv->i_init_delta = convert_timebase_ms( p_picture->i_dts + p_flv->i_delay_time, p_flv->d_timebase );
24.
              dts = p_flv->i_framenum > p_flv->i_delay_frames
25.
                  ? convert_timebase_ms( p_picture->i_dts, p_flv->d_timebase )
                 : p_flv->i_framenum * p_flv->i_init_delta / (p_flv->i_delay_frames + 1);
26.
27.
              cts = convert_timebase_ms( p_picture->i_pts, p_flv->d_timebase );
      }
28.
29.
          else
      {
30.
31.
              \label{eq:dts} dts = convert\_timebase\_ms( p\_picture->i\_dts + p\_flv->i\_delay\_time, p\_flv->d\_timebase );
32.
              cts = convert_timebase_ms( p_picture->i_pts + p_flv->i_delay_time, p_flv->d_timebase );
33.
34.
      offset = cts - dts;
35.
      if( p flv->i framenum )
36.
37.
38.
              if( p flv->i prev dts == dts )
                  x264_cli_log( "flv", X264_LOG_WARNING, "duplicate DTS %"PRId64" generated by rounding\n"
39.
                                                decoding framerate cannot exceed 1000fps\n", dts );
40.
41.
              if( p flv->i prev cts == cts )
               x264_cli_log( "flv", X264_LOG_WARNING, "duplicate CTS %"PRId64" generated by rounding\n"
42.
                                                 composition framerate cannot exceed 1000fps\n", cts );
43.
44.
45.
          p_flv->i_prev_dts = dts;
46.
      p_flv->i_prev_cts = cts;
47.
48.
      // A new frame - write packet header
49.
          flv_put_byte( c, FLV_TAG_TYPE_VIDEO );
50.
        flv_put_be24( c, 0 ); // calculated later
51.
          flv put be24( c, dts );
52.
      flv_put_byte( c, dts >> 24 );
          flv_put_be24( c, 0 );
53.
54.
55.
          p flv->start = c->d cur;
      flv_put_byte( c, p_picture->b_keyframe ? FLV_FRAME_KEY : FLV_FRAME_INTER );
56.
57.
          flv_put_byte(c, 1); // AVC NALU
58.
      flv_put_be24( c, offset );
59.
60.
      if( p_flv->sei )
61.
62.
              flv_append_data( c, p_flv->sei, p_flv->sei_len );
63.
              free( p_flv->sei );
64.
              p_flv->sei = NULL;
65.
66.
      flv_append_data( c, p_nalu, i_size );
67.
68.
          unsigned length = c->d cur - p flv->start;
          flv_rewrite_amf_be24(c, length, p_flv->start-10);
69.
          flv_put_be32( c, 11 + length ); // Last tag size
70.
71.
          CHECK( flv_flush_data(c));
72.
73.
          p_flv->i_framenum++;
74.
75.
          return i_size;
76.
```

flv_output 中的可以看出write_frame()中完成了FLV封装格式中一个Tag单元的创建。

cli_input_t

[cpp] 📳 📑

x264项目中和cli_input_t结构体相关的源代码都位于根目录的input文件夹下。cli_input_t的定义位于input\input.h,如下所示。

```
[cpp] 📳 🔝
      typedef struct
2.
      {
          int (*open_file)( char *psz_filename, hnd_t *p_handle, video_info_t *info, cli_input_opt_t *opt );
3.
      int (*picture_alloc)( cli_pic_t *pic, int csp, int width, int height );
4.
          int (*read_frame)( cli_pic_t *pic, hnd_t handle, int i_frame );
6.
      int (*release_frame)( cli_pic_t *pic, hnd_t handle );
7.
          void (*picture clean)( cli pic t *pic );
         int (*close file)( hnd t handle );
8.
9.
     } cli input t;
10.
11.
      extern const cli input t raw input;
12.
     extern const cli input t y4m input;
13.
      extern const cli input t avs input;
14.
      extern const cli_input_t lavf_input;
15.
      extern const cli_input_t ffms_input;
```

从源代码中可以看出,cli_input_t中一共包含了open_file(),picture_alloc(),read_frame(),release_frame(),picture_clean(),close_file()六个接口。在x264中有raw_i nput, y4m_input, avs_input, lavf_input, ffms_input这几个cli_output_t结构体,分别对应H.264裸流,Y4M,AVS,LAVF,FFMS格式(后几种没有接触过)。下面举例看两个结构体:raw_input和y4m_input。

raw_input (纯YUV像素数据的cli_input_t结构体)

raw input的定义位于input\raw.c,该文件内容如下所示。

```
1.
      #include "input.h'
      #define FAIL_IF_ERROR( cond, ... ) FAIL_IF_ERR( cond, "raw", __VA_ARGS
2.
3.
4.
      typedef struct
5.
6.
         FILE *fh;
7.
          int next_frame;
      uint64_t plane_size[4];
8.
          uint64_t frame_size;
9.
10.
      int bit_depth;
11.
     } raw hnd t;
12.
13.
      //打开raw YUV格式文件
      static int open file( char *psz filename, hnd t *p handle, video info t *info, cli input opt t *opt )
14.
15.
16.
          raw_hnd_t *h = calloc( 1, sizeof(raw_hnd_t) );
17.
          if(!h)
      return -1;
18.
19.
20.
      if( !opt->resolution )
21.
             //如果没有设置分辨率
22.
23.
              //尝试从文件名中解析分辨率
             /* try to parse the file name */
24.
25.
              for( char *p = psz filename; *p; p++ )
             if( *p >= '0' && *p <= '9' && sscanf( p, "%dx%d", &info->width, &info->height ) == 2
26.
27.
                     break:
28.
29.
          else
            sscanf( opt->resolution, "%dx%d", &info->width, &info->height );
30.
          //没有分辨率信息的话,会弹出错误信息
31.
32.
        FAIL_IF_ERROR( !info->width || !info->height, "raw input requires a resolution.\n" )
33.
          //设置颜色空间
34.
      if( opt->colorspace )
35.
36.
              for( info->csp = X264_CSP_CLI_MAX-1; info->csp > X264_CSP_NONE; info->csp-- )
37.
38.
                  if( x264_cli_csps[info->csp].name && !strcasecmp( x264_cli_csps[info->csp].name, opt->colorspace ) )
39.
40.
41.
              FAIL_IF_ERROR( info->csp == X264_CSP_NONE, "unsupported colorspace `%s'\n", opt->colorspace );
42.
43.
          else /* default */
             info->csp = X264_CSP_I420;//默认为YUV420P
44.
45.
          //颜色位深
46.
         h->bit depth = opt->bit depth;
          FAIL\_IF\_ERROR( \ h->bit\_depth \ < 8 \ || \ h->bit\_depth \ > 16, \ "unsupported bit depth \ `%d'\n", \ h->bit\_depth \ );
47.
48.
         if( h->bit_depth > 8 )
49.
              info->csp |= X264_CSP_HIGH_DEPTH;
50.
          if( !strcmp( psz_filename, "-" ) )
51.
             h->fh = stdin; //从管道输入
52.
53.
54.
            h->fh = x264_fopen( psz_filename, "rb" ); //打开文件
55.
          if( h->fh == NULL )
         return -1;
56.
57.
      info->thread safe = 1;
58.
59.
          info->num frames = 0;
          info->vfr = 0;
60.
61.
62.
          const x264_cli_csp_t *csp = x264_cli_get_csp( info->csp );
```

```
for( int i = 0; i < csp->planes; i++ )
 63.
 65.
                h->plane_size[i] = x264_cli_pic_plane_size( info->csp, info->width, info->height, i );
 66.
                h->frame_size += h->plane_size[i];
 67.
                 ^{\prime *} x264 cli pic plane size returns the size in bytes, we need the value in pixels from here on ^{*\prime}
               h->plane size[i] /= x264 cli csp depth factor( info->csp );
 68.
 69.
 70.
 71.
            if( x264 is regular file( h->fh ) )
 72.
 73.
                fseek( h \rightarrow fh, \theta, SEEK_END );
 74.
                uint64_t size = ftell( h->fh );
 75.
                fseek( h->fh, 0, SEEK_SET );
 76.
                info->num_frames = size / h->frame_size
 77.
 78.
 79.
            *p_handle = h;
 80.
           return 0;
 81.
 82.
       //读取一帧数据-内部
 83.
       static int read frame internal( cli pic t *pic, raw hnd t *h, int bit depth uc )
 84.
 85.
 86.
           int error = 0:
 87.
            int pixel_depth = x264_cli_csp_depth_factor( pic->img.csp );
 88.
           //一个分量一个分量读
 89.
            for( int i = 0; i < pic->img.planes && !error; i++ )
 90.
 91.
                //fread()读取
 92.
                error |= fread( pic->img.plane[i], pixel_depth, h->plane_size[i], h->fh ) != h->plane_size[i];
 93.
                if( bit_depth_uc )
 94.
 95.
                    /* upconvert non 16bit high depth planes to 16bit using the same
                    * algorithm as used in the depth filter. */
 96.
 97.
                    uint16 t *plane = (uint16 t*)pic->imq.plane[i];
                    uint64_t pixel_count = h->plane_size[i];
 98.
 99.
                    int lshift = 16 - h->bit depth:
100.
                    for( uint64 t j = 0; j < pixel count; j++ )</pre>
101.
                        plane[j] = plane[j] << lshift;
102.
103.
104.
           return error;
105.
106.
       //读取一帧数据
107.
        static int read_frame( cli_pic_t *pic, hnd_t handle, int i_frame )
108.
109.
            raw_hnd_t *h = handle;
110.
111.
            if( i_frame > h->next_frame )
112.
113.
                if( x264 is regular file( h->fh ) )
                   fseek( h->fh, i_frame * h->frame_size, SEEK_SET ); //fseek()。偏移量=帧序号*帧大小
114.
115.
                else
116.
                   while( i_frame > h->next_frame )
117.
118.
                        //读取一帧数据-内部
119.
                        if( read_frame_internal( pic, h, 0 ) )
120.
                            return -1;
121.
                        h->next_frame++;
122.
123.
124.
125.
            if( read_frame_internal( pic, h, h->bit_depth & 7 ) )
126.
               return -1;
127.
       h - next_frame = i_frame + 1;
128.
129.
            return 0:
130.
       }
131.
132.
       //关闭文件
133.
        static int close_file( hnd_t handle )
134.
135.
            raw_hnd_t *h = handle;
136.
           if( !h || !h->fh )
137.
138.
            //fclose()关闭文件
139.
            fclose( h->fh );
140.
          free( h );
141.
            return 0;
142.
        //raw格式对应的数组
143.
       const cli_input_t raw_input = { open_file, x264_cli_pic_alloc, read_frame, NULL, x264_cli_pic_clean, close_file };
144.
```

从源代码中可以看出,raw_input 中的open_file()函数在打开YUV/像素数据的时候,会首先判断是否设置了宽和高(YUV)是纯像素数据,没有宽和高信息),如果没有设置,则会尝试从文件路径中解析宽和高信息。如果成功完成上述步骤,open_file()就会调用x264_fopen()打开输入文件。其他的函数在源代码中都写了注释,就不再重复记录了。

y4m_input的定义位于input\y4m.c,如下所示。

```
[cpp] [a]

1. const cli_input_t y4m_input = { open_file, x264_cli_pic_alloc, read_frame, NULL, x264_cli_pic_clean, close_file };
```

该文件内容较多,不再进行详细分析。在这里看一个打开文件的函数open_file()。该函数的定义如下所示。

```
[cpp] 📳 📑
      typedef struct
2.
3.
          FILE *fh;
4.
      int next_frame;
5.
          int seq_header_len;
6.
     int frame_header_len;
          uint64_t frame_size;
     uint64_t plane_size[3];
8.
9.
          int bit_depth;
10.
     } y4m hnd t;
11.
12.
     #define Y4M MAGIC "YUV4MPEG2"
      #define MAX YUV4 HEADER 80
13.
      #define Y4M FRAME MAGIC "FRAME"
14.
      #define MAX FRAME HEADER 80
15.
16.
17.
      static int parse_csp_and_depth( char *csp_name, int *bit_depth )
18.
19.
          int csp
                    = X264_CSP_MAX;
20.
21.
          /* Set colorspace from known variants */
22.
      if( !strncmp( "420", csp_name, 3 ) )
23.
             csp = X264_CSP_I420;
24.
      else if( !strncmp( "422", csp name, 3 ) )
25.
             csp = X264_CSP_I422;
      else if( !strncmp( "444", csp_name, 3 ) && strncmp( "444alpha", csp_name, 8 ) ) // only accept alphaless 4:4:4
26.
27.
             csp = X264_CSP_I444;
28.
          /* Set high bit depth from known extensions */
29.
30.
      if( sscanf( csp_name, "%*d%*[pP]%d", bit_depth ) != 1 )
31.
              *bit_depth = 8;
32.
33.
          return csp;
34.
35.
      static int open_file( char *psz_filename, hnd_t *p_handle, video_info_t *info, cli_input_opt_t *opt )
36.
37.
38.
          y4m hnd t *h = malloc( sizeof(y4m hnd t) );
39.
          int i;
40.
      uint32_t n, d;
41.
          char header[MAX YUV4 HEADER+10];
        char *tokend, *header end;
42.
          int colorspace = X264 CSP NONE;
43.
      int alt_colorspace = X264_CSP_NONE;
44.
          int alt_bit_depth = 8;
45.
      if( !h )
46.
47.
             return -1;
48.
49.
          h - next_frame = 0;
     info->vfr = 0;
50.
51.
     if( !strcmp( psz_filename, "-" ) )
52.
53.
             h->fh = stdin;
54.
      else
55.
             h->fh = x264 fopen(psz filename, "rb");
      if( h->fh == NULL )
56.
57.
             return -1:
58.
          h->frame_header_len = strlen( Y4M_FRAME_MAGIC )+1;
59.
60.
61.
          /* Read header */
62.
       //解析Y4M格式的文件头
63.
          for( i = 0; i < MAX_YUV4_HEADER; i++ )</pre>
64.
65.
              header[i] = fgetc(h->fh);
             if( header[i] == '\n' )
66.
67.
              {
68.
                   /* Add a space after last option. Makes parsing "444" vs
                     "444alpha" easier. */
69.
                  header[i+1] = 0x20;
70.
                  header[i+2] = 0;
71.
72.
                  break:
73.
             }
74.
75.
          if( i == MAX_YUV4_HEADER || strncmp( header, Y4M_MAGIC, strlen( Y4M_MAGIC ) ) )
76.
             return -1;
77.
78.
          /* Scan properties */
79.
          header_end = &header[i+1]; /* Include space */
          h->seq_header_len = i+1;
80.
```

```
81.
            for( char *tokstart = &header(strlen( Y4M MAGIC )+1): tokstart < header end: tokstart++ )</pre>
 82.
               if(*tokstart == 0x20)
 83.
 84.
                   continue:
 85.
                switch( *tokstart++ )
 86.
                    case 'W': /* Width. Required. */
 87.
 88.
                       info->width = strtol( tokstart, &tokend, 10 );
 89.
                       tokstart=tokend;
 90.
                       break;
 91.
                    case 'H': /* Height. Required. */
                     info->height = strtol( tokstart, &tokend, 10 );
 92.
 93.
                       tokstart=tokend;
 94.
                       break;
                    case 'C': /* Color space */
 95.
                     colorspace = parse csp and depth( tokstart, &h->bit depth );
 96.
 97.
                       tokstart = strchr( tokstart, 0x20 );
 98.
                       break;
                    case 'I': /* Interlace type */
 99.
100.
                       switch( *tokstart++ )
101.
                        {
102
                            case 't':
103.
                               info->interlaced = 1;
104.
                               info->tff = 1:
105.
                               break;
106.
                            case 'b':
107.
                               info->interlaced = 1;
108.
                               info->tff = 0;
109.
                               break;
110.
                           case 'm':
111.
                               info->interlaced = 1;
                              break;
112.
                           //case '?':
113.
                           //case 'p':
114.
115.
                            default:
116.
                              break:
117.
118.
                       break;
119.
                    case 'F': /* Frame rate - 0:0 if unknown */
120.
                       if( sscanf( tokstart, "%u:%u", &n, &d ) == 2 && n && d )
121.
                        {
122.
                           x264_reduce_fraction( &n, &d );
123.
                           info->fps num = n;
124.
                           info->fps den = d;
125.
                       }
126.
                       tokstart = strchr( tokstart, 0x20 );
127.
                       break:
                    case 'A': /* Pixel aspect - 0:0 if unknown */
128
129.
                        /st Don't override the aspect ratio if sar has been explicitly set on the commandline. st/
130
                       if( sscanf( tokstart, "%u:%u", &n, &d ) == 2 && n && d )
131.
132.
                           x264_reduce_fraction( &n, &d );
133.
                           info->sar_width = n;
134.
                           info->sar_height = d;
135.
136.
                       tokstart = strchr( tokstart, 0x20 );
137.
                       break;
                    case 'X': /* Vendor extensions */
138.
                       if( !strncmp( "YSCSS=", tokstart, 6 ) )
139.
140.
141.
                            /* Older nonstandard pixel format representation */
142.
                           tokstart += 6:
143.
                           alt colorspace = parse csp and depth( tokstart, &alt bit depth );
144.
145
                        tokstart = strchr( tokstart, 0x20 );
146.
                       break;
147
148.
149.
150.
       if( colorspace == X264_CSP_NONE )
151.
152.
               colorspace = alt colorspace;
153.
               h->bit_depth = alt_bit_depth;
154.
155.
       // default to 8bit 4:2:0 if nothing is specified
156.
           if( colorspace == X264 CSP NONE )
157.
158.
          {
159.
                colorspace
                             = X264_CSP_I420;
160.
               h->bit_depth = 8;
161.
162.
163.
            FAIL\_IF\_ERROR(\ colorspace <= X264\_CSP\_NONE \ | | \ colorspace >= X264\_CSP\_MAX, \ "colorspace unhandled\n" \ )
164.
           FAIL_IF_ERROR( h->bit_depth < 8 || h->bit_depth > 16, "unsupported bit depth `%d'\n", h->bit_depth );
165.
166.
           info->thread safe = 1;
167.
            info->num frames = 0;
168.
                        = colorspace;
           info->csp
169.
           h->frame_size
                             = h->frame header len:
170.
           if( h->bit_depth > 8 )
171.
```

```
into->csp |= X264_CSP_HIGH_DEPTH;
1/2.
173.
174.
       const x264_cli_csp_t *csp = x264_cli_get_csp( info->csp );
175.
176.
       for( i = 0: i < csp->planes: i++ )
177.
178.
               h->plane_size[i] = x264_cli_pic_plane_size( info->csp, info->width, info->height, i );
179.
               h->frame size += h->plane size[i];
180.
               /* x264 cli pic plane size returns the size in bytes, we need the value in pixels from here on */
181.
               h->plane_size[i] /= x264_cli_csp_depth_factor( info->csp );
182.
183.
       /* Most common case: frame_header = "FRAME" */
184.
185.
           if( x264_is_regular_file( h->fh ) )
186.
187.
               uint64_t init_pos = ftell( h->fh );
188.
               fseek( h->fh, 0, SEEK_END );
               uint64_t i_size = ftell( h->fh );
189.
190.
               fseek( h->fh, init_pos, SEEK_SET );
191.
               info->num frames = (i size - h->seq header len) / h->frame size;
192.
193.
194.
           *p handle = h:
195.
           return 0:
196.
```

从源代码可以看出,y4m_input中的open_file()完成了Y4M文件的打开和文件头解析的功能。

cli_vid_filter_t

x264项目中和cli_vid_filter_t结构体相关的源代码都位于根目录的filters文件夹下。cli_vid_filter_t的定义位于filters\video\video\video.h,如下所示。

```
[cpp] 🗐 🔝
 1.
       struct cli_vid_filter_t
 2.
      {
           /* name of the filter */
 3.
      const char *name:
 4.
           /* help: a short message on what the filter does and how to use it.
 5.
      * this should only be implemented by filters directly accessible by the user */
 6.
           void (*help)( int longhelp );
      /* init: initializes the filter given the input clip properties and parameter to adjust them as necessary
 8.
 q
            * with the given options provided by the user.
 10.
      * returns 0 on success, nonzero on error. */
 11.
           int (*init)( hnd_t *handle, cli_vid_filter_t *filter, video_info_t *info, x264_param_t *param, char *opt_string );
      /* get_frame: given the storage for the output frame and desired frame number, generate the frame accordingly.
 12.
            \boldsymbol{*} the image data returned by get_frame should be treated as const and not be altered.
 13.
      * returns 0 on success, nonzero on error. */
 14.
 15.
           int (*get_frame)( hnd_t handle, cli_pic_t *output, int frame );
 16.
      /* release_frame: frame is done being used and is signaled for cleanup
            st returns 0 on succeess, nonzero on error. st/
 17.
       int (*release_frame)( hnd_t handle, cli_pic_t *pic, int frame );
 18.
           /* free: run filter cleanup procedures. */
 19.
       void (*free)( hnd_t handle );
 20.
 21.
           /st next registered filter, unused by filters themselves st/
 22.
          cli_vid_filter_t *next;
23. };
```

从源代码中可以看出,cli_vid_filter_t中一共包含了help(),init(),get_frame(),release_frame(),free()几个接口。下面举例看两个Filter结构体: source_filter:不作任何处理。 resize filter:拉伸。

source filter (没有功能的cli vid filter t结构体)

source_filter的定义位于filters\video\source.c,该文件内容如下所示。

```
[cpp] 📳 📑
       #include "video.h"
  2.
  3.
       \slash This filter converts the demuxer API into the filtering API for video frames.
  4.
       * Backseeking is prohibited here as not all demuxers are capable of doing so. */
  5.
  6.
       typedef struct
  7.
  8.
           cli pic t pic:
           hnd t hin;
  9.
 10.
          int cur frame;
 11.
       } source_hnd_t;
 12.
 13.
       cli_vid_filter_t source_filter;
 14.
       static int init( hnd_t *handle, cli_vid_filter_t *filter, video_info_t *info, x264_param_t *param, char *opt_string )
 15.
 16.
 17.
           source_hnd_t *h = calloc(1, sizeof(source_hnd_t));
 18.
       if( !h )
 19.
 20.
       h->cur_frame = -1;
 21.
 22.
       if( cli input.picture alloc( &h->pic, info->csp, info->width, info->height ) ;
 23.
               return -1;
 24.
 25.
           h->hin = *handle:
       *handle = h;
 26.
 27.
           *filter = source filter:
 28.
 29.
           return 0:
       }
 30.
 31.
 32.
       static int get_frame( hnd_t handle, cli_pic_t *output, int frame )
 33.
 34.
          source_hnd_t *h = handle;
 35.
           /* do not allow requesting of frames from before the current position */
 36.
       if( frame <= h->cur frame || cli input.read frame( &h->pic, h->hin, frame ) )
 37.
               return -1;
       h->cur frame = frame;
 38.
 39.
           *output = h->pic:
 40.
          return 0:
 41.
 42.
 43.
       static int release_frame( hnd_t handle, cli_pic_t *pic, int frame )
 44.
 45.
           source_hnd_t *h = handle;
 46.
       if( cli_input.release_frame && cli_input.release_frame( &h->pic, h->hin ) )
 47.
 48.
           return 0;
 49.
 50.
 51.
       static void free filter( hnd t handle )
 52.
           source hnd t *h = handle;
 53.
          cli input.picture clean( &h->pic );
 54.
           cli input.close file( h->hin );
 55.
 56.
           free( h );
 57.
 58.
59. cli_vid_filter_t source_filter = { "source", NULL, init, get_frame, release_frame, free_filter, NULL };
```

从源代码中可以看出,source_filter的get_frame()直接调用了cli_input_t的read_frame();而它的release_frame()也是直接调用了cli_input_t的release_frame()。简而言之,source_filter相当于是一个cli_input_t。

resize_filter (拉伸功能对应的cli_vid_filter_t结构体)

resize_filter的定义位于filters\video\resize.c,该结构体定义如下。

由于resize_filter涉及到的代码比较多,在这里仅看一下它的get_frame()的定义。

```
[cpp] 📳 📑
      static int get_frame( hnd_t handle, cli_pic_t *output, int frame )
2.
     {
3.
          resizer_hnd_t *h = handle;
      if( h->prev_filter.get_frame( h->prev_hnd, output, frame ) )
4.
             return -1;
5.
     if( h->variable_input && check_resizer( h, output ) )
6.
7.
             return -1;
8.
     h->working = 1;
         if( h->pre_swap_chroma )
9.
10.
             XCHG( uint8_t*, output->img.plane[1], output->img.plane[2] );
11.
         if( h->ctx )
12.
             sws_scale( h->ctx, (const uint8_t* const*)output->img.plane, output->img.stride,
13.
14.
                       0, output->img.height, h->buffer.img.plane, h->buffer.img.stride );
15.
             output->img = h->buffer.img; /* copy img data */
16.
17.
18.
             output->img.csp = h->dst_csp;
19.
          if( h->post_swap_chroma )
20.
        XCHG( uint8_t*, output->img.plane[1], output->img.plane[2] );
21.
22.
         return 0;
23. }
```

可以看出resize_filter中调用了libswscale类库中的sws_scale()对图像完成了拉伸工作。

注:拉伸滤镜需要libswscale类库的支持。

至此cli_output_t,cli_input_t,cli_vid_filter_t这3个在x264中与输入输出有关的结构体的源代码就分析完毕了。有关x264命令行工具的源代码分析工作也就做完了。下一篇文章开始对libx264内部的源代码进行分析。

雷霄骅

leixiaohua1020@126.com

http://blog.csdn.net/leixiaohua1020

版权声明:本文为博主原创文章,未经博主允许不得转载。 https://blog.csdn.net/leixiaohua1020/article/details/45583217

文章标签: x264 H.264 视频编码 源代码 YUV

个人分类: x264

所属专栏: 开源多媒体项目源代码分析

此PDF由spygg生成,请尊重原作者版权!!!

我的邮箱:liushidc@163.com