Chapter 3 Process Description and Control

Req. of an OS wrt. Processes

- Use multiple processes to maximize processor utilization while providing reasonable response time
 - Uniprocessor: interleave execution of procs.
 - Multiprocessor: interleaving and parallel execution of procs.
- Allocate resources to processes
- Support interprocess communication and user creation of processes

Previously Introduced Concepts

- Computer platform consists of a collection of hardware resources
 - Processor, main memory, timers, IOs
- Computer applications are developed to perform some task
 - Bespoke system vs general workstations
- Inefficient for applications to be written directly for a given hardware platform
 - Code reuse among applications
 - Need to manage multiprogramming (do you really want to put this into the application?)
 - Protect data, IO, etc (can you put this into the application?)
- Some still believe otherwise
 - Consider porting assembly code?

Previously Introduced Concepts

- OS provides a convenient, feature rich, secure, and consistent interface for applications to use
- OS provides a uniform, abstract representation of resources that can be requested and accessed by application => a virtual machine

HOW DOES THE OS MANAGE PROCESSES?

Process (possible definitions)

- A program in execution
- An instance of a program running on a computer
- The entity that can be assigned to and executed on a processor
- A unit of activity characterized by
 - execution of a sequence of instructions
 - current state
 - associated set of system instructions

Process (revisited)

- Consists of three components
 - An executable program
 - Associated data needed by the program
 - Execution context of the program
 - All information the operating system needs to manage the process

So what are the process elements in detail?

Process Elements

- Identifier
 - Usually abbreviated as PID
- State
 - E.g., running state
- Priority
 - relative to other processes

Process Elements

- Memory pointers
 - Pointers + shared memory blocks
- Context data
 - Registers, PSW, program counter
- I/O status information
 - Outstanding I/O requests, used I/O devices
- Accounting information
 - Amount of processor time, time limits, threads
 - Try out 'top', 'ulimit'


Process Control Block (PCB)

- The data structure that contains the process elements
- Created and managed by the operating system
- Allows support for multiple processes

Question!

Do you allow the user to manipulate the elements of the process control block? Not directly, partially yes (e.g., set priority through command)

Process Control Block



Varies between OSs => Very small for embedded OS

Figure 3.1 Simplified Process Control Block

Example PICOS18

```
typedef rom const struct rom desc tsk
 unsigned char prioinit;
  unsigned char *stackAddr;
 void (*addr_ROM)(void);
  unsigned char tskstate;
  unsigned char tskid;
 unsigned int stksize;
 rom_desc_tsk;
```

Instantiation

```
/**********************************
    ------task VM ------
*****************************
rom_desc_tsk rom_desc_task_vm = {
 TASK VM PRIO,
                          /* prioinit from 0 to 15
                       /* stack address (16 bits)
 _stack_vm,
                                             */
 TASK VM,
                       /* start function
 READY,
                      /* state at init phase
 TASK_VM_ID,
                        /* id tsk from 0 to 15
                         /* stack size (16 bits)
 sizeof(_stack_vm)
```

Trace of the Process

- Sequence of instruction that execute for a process
- Dispatcher switches the processor from one process to another

Example Execution (Setup)

5000	8000	12000
5001	8001	12001
5002	8002	12002
5003	8003	12003
5004		12004
5005		12005
5006		12006
5007		12007
5008		12008
5009		12009
5010		12010
5011		12011

(a) Trace of Process A

(b) Trace of Process B (c) Trace of Process C

5000 = Starting address of program of Process A

8000 = Starting address of program of Process B

12000 = Starting address of program of Process C

Figure 3.3 Traces of Processes of Figure 3.2

Example Execution (Memory Layout)





Figure 3.2 Snapshot of Example Execution (Figure 3.4) at Instruction Cycle 13

Combined Trace of All Processes




100 = Starting address of dispatcher program

Shaded areas indicate execution of dispatcher process; first and third columns count instruction cycles; second and fourth columns show address of instruction being executed

Two-State Process Model


- Looking at the previous example: A process may be in one of two states
 - Running
 - Not-running



- · How to accommodate model in OS design?
 - We already have PCBs and need ...

OS Structure (so far)

- 1. Store data about the process (process control block)
- 2. Processes must wait in some sort of queue until it's their turn.



(b) Queuing diagram

Process Creation

Table 3.1 Reasons for Process Creation

New batch job

The OS is provided with a batch job control stream, usually on tape or disk. When the OS is prepared to take on new work, it will read the next sequence of job control commands.

A user at a terminal logs on to the system.

The OS can create a process to perform a function on behalf of a user program, without the user having to wait (e.g., a process to control printing).

Spawned by existing process

For purposes of modularity or to exploit parallelism, a user program can dictate the creation of a number of processes.

Process spawning: a parent process explicitly creates a child process.

→ check this with 'ps'

Process Termination

Table 3.2 Reasons for Process Termination

Normal completion	The process executes an OS service call to indicate that it has completed running.
Time limit exceeded	The process has run longer than the specified total time limit. There are a number of possibilities for the type of time that is measured. These include total
ulimit	elapsed time ("wall clock time"), amount of time spent executing, and, in the case of an interactive process, the amount of time since the user last provided any input.
Memory unavailable	The process requires more memory than the system can provide.
Bounds violation	The process tries to access a memory location that it is not allowed to access.
Protection error	The process attempts to use a resource such as a file that it is not allowed to use, or it tries to use it in an improper fashion, such as writing to a read-only file.
Arithmetic error	The process tries a prohibited computation, such as division by zero, or tries to store numbers larger than the hardware can accommodate.

Explain: core dump

Process Termination

Time overrun The process has waited longer than a specified maximum for a certain event to

occur.

I/O failure An error occurs during input or output, such as inability to find a file, failure to

read or write after a specified maximum number of tries (when, for example, a defective area is encountered on a tape), or invalid operation (such as reading

from the line printer).

Invalid instruction The process attempts to execute a nonexistent instruction (often a result of

branching into a data area and attempting to execute the data).

Privileged instruction The process attempts to use an instruction reserved for the operating system.

Data misuse A piece of data is of the wrong type or is not initialized.

Operator or OS intervention For some reason, the operator or the operating system has terminated the process

(for example, if a deadlock exists).

Parent termination When a parent terminates, the operating system may automatically terminate all

of the offspring of that parent.

Parent request A parent process typically has the authority to terminate any of its offspring.

Explain: 'kill –SIGTERM' and others (compare SIGKILL and SIGTERM)

Simple Queuing Mechanism is Inefficient

- ... because some processes are
 - Not-running but ready to execute
 - Not-running and blocked
- With a single queue: Dispatcher must scan list to find process not-running, ready, and in queue the longest
- With multiple queues: first pick the right queue and then go round robin.

But what multiple queues should we have and how does it affect the states?

A Five-State Model

Refine the not-running state:

- Running: the process currently executed
- Ready: a process that can be executed
- Blocked/Waiting: a process that cannot execute, because it waits for something
- New: a new process to enter the system
- Exit: a halted or aborted process

Five-State Process Model




Figure 3.6 Five-State Process Model

Explain: preemption

Process States





Figure 3.7 Process States for Trace of Figure 3.4


Using Two Queues



What's the problem with it?

Problem: unblocking a task requires the OS to search through that list

Multiple Blocked Queues




(b) Multiple blocked queues

Suspended Processes


- Problem: Processor is faster than I/O so all processes could be waiting for I/O
- Solution: admit more processes
- Swap blocked processes to disk to free up more memory
- Blocked state becomes suspend state when swapped to disk
- Two new states
 - Blocked/Suspend
 - Ready/Suspend

One Suspend State



(a) With One Suspend State

Two Suspend States



Reason for Process Suspension

Table 3.3 Reasons for Process Suspension

Swapping	The OS needs to release sufficient main memory to bring in a process that is ready to execute.
Other OS reason	The OS may suspend a background or utility process or a process that is suspected of causing a problem.
Interactive user request	A user may wish to suspend execution of a program for purposes of debugging or in connection with the use of a
Notes!	resource.
Timing	A process may be executed periodically (e.g., an accounting or system monitoring process) and may be suspended while waiting for the next time interval.
Parent process request	A parent process may wish to suspend execution of a descendent to examine or modify the suspended process, or to coordinate the activity of various descendants.

HOW DOES THE OS MANAGE RESOURCES?

Processes and Resources

Dashed line = Waiting




Figure 3.10 Processes and Resources (resource allocation at one snapshot in time)

Operating System Control Structures

- Information about the current status of each process and resource
- Tables are constructed for each entity that the operating system manages

Memory Tables

- ... used to keep track of main & secondary (virtual) memory
- Allocation of main memory to processes
- Allocation of secondary memory to processes
- Protection attributes for access to shared memory regions
- Information needed to manage virtual memory

I/O Tables

- ... used by the OS to manage I/O devices (see /proc directory)
- I/O device is available or assigned
- Status of I/O operation
- Location in main memory being used as the source or destination of the I/O transfer
- Example: /proc directory

File Tables

- Existence of files
- Location on secondary memory
- Current Status
- Attributes (e.g., rwxr--r--)
- Sometimes this information is maintained by a file management system
- Example: fuser –u /

Process Table

- Where process is located in memory
- Attributes in the process image
 - Program
 - Data
 - Stack
 - Process control block (aka task control block, process descriptor, task descriptor)
 - Question: How/when does the OS create these tables?

Process Image

Table 3.4 Typical Elements of a Process Image

User Data

The modifiable part of the user space. May include program data, a user stack area, and programs that may be modified.

User Program

The program to be executed.

System Stack

Each process has one or more last-in-first-out (LIFO) system stacks associated with it. A stack is used to store parameters and calling addresses for procedure and system calls.

Process Control Block

Data needed by the operating system to control the process (see Table 3.5).




Figure 3.11 General Structure of Operating System Control Tables

Process identification

- Identifiers
 - Numeric identifiers that may be stored with the process control block include
 - Identifier of this process (= unique key)
 - Identifier of the process that created this process (parent process)
 - User identifier
 - Defined by pid_t(demo: chase down pid_t on ece.uwaterloo.ca)

- Processor State Information
 - User-Visible Registers
 - A user-visible register is one that may be referenced by means of the machine language that the processor executes while in user mode. Typically, there are from 8 to 32 of these registers, although some RISC implementations have over 100.
 - Might be as low as only 1 working register

Processor State Information

Control and Status Registers

These are a variety of processor registers that are employed to control the operation of the processor. These include

- Program counter: Contains the address of the next instruction to be fetched
- Condition codes: Result of the most recent arithmetic or logical operation (e.g., sign, zero, carry, equal, overflow)
- Status information: Includes interrupt enabled/disabled flags, execution mode

Processor State Information

- Stack Pointers
 - Each process has one or more last-in-first-out (LIFO) system stacks associated with it. A stack is used to store parameters and calling addresses for procedure and system calls. The stack pointer points to the top of the stack.

- Process Control Information
 (... meta info for handling processes, differs for each OS → design criteria)
 - Scheduling and State Information
 - Needed to perform scheduling function:
 - Process state: e.g., running, ready, waiting, ...
 - Priority: e.g., 0-255
 - Scheduling related information: e.g., cpu time, slack, deadlines
 - Importance

- Process Control Information
 - Data Structuring
 - Linked list with for child processes
 - Linked list for same priority processes
 - Linked list for 'cohort' processes

Process Control Information

- Interprocess Communication
 - Various flags, signals, and messages may be associated with communication between two independent processes. Some or all of this information may be maintained in the process control block.

Process Privileges

 Processes are granted privileges in terms of the memory that may be accessed and the types of instructions that may be executed. In addition, privileges may apply to the use of system utilities and services.

Process Control Information

- Memory Management
 - This section may include pointers to segment and/or page tables that describe the virtual memory assigned to this process.
- Resource Ownership and Utilization
 - Resources controlled by the process may be indicated, such as opened files. A history of utilization of the processor or other resources may also be included; this information may be needed by the scheduler.

Processor State Information

- Contents of processor registers
 - User-visible registers
 - Control and status registers
 - Stack pointers
- Program status word (PSW)
 - contains status information
 - Example: the EFLAGS register on Pentium machines

Modes of Execution

- User mode
 - Less-privileged mode
 - User programs typically execute in this mode
- System mode, control mode, or kernel mode
 - More-privileged mode
 - Kernel of the operating system
- Can you think of why you want more modes?
- ¬ granular access (crappy drivers can't kill the machine), virtual machines, sandboxing downloaded programs

Steps in Process Creation

- 1. Assign a unique process identifier
- 2. Allocate space for the process
- 3. Initialize process control block
- 4. Set up appropriate linkages
 - Ex: add new process to linked list used for scheduling queue
- 5. Create of expand other data structures
 - Ex: maintain an accounting file

When to Switch a Process

 Looks easy, but is quite tricky if you want to provide guarantees (e.g., bandwidth, performance, etc)

Possible choices when to switch:

- Clock interrupt
 - process has executed for the maximum allowable time slice
- I/O interrupt (= I/O completed)
- Memory fault
 - memory address is in virtual memory so it must be brought into main memory

When to Switch a Process

Trap

- error or exception occurred
- may cause process to be moved to Exit state
- Used for debugging (ICD)
- Supervisor call
 - Switch to kernel process

Steps for a Process Switch

- Save context of processor including program counter and other registers
- Update the process control block of the process that is currently in the Running state
- Move process control block to appropriate queue – ready; blocked; ready/suspend
- Select another process for execution

Change of Process State

- Update the process control block of the process selected
- Update memory-management data structures
- Restore context of the selected process

References


Recommended Reading:

Chapter three of Stallings book

Optional Reading:

O'Gorman,

 "The Linux Process Manager –
 The internals of scheduling, interrupts and signals", Wiley 2003 (Ch 1-3)



PROCESS SWITCH REVISITED

In part based on slides by S. Fischmeister, A. Tanenbaum & Mark Handley

SE350 - Thomas Reidemeister

Review: When to Switch Processes


- Clock interrupt
- I/O interrupt (= I/O completed)
- Memory fault
- Trap
- Supervisor call

Review: Process Switching Steps


- Save context of processor including program counter and other registers
- 2. Update the process control block of the process that is currently in the Running state
- Move process control block to appropriate queue – ready; blocked; ready/suspend
- 4. Select another process for execution
- Update the process control block of the process selected
- 6. Update memory-management data structures
- 7. Restore context of the selected process

An Context Switch Occurs

Storing a snapshot.



Resuming Another Process



Example: PICOS18

- Kernel for Microchip PIC18 controllers
- Many functions of a microkernel
 - Events
 - Interrupts
 - Counters/alarms
 - Multitasking

Schedule()

```
* Force a scheduler action
 @return Status E OK if a service is called inside an ISR
          or never returns
StatusType Schedule(void)
                                   OS does not use HW protection,
                                   instead "kernel mode" is emulated.
 INTCONbits.GIEL = 0;
 kernelState |= SERVICES;
 if (kernelState & ISR)
 return (E_OK);
                                         Step 1: Save all context info
 kernelState &= ~SERVICES;
if (kernelState & USER)
  SAVE_TASK_CTX(stack_low, stack_high);
 SCHEDULE;
 return (E_OK);
                                        Step 2-7: ...
```

```
#define SAVE_TASK_CTX(stack_low, stack_high)
                                             Hint: Disable means
 /* Disable global interrupt. */
                                             hold interrupts.
asm
         INTCON, 6, 0
    bcf
                                             Pending interrupts serviced,
    movff STATUS, PREINC1
                                             when enabled again
    movff WREG, PREINC1
endasm
 /* Store the necessary registers to the stack. */
asm
    movff BSR, PREINC1
                                       WREG – working register
    movff FSR2L, PREINC1
                                       FSR – address registers
    movff FSR2H, PREINC1
                                       TBDLPTRx, TABx – other address
    movff FSR0L, PREINC1
                                       registers
    movff FSR0H, PREINC1
    movff TBLPTRU, PREINC1
                                       Hint: PIC supports several indirect
    movff TBLPTRH, PREINC1
                                       addressing modes through address
    movff TBLPTRL, PREINC1
                                       registers.
    movff TABLAT, PREINC1
    movff PRODH, PREINC1
    movff PRODL, PREINGE350 - Thomas
                                       Coldfire is "easier"
                                                      65
  endasm
                       Reidemeister
```

```
/* Store the .tempdata and MATH_DATA areas. */
 asm
   movlw TEMP_SIZE+1
   clrf FSR0L, 0
   clrf FSR0H, 0
 endasm
   while (WREG--)
    asm
     movff POSTINC0, PREINC1
    endasm
```

Hint:

tmpdata = temporary variables (used by ISRs).

MATH DATA = return values used from mathematical library **Functions (compiler extensions)**

All data from embedded libs that assume a single program need to be stored in the context as well.

```
/* Store the HW stack area. */
  _asm
    movff STKPTR, FSR0L
  endasm
    while (STKPTR > 0)
     asm
      movff TOSL, PREINC1
      movff TOSH, PREINC1
      movff TOSU, PREINC1
      pop
     endasm
```

```
/* Store the number of addresses on the HW stack */
 asm
   movff FSR0L, PREINC1
   movf PREINC1, 1, 0
 endasm
 /* Store the SW stack addr. */
 asm
   movff stack_low, FSR0L
   movff stack_high, FSR0H
   movff FSR1L, POSTINC0
   movff FSR1H, POSTINC0
 endasm
```

sched - Part 1

```
sched
  GLOBAL _sched
  #IFDEF POSTTASKHOOK
                                                    Steps 3 ... 6
    call PostTaskHook
  #ENDIF
 ... // skipped code here to select the next task
restore ctx
  GLOBAL _restore_ctx
                                              Hint: Interrupts still disabled.
  movlb 0
       kernelState, 0
                            ; Change the kernel to USER mode
  bsf
  IocateTaskDescEntry
  locateStackAddrField
  loadNextAddrTo FSR0L, FSR0H ; Extract task's stack addr
  loadNextAddrTo startAddressL, startAddressH
                      : Extract task's code addr
: Go chech whether the stack overflow occurred
  goto _checkPanic
                       SE350 - Thomas
                                                      69
```

Reidemeister

sched - Part 2

```
; If the stack remains intact, restore the task's context
_restore_now
GLOBAL _restore_now
movlb 0
movff POSTDEC1, temp
movff POSTDEC1, temp ; Extract # of H/W stack entries
clrf STKPTR ; backed up previously
... // skipped a section here
```


sched – Part 3

```
restoreNextTmpdataByte
  movff POSTDEC1, POSTDEC0
                                  ; Restore .tmpdata + MATH_DATA
 movf FSR0L, w
                           : section
 btfss STATUS, N
       restoreNextTmpdataByte
 bra
 movff POSTDEC1, PRODL
                                : Restore the rest of SFRs saved
 movff POSTDEC1, PRODH
                                 ; in previously task swapping out
 movff POSTDEC1, TABLAT
                                    Q1: Anybody notices anything
 movff POSTDEC1, TBLPTRL
                                    about the this process (up to now)?
 movff POSTDEC1, TBLPTRH
 movff POSTDEC1, TBLPTRU
 movff POSTDEC1, FSR0H
 movff POSTDEC1, FSR0L
                                    Q2: How about starting process for
 movff POSTDEC1, FSR2H
                                    the first time?
 movff POSTDEC1, FSR2L
 movff POSTDEC1, BSR
 movff POSTDEC1, WREG
 movff POSTDEC1, STATUS
                                               Resumes proc. execution.
       INTCON, 6
                          ; Enable OS/low prior. interrupt
 bsf
                      ; Exila 5 35 Pere Thous mass need at
  retfie
                                                         71
```


Reidemeister

EXECUTION OF THE OPERATING SYSTEM

Exception Handling




User Exception Handling



Reidemeister

74

Processing a System Call



SE350 - Thomas Reidemeister


Example System Call

Call from C program:

count = read(fd, &buffer, length);


- read up to length bytes of data from from file
- descriptor fd into buffer, and returns the number of
- bytes actually read, or -1 if an error occurred.
- C library call for read() calls the read system call.

Steps in Making a System Call



SE350 - Thomas Reidemeister

Steps in Making a System Call



There are 11 steps in making the system call SE350 - Thomas reach (if the parties, nbytes) 78

Non-process Kernel

- Execute kernel outside of any process
- Operating system code is executed as a separate entity that operates in privileged mode
- Own memory, own call stack
- The concept of processes only applies to user programs
- All OS calls are blocking

Execution Within User Processes

- OS is primarily a collection of routines
- Operating system software within context of a user process
- Process executes in privileged mode when executing operating system code
- Perform a "context switch" (mode switch)
 when entering a system call, but continue
 with the same process.






Figure 3.16 Process Image: Operating System Executes Within User Space

Process-Based Operating System


- Implement operating system as a collection of system processes
- Useful in multi-processor or multi-computer environment
- Good choice for real-time systems
 - Use kernel threads for I/O and other events



(a) Separate kernel



(b) OS functions execute within user processes



(c) OS functions execute as separate processes

Figure 3.15 Relationship Between Operating System and User Processes