




# Operating System

---

**Prof. Sumersing Patil**  
Assistant Professor  
CSE - AI&DS





CHAPTER-3  
Inter-Process  
Communication



# SYLLABUS

Sr.	Topic	Weightage	Teaching Hrs.
3	<b>INTER-PROCESS COMMUNICATION:</b>  Critical Section, Race Conditions, Mutual Exclusion, Hardware Solution, Strict Alternation, Peterson's Solution, The Producer\Consumer Problem, Semaphores, Event Counters, Monitors, Message Passing, Classical IPC Problems: Reader's & Writer Problem, Dinning Philosopher Problem etc.	15%	6



## Introduction To IPC

- **IPC** refers to a mechanism which allows communication between two or more processes to perform their actions simultaneously.
- Processes that are executing concurrently in a program are of two types-
- (i) **Independent Processes:-**These are those processes which does not dependent on execution of other process in same program. Independent processes don't share data with another process.



## Why we need IPC?


**There are several reasons which allows processes to co-operate:-**

- (i) Information sharing
- (i) Computation speedup
- (i) Modularity
- (i) Convenience



# IPC

- There are two models for IPC
  - a. Message Passing
  - b. Shared Memory





## Race condition

**Race condition** is a situation arise due to concurrent execution of more than one processes which are accessing and manipulating the same shared data and the result of execution depends upon the specific order where the access take place.

Race condition leads to inconsistency which is totally undesirable.

### Reasons for Race Condition

1. Exact instruction execution order cannot be predicted




## Example of race condition

Thread 1	Thread 2		Integer value
			0
read value		←	0
increase value			0
write back		→	1
	read value	←	1
	increase value		1
	write back	→	2

Thread 1	Thread 2		Integer value
			0
read value		←	0
	read value	←	0
increase value			0
	increase value		0
write back		→	1
	write back	→	1



# Critical Section





## Critical

- Critical section is **piece of code** which contains some shared code or variable which is accessible by each process concurrently in order to complete execution.
- There must be only one process is allowed at a time in critical section otherwise more than one access may lead to inconsistency.
- Concurrent accesses to shared resources can lead to unexpected or erroneous behaviour , so part of the program



# Critical section




Figure :1 [image source google ]



## Need of critical section

- Process A have to read variable 'x' and process B has to write to the same variable 'x' at the same time
- if A needs to read the updated value of 'x', executing Process A and Process B at the same time may not give required results. To prevent this, variable 'x' is protected by a critical section.
- First, B gets the access to the section. Once B finishes writing the value, A gets the access to the critical section.

Process A:

```
// Process A  
.  
. .  
b = x + 5; // instruction executes at time = Tx  
.
```

Process B:

```
// Process B  
.  
. .  
x = 3 + z; // instruction executes at time = Tx  
.
```



## Mutual

### Exclusion

A way of making sure that if one process is using a shared variable or file; the other process will be excluded (stopped) from doing the same





## Mutual Exclusion

- A mutual exclusion (mutex) is a program object that prevents simultaneous access to a shared resource.
- This concept is used in concurrent programming with a critical section, a piece of code in which processes or threads access a shared resource.



## Critical-Section Problem

- Consider system of  $n$  processes  $\{P_0, P_1, \dots, P_{n-1}\}$
- Each process has **critical section** segment of code
  - Process may be changing common variables, updating table, writing file, etc
  - When one process in critical section, no other is allowed to be in its critical section
- ***Critical section problem*** is to design protocol to solve this



## Critical-Section Problem

Each process

- Each process must request permission to enter its critical section. The section of code implementing this request is the **entry section**,
- may follow critical section with **exit section**,
- then **remainder section**

do {

*entry section*

critical section

*exit section*

remainder section

} while (true);



## Solving Critical-Section Problem

Any good solution to the problem following four must satisfy conditions:

### 1. Mutual Exclusion:

- No two processes may be simultaneously inside the same critical section.

### 2. Bounded Waiting:

- No process should have to wait forever to enter a critical section.

### 3. Progress:

- No process running outside its critical region may block other processes.

### 4. Arbitrary Speed:

- No assumption can be made about the



## Mutual Exclusion with busy waiting

- Mechanisms for achieving mutual exclusion with busy waiting
  - Disabling interrupts
  - Shared lock variable
  - Strict alteration
  - TSL (test and set lock) instruction
  - Exchange instruction
  - Peterson's solution




## Disabling Interrupts

- Each process **disables all interrupts** just after entering in its critical section and **re-enable all interrupts** just before leaving critical section.
- With interrupts turned off the **CPU** could not be **switched** to other process.
- Hence, no other process will enter its critical and mutual exclusion achieved



## Disabling Interrupts

```
while (true)
{
    < disable interrupts >;
    < critical section >;
    < enable interrupts >;
    < remainder section>;
}
```





## Disabling Interrupts

- **Problems:**

- Unattractive or unwise to give user processes the power to turn off interrupts.
- What if one of them did it (disable interrupt) and never turned them on (enable interrupt) again? That could be **the end of the system**.
- If the system is a multiprocessor, with two or more CPUs, disabling interrupts affects only the CPU that executed the disable instruction. The other ones will continue running and can access the shared memory.



## Shared lock variable


- A shared variable lock having value 0 or 1.
- Before entering into critical region a process checks a shared variable lock's value.
  - If the value of lock is 0 then set it to 1 before entering the critical section and enters into critical section and set it to 0 immediately after leaving the critical section.
  - If the value of lock is 1 then wait until it becomes 0 by some other process which is in critical section.



## Shared lock variable

□ Algorithm:  
while (true)

```
{           < set shared variable  
to 1>;  
< critical section >;  
< set shared variable to 0>;  
< remainder section>;  
}
```





## Shared lock variable

### □ Problem:

- If process P0 sees the value of lock variable 0 and before it can set it to 1 context switch occurs.
- Now process P1 runs and finds value of lock variable 0, so it sets value to 1, enters critical region.
- At some point of time P0 resumes, sets the value of lock variable to 1, enters critical region.
- Now two processes are in their critical regions accessing the same shared memory, which violates the mutual exclusion condition.




## Strict Alteration

- Integer variable '**turn**' keeps track of whose turn is to enter the critical section.
- Initially  $\text{turn}=0$ . Process 0 inspects **turn**, finds it to be 0, and enters in its critical section.
- Process 1 also finds it to be 0 and therefore sits in a loop continually testing '**turn**' to see when it becomes 1.
- *Continuously testing a variable waiting for some event to appear is called the **busy waiting**.*
- When process 0 exits from critical region it sets **turn** to 1 and now process 1 can find it to be 1 and enters in to critical region.




## Strict Alteration





## Strict Alteration (Disadvantages)

- Consider the following situation for two processes P0 and P1.
- P0 leaves its critical region, set turn to 1, enters non critical region.
- P1 enters and finishes its critical region, set turn to 0.
- Now both P0 and P1 in non-critical region.
- P0 finishes non critical region, enters critical region again, and leaves this region, set turn to 1.
- P0 and P1 are now in non-critical region.






## Strict Alteration (Disadvantages)

- P0 finishes non critical region but cannot enter its critical region because turn = 1 and it is turn of P1 to enter the critical section.
- Hence, P0 will be blocked by a process P1 which is not in critical region. This violates one of the conditions of mutual exclusion.
- It wastes CPU time, so we should avoid busy waiting as much as we can.

**Another Disadvantage:** Taking turns is not a good idea when one of the other processes makes a mistake.





# TSL (Test and Set Lock) Instruction

enter\_region      (Before entering its critical region, process calls enter\_region)

n: TSL REGISTER,LOCK |copy lock variable to register

set lock to 1      |was lock variable 0?

CMP REGISTER,#0      |if it was nonzero, lock was set, so

JNE      |loop  
|return to caller: critical region

enter\_region entered

(When process wants to leave critical region, it calls leave\_region)

n: MOVE LOCK,#0      |store 0 in lock

variable  
|return to  
caller




Process  
A

Process  
B

T1

T3

T4





# Exchange Instruction

- Algori

thm

MOVE regio

REGISTER#1

REGISTER,LOCK

|lock variable

CMP

REGISTER#0

MOVE enter\_region

|if it was nonzero, lock was set,

so loop

RET

leave\_region:

(When process wants to leave critical region, it calls  
leave\_region)

MOVE

LOCK,#0

T

|put 1 in the  
register

|swap content of register &  
lock variable

|was lock variable  
0?

|if it was nonzero, lock was set,

|return to caller: critical region  
entered

|store 0 in lock  
variable

|return to  
caller



## Peterson's Solution

- Peterson's algorithm (or Peterson's solution) is a concurrent programming **algorithm** for mutual exclusion that allows two or more processes to share a single-use resource **without conflict**, using only shared memory for communication.
- In ~~the algorithm~~ two processes share two variables:
  - turn
  -
- The <sup>flag</sup> variable indicates **whose turn it is** to enter the critical section  $\text{flag}[i] = \text{true}$   $P_i$
- The array is used to indicate if a process is **ready** to enter



## Peterson's Solution

# Process-0 Process-1

```
flag[0] = true;  
turn = 1;  
while (flag[1] && turn == 1)  
{  
    // busy wait  
}  
// critical section  
...  
// end of critical section  
flag[0] = false;
```

```
flag[1] = true;  
turn = 0;  
while (flag[0] && turn == 0)  
{  
    // busy wait  
}  
// critical section  
...  
// end of critical section  
flag[1] = false;
```



## Peterson's Solution

### □ Three Essential Criteria

#### [1] Mutual exclusion

- P0 and P1 can **never** be in the critical section at the **same time**:
- If P0 is in its critical section, then `flag[0]` is true. In addition, either `flag[1]` is false (meaning P1 has left its critical section), or `turn` is 0.



## Peterson's Solution

### [2] Progress

- if no process is executing in its critical section and some processes wish to enter their critical sections,
- then only those processes that are not executing in their remainder sections can participate in making the decision as to which process will enter its critical section next.

### [3] Bounded waiting

- Bounded waiting means that the number of times a process is bypassed by another process after it has indicated its desire to enter the critical section is bounded by a function of the number of processes in the system.



## Peterson's Solution


### **Disadvantages:-**

- (i) It involves Busy waiting.
- (ii) It is limited to 2 processes.



# Producer Consumer problem

- It is multi-process synchronization problem.
- It is also known as bounded buffer problem.
- This problem describes two processes **producer** and **consumer**, who share common, fixed size buffer.
- Producer process
  - Produce some information and put it into buffer
- Consumer process
  - Consume this information (remove it from the buffer)





## What Producer Consumer problem is?

- The problem is to make sure that the producer won't try to add data (information) into the buffer if it is full and consumer won't try to remove data (information) from the an empty buffer.
- Solution for producer:
  - Producer either go to sleep or discard data if the buffer is full.
  - Once the consumer removes an item from the buffer, it notifies (wakeup) the producer to put the data into buffer.
- Solution for consumer:
  - Consumer can go to sleep if the buffer is empty.
  - Once the producer puts data into buffer, it notifies (wakeup) the consumer to remove (use) data from buffer.



## What Producer Consumer problem is?

- Buffer is empty ✓  
Producer want to produce ✓


- Consumer want to consume ✗

- Buffer is full ✗  
Producer want to produce ✗

- Consumer want to consume ✗

- Buffer is partial filled ✗  
Producer want to produce ✓


- Consumer want to consume ✓






# Producer Consumer problem using Sleep & Wakeup

```
#define N  
4 int  
count=0;  
void producer  
(void)  
while (true)  
{  
    item=produce_item  
(); if (count==N)  
sleep();  
insert_item(item);  
count=count+1;  
} if(count==1)  
wakeup(consumer);
```



# Producer Consumer problem using Sleep & Wakeup

```
void consumer
(void) int item;
{
    while
        (true)
    {
        if (count==0)
            sleep();
        item=remove_item
        (); count=count-1;
        if(count==N-1)
            wakeup(produce
        } r);
        consume_item(item);
```





# Problem

Problem with this solution is that it contains a race condition that can **lead to a deadlock**.

(How???)

- The consumer has variable **count**, and it's zero just about to move inside the if block before calling sleep, the consumer is the producer suspended. and
- The producer creates an item, puts into the buffer, **count**. and increases
- Because the buffer was empty the last producer addition, to the

```
void consumer
(void)
{
    while(item; Context Switching
        (true)
        if (count==0)
            sleep();
        item=remove_item
        (); count=count-1;
        if(count==N-1)
            wakeup(producer);
        consume_item(item);
```



## Problem in Sleep & Wakeup

- Unfortunately the consumer wasn't yet sleeping, and the wakeup call is lost.
- When the consumer resumes, it goes to sleep and will never be awakened again. This is because the consumer is only awakened by the producer when **count** is equal to 1.
- The producer will loop until the buffer is full, after which it will also go to sleep.
- ***Finally, both the processes will sleep forever.*** This solution therefore is

```
void consumer(void)
{
    int item;
    while
    (true)
    {
        if (count==0)
            sleep();
        item=remove_item
        (); count=count-1;
        if(count==N-1)
            wakeup(produce
        }
    r);
    consume_item(item);
```



## Mutex Locks

- Previous solutions are complicated and generally inaccessible to application programmers
- OS designers build software tools to solve critical section problem
- Simplest is **mutex lock**
- Protect a critical section by:
  - first **acquire()** a lock
  - then **release()** the lock
  - Boolean variable indicating if lock is available or not
- Calls to **acquire()** and **release()** must be **atomic**
  - Usually implemented via hardware atomic instructions
- But this solution requires **busy waiting**



## Mutex Locks

```
acquire() {  
    while (!available)  
        ; /* busy wait */  
    available = false;  
}  
release() {  
    available = true;  
}  
while (true) {  
    acquire lock  
    critical section  
    release lock  
    remainder section
```

## Mutex Locks

```
mutex buffer_mutex;
semaphore fillCount = 0;
semaphore emptyCount = BUFFER_SIZE;

procedure producer() {
    while (true) {
        item = produceItem();
        down(emptyCount);
        down(buffer_mutex);
        putItemIntoBuffer(item);
        up(buffer_mutex);
        up(fillCount);
    }
}

procedure consumer() {
    while (true) {
        down(fillCount);
        down(buffer_mutex);
        item = removeItemFromBuffer();
        up(buffer_mutex);
        up(emptyCount);
        consumeItem(item);
    }
}
```



## Semaphore

- A semaphore is a variable that provides an abstraction for controlling the access of a shared resource by multiple processes in a parallel programming environment.
- Semaphores solve the problem of **lost wakeup calls**.
- There are 2 types of semaphores:
  1. **Binary semaphores** :-
    - Binary semaphores can take only 2 values (0/1).
    - Binary semaphores have 2 methods associated with it (up, down / lock, unlock/ signal, wait).
    - They are used to acquire locks.
  2. **Counting semaphores** :-
    - Counting semaphore can have possible values more than two.



## Semaphor

- We want functions `insert_item` and `remove_item` such that the following hold:
  - **Mutually exclusive access to buffer:** At any time only one process should be executing (either `insert_item` or `remove_item`).
  - **No buffer overflow:** A process executes `insert_item` only when the buffer is not full (i.e., the process is blocked if the buffer is full).
  - **No buffer underflow:** A process executes `remove_item` only when the buffer is not empty (i.e., the process is blocked if the buffer is empty).



## Semaphor

- We want functions `insert_item` and `remove_item` such that the following hold:
  - No busy waiting.
  - No producer starvation: A process does not wait forever at `insert_item()` provided the buffer repeatedly becomes full.
  - No consumer starvation: A process does not wait forever at `remove_item()` provided the



## Semaphor

Two operations on semaphores are defined.

### 1. Down Operation

- The down operation on a semaphore checks to see if the value is greater than 0.
- If so, it decrements the value and just continues.
- If the value is 0, the process is put to sleep without completing the down for the moment.
- *Checking the value, changing it, and possibly going to sleep, are all done as a single, indivisible atomic action.*
- It is guaranteed that once a semaphore operation has started, no other process can access the semaphore until the operation has completed or blocked.



## Semaphor

Two operations on semaphores are defined.


### 2. Up Operation

- The up operation increments the value of the semaphore addressed.
- If one or more processes were sleeping on that semaphore, unable to complete an earlier down operation, one of them is chosen by the system (e.g., at random) and is allowed to complete its down.
- The operation of incrementing the semaphore and waking up one process is also indivisible.
- *No process ever blocks doing an up, just as no process ever blocks doing a wakeup in the earlier model.*



# Producer Consumer problem using


```
#define N 4
typedef int
semaphore;
semaphore mutex=1;
semaphore
empty=N;
semaphore full=0;
void producer (void)
(true)
{
item=produce_item
(); down(&empty);
down(&mutex);
insert_item(item);
up(&mutex);
up(&full);
```





# Producer Consumer problem using Semaphore

```
void consumer
{void) int item;
    while
    (true)
    {
        down(&full);
        down(&mutex);
        item=remove_item(ite
m); up(&mutex);
        up(&empty);
        consume_item(item);
    }
}
```





## Monitor

- A higher-level synchronization primitive.
- A monitor is a collection of procedures, variables, and data structures that are all grouped together in a special kind of module or package.
- Processes may call the procedures in a monitor whenever they want to, ***but they cannot directly access the monitor's internal data structures from procedures declared outside the monitor.***



## Monitor

- Monitors have an important property for achieving mutual exclusion: only one process can be active in a monitor at any instant.
- When a process calls a monitor procedure, the first few instructions of the procedure will check to see if any other process is currently active within the monitor.
- If so, the calling process will be suspended until the other process has left the monitor. If no other process is using the monitor, the calling process may enter.



## Producer consumer problem using monitor

- The solution proposes *condition variables*, along operations on them, ***wait and signal***.
- When a monitor procedure discovers that it cannot continue (e.g., the producer finds the buffer full), it does a wait on some condition variable, ***full***.
- This action causes the calling process to block. It also allows another process that had been previously prohibited from entering the monitor to enter now.



## Producer consumer problem using monitor

- This other process the consumer, can wake up its sleeping partner by doing a signal on the condition variable that its partner is waiting on.
- To avoid having two active processes in the monitor at the same time a signal statement may appear only as the final statement in a monitor procedure.
- If a signal is done on a condition variable on which several processes are waiting, only one of them, determined by the system scheduler, is revived.



## Producer consumer problem using

```
monitor ProducerConsumer {  
    int itemCount;  
    condition full;  
    condition empty;  
  
    procedure add(item) {  
        while (itemCount == BUFFER_SIZE)  
            wait(full);  
        }  
  
        putItemIntoBuffer(item);  
        itemCount = itemCount + 1;  
  
        if (itemCount == 1) {  
            notify(empty);  
        }  
    }
```

```
procedure remove() {  
    while (itemCount == 0) {  
        wait(empty);  
    }  
  
    item = removeItemFromBuffer();  
    itemCount = itemCount - 1;  
  
    if (itemCount == BUFFER_SIZE - 1)  
        notify(full);  
}
```



## Producer consumer problem using

```
procedure producer() {  
    while (true) {  
        item = produceItem();  
        ProducerConsumer.add(item);  
    }  
}  
  
procedure consumer() {  
    while (true) {  
        item = ProducerConsumer.remove();  
        consumeItem(item);  
    }  
}
```



## Event

- An event counter is a special data type that contains an integer value that can only be incremented. Three operations are defined for event counters:
- `read(E)`: return the current value of event counter E
- `advance(E)`: increment E
- `await(E,v)`: wait until E has a value greater than or equal to v



## Event

- Here is an example of the producer-consumer problem implemented with event counters.
- Both the consumer and producer maintain a sequence number locally.
- Think of the sequence number as the serial number of each item that the producer produces.
- From the consumer's point, think of the sequence number as the serial number of the next item that the consumer will consume.



## Event

- *in* is the number of the **latest item that was added** to the buffer. The event counter *out* is the serial number of the **latest item that has been removed** from the buffer.
- The **producer** needs to ensure that there's a **free slot** in the buffer and will wait (sleep) until the **difference between the sequence number and out** (the last item consumed) is **less** than the buffer size.
- The **consumer** needs to wait (sleep) until there is at least one item in the buffer; that is, *in* is **greater than or equal** to the



## Event

```
#define N 4      /* four slots in the buffer */
event_counter in=0;      /* number of items inserted into buffer */
event_counter out=0;     /* number of items removed from buffer */

producer() {
    int sequence=0;
    for (;;) {
        produce_item(&item);          /* produce something */
        sequence++;                  /* item # of item produced */
        await(out, sequence-N);     /* wait until there's room */
        enter_item(&item);          /* put item in buffer */
        advance(&in);              /* let consumer know there's one more item */
    }
}
consumer() {
    int sequence=0;
    for (;;) {
        sequence++;                  /* item # we want to consume */
        await(in, sequence);        /* wait until that item is present */
        remove_item(&item);         /* get the item from the buffer */
        advance(&out);             /* let producer know item's gone */
        consume_item(&item);        /* consume it */
    }
}
```



## Readers Writer Problem

- Readers problem is another example  
**synchronization** problem of a classic writer
- **Problem Statement**
  - There is a **shared resource** which should be accessed by **multiple processes**.
  - There are two types of processes in this context.  
They are **reader** and **writer**.



## Readers Writer Problem

- Any number of **readers** can read from the shared resource simultaneously, but **only one writer can write** to the shared resource.
- When a **writer** is writing data to the resource, **no other process can access** the resource.
- A **writer** cannot write to the resource **if there are non zero number of readers** accessing the resource at that time.



## Solution

- From the above problem statement, it is evident that readers have higher priority than writer.
- Here, we use one mutex (`m`) and a semaphore (`w`). An integer variable `read_count` is used to maintain the number of readers currently accessing the resource.
- The variable `read_count` is initialized to 0. A value of 1 is given initially to `m` and `w`.



## Solution

- Instead of having the process to acquire lock on the shared resource, we use the **mutex m to make the process to acquire and release lock whenever it is updating the read\_count variable.**



## writer process

```
while(TRUE) {
```

```
    wait(w); // waits on the w semaphore until it gets a  
chance to write to the resource
```

```
    /*perform the
```

```
write operation */
```

```
    signal(w); //it increments w so that the next writer  
access the  
resource.
```

```
}
```



## Reader

```

while(TRUE) {
    wait(m);      //acquire
    lock read_count++;
    if(read_count == 1)
        wait(w); signal(m);
        //release lock
    /* perform the
       reading operation
    */
    wait(m);      // acquire
    lock read_count--;
    if(read_count == 0)
        signal(w);
    signal(m);   // release
}

```

O  
R

```

void Reader
{void)
while
(true)
{
down(&mutex);
if(read_count==
1)
reader_down(&db)
up(&mutex)
reader_count
read_database
();
reader_count;
down(&mutex);
if(reader_count==
0) up(&db)
up(&mutex)
reader_count
}

```

//gain access to reader  
count  
//increment reader  
counter  
//if this is first process to read  
DB  
//prevent writer process to access  
DB  
//allow other process to  
access  
//gain access to reader  
count  
//decrement reader  
counter  
//if this is last process to read  
DB  
//leave the control of DB, allow writer  
process  
//allow other process to  
access



## Cont.

- On the other hand, in the code for the **reader**, the lock is acquired whenever the **read\_count** is updated by a process.
- When a **reader wants to access** the resource, first it **increments the read\_count** value, then accesses the resource and then decrements the **read\_count** value.
- The **semaphore w** is used by the **first reader** which enters the critical section and the **last reader which exits** the critical section.



## Cont.

- The reason for this is, when the **first reader enters** the critical section, the **writer is blocked** from the resource. Only new readers can access the resource now.
- Similarly, when the **last reader exits** the critical section, it **signals the writer** using the **w semaphore** because there are zero readers now and a **writer can have the chance** to access the resource.



## Message Passing


- One of the two techniques for communicating between parallel processes (the other being shared memory ).
- A common use of message passing is for **communication in a parallel computer**.
- A process running on **one processor** may send a message to a process running on the **same processor or another**.



# Message

## □ Message passing definition

- Message passing is a form between processes of communication used in object-oriented objects, programming, inter-process communication and parallel computing.





## Message

- Message passing can be **synchronous** or **asynchronous**.
- Synchronous message passing systems require the **sender** and **receiver** to **wait** for each other while transferring the message.
- In asynchronous communication the sender and receiver **do not wait** for each other while transfer of messages is being done.



## Message

- This method will use two primitives

1. Send: It is used to send message.

- Send (destination, &message)
- In above syntax destination is the process to which sender want to send message and message is what the sender wants to send.

2. Receive: It is used to receive message.

- Receive (source, &message)
- In above syntax source is the process that has send message and message is what the sender has sent.



## Producer Consumer problem using message

```
#define N 100 //number of slots in buffer
void producer (void)
{
    int item;
    message m; while
    (true)
    {
        receive(oddsem, item); //message buffer
        build_message(&m, item); //generate something to put in buffer
        send(consumer, &m); //wait for an empty to arrive //construct a message to send item to consumer
    }
}
```



## Producer Consumer problem using message

```
void consumer (void)
{
    int item, i;
    message
    m;
    for (i=0; i<N; i++) send (producer, &m); //send N
    empties
    while (true)
        receive (producer,
        &m); //get message containing item
        item=extract_item(&
        m); //extract item from message
        send (producer,
        &m); //send back empty reply
        consume_item
        (item);
    }
```



## Dining Philosopher's Problem

### □ PROBLEM STATEMENT

- Consider there are **five philosophers** sitting around a circular dining table.
  - The dining table has **five chopsticks** and a bowl of rice in the middle as shown in the figure.
  - At any instant, a philosopher **is either eating or thinking**.
  - When a philosopher wants to eat, he uses **two chopsticks** - one from their **left** and one from their **right**.
  - When a philosopher wants to **think**, he keeps **down both chopsticks** at their original place





# Dining Philosopher's

- The case of 5 philosophers (and 5 chopsticks only)
  - - Shared Bowl of rice (data set)
    - Semaphore **chopstick [5]** initialized to 1 (free)
- **Observation:** Occasionally try to pick up 2 chopsticks (left and right) to eat from bowl
  - One chopstick at a time
  - Need **both** chopsticks to eat, then release **both** when done
  - **Problem:** not enough chopsticks for all
    - N philosophes and

□ **The structure of Philosopher *i*:**

```
while (true) {
    wait (chopstick[i]); // wait to
    get the left stick
    wait (chopstick[(i + 1) %
5]); // get the right
    // eat
    signal (chopstick[i]);
    signal (chopstick[(i + 1) %
5]);
    // think /////////////////
};
```



## Dining Philosopher's Problem

- When a philosopher wants to eat the rice, he **will wait for the chopstick** at his **left** and picks up that chopstick.
- Then he waits for the **right** chopstick to be **available**, and then **picks it** too. **After eating**, he puts both the chopsticks down.

**Problem:** If all five philosophers are hungry simultaneously, and each of them pickup one chopstick, then a **deadlock** situation occurs because they will be waiting for another chopstick forever.



## Dining Philosopher's Problem

### □ ***The possible solutions for this are:***

- A philosopher must be allowed to pick up the chopsticks only if both the left and right chopsticks are available.
- Allow only four philosophers starts eating. That way, if all the four philosophers pick up four chopsticks, there will be one chopstick left on the table. So, one philosopher can start eating and eventually, two chopsticks will be available. In this way, deadlocks can be avoided.



## Solutio

- This solution uses only Boolean semaphores.
- There is one global semaphore to provide mutual exclusion for execution of critical protocols.
- There is one semaphore for each chopstick.
- In addition, a local two-phase prioritization scheme is used, under which philosophers defer to their neighbors who have declared themselves "hungry."

system DINING\_PHILOSOPHERS

VAR

```
me:    semaphore, initially 1;          /* for mutual exclusion */  
s[5]: semaphore s[5], initially 0;      /* for synchronization */  
pflag[5]: {THINK, HUNGRY, EAT}, initially THINK; /* philosopher flag */
```



## Solution

As before, each philosopher is an endless cycle of thinking and eating.

```
procedure philosopher(i)
{
    while TRUE do
    {
        THINKING;
        take_chopsticks(i);
        EATING;
        drop_chopsticks(i);
    }
}
```



## Solution

The `take_chopsticks` procedure involves checking the status of neighboring philosophers and then declaring one's own intention to eat.

This is a two-phase protocol; first declaring the HUNGRY, st going on to EAT. then

```

procedure take_chopsticks(i)
{
    DOWN(me);                      /* critical section */
    pflag[i] := HUNGRY;
    test[i];
    UP(me);                        /* end critical section */
    DOWN(s[i])                     /* Eat if enabled */
}

void test(i)                  /* Let phil[i] eat, if waiting */
{
    if ( pflag[i] == HUNGRY
        && pflag[i-1] != EAT
        && pflag[i+1] != EAT)
        then
        {
            pflag[i] := EAT;
            UP(s[i])
        }
}

```



## Solution

- x **DIGITAL LEARNING CONTENT**



**Parul® University**



[www.paruluniversity.ac.in](http://www.paruluniversity.ac.in)